



eNetwork	DFSMS/MVS	IMS	RMF
geoManager	DFSMSdfp	IMS/ESA	RS/6000
AD/Cycle	DFSMSdss	IP PrintWay	S/390
ADSTAR	DFSMShsm	IPDS	S/390 Parallel Enterprise Server
AFP	DFSMSrmm	Language Environment S	SecureWay
APL2	DFSORT	Multiprise	StorWatch
APPN	Enterprise System 3090	MQSeries	Sysplex Timer
BookManger	Enterprise System 4381	MVS/ESA Network Station	System/390 System REXX
BookMaster	Enterprise System 9000		
C/370	ES/3090	NetSpool	SystemView
CallPath	ES/4381	OfficeVision/MVS	SOM
CICS	ES/9000	Open Class	SOMobjects
CICS/ESA	ESA/390	OpenEdition	SP
CICS/MVS	ESCON	OS/2	VisualAge
CICSPlex	First Failure Support Technology	OS/390	VisualGen
COBOL/370	FLowMark	Parallel Sysplex	VisualLift
DataPropagator	FFST	Print Services Facility         VTAM           PrintWay         WebSphere           ProductPac         3090           PR/SM         3890/XP	VTAM
DisplayWrite	GDDM		3090
DB2	ImagePlus		
DB2 Universal Database	Intelligent Miner		
DFSMS	IBM	QMFr	z/OS
	IBM System z	RACF	z/OS.e








## **SADMP Dump Data Set Utility Panel**


```
AMDSAPUT ------ SADMP DASD Dump Data Set Utility ---
Command ==>
Enter/verify parameters. Use ENTER to perform function, END to terminate
 Function ==> R ( C - Clear, D - Define, R - Reallocate)
        ==>
 DSNAME
 Volume serial numbers: (1-32)
   1-8 VOL001
   9-16
   17 - 24
   25 - 32
 Unit ==> 3390 (3380, 3390, or 9345)
 Cylinders ==> 500 (cylinders per volume)
 DSNTYPE ==> E ( B - Basic, L - Large, E - ExtReq)
 CATALOG ==> Y (Y or N)
 EATTR ==> N ( N - No, O - Optional)
 Optional SMS classes: (May be required by installation ACS routines)
 StorClas ==>
                        DataClas ==>
                                                 MqmtClas ==>


    Redbooks
    © Copyright IBM Corp. 2010. All rights reserved.
```





















## Using AMDSADDD to allocate and initialize an extended SADMP data set


----- TSO COMMAND PROCESSOR --ENTER TSO COMMAND, CLIST, OR REXX EXEC BELOW: ==> exec 'sys1.sblscli0(amdsaddd)' What function do you want? Please enter DEFINE if you want to allocate a new dump data set define Please enter VOLSER or VOLSER(dump data set name) or (VOLLIST) or (VOLLIST)(dump\_data set\_name) (SADPK1, SADPK2) (SADMP.SAMPLE) Please enter the device type for the dump data set Device type choices are 3380 or 3390 or 9345 (An SMS STORAGE CLASS, DATA CLASS, AND MANAGEMENT CLASS MAY ALSO BE SPECIFIED WITH THE DEVICE TYPE) (3390, STORCLAS, DATACLAS, MGMTCLAS) Please enter the number of cylinders (per volume) 400 Do you want the dump data set to be cataloged? Please respond Y or N y Specify the DSNTYPE. Reply BASIC or LARGE or EXTREQ EXTREO Specify the extended attributes for the dump data set. Reply OPT or NO OPT TIME-11:54:59 PM. CPU-00:00:00 SERVICE-58954 SESSION-00:07:25 AUGUST 1,2009 **Pedbooks** © Copyright IBM Corp. 2010. All rights reserved.





























## Using the New PDS Function in Batch



		//IPCSPRNT	JOB	<pre>EEA,GO,MSGCLASS=A,MSGLEVEL=(1,1)</pre>
		//L2REPORT	EXEC	C PGM=IKJEFT01,DYNAMNBR=20,REGION=3000K
		//SYSPROC	DD	DSN=SYS1.SBLSCLI0,DISP=SHR
		//IPCSDDIR	DD	DSN=SYS2.DDIR,DISP=SHR
		//IPCSPDS	DD	DSN=PMRXXXXX.YYY.ZZZ,DISP=SHR
		//IPCSPRNT	DD	SYSOUT=*
		//IPCSTOC	DD	SYSOUT=*
		//SYSTSPRT	DD	SYSOUT=*
		//SYSUT1	DD	UNIT=SYSDA,SPACE=(CYL,(50,50))
		//DUMP	DD	DSN=DUMP.S00010,DISP=SHR
		//INDD	DD	DSN=DUMP.S00010,DISP=SHR
		//SYSTSIN	DD	*
		IPCSDDIR	'SYS	32.DDIR'
		IPCS NOP	ARM	
		SETDEF DI	ONAME	C(DUMP) LIST NOCONFIRM NOPRINT NOTERMINAL PDS
		SYSTRACE	TTC	CH(LIST) TIME(LOCAL)
		SETDEF 1	NOPDS	5
		END		
	@ R	/*		
l				

## Allocation Attributes for Print Partitioned Data Sets

The FREE command to free the allocated partitioned data set - FREE DDNAME(IPCSPDS)

Attribute	IPCSPDS Partitioned Data Set			
DDNAME or FILE	IPCSPDS			
DISP	NEW, SHR or OLD			
DSORG	РО			
RECFM	VBA			
LRECL	Minimum value: 83 Maximum value: 255 Default value: Value specified in session parameters or 137			
BLKSIZE	Must be greater than or equal to LRECL + 4. If you specify none, IPCS uses 4 + (4 * LRECL) as BLKSIZE.			
SPACE	You determine the space for the data sets.			
Redbooks © Copyright IBM Corp. 2010. All rights reserved.				

