



**Program Directory for
DB2 Server for VSE
and
Guest Sharing for VSE**

Version 7 Release 1, Modification Level 0

Program Number 5697-F42

for Use with
VSE/ESA

Document Date: September 2000

G110-4999-00

Note!

Before using this information and the product it supports, be sure to read the general information under "Notices" on page ix.

This program directory, dated September 2000, applies to DB2 Server for VSE Version 7 (DB2 for VSE) Release 1, Modification Level 0 , Program Number 5697-F42 for the following:

COMPIDs	Feature Numbers	System Name
5697-F42-01	5821	VSE/ESA
5697-F42-01	5822	VSE/ESA
5697-F42-01	5824	VSE/ESA
5697-F42-01	6016	VSE/ESA

A form for reader's comments appears at the back of this publication. When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© **Copyright International Business Machines Corporation 1981, 2000. All rights reserved.**

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

Contents

Notices	ix
Trademarks and Service Marks	ix
1.0 Chapter 1. Before You Begin	1
1.1 Program Materials	1
1.1.1 Basic Machine-Readable Material	1
1.1.2 Optional Machine-Readable Material	2
1.1.3 Program Publications	3
1.1.3.1 Basic Program Publications	3
1.1.3.2 Optional Program Publications	4
1.1.4 Program Source Materials	4
1.2 Program Support	4
1.2.1 Preventive Service Planning	4
1.2.2 Statement of Support Procedures	5
1.3 Program and Service Level Information	5
1.3.1 Program Level Information	5
1.3.2 Service Level Information	5
1.3.3 Cumulative Service Tape	6
1.4 Installation Requirements and Considerations	6
1.4.1 System Requirements	6
1.4.1.1 Operating System Requirements	6
1.4.1.2 Machine Requirements	6
1.4.1.3 Programming Requirements	6
1.4.1.3.1 Prerequisite Programs	6
1.4.2 DASD Storage Requirements	8
1.4.3 Processor Storage Requirements	8
1.5 Initial Considerations for Installing DB2 Server on a VSE System	9
1.5.1 Placement of DB2 Server for VSE Distribution Libraries	9
1.5.2 Machine-Readable Material	9
1.6 IBM Supplied Installation Aids	10
2.0 Chapter 2. Preparing to Install DB2 Server for VSE 7.1	11
2.1 Preparation Step 1: Setup the VSE Environment	12
2.1.1 DB2 Server for VSE Key Enablement	13
2.2 Preparation Step 2: Allocate DASD for the Distribution Library	14
2.3 Preparation Step 3: Allocate DASD for the Starter Database	15
2.4 Preparation Step 4: Restore the Distribution Library	16
2.5 Preparation Step 5: Prepare the CICS Environment	17
2.5.1 CICS Table Entries Required by DB2 Server for VSE 7.1	19
2.5.2 Entries Required in DFHSIT	20
2.5.2.1 Entries in DFHTCT Required by ISQL	21
2.5.2.2 Entries in DFHTCT for CICS Local Terminal Printers	21

2.5.2.3	Entries in DFHFCT for DB2 Server for VSE	21
2.5.3	CICS Journaling Support	22
2.5.4	CICS Restart Resynchronization Support	23
2.5.5	CICS Transaction Server (TS) considerations	24
2.6	Preparation Step 6: Define DB2 Server Programs and Transactions to CICS	24
2.7	Preparation Step 7: Setup the SQLGLOB and BIND files	25
2.7.1	Defining the Global Variable File (SQLGLOB)	25
2.7.2	Updating the SQLGLOB file with IBM-Supplied Global Defaults	26
2.7.3	Defining the Preprocessor Bind File	26
2.7.4	Defining the Preprocessor Bind Work File (BINDWFILE)	27
2.7.5	Converting the ISQL Bind File to a VSAM File	28
2.8	Preparation Step 8: Define VSAM Data Sets for the Starter Database	28
2.9	Updating Labels for the new datasets	30
3.0	Chapter 3. Installing DB2 Server for VSE	31
3.1	Installation Step 1: Setup the DBNAME Directory	32
3.2	Installation Step 2: Link-Edit the DB2 Server for VSE Online Support Components	33
3.3	Installation Step 3: Generate the Starter Database	34
3.4	Installation Step 4: Install Optional Database Components	37
3.5	Installation Step 5: Reload CCSID-Related Phases Package	38
3.6	Installation Step 6: Selecting National Language Support	39
3.6.1	Install Language and Help Text	39
3.7	Installation Step 7: Grant SCHEDULE Authority	41
3.8	Installation Step 8: Start the Application Server in Multiple User Mode	41
3.9	Installation Step 9: Create CCSID-Related Phases	42
3.10	Installation Step 10: Run the Sample Programs to Verify Installation	43
3.11	Installation Step 11: Run ISQL to Verify Installation	44
3.11.1	Starting the CICS System	44
3.11.1.1	Starting the DB2 Server for VSE Online Support	45
3.11.2	Starting ISQL	46
3.11.3	Verify the Installation	46
3.11.4	Stopping ISQL	47
3.12	Installation Step 12: Stop the Application Server	47
3.12.1	Stopping the DB2 Server for VSE Online Support	47
3.12.2	Stopping the CICS System	48
3.12.3	Stopping the Application Server	48
3.13	Post-Installation Activities	48
3.14	Installation Step 13: Add New Users to the Database	48
3.15	Installation Step 14: Change the Database Administrator Password	49
3.16	Installation Step 15: System Customization Activities	50
3.16.1	VSE Guest Sharing	51
3.16.2	VSE Guest Machine Parameters	51
4.0	Chapter 4. Migrating an Existing Database	53
4.1	Migration Step 1: Space Verification and DATE/TIME Option Verification	54
4.1.1	Directory Space	54

4.1.2	Storage Pool Space	55
4.1.3	DATE/TIME Options	55
4.2	Migration Step 2: Archiving a Database	56
4.3	Migration Step 3: Prepare the Database for Migration	56
4.4	Migration Step 4: Migrate the DBNAME Directory	57
4.5	Migration Step 5: Format the DB2 Server for VSE Logs	58
4.6	Migration Step 6: Update the DB2 Server for VSE Catalog to the 7.1 Level	59
4.7	Migration Step 7: Reload the DBS Utility Package	60
4.8	Migration Step 8: Update the DB2 Server for VSE Database	60
4.9	Migration Step 9: Migrate the HELP Text Tables	61
4.10	Migration Step 10: Reload English HELP Text into a Database	62
4.10.1	Install Language	62
4.11	Migration Step 11: Reload ISQL into a Database	62
4.12	Migration Step 12: Reload CCSID-Related Phases Package	63
4.13	Migration Step 13: Load FIPS Flagger into a Database	63
4.14	Migration Step 14: Determine the Primary Keys to be Recreated	63
4.15	Migration Step 15: Revoke CONNECT Authority from ALLUSERS	64
4.16	Migration Step 16: Reset the Password for User SQLDBA	65
4.17	Migration Step 17: Start the Application Server in multiple user mode	65
4.18	Migration Step 18: Create CCSID-Related Phases	65
4.19	Migration Step 19: System Customization Activities	66
5.0	Chapter 5. Maintenance Activities	67
5.1	DBS Utility Maintenance	67
5.1.1	Reloading the DBS Utility Package (SQLDBA.ARIDSQL)	67
5.2	Messages and HELP Text Maintenance	68
5.2.1	Installing the HELP Text after DB2 Server for VSE Installation	68
5.2.2	Removing Messages and HELP Text from Your DB2 Server for VSE System	69
5.3	Online Resource Adapter Control Maintenance	71
5.3.1	Installing Online Resource Adapter Control after DB2 Server for VSE Installation	71
5.3.2	Re-Link-Editing Online Resource Adapter Control	71
5.4	ISQL Maintenance	72
5.4.1	Installing ISQL after DB2 Server for VSE Installation	72
5.4.2	Reloading the ISQL Package (SQLDBA.ARIISQL)	72
5.4.3	Re-Link-Editing ISQL	73
5.4.4	Re-Link-Editing the ISQL ITRM Terminal Transaction	74
5.4.5	Re-Link-Editing the ISQL ITRM Terminal Extension Program	75
5.5	CCSID-Related Phases Maintenance	76
5.5.1	Reloading the CCSID-Related Phases Package (SQLDBA.ARIRSQR)	76
5.5.2	Recreating the CCSID-Related Phases	76
5.6	FIPS Flagger Maintenance	76
5.6.1	Reloading the FIPS Flagger Package (SQLDBA.ARIFCRD)	77
5.7	DB2 Server for VSE Library Maintenance	78
5.7.1	Replacing DB2 Server for VSE	78
5.7.2	Purging DB2 Server for VSE Libraries	78
5.8	DB2 Server for VSE Link Books	78

6.0 Appendix A. How to Use the Job Manager	81
6.1 Overview of Installation and Migration	81
6.2 Installation	81
6.3 Migration	81
6.4 Optional Steps	81
6.5 The Job Manager	82
6.5.1 How Parameter Substitution Works	82
6.5.2 How Job List Works	83
6.5.2.1 How to Run All Jobs Again	84
6.5.3 Starting the Job Manager	84
6.5.3.1 User Interface	85
6.5.4 Execution of Jobs Submitted by the Job Manager	86
6.5.5 How the Job Results are Evaluated	87
6.5.6 What Should You Keep in Mind	87
6.6 The Disclaimer	88
7.0 Appendix B. Techniques Used for Installation	89
7.1 Embedding Database Identification Statements	89
7.2 Embedding DB2 Server for VSE Library Identification Statements	89
7.3 Using the READ MEMBER Statement	89
7.4 Running the DBS Utility in Single User Mode	90
7.5 Suppressing Preprocessor Output	91
8.0 Appendix C. Procedures Provided by IBM	92
9.0 Appendix D. A-Type Source Members	94
10.0 Appendix E. Z-Type Source Members	97
11.0 Appendix F. Additional CICS and VSE Updates for the DB2 Server System	100
11.1 Additional Updates Required for the CICS Monitoring Facility	100
11.1.1 DFHJCT Entries	100
11.1.2 DFHMCT Entries	101
11.1.3 DFHSIT Entries	103
11.2 Additional Updates for DB2 Server Accounting	103
11.3 Additional Updates for CIRB Auto-Initiation	103
11.3.1 DFHTCT Entries Required for Card Reader Line Printer Support	103
11.3.2 DFHTCT Entries Required for Sequential DASD Support	104
11.4 Additional Updates Required for the Online Resource Adapter DRDA Router Tracing	105
12.0 Bibliography	108
13.0 Reader's Comments	111

Figures

1.	Basic Material: Program Tape	1
2.	Program Tape: File Content	1
3.	Optional Material: Data Restore	2
4.	Optional Material: DB2 Server for VSE Guest Sharing	2
5.	Optional Material: Control Center	3
6.	Optional Material: Query Management Facility (QMF)	3
7.	Basic Material: Unlicensed Publications	3
8.	Basic Material: Licensed Publications	4
9.	PSP Upgrade and Subset ID	4
10.	Component IDs	5
11.	VSE Environments	8
12.	Scanning the DB2 Server for VSE 710 Distribution Library	10
13.	Sample Report from the Scan Job	10
14.	Preparation Steps	11
15.	Description of global parameters	12
16.	DASD Storage Requirements for DB2 Server for VSE Library	14
17.	Recommended Starter Database DASD Sizes	15
18.	Job ARIS71AD (Using MSHP to Install DB2 Server for VSE)	16
19.	Starting the CICS System for Use with ISQL	18
20.	DFHFCT Sample entries	22
21.	DFHJCT Examples for CICS Journaling	23
22.	The parameters for ARIS71JD	25
23.	The parameters for ARIS718D	26
24.	The parameters for ARIS717D	27
25.	The parameters for ARIS719D	27
26.	The parameters for ARISIQBD	28
27.	The parameters for ARIS71CD	28
28.	The parameters for ARISSTD L	30
29.	Steps to Install DB2 Server for VSE Version 7 Release 1	31
30.	Description of global parameters	32
31.	Job ARISBDID (Setup DBNAME directory)	33
32.	The parameters for ARISBDID	33
33.	The parameters for ARIS71BD	34
34.	Job ARIS71DD (Generating a Database)	35
35.	A-type source member ARISDBG	37
36.	The parameters for ARIS71ED	38
37.	The parameters for ARIS71HZ	39
38.	The parameters for ARIS71JZ	40
39.	The parameters for ARIS380D	40
40.	The parameters for ARIS71FD	41
41.	The parameters for ARIS71GD and ARIS71GZ	42
42.	The parameters for ARISCNVD	43

43.	The parameters for ARIS6C2D	43
44.	The parameters for ARIS6CD	44
45.	The parameters for ARIS6FTD	44
46.	The parameters for ARIS6PLD	44
47.	Installation Verification Display	47
48.	Stopping the Application Server	48
49.	Adding New User IDs to the Database	49
50.	Job ARIS71VD (Example of Changing the SQLDBA Password in the Database)	50
51.	DBNAME directory 6.1 format	51
52.	Steps to Migrate an Existing Database to Version 7 Release 1	53
53.	Description of Global Parameters.	54
54.	Job ARIS71SL (DB2 Server Library Definitions)	54
55.	Job ARIS71ND (Prepare the Database for Migration)	57
56.	Alter DB2 Server VSAM Clusters Shareoptions	57
57.	The parameters for ARISBDID	58
58.	The parameters for ARIS71OD	58
59.	The parameters for ARIS71PD	59
60.	The parameters for ARIS71NZ	65
61.	Reloading the DBS Utility Package	67
62.	Reinstalling the HELP Text into the Database	68
63.	Removing ISQL HELP Text and Messages from the Database	70
64.	Re-Link-Editing Online Resource Adapter Control	71
65.	Reloading the ISQL Package	72
66.	Re-Link-Editing ISQL	73
67.	Re-Link-Editing the ISQL ITRM Terminal Transaction	74
68.	Re-Link-Editing the ISQL ITRM Terminal Extension Program	75
69.	Reloading the CCSID-Related Phases Package	76
70.	Reloading the FIPS Flagger Package	77
71.	Purging DB2 Server for VSE Libraries	78
72.	Link Books for the DB2 Server for VSE Components	79
73.	The description of parameters in ARISIVAR	82
74.	The description of Global parameters in the ARISIVAR	83
75.	Description of each column in a job list	83
76.	Starting the Job Manager	84
77.	Sample user answers when running the Job Manager	85
78.	Console output from the Job Manager	86
79.	Example of Running the DBS Utility in Single User Mode	91
80.	Example of JCL Required to Punch A-Type Members	96
81.	Example of JCL Required to Punch Z-Type Members	99
82.	DFHJCT Examples for CICS Monitoring Facility	101
83.	DFHMCT Example for CICS Monitoring Facility	102
84.	DFHTCT Examples for CRLP Support	104
85.	Auto-initiating CIRB using CRLP support	104
86.	DFHTCT Examples for Sequential DASD Support	105
87.	DFHDCT Example	106

Notices

References in this document to IBM products, programs, or services do not imply that IBM intends to make these available in all countries in which IBM operates. Any reference to an IBM product, program, or service is not intended to state or imply that only IBM's product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe on any of IBM's intellectual property rights may be used instead of the IBM product, program, or service. Evaluation and verification of operation in conjunction with other products, except those expressly designated by IBM, is the user's responsibility.

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the

International Business Machines Corporation
IBM Director of Licensing
North Castle Drive, Armonk, NY
10504-1785, USA

Trademarks and Service Marks

The following terms, denoted by an asterisk (*), used in this document, are trademarks or service marks of IBM Corporation in the United States or other countries:

IBM	RETAIN
DATABASE 2	CICS/VSE
DB2 Server for VSE	DRDA
DB2	CICS
VSE/ESA	VTAM
DB2 Server for VSE & VM	VM/ESA

The following terms, denoted by a double asterisk (**), used in this document, are trademarks of other companies as follows:

None

1.0 Chapter 1. Before You Begin

1.1 Program Materials

An IBM program is identified by a program number and a feature code. The program number for DB2 for VSE is 5697-F42.

The program announcement material describes the features supported by DB2 for VSE. Ask your IBM marketing representative for this information if you have not already received a copy.

The following sections identify:

- The basic and optional program materials available with this program

1.1.1 Basic Machine-Readable Material

The distribution medium for this program is 9-track magnetic tape (written at 6250 BPI), 3480 cartridge, 1/4-inch tape cartridge or 4mm tape cartridge. The tape or cartridge contains all the programs and data needed for installation. Figure 1 describes the tape or cartridge. Figure 2 describes the file content of the program tape or cartridge.

Note: The program tape and cartridge contain “Restricted Materials of IBM.”

Figure 1. Basic Material: Program Tape

Medium	Feature Number	Physical Volume	External Label Identification	VOLSER
6250 tape	5821	1	DB2 Server for VSE	N/A
		1	DB2 VSE Help Text	N/A
		1	DProp Capture for VSE	N/A
3480 cart.	5822	1	DB2 Server for VSE	N/A
		1	DB2 VSE Help Text	N/A
		1	DProp Capture for VSE	N/A
1/4 inch cart.	5824	1	DB2 Server for VSE	N/A
		1	DB2 VSE Help Text	N/A
		1	DProp Capture for VSE	N/A
4 mm cart.	6016	1	DB2 Server for VSE	N/A
		1	DB2 VSE Help Text	N/A
		1	DProp Capture for VSE	N/A

Figure 2 (Page 1 of 2). Program Tape: File Content

VOLSER	File	Name
N/A	1	DB2 for VSE Copyright Records

Figure 2 (Page 2 of 2). Program Tape: File Content

VOLSER	File	Name
N/A	2	DB2 for VSE History Files
N/A	3	DB2 for VSE Product
N/A	4	Tape Mark
N/A	5	Tape Mark

1.1.2 Optional Machine-Readable Material

The distribution medium for optional machine-readable material is 9-track magnetic tape (written at 6250 BPI), 3480 cartridge, 1/4-inch tape cartridge, or 4 mm tape cartridge. Figure 3, Figure 5, and Figure 6 on page 3 describes the tape or cartridge.

Note: The optional machine-readable material (tape or cartridge) contains “Restricted Materials of IBM.”

Figure 3. Optional Material: Data Restore

Feature Number	Medium	Physical Volume	Tape Content	External Tape Label
5962	6250 tape	1	Data Restore for VSE	Data Restore VSE
5963	3480 cart.	1	Data Restore for VSE	Data Restore VSE
5952	1/4 inch cart.	1	Data Restore for VSE	Data Restore VSE
6045	4 mm cart.	1	Data Restore for VSE	Data Restore VSE

Figure 4. Optional Material: DB2 Server for VSE Guest Sharing

Feature Number	Medium	Physical Volume	Tape Content	External Tape Label
5801	6250 tape	1	DB2 Server for VSE (GS)	DB2 Server for VSE (GS)
5802	3480 cart.	1	DB2 Server for VSE (GS)	DB2 Server for VSE (GS)
5804	1/4 inch cart.	1	DB2 Server for VSE (GS)	DB2 Server for VSE (GS)
6008	4 mm cart.	1	DB2 Server for VSE (GS)	DB2 Server for VSE (GS)

Figure 5. Optional Material: Control Center

Feature Number	Medium	Physical Volume	Tape Content	External Tape Label
5988	6250 tape	1	Control Center for VSE	Control Center VSE
5989	3480 cart.	1	Control Center for VSE	Control Center VSE
5978	1/4 inch cart.	1	Control Center for VSE	Control Center VSE
6047	4 mm cart.	1	Control Center for VSE	Control Center VSE

Figure 6. Optional Material: Query Management Facility (QMF)

Feature Number	Medium	Physical Volume	Tape Content	External Tape Label
6094	6250 tape	1	QMF for VSE	QMF for VSE V7 (E)
6092	3480 cart.	1	QMF for VSE	QMF for VSE V7 (E)
6091	1/4 inch cart.	1	QMF for VSE	QMF for VSE V7 (E)
6093	4 mm cart.	1	QMF for VSE	QMF for VSE V7 (E)

1.1.3 Program Publications

The following sections identify the basic and optional publications for DB2 for VSE.

1.1.3.1 Basic Program Publications: Figure 7 identifies the basic program publications for DB2 for VSE. One copy of each of these publications is included when you order the basic materials for DB2 for VSE. For additional copies, contact your IBM representative.

An asterisk (*) beside the Form Number indicates it contains "Restricted Materials of IBM."

Figure 7 (Page 1 of 2). Basic Material: Unlicensed Publications

Publication Title	Form Number
<i>DB2 Server for VSE & VM Operation.</i>	SC09-2986
DB2 Server for VSE & VM Overview	GC09-2806
<i>DB2 Server for VSE & VM Interactive SQL Guide and Reference</i>	SC09-2990
<i>DB2 Server for VSE & VM Database Administration</i>	SC09-2888

Figure 7 (Page 2 of 2). Basic Material: Unlicensed Publications

Publication Title	Form Number
DB2 Server for VSE System Administration	SC09-2981
DB2 Server for VSE & VM Application Programming	SC09-2889
DB2 Server for VSE & VM Database Services Utility	SC09-2983
DB2 Server for VSE & VM SQL Reference	SC09-2989
DB2 Server for VSE & VM Quick Reference	SC09-2988
DB2 Server for VSE Messages and Codes	GC09-2985
DB2 Server for VSE & VM Performance Tuning Handbook	GC09-2987
DB2 Server for VSE & VM Master Index and Glossary	SC09-2890
DB2 Server for VSE & VM Licensed Program Specifications for VM Systems and for VSE Systems	GC09-2982

Figure 8. Basic Material: Licensed Publications

Publication Title	Form Number
DB2 for VSE Diagnosis Guide and Reference	LC09-2673(*)

1.1.3.2 Optional Program Publications: There are no optional publications for DB2 for VSE.

1.1.4 Program Source Materials

There are no source materials available for DB2 for VSE.

1.2 Program Support

This section describes the IBM support available for DB2 for VSE.

1.2.1 Preventive Service Planning

Before installing DB2 for VSE, check with your IBM Support Center or use either Information/Access or SoftwareXcel Extended to see whether there is additional Preventive Service Planning (PSP) information that you should know. To obtain this information, specify the following UPGRADE and SUBSET values:

Figure 9. PSP Upgrade and Subset ID

UPGRADE	SUBSET	RETAIN Release
DB2VSEVM710	DB2VSE	1NO

1.2.2 Statement of Support Procedures

Report any difficulties you have using this program to your IBM Support Center. If an APAR is required, the Support Center will provide the address to which any needed documentation can be sent.

Figure 10 on page 5 identifies the component IDs (COMPID) for DB2 for VSE.

Figure 10. Component IDs

COMP ID	Component Name	CLC
5697-F42-01	DB2 Server for VSE V710	1NO

1.3 Program and Service Level Information

This section identifies the program and any relevant service levels of DB2 for VSE. The program level refers to the APAR fixes incorporated into the program. The service level refers to the PTFs integrated. Information about the cumulative service tape is also provided.

1.3.1 Program Level Information

This version of DB2 Server for VSE has incorporated all closed APARs from previous versions/releases at the time of the product General Availability.

1.3.2 Service Level Information

Check the DB2VSEVM710 PSP bucket for any additional PTFs that should be installed or any additional install information.

The following VSE APARs are required for Extended User Buffering support which has been enabled in DB2/VSE 7.1:

- DY44838 / UD51237
- DY45312 / UD51312

Warning: without the previous two APARs, you may experience Data corruption.

VSE/AF PTF numbers to APAR DY45460, solving the EOJ cleanup problem:

- **VSE 2.3**
 - UD51472 - production PTF
 - UD51473 - generation PTF
- **VSE 2.4**
 - UD51474 - production PTF

– UD51475 - generation PTF

LE 1.4.0 PTF/APAR numbers, solving TCP/IP EOJ cleanup problem:

- UQ40116 / PQ34038
- UQ44201 / PQ36618

VSE/ESA 2.3 and VSE/ESA 2.4 the PTF/APAR numbers:

- UQ44071 / PQ29053
- UQ32767 / PQ26600
- UQ38659 / PQ27252

1.3.3 Cumulative Service Tape

There is no cumulative service tape for DB2 for VSE.

1.4 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating DB2 Server for VSE.

1.4.1 System Requirements

This section describes the environment of the system required to install and use DB2 for VSE.

1.4.1.1 Operating System Requirements:

DB2 for VSE operates under the VSE/ESA operating system release 2.3.1 or higher.

If DB2 for VSE is being installed on VSE/ESA 2.5 or higher, a valid DB2 product key must be installed.

1.4.1.2 Machine Requirements:

One tape drive supported by VSE/ESA is required for installation.

1.4.1.3 Programming Requirements:

1.4.1.3.1 Prerequisite Programs:

This section summarizes the program products required or recommended for the DB2 for VSE functions and environments available with this release. Unless otherwise stated, the database manager works with all subsequent versions, releases, and modification levels of the products listed in this section as well as with equivalent non-IBM products.

When installing DB2 for VSE on a VSE system, you require an environment provided by VSE/Enterprise Systems Architecture Version 2 Release 3 Modification 1 or later. DB2 for VSE requires VSE/VSAM, which comes included with this operating system.

This operating system also includes the following licensed program products that DB2 for VSE requires:

- VSE/POWER for Query/Report Writing support
- VSE/ICCF for an interactive development environment and
- CICS/VSE for online support.

The VSE/ESA Version 2 Release 3.1 system supplies the minimum requirements to support DB2 for VSE. However, the APARS described in "*Service Level Information*" must be applied.

Refer to the planning manual for your VSE system to determine whether DB2 for VSE is supported as an optional product.

If you have CICS Transactions that access local DB2 for VSE Server(s), you must use the restart resynchronization capability of CICS. *Section 2.6: Prepare the CICS Environment*, describes the CICS table updates needed to use restart resynchronization.

If you plan to use non-DB2 for VSE facilities to backup a database, you can use the VSE/VSAM Backup/Restore Feature.

Note: Backing up your data is vital to provide operational integrity.

Users of Double-Byte Character Set (DBCS) data should consider the following:

- PL/I programs using DBCS require no additional preprocessing (the PL/I compiler supports DBCS).
- DBCS variables and constants are not supported in FORTRAN and Assembler programs. This does not prevent you from using DBCS in dynamically defined SQL statements.
- In COBOL II Release 2 programs for VSE, SQL identifiers, SQL host variables, and SQL labels with DBCS characters can be used in SQL statements. The COBOL Kanji Preprocessor is not required.

A complete description of the software and hardware requirements is listed in chapter 1 of the *DB2 Server for VSE System Administration manual*, GC09-2981. Read this chapter before you begin your installation.

DB2/VSE Environments	DB2/VSE Components ¹			Supported Languages				
	Base	ORA	ISQL	PL/I	Cobol	Fortran	C	ASM
Batch	X			X	X	X	X	X
Online	X	X	X	X	X		X	X
Interactive application development	X	X	X	X	X	X	X	X
Query/Report Writing	X	X	X					
DRDA Requestor		X	X	X	X		X	X
Notes: 1 For this column: <ul style="list-style-type: none"> • Base refers to the database manager components that support batch applications, the pre-processors, and the utilities including the database services (DBS) utility. • ORA (online resource adapter) refers to the DB2 Server for VSE support for transaction processing (CICS*) environments. • ISQL refers to the terminal user query and report-writing facilities. 								

Figure 11. VSE Environments

Prerequisite programs should be installed before you begin to do any of the steps described in this manual.

1.4.2 DASD Storage Requirements

DASD storage requirements are described in *Chapter 2*.

Notes:

- National Language Versions of the DB2/VSE HELP TEXT and messages are included with the DB2 for VSE basic material.
- These allocations include approximately 25 percent free space to allow for maintenance.
- Maintain System History Program (MSHP) auxiliary history file are based on suggested values in the VSE/ESA System Control Statements manual for your VSE operating system.
- FB-512 devices include 0671, 3370, 9332, 9335, and 9336 storage devices.

1.4.3 Processor Storage Requirements

The storage requirements for DB2 for VSE partition are:

- 9 MB without DRDA support
- 15 MB with DRDA support.

1.5 Initial Considerations for Installing DB2 Server on a VSE System

1.5.1 Placement of DB2 Server for VSE Distribution Libraries

When you use the installation function provided by VSE/Interactive Interface (VSE/II), choose option 2: "Install Programs--V1 Format". The job stream generated copies DB2 Server for VSE installation tape in the VSE library PRD2.DB2710.

If you are using the V2 format dialog, do not perform option 1: "Prepare for Installation" because the distribution tape is nonstacked.

1.5.2 Machine-Readable Material

IBM distributes machine-readable DB2 Server material on magnetic tape (reel or cartridge, non-stack). The format of the tape for VSE is:

File 1	DB2 Server for VSE Copyright Records
File 2	DB2 Server for VSE History File
File 3	DB2 Server for VSE Product
File 4	Tape Mark
File 5	Tape Mark.

This tape is intended for processing by the VSE Maintain System History Program (MSHP), or VSE/II. You will need the following information to download DB2 Server for VSE:

- The tape label for DB2 Server for VSE is DB2/VSE....7.1.0
- The library for the product is PRD2
- The sublibrary for the product is DB2710.

Be sure you have a distribution tape in the correct format for your VSE system. To verify this tape, scan it by running the sample JCL shown in Figure 12 on page 10. Figure 13 on page 10 shows a sample report from a scan job.

```

// JOB SCAN TAPE
* *****
* PLEASE MOUNT DB2 SERVER R7.1.0 DISTRIBUTION TAPE ON A TAPE DRIVE
* AND ASSIGN SYS006 TO THAT TAPE DRIVE.
* THEN PRESS THE ENTER KEY WHEN READY ...
* *****
// PAUSE          PLEASE ASSIGN SYS006 NOW ...
// MTC REW,SYS006
// EXEC LIBR
RESTORE * TAPE=SYS006 SCAN=YES
/*
/ &

```

Figure 12. Scanning the DB2 Server for VSE 710 Distribution Library

```

RESTORE * TAPE=SYS006 SCAN=YES
L059I BACKUP FILE ID = 'DB2/VSE...7.1.0'
L123I HISTORY FILE FOUND ON TAPE
L091I SUBLIBRARY PRD2.DB2710 FOUND ON INPUT TAPE
APPROXIMATE SPACE REQUIREMENT: 25037 LIBRARY BLOCKS
3375 : 1002 TRACKS = 83 CYLINDERS 6 TRACKS
3380 : 808 TRACKS = 53 CYLINDERS 13 TRACKS
3390 : 759 TRACKS = 50 CYLINDERS 9 TRACKS
9345 : 895 TRACKS = 59 CYLINDERS 10 TRACKS
FBA : 50094 BLOCKS
L113I RETURN CODE OF RESTORE IS 0

```

Figure 13. Sample Report from the Scan Job

1.6 IBM Supplied Installation Aids

To help you install DB2 Server for VSE, or migrate existing databases, sample job control members are supplied as Z-type source members on the installation tape.

Some of the job control members will require modifications before submitting them for execution. These members and the required changes are discussed in the preparation, installation and migration chapters.

A REXX exec is supplied to aid in the modification and execution of these jobs. You can also punch these members out of the installation library into VSE/ICCF or another editor, for changes and submission.

2.0 Chapter 2. Preparing to Install DB2 Server for VSE 7.1

To prepare to install DB2 Server for VSE:

1. Read "Appendix A: How to Use the Job Manager".
2. Read "Planning for Installation" in the DB2 Server for VSE System Administration Manual
3. Ensure that the VSE operating system and all necessary programs are already installed and running correctly. (See "Prerequisite Programs" in Chapter 1)
4. Review this document completely before installing DB2 Server for VSE. For any optional steps, understand why the step is optional.
5. Review the section on service considerations, check for any prerequisite program temporary fixes (PTFs). Contact the IBM Support Center, or access with Information/Access or IBM Link, to see whether there is any additional preventative service planning (PSP) information which you should be aware of.
6. Complete all of the mandatory steps in this chapter, and any optional ones that apply to your installation. These steps are shown in Figure 14.

Step	Optional/ Mandatory	Automated/ Manual	Description
1	M	Manual	Set up the VSE Environment
2	M	Manual	Allocate DASD for the Distribution Library
3	M ¹	Manual	Allocate DASD for the Starter Database
4	M	Manual	Restore the DB2 Server for VSE Distribution Library
5	O	Manual	Prepare the CICS Environment
6	O	Automated	Define CICS programs and Transactions
7	O	Automated	Setup the SQLGLOB and BIND files
8	M ¹	Automated	Define VSAM Data Sets for the Starter Database
9	O	Automated	Updating Labels for the New Datasets

Figure 14. Preparation Steps

Note:

1. The Starter Database is mandatory for Installation, and optional for Migration

Figure 15 on page 12 includes the global variables required in the Preparation Step.

Parameter Name	Default value	Description	Used in member:
GLOBCAT	VSESP.USER.CATALOG	The default VSAM catalog where SQLGLOB resides	ARIS71CD, ARISSTD
BINDFILE	DB2.BIND.MASTER	This is the name of the dataset which will hold the global variables	ARIS71CD, ARISSTD, ARIS717D, ARISIQBD
BINDWFILE	DB2.BIND.WORKF	This is the name of the dataset which will hold the preprocessor bind packages.	ARIS71CD, ARISSTD, ARIS719D
MASTERFILE	DB2.SQLGLOB.MASTER	This is the name of the dataset which will hold the global variables	ARIS71CD, ARISSTD, ARIS718D, ARISGDEF
ATYPE	CYL	The type of allocation unit for database IDCHMC DEFINE. The default allocation unit is Cylinders. Use BLK for FBA devices, or CYL for (E) CKD devices	ARIS71CD, ARIS717D, ARIS719D

Figure 15. Description of global parameters

2.1 Preparation Step 1: Setup the VSE Environment

This step is mandatory

If you are migrating from a previous release of DB2 for VSE, you may have to increase the partition size. Refer to *DB2 Server for VSE System Administration* manual for more information.

Ensure that your VSE system is prepared as follows:

- Equip the system with a tape drive for the type of distribution tape ordered.
- Be sure that the system files are assigned correctly. During the installation process, input is read from SYSIPT and source members from the DB2 Server for VSE sublibrary. Output is written to the printer file, SYSLST, and the SYS001 workfile.
- Ensure that the SYS001 workfile size is at least equal to 1 cylinder on an IBM 3380 DASD (960 blocks on FBA devices).

See the *DB2 Server for VSE System Administration* manual for detailed information about capacity planning for storage requirements.

The partition sizes given below are the minimum required to successfully install or migrate a database. For a detailed discussion of how to calculate partition sizes based on real operating conditions see the *DB2 Server for VSE System Administration* manual. Also, refer to the *IBM VSE/ESA Planning* for information

about partition configuration that could be used during the installation of optional program product such as DB2 Server for VSE.

- Compiling and running application programs - 2.0 megabytes;
- CICS system to support ISQL - 8.0 megabytes;
 - to support DRDA Requester, approximately 1 additional megabyte is required for the resident online resource adapter
- DB2 Server for VSE partition:
 - without DRDA - 5.0 megabytes;
 - with DRDA - 6.5 megabytes;

Note! When the application server is started in single user mode, both the application server and the installation application program are executed in the DB2 Server for VSE partition.

When the application server is started in multiple user mode:

- Batch installation application programs can be started in any partition with enough storage. The library search assignment must include the DB2 Server for VSE 7.1 sublibraries for installation programs executed in the partition.
- ISQL must be executed in the CICS partition.
- If the ISQL facility will be used in the CICS partition, the available CICS dynamic transaction storage size must be at least 900 kilobytes to support ISQL. See *"Installation Step 2: Link-Edit the DB2 Server for VSE 7.1 Online Support Components"*.

VSE/REXX Version 6 Release 1 must be enabled.

2.1.1 DB2 Server for VSE Key Enablement

Users on VSE/ESA Version 2 Release 5 and later, who want to run DB2 Server for VSE, are required to install a DB2 permanent product activation key, or a DB2 "90-day trial mode" product key.

VSE/ESA Version 2 Release 5 and later is shipped with a DB2 "90-day trial mode" product key. After the 90-day trial period is over, it is necessary to supply a DB2 permanent product key. This DB2 permanent product key is supplied automatically from IBM whenever an order is placed for DB2 Server for VSE & VM.

DB2 product enabling is driven by a phase which can be generated by the following EXEC IVALPKEY. The statement to execute IVALPKEY is supplied by VSE/ESA Version 2 Release 5, and later, in the member SKUSERBG in ICCF library 59.

```
// EXEC IVALPKEY,PARM='PRODUCT=DB2 KEY=0000-1111-2222-3333-4444 CUSTINFC  
0=C111-111-1111'
```

The key that appears in this EXEC statement is the DB2 "90-day trial mode" product key. Please note that the 90-day trial period starts when IVALPKEY is run (and not when DB2 Server for VSE is installed). Each time DB2 Server for VSE is accessed, message ARI4027W is displayed informing you of the number of days left within the 90-day trial period.

Once you have completed a license agreement for DB2 Server for VSE, you will replace the string shown in the sample EXEC statement with the DB2 permanent product activation key.

IVALPKEY must be run whenever the VSE/ESA operating system is IPLed. Therefore, it is recommended that you place the statement to execute IVALPKEY on the POWER RDR queue so that it is released automatically at each IPL of the VSE/ESA system during background processing.

If IVALPKEY is not run when the VSE/ESA operating system is IPLed, DB2 Server for VSE cannot be installed, migrated or started.

Users on VSE/ESA Version 2 Release 4, or earlier, who want to run DB2 Server for VSE, are **not** required to install a DB2 permanent product activation key, or a DB2 "90-day trial mode" product key.

2.2 Preparation Step 2: Allocate DASD for the Distribution Library

This step is mandatory

APPROXIMATE SPACE REQUIREMENT: 27,181 LIBRARY 1K BLOCKS.

DASD Storage Requirements for DB2 Server for VSE Library

APPROXIMATE SPACE REQUIREMENT: 27,181 LIBRARY BLOCKS		
DASD Device Type	Approximate Library Space Required	MSHP History File Space Required
3375	100 cylinders	15 tracks
3380	64 cylinders	15 tracks
3390	60 cylinders	15 tracks
9345	71 cylinders	15 tracks
FB-512	59,150 blocks	900 blocks

Figure 16. DASD Storage Requirements for DB2 Server for VSE Library

Notes:

1. These allocations include approximately 25% free space to allow for maintenance.
2. The sizes for the Maintain System History Program (MSHP) auxiliary history files are based on suggested values in the IBM VSE/ESA System Control Statements manual for your VSE operating system.

3. FB-512 devices include 0671, 3370, 9332, 9335, and 9336 storage devices.

2.3 Preparation Step 3: Allocate DASD for the Starter Database

This step is mandatory for the installation process, but optional for the migration process.

Allocate VSAM space for the Starter Database.

Figure 17 shows the approximate size of the Starter Database on various devices.

<i>Figure 17. Recommended Starter Database DASD Sizes</i>					
Starter Data- base Data Set Allocations	3375 Cyls	3380 Cyls	3390 Cyls	9345 Cyls	FB-512 Blocks
Directory	53	34	29	38	31,620
Log	13	8	7	9	9,600
Data Extend					
Minimum	38	24	21	27	28,800
Recommended	121	77	65	85	92,400
Total Allo- cations					
Minimum	104	66	57	74	70,020
Recommended	187	119	101	132	133,620

Notes for Figure 17:

- A complete explanation of the Starter Database is in the *DB2 Server for VSE System Administration* manual.
- Fixed block (FB) storage devices store data in blocks of fixed size. These blocks are addressed by block number relative to the beginning of the particular file.

In the installation process, you have to supply your own volume identifier when defining VSAM data sets. Note that the Starter Database is designed to be installed on a single volume of a given device type. Refer to the *DB2 Server for VSE System Administration* manual for more information on adding dbextents.

You can use any DASD currently supported by VSE/VSAM in your VSE system. If you are defining your own database instead of using the Starter Database, refer to the *DB2 Server for VSE System Administration* manual to estimate the space you require for a particular device to support a database of a given size.

You can easily add dbextents or enlarge the directory after the database is generated. A utility program, ARIMEXBD, is available to increase the size of the directory to support a larger VSAM dataset. (See the *DB2 Server for VSE System Administration* manual for information on ARIMEXBD.) Given the dbspace

definitions for the Starter Database, the actual space supported for public and private dbspaces is about 4.6 gigabytes.

2.4 Preparation Step 4: Restore the Distribution Library

This step is mandatory.

You can restore the DB2 Server for VSE Distribution Library in two ways. We recommend using the VSE/Interactive Interface, Product Installation Dialog in VSE/ESA. If you use this method, you need to know that DB2 Server for VSE is shipped on a **NON-STACKED V2 FORMAT** tape. For directions on using this method, refer to the *IBM VSE/ESA Installation* for your VSE operating system.

Alternatively, you may create the job control member shown in Figure 18 to restore the Distribution Library. Mount the distribution tape and run your modified job.

```
// JOB ARIS71AD          INSTALL DB2 Server
// MTC REW, cuu          *-- REWIND TAPE
// ASSGN SYS002, cuu1    *-- AUXILIARY HISTORY FILE
// ASSGN SYS005, UA      *-- NO RESTORE TO XXXXXX
// ASSGN SYS006, cuu    *-- DISTRIBUTION TAPE
// OPTION CATAL
// EXEC MSHP
INSTALL PRODUCT FROMTAPE ID='DB2/VSE....7.1.0' - *--ACTUAL TAPE ID (1)
PROD IN=PRD2.DB2710 *-- IDENTIFICATION OF LIBRARIES (2)
DEFINE HISTORY AUX EXTENT=xxx:yyy
/*
// MTC RUN, cuu
/ &
```

Figure 18. Job ARIS71AD (Using MSHP to Install DB2 Server for VSE)

Notes for Figure 18:

- Before execution, modify the above statements as follows:

cuu Replace with the address of the tape drive.

cuu1 Replace with the address of the disk drive on which the auxiliary history file resides.

xxx Replace with the starting address of the auxiliary history file (in tracks or blocks).

yyy Replace with the size of the auxiliary history file (in tracks or blocks).

- You receive various messages from MSHP. These messages are normal and can be ignored. If you want more details about the MSHP control statements, refer to the *DB2 Server for VSE Messages and Codes* manual.
- Later installation steps do not require the distribution tape.

(1) **DB2/VSE....7.1.0'** is the actual ID of the tape.

(2) If necessary, replace **PRD2.DB2710** with the library and sublibrary names you used in Figure 18.

2.5 Preparation Step 5: Prepare the CICS Environment

If you will **not** be using DB2 Server for VSE in an CICS interactive environment, or if you will **not** be using ISQL, skip this step.

This step is optional for the installation process, but mandatory for the users who are **migrating** from a previous release and **are** using ISQL.

To prepare the CICS system for DB2 Server for VSE, update the CICS control tables and modify the CICS startup job control. The modifications to the tables take effect the next time the CICS system is stopped for maintenance and then restarted. The changes to the startup job control ensure that the CICS system can find the DB2 Server for VSE 7.1 sublibrary, and that the CICS subpool is properly defined. You may also define a printer for ISQL.

You need to update the CICS control tables and startup job control to include journaling and the restart resynchronization facility, to ensure the coordinated rollback of a CICS activity when a DB2 Server for VSE activity is being rolled back. This is a requirement for CICS Database Switching support. Refer to the *DB2 Server for VSE System Administration* manual for detailed information about this support.

Note: You have to allocate and format the journal files before restarting CICS.

Modifying the CICS Start-Up JCL

Figure 19 on page 18 shows an example of CICS startup job control for the application server. Make sure that you add the DB2 Server for VSE sublibrary in your library concatenation chain for your startup job.

```

// JOB CICS START
// LIBDEF PHASE,SEARCH=(PRD2.DB2710,...)
// UPSI 1          (1)
*
*
*
// DLBL SQLBIND,'DB2.BIND.MASTER',,VSAM=catalog,DISP=(OLD,KEEP) (5)
// DLBL SQLGLOB,'DB2.SQLGLOB.MASTER',,VSAM=catalog,DISP=(OLD,KEEP)
// DLBL ARITRAC,'TRACE.FILE1',
// EXTENT ,VOLXXX,1,0,nnn,120 (5) (6)
// ASSGN SYS007,cnn
*
*
*
// ASSGN SYS098,cuu (2)
// EXEC DFHSIP,SIZE=nnnnK *-- DETERMINATION OF THE CICS SUBPOOL SIZE (3)
*
*
*
*
| Optional CICS System      | *
| Initialization Parameter | (4)
| Override Statements      | *
*
*
/*
/ &

```

Figure 19. Starting the CICS System for Use with ISQL

Notes for Figure 19:

- (1) In a VSE/ICCF environment, place the UPSI statement after the EXEC statement (see note 3 below). The UPSI setting shown in the example allows reconfiguration at initialization time and console responses from SYSIPT. You may need to use different UPSI settings for your environment.
- (2) The logical unit SYS098 is used for ISQL report output. For multiple-copy support, assign SYS098 to a VSE/POWER-intercepted printer (**cuu**). ISQL uses the 8-position resource name "PRINT98" to control use of the printer.
- The logical unit SYS098 is also used for the Online Resource Adapter FFDC Dump output.
- (3) The EXEC statement parameter SIZE=**nnnnK** controls the CICS subpool size, which is the amount of dynamic storage remaining after the CICS system assigns storage for management and resident program purposes, and is shared by all CICS transactions. (**nnnn**) specified depends on the CICS configuration.

If the CICS system is being run in a VSE/ICCF environment:

- Replace the EXEC statement shown in Figure 19 with:

```
// EXEC DTSINIT,SIZE=nnnnK
```

- Consider increasing the size of the VSE/ICCF interactive partition for the CICS system to at least 8 megabytes.

If VSE/ICCF is running as a subtask under the CICS/VSE 2.2 or later system, you need to add at least 3 megabytes of virtual storage below the 16MB line reserved for the CICS/VSE partition (SIZE value). Refer to the *IBM VSE/ESA Planning* manual for more information on how to allocate storage for a CICS/VSE system.

- (4) DB2 Server for VSE 7.1 requires the CICS system to support journaling. Set bit 1 of the UPSI to 1 to force the CICS system to read the optional CICS system initialization parameter override statements from SYSIPT. You can then include the journaling parameter in the override statements.
- (5) These are the job control statements for the BIND file, the SQLGLOB file, and the trace output DASD SAM file to the CICS startup JCL. The file IDs specified for SQLBIND and SQLGLOB must be identical to the name of the file that was specified in the respective DEFINE command of IDCAMS and listed in the VSE/VSAM catalog. See "Preparation Step 8: Setup the SQLGLOB and BIND files" for more information on the IDCAMS DEFINE CLUSTER jobs for the SQLGLOB and SQLBIND files. SQLBIND is an optional dataset, it is only required for DRDA application requester functions.

It is recommended that SQLGLOB and SQLBIND DLBL statements be placed in Standard Labels (see Figure 28 on page 30).

- (6) If the output of the application requester trace is directed to tape, a TLBL statement for the trace output file must be included in the CICS start-up job instead. An example of a TLBL statement for a trace output file is as follows:

```
// TLBL ARITRAC,'TRACE.FILE2'
```

2.5.1 CICS Table Entries Required by DB2 Server for VSE 7.1

The following CICS resources must be updated to define the DB2 Server for VSE online support and ISQL to the CICS system. DB2 Server for VSE programs and transactions in the CICS System Definition (CSD) file:

DFHSIT	System Initialization Table
DFHTCT	Terminal Control Tables.
DFHFCT	File Control Table

The entries required for each table are described later in this step.

This manual describes only the CICS resources required for DB2 Server for VSE: it does not attempt to provide a tutorial on CICS installation and table definition. For complete descriptions of the CICS tables and parameters, refer to the *CICS* manuals.

To update the CICS tables, you must make the changes and recompile them. However, you have to wait until the CICS system is stopped and restarted for the changes to take effect. You can change programs

and transactions with a batch job, or online using the Resource Definition Online (RDO) tool. For more information on RDO and CEDA, see the *CICS/VSE Resource Definition (Online)*.

Beside the minimum entries required to use DB2 Server for VSE online support and ISQL, the CICS Journaling Support and the CICS Restart Resynchronization Support must be enabled. These are discussed in "CICS Journaling Support" on page 21 and in "CICS Restart Resynchronization Support" on page 22, respectively. In addition, you may make optional entries that allow you to use:

- CICS Monitoring Facility
- DB2 Server for VSE Accounting.

For a description of the entries required for each optional feature for CICS/ESA, refer to *Appendix F, "Additional CICS and VSE Updates for the DB2 Server System"*.

2.5.2 Entries Required in DFHSIT

The DFHSIT macro must always include:

AMXT=nn Limit on the number of active tasks within the CICS system.

If you are adding DB2 Server for VSE work to an existing CICS environment, consider increasing the AMXT value. Each active ISQL user requires *two* active tasks within the CICS system. (If the AMXT limit is reached, response time may be adversely affected.)

DBP=YES|xx Dynamic transaction backout support.

Specifying DBP=YES requests use of the *default* dynamic transaction backout module. The DBP parameter can be specified as DBP=xx, where "xx" is the 2-character suffix of the module to be used.

EXEC=YES Command-level support.

EXITS=YES User exits will be used.

TST=NO|xx Identifies the auxiliary temporary storage program support.

Temporary storage queues defined to ISQL must be non-recoverable, because recoverable storage queues are incompatible with ISQL. Temporary storage queues with names like CISQXXXX and XXXXCISQ (where XXXX is the terminal ID) are reserved for use by ISQL, and should not be used by other CICS applications.

For information about the optional DFHSIT entries to control access to ISQL, see the *DB2 Server for VSE System Administration* manual.

The DB2 Server for VSE installation process assumes that the application name identified by the DFHSIT APPLID parameter is DBDCCICS. If the application name is not DBDCCICS, take special action (see *"Installation Step 7: Grant SCHEDULE Authority"*).

2.5.2.1 Entries in DFHTCT Required by ISQL:

The DFHTCT TYPE=TERMINAL macro must include:

ALTSCRN=(lines,columns) Alternate screen size

This parameter is optional. Specify it if you want to use ISQL large-screen support for IBM 3270 terminals with screens larger than 24 rows by 80 columns.

DEFSCRN=(24,80) Default screen size

TRMSTAT=TRANSCEIVE Terminal status.

2.5.2.2 Entries in DFHTCT for CICS Local Terminal Printers:

The DFHTCT TYPE=TERMINAL macro should include the ALTPAGE and PGESIZE parameters.

If you specify FORMFEED=YES, the value you use for these two parameters should match the page size of the CICS local terminal printer since the ISQL SET command will no longer have full control over the page size.

If you specify FORMFEED=NO, assign the value (1,132) to the ALTPAGE and PGESIZE parameters. This will allow the ISQL SET command to have full control over the page size.

To use the ISQL terminal printer support, define a DFHTCT entry for each terminal printer.

2.5.2.3 Entries in DFHFCT for DB2 Server for VSE: The entries in sample ARIS71FC, a PROC-type member, should be placed in the File Control Table (FCT) for the CICS system in which online support is required. You can use a COPY statement to include the entries. If you change the suffix on the FCT INITIAL statement, code an FCT=xx override on CICS Initialization JCL.

```

*****
*          DB2 FOR VSE AND VM 7.1  FCT ENTRIES          *
*****
*
* * * * *
*          GLOBAL Variables
* * * * *
*
SQLGLOB DFHFCT TYPE=FILE,          X
ACCMETH=(VSAM,KSDS),              X
FILE=SQLGLOB,                      X
FILSTAT=(ENABLED,OPENED),         X
SERVREQ=(ADD,BROWSE,DELETE,UPDATE), X
RSL=PUBLIC,                        X
STRNO=2
* * * * *
*          Preprocessor BIND file
* * * * *
*
SQLBIND DFHFCT TYPE=FILE,          X
ACCMETH=(VSAM,KSDS),              X
FILE=SQLBIND,                      X
FILSTAT=(ENABLED,OPENED),         X
SERVREQ=BROWSE,                   X
RSL=PUBLIC,                        X
STRNO=2

```

Figure 20. DFHFCT Sample entries

2.5.3 CICS Journaling Support

If the CICS Journaling Support wasn't enabled when the CICS system was installed, you have to update the following CICS tables to provide the Journaling Support required by DB2 Server for VSE.

- DFHJCT** Journal Control Table
- DFHSIT** System Initialization Table.

DFHJCT Entries:

A journal used for the CICS system log must be defined in DFHJCT by specifying JFILEID=SYSTEM in a DFHJCT TYPE=ENTRY macro.

Figure 21 on page 23 shows an example of how to code DFHJCT for a CICS system log allocated to a 3380 DASD device.


```

DFHJCT TYPE=INITIAL,SUFFIX=jj      (1)
DFHJCT TYPE=ENTRY,                X
      JFILEID=SYSTEM,              X
      BUFSIZE=1024,                X
      BUFSUV=1024,                 X
      JOUROPT=(CRUCIAL,INPUT),     X
      JTYPE=DISK1,                  X
      OPEN=INITIAL,                 X
      DEVADDR=sysxxx,               (2) X
      JDEVICE=3380
DFHJCT TYPE=FINAL
END DFHJCTBA

```

Figure 21. DFHJCT Examples for CICS Journaling

Notes for Figure 21:

- CICS journal files must be formatted before use. See the CICS manuals for information on CICS journal files.
- (1) The SUFFIX value **jj** must be supplied in the DFHSIT JCT=**jj** parameter.
- (2) **sysxxx** is the logical unit address for the CICS system log journal (JFILEID=SYSTEM) assigned to a 3380 DASD file.

DFHSIT Entries:

The DFHSIT macro must include the JCT parameter. Specify JCT=YES or JCT=(**jj**<,....>) where **jj** is the SUFFIX parameter value specified in the DFHJCT TYPE=INITIAL macro defining the CICS system log journal data set.

2.5.4 CICS Restart Resynchronization Support

If the CICS Restart Resynchronization Support was not enabled when the CICS system was installed, you have to update the following CICS tables to enable the CICS Restart Resynchronization capability.

- DFHJCT** Journal Control Table
- DFHSIT** System Initialization Table.

DFHJCT Entries:

A journal used for the CICS system log must be defined in the DFHJCT by specifying JFILEID=SYSTEM in a DFHJCT TYPE=ENTRY macro.

Figure 21 is an example of how you could code your DFHJCT for a CICS system log allocated to a 3380 DASD device.

Programs and Transactions: Use the CICS RDO tool to add the resources required for CICS Restart Resynchronization.

CEDA ADD GROUP(DFHRMI) LIST(VSELIST)

Use the list that is coded in the value for GRPLIST in your DFHSIT or CICS startup.

DFHSIT Entries:

The DFHSIT macro must include the JCT parameter. Specify JCT=YES or JCT=(jj<,....>) where **jj** is the SUFFIX parameter value specified in the DFHJCT TYPE=INITIAL macro defining the CICS system log journal data set.

2.5.5 CICS Transaction Server (TS) considerations

CICS internal security and therefore the CICS Sign-On table (DFHSNT) has been withdrawn in CICS TS for VSE/ESA 2.4. Instead, any external security manager (ESM) may be used that conforms to the VSE/ESA RACROUTE interface. Alternatively, the basic form of external security manager VSE/ESA 2.4 may be used. The BSM provides sign-on and transaction attach security only.

When using an ESM, refer to the relevant documentation supplied with the ESM on defining DB2 for VSE user id(s), operator data and transaction security. If the BSM is used, DB2 for VSE userids in the DFHSNT and DB2 for VSE transactions must be defined using the VSE Interactive Interface

As the CICS TS System Definition (CSD) file is not compatible with earlier versions of CICS (e.g. CICS 2.3), a separate CSD file must be defined and all DB2 for VSE entries added using the DFHCSDUP utility provided with CICS TS.

For DB2 for VSE with CICS TS, the following System Initialization (DFHSIT) parameters are obsolete. Refer to the CICS Release Guide below for a complete list of obsolete DFHSIT parameters.

AMXT=
EXEC= (command level is mandatory)
EXITS= (the user-exit interface is always enabled)
MONITOR= (replaced by new monitoring parameters)

For more information on installing DB2 for VSE V7.1 with CICS TS, refer to the following publications:

CICS Release Guide	GC33-1645
CICS Migration Guide	GC33-1646
CICS Resource Definition Guide	SC33-1653

2.6 Preparation Step 6: Define DB2 Server Programs and Transactions to CICS

Job name is ARIS71JD.

This step is mandatory if you will be using ISQL or online CICS transactions.

Start Job Manager - see Figure 76 on page 84.

Parameter Name	Default value	Description
GROUP	DB2710	Name of the group that contains the run time routines and is in the group list used during CICS startup.
CICSFILE	CICS.CSD	The VSAM catalog where CICSFILE resides
CSDCAT	VSESP.USER.CATALOG	The VSAM catalog where CICSFILE resides
TRANSEC	2	The transaction is a security transaction. This transaction is used to maintain the DB2 Server for VSE global variables. Refer to the <i>DB2 Server for VSE System Administration</i> manual.

Figure 22. The parameters for ARIS71JD

Expected return code is 4.

2.7 Preparation Step 7: Setup the SQLGLOB and BIND files

This step is mandatory if you will be using ISQL or online CICS transactions, or developing applications to access remote databases using DRDA.

This step is optional for Migration.

If you have used the default name for your existing DB2 system, then you should use a different dataset name, if you are performing the installation process, and will be running both DB2 for VSE releases.

The SQLGLOB file is used to contain DB2 Server for VSE Global variables. Refer to the *DB2 Server for VSE System Administration* manual for more information.

2.7.1 Defining the Global Variable File (SQLGLOB)

Job ARIS718D will be submitted to the VSE environment, followed by the jobs ARISGDEF, ARIS717D, and ARIS719D.

Parameter Name	Default value	Description
VOLUME	XXXXXX	The volume in the VSAM catalog, where the dataset will be defined
ATYPE1	TRACKS	The default allocation unit is Tracks. Use BLK for FBA devices.
ALLOC1	15	This is the primary space allocation for the VSAM dataset. The size of the dataset is based on the number of CICS users of DB2 for VSE. There will be one record for each user who does not use the system global defaults, and will use his/her own. The default allocation is sufficient for about 6000 users.
ALLOC2	5	This is the secondary space allocation for the VSAM dataset. The allocation unit is in tracks.

Figure 23. The parameters for ARIS718D

See global parameters.

The expected return code is 0. Return code 12 means that MASTERFILE already exists.

2.7.2 Updating the SQLGLOB file with IBM-Supplied Global Defaults

Submit ARISGDEF to update the SQLGLOB file with the IBM-supplied global SQLGLOB default values.

See global parameters.

Expected return code is 0.

2.7.3 Defining the Preprocessor Bind File

ARIS717D is only required if you will be using DRDA CICS Application Requestor support. This dataset is a repository for preprocessor bind package records, that will be bound to remote application servers.

Parameter Name	Default value	Description
BINDCAT	VSESP.USER.CATALOG	The VSAM catalog where BINDFILE resides
VOLUME	XXXXXX	The volume in the VSAM catalog, where the BINDFILE will be defined
ALLOC1	10	This is the primary space allocation for the VSAM dataset. The size of the dataset is based on the number of bind files contained in it, and on the size of the packages. The allocation unit is ATYPE parameter.
ALLOC2	5	This is the secondary space allocation for the VSAM dataset. The size of the dataset is based on the number of bind files contained in it, and on the size of the packages. The allocation unit is ATYPE parameter.

Figure 24. The parameters for ARIS717D

Expected return code is 0. Return code 12 means that BINDFILE already exists.

2.7.4 Defining the Preprocessor Bind Work File (BINDWFILE)

ARIS719D is only required if you will be using DRDA CICS Application Requestor support. This dataset is required by the preprocessor when creating bind packages, that will be bound to remote application servers.

Parameter Name	Default value	Description
BINDWCAT	VSESP.USER.CATALOG	The VSAM catalog where BINDFILE resides
VOLUME	XXXXXX	The volume in the VSAM catalog, where the BINDFILE will be defined
ALLOC1	1	This is the primary space allocation for the VSAM dataset. The size of the dataset is based on the size of the packages. The allocation unit is Cylinders
ALLOC2	1	This is the secondary space allocation for the VSAM dataset. The size of the dataset is based on the size of the packages. The allocation unit is Cylinders

Figure 25. The parameters for ARIS719D

Expected return code is 0. Return code of 12 means that BINDWFILE already exists.

2.7.5 Converting the ISQL Bind File to a VSAM File

ARISIQBD is only required if you will be using DRDA CICS Application Requestor support. The ISQL package is required by ISQL, to be installed on remote application servers. ARISIQBD will store the supplied A-type member ARISIQBD in the Bind file.

Parameter Name	Default value	Description
BINDCAT	VSESP.USER.CATALOG	The VSAM catalog where BINDFILE resides

Figure 26. The parameters for ARISIQBD

Expected return code is 0.

If the ISQL bind file cannot be stored on the VSAM dataset, the following message is displayed on the VSE console:

```
ISQL BIND FILE CANNOT BE BUILT DUE TO ERROR
```

Otherwise, the following message will be displayed:

```
ISQL BIND FILE BUILT SUCCESSFULLY
```

2.8 Preparation Step 8: Define VSAM Data Sets for the Starter Database

Job name is ARIS71CD.

This step is mandatory for installation and optional for Migration.

ARIS71CD is only required if you will be building the starter database. This job contains two steps: create a VSAM user catalog and create the datasets required for the starter database. If you will be creating the database in an existing catalog, then set the NEWUSERCAT parameter to NO and you may omit the (*) entries.

You should initially install the Starter Database, because it helps you to ensure that DB2 Server for VSE is installed correctly. If you are migrating from a previous release of DB2 (or SQL/DS), allocate a new area for the Starter Database. When you are ready to generate your own database, refer to the *DB2 Server for VSE System Administration* manual.

Figure 27 (Page 1 of 2). The parameters for ARIS71CD

Parameter Name	Default value	Description
----------------	---------------	-------------

<i>Figure 27 (Page 2 of 2). The parameters for ARIS71CD</i>		
DBCAT	SQLCAT	This is the name of the user catalog which will hold the starter database
NEWUSERCAT	YES	Submit job control to create the new user catalog
SPACE (*)	1	This is the minimum DASD space required for the new user catalog. Space unit allocation defined using parameter ATYPE - see Figure 15 on page 12
VOLUME1 (*)	XXXXXX	The volume in the new VSAM catalog.
SPACE1 (*)	117	This is the minimum DASD space required for the starter database Space unit allocation defined using parameter ATYPE - see Figure 15 on page 12
DIRFILE	SQL.BDISK.STARTER.DB	Directory extent
SPACE2	34	Size for the database directory extent Space unit allocation defined using parameter ATYPE - see Figure 15 on page 12
VOLUME2	XXXXXX	The volume on which directory extent resides
LOGFILE	SQL.LOGDSK1.STARTER.DB	Log extent
SPACE3	08	Size for the log extent Space unit allocation defined using parameter ATYPE - see Figure 15 on page 12
VOLUME3	XXXXXX	The volume on which log extent resides
EXTFILE	SQL.DDSK1.STARTER.DB	Data extent
SPACE4	72	Size for the data extent Space unit allocation defined using parameter ATYPE - see Figure 15 on page 12
VOLUME4	DB2DSK	The volume on which data extent resides

Expected return code is 0.

Note:

- We recommend that you use a VSAM user catalog for the Starter Database.
- The allocations used in this job are defined for 3390 DASD. If you use other DASD, refer to Figure 17 on page 15.
- Read "*Appendix A: What should you keep in mind*".

2.9 Updating Labels for the new datasets

Job name is ARISSTD.L.

This step is optional.

The job will add the labels for the new datasets to the standard label area.

It is recommended that the labels for the new datasets (SQLGLOB, SQLBIND, and BINDWKF) be added to the system standard labels at system initialization. Please refer to the "VSE/ESA System Control Statements" and the "VSE Guide to System Functions" for more information.

Parameter Name	Default value	Description
BINDCAT	VSESP.USER.CATALOG	The VSAM catalog where BINDFILE resides
BINDWCAT	VSESP.USER.CATALOG	The VSAM catalog where BINDWFILE resides

Figure 28. The parameters for ARISSTD.L

Also see global parameters.

Note: The DLBL for BINDWKF must not have the DISP parameter coded.

Expected return code is 0.

3.0 Chapter 3. Installing DB2 Server for VSE

To install this product:

1. Read "Appendix A: How to Use the Job Manager".
2. Refer to Appendix B, "Techniques Used for Installation" for a description of how to adapt the IBM-supplied materials to your local needs.
3. Complete the steps in Chapter 2, "Preparing to Install DB2 Server for VSE 7.1"
4. Perform all the mandatory steps in this chapter, and any of the optional ones that apply to your installation (See Figure 29).

Note: If you are migrating from a previous release of DB2 Server for VSE, you may only need to perform "Installation Step 2". The other steps in this chapter are optional.

Attention: If any procedure within any of the steps in this chapter fails to execute successfully, fix the problem and rerun the step again before continuing.

Step	Optional/ Mandatory	Automated/ Manual	Description
1	Mandatory	Manual/ Automated	Set up DBNAME Directory
2	Optional	Automated	Link-Edit the DB2 Server for VSE online Support Components
3	Mandatory	Automated	Generate the Starter Database
4	Optional	Automated	Install Optional Database Components
5	Mandatory	Automated	Reload CCSID-Related Phases Package
6	Optional	Automated	Selecting National Language Support
7	Optional	Automated	Grant Schedule Authority
8	Mandatory	Automated	Start the Application Server in Multiple User Mode
9	Mandatory	Automated	Create CCSID-Related Phases
10	Optional	Automated	Run the Sample Programs to verify Installation
11	Optional	Manual	Run ISQL to Verify Installation
12	Optional	Manual	Stop the Application Server
13	Optional	Manual	Add New Users to the Database
14	Optional	Manual	Change the Database Administrator Password
15	Optional	Manual	System Customization Activities

Figure 29. Steps to Install DB2 Server for VSE Version 7 Release 1

Parameter Name	Default value	Description	Used in member:
PROC1	ARIS71DB	DB2 Server DATABASE ID Proc	ARIS71WD
COMPILELIB	PRD2.DB2710	Library for cataloging PHASE type members	ARISCNVD, ARIS6ASD, ARIS6C2, ARIS6CD, ARIS6PLD, ARIS6FTD
WDISK	SYSWK1	Sequential workdisk volume	ARISCNVD, ARIS6ASD, ARIS6C2, ARIS6CD, ARIS6PLD, ARIS6FTD
START	xxxx	Start track or block allocated for SYSPUNCH and SYSIPT.	ARISCNVD, ARIS6ASD, ARIS6C2, ARIS6CD, ARIS6PLD, ARIS6FTD
FOR	xxxx	Extent size in tracks or blocks allocated for SYSPUNCH and SYSIPT.	ARISCNVD, ARIS6ASD, ARIS6C2, ARIS6CD, ARIS6PLD, ARIS6FTD
GLOBFILE	DB2.SQLGLOB.MASTER	This is the name of the dataset which will hold the global variables	ARIS6ASD, ARIS6CD, ARIS6PLD, ARIS6FTD
CATALOG	VSESP.USER.CATALOG	The VSAM catalog where SQLGLOB resides	ARIS6ASD, ARIS6CD, ARIS6PLD, ARIS6FTD
LELIB	PRD2.SCEEBASE	Language Environment library	ARIS6C2D, ARIS6CD, ARIS6PLD

Figure 30. Description of global parameters

3.1 Installation Step 1: Setup the DBNAME Directory

Job name is ARISBDID.

This step is mandatory.

1. Punch the A-type source member ARISDIRD.
2. Update the DBNAME and other parameters. See *DB2 Server for VSE System Administration* manual "Chapter 2: Setting Up the DBNAME Directory" for information about the input file format and syntax.
3. Re-catalog the A-type source member ARISDIRD.

Start Job Manager - see Figure 76 on page 84.

Job ARISBDID (see Figure 31 on page 33) converts A-type source member ARISDIRD into an assembler source file, which will be assembled and link-edited into the Ddbname Directory Phase (ARICDIRD.PHASE).

```

// SETPARM ISMIGR=%%MIGRATION%%
// IF ISMIGR='NO' THEN
// GOTO GENERATE
// EXEC REXX=ARICCDID, PARM='%%PLIB%%.%%INPUT%% %%LIB1%%.%%OUTPUTA%%'
/. GENERATE
// LIBDEF *,SEARCH=%%LIB1%%
// LIBDEF PHASE,CATALOG=%%COMPILELIB%%          *-- UPDATE LIBRARY
// EXEC REXX=ARICBDID,PARM='%%LIB1%%.%%OUTPUTB%%' (1)
// IF $RC < 4 THEN
// GOTO EXITOK
/. ERREXIT
* SQL/DS DBNAME DIRECTORY CANNOT BE BUILT DUE TO ERROR
// GOTO SQLDONE
/. EXITOK
* SQL/DS DBNAME DIRECTORY BUILT SUCCESSFULLY
/. SQLDONE

```

Figure 31. Job ARISBDID (Setup DBNAME directory)

Notes for Figure 31:

- (1) %%LIB1%%.%%OUTPUTB%% is the input Dbname Directory source member. The default parameter is: 'PRD2.DB2710.ARISDIRD.A' - see Figure 32.

Parameter Name	Default value	Description
MIGRATION	NO	Should be 'NO' for Installation process
OUTPUTB	ARISDIRD.A	Member containing defaults for DBNAME
LIB1	PRD2.DB2710	Installation Library

Figure 32. The parameters for ARISBDID

ARICDIRD.PHASE creates with a return code of 0.

3.2 Installation Step 2: Link-Edit the DB2 Server for VSE Online Support Components

Job name is ARIS71BD.

This step is optional.

If you will not be using DB2 Server for VSE online support in a CICS interactive environment, skip this step.

Job control member ARIS71BD is used to link-edit the online support components. The link-edit will include the CICS interface modules DFHEAI and DFHEAI0, found in the CICS PRD1.BASE sublibrary.

The output is cataloged to the installation library by default. If you want to use your own libraries, change the parameter value.

If you do not want ISQL support, and only want support for your own CICS online applications, then set the ARIS140D, ARIS150D, and ARIS160D parameters to *.

Parameter Name	Default value	Description
CICSLIB	PRD1.BASE	This is the name of the sublibrary where CICS components are installed. ¹
ARIS140D	//	Default parameter to include ISQL support. Enter * to omit this job.
ARIS150D	//	Default parameter to include ISQL support. Enter * to omit this job.
ARIS160D	//	Default parameter to include ISQL support. Enter * to omit this job.

Figure 33. The parameters for ARIS71BD

Note: (1) The library search path is:

```
// LIBDEF *,SEARCH=(%%LIBNAME%%,%%CICSLIB%%,PRD2.CONFIG)
where LIBNAME is the installation library name. See Figure 77 on page 85.
```

Expected return code is 0.

3.3 Installation Step 3: Generate the Starter Database

Job name is ARIS71DD.

This step is mandatory for the installation process, but optional for the migration process.

Member ARIS71DD, shown in Figure 34 on page 35, is used to generate the Starter Database. The job ends with an SQL return code of 0 if it was successful. A return code of 6 is also acceptable from the ARISDBSD procedure executed by procedures ARIS050D and ARIS055D. The return code for the job is displayed in the SYSLST output. Verify that the job is completed successfully before continuing.

Job ARIS71DD does the following:

1. Starts the application server from the "cold start" (STARTUP=C) condition. It then generates the Starter Database.
2. Uses the assembler preprocessor to create the DBS utility package.
3. Uses the DBS utility to finish generating the database.
4. Uses the DBS utility to load sample tables and routines.

When the application server is cold-started, it reads the statements that specify how the database is to be generated from SYSIPT. Details of the syntax and sequence required for these statements are in the *DB2 Server for VSE System Administration* manual.

There are no non-global parameters for ARIS71DD.

```
// JOB ARIS71DD          DATABASE DBGEN AND SET UP
// LIBDEF PROC,SEARCH=(%%LIBNAME%%)
// DLBL VSEUCAT,'%%CATALOG%%',,VSAM
// DLBL SQLGLOB,'%%GLOBFILE%%',0,VSAM,CAT=VSEUCAT,DISP=(OLD,KEEP)
// EXEC PROC=ARIS71SL   *-- DB2 SERVICE/PRODUCTION LIBRARY ID PROC
// EXEC PROC=ARIS71DB   *-- DB2 DATABASE ID PROC           (1)
// EXEC PROC=ARIS030D   *-- GENERATE THE STARTER DATABASE   (2)
// EXEC PROC=ARIS040D   *-- PREPARE THE DBS UTILITY         (3)
// IF $RC>4 THEN
// GOTO EXITERR
// EXEC PROC=ARIS050D   *-- FINISH DATABASE SET UP         (4)
// EXEC PROC=ARIS055D   *-- LOAD SAMPLE TABLES AND ROUTINES (5)
// GOTO EXITOK
/. EXITERR
* UNACCEPTABLE ERROR OCCURRED.
* PLEASE INVESTIGATE.
  CANCEL
/. EXITOK
/&
```

Figure 34. Job ARIS71DD (Generating a Database)

Expected return code is 6.

Notes:

1. Procedure ARIS71DB contains the job control statements that identify the database files, log, directory, and database extents. For more information about ARIS71DB, refer to *"Embedding Database Identification Statements"* on page 87 Section 7.1.
2. Procedure ARIS030D generates the Starter Database by reading A-type source member ARISDBG for the database in Figure 35 on page 37. These statements determine the configuration and maximum size of the database being generated. By changing this source member, you can generate a custom database. Respond with *"DBGEN"* to DB2 Server for VSE message ARI0919D.
3. Procedure ARIS040D uses the DB2 Server for VSE Assembler preprocessor (program ARIPRPA) to create the DB2 Server for VSE DBS utility package. Program ARIPRPA is completed successfully with a return code of 4. This program requires the SYS001 workfile referred to in *"Preparation Step 2: Set Up the VSE Environment"*. Do **not** change procedure ARIS040D or the A-type source member it reads (ARIDSQLP).
4. Procedure ARIS050D uses the DBS utility to execute SQL commands that finish generating the database. A return code of 6 from this procedure is acceptable and may be ignored. Do **not** change procedure ARIS050D or the A-type source member it reads (ARISDBU). ARISDBU performs the following:
 - Grants RUN authority to PUBLIC for the DBS utility package SQLDBA.ARIDSQLP.

- Loads tables for CCSID support.
 - Acquires three public dbspaces: HELPTEXT, ISQL, and SAMPLE.
 - Creates the SQLDBA.SYSLANGUAGE table in the dbspace named PUBLIC.SYS0001. The command also creates indexes SQLDBA.SYSLANGINDEX and SQLDBA.SYSLANGIDINDEX.
 - Creates HELP Text tables SQLDBA.SYSTEXT1 and SQLDBA.SYSTEXT2 in the dbspace named PUBLIC."HELPTEXT". SQLDBA.SYSTEXT2INDEX.
 - Creates the ISQL sample routine table EXAMPLE.ROUTINE, and an index for it named EXAMPLE.RINDEX.
 - Creates view SQLDBA.SYSUSERLIST in catalog SYSTEM.SYSUSERAUTH, and grants SELECT authority to PUBLIC on the view.
 - Grants SELECT authority to PUBLIC for all DB2 Server for VSE catalog tables except the SYSTEM.SYSUSERAUTH catalog, and database CONNECT authority to all users (ALLUSERS).
 - Reloads the preprocessor package for DBCS support.
5. Procedure ARIS055D reads A-type source members ARISAMDB and ARISAMPI, which contain commands that creates sample tables SQLDBA.DEPARTMENT, SQLDBA.EMPLOYEE, SQLDBA.ACTIVITY, SQLDBA.PROJECT, SQLDBA.EMP_ACT, and SQLDBA.PROJ_ACT.

A return code of 6 from this procedure is acceptable and may be ignored.

```

CUREXTNT=1
MAXPOOLS=256
MAXEXTNT=256
MAXDBSPC=10240
END
1 1
END
PUBLIC 12800 1
PUBLIC 2048 1
PUBLIC 8192 1
PUBLIC 1024 1
PUBLIC 512 1
PUBLIC 1024 1
PUBLIC 1024 1
PUBLIC 1024 1
PUBLIC 5120 1
PUBLIC 256 1
PUBLIC 256 1
PUBLIC 128 1
PUBLIC 128 1
PUBLIC 128 1
PUBLIC 128 1
PUBLIC 128 1
PUBLIC 128 1
PRIVATE 128 1
PRIVATE 128 1
PRIVATE 128 1
PRIVATE 128 1
PRIVATE 128 1
INTERNAL 80 1024 1
END

```

Figure 35. A-type source member ARISDBG

Note: It is important to understand the VALUES specified in ARISDBG. These can have an impact in a production Database. For details about the syntax of these control statements, refer to the *DB2 Server for VSE System Administration* manual.

3.4 Installation Step 4: Install Optional Database Components

Job name is ARIS71ED.

This step is optional.

We recommend that you install **all** these optional database components, even if you do not plan to use them now. Job ARIS71ED contains the job control statements to load the optional components of a database into a Starter Database. You may omit specific optional components by removing the procedures in job ARIS71ED that create that component.

If you do not want ISQL support, then set the ARIS110D, ARIS120D, ARIS130D parameters to *.

Parameter Name	Default value	Description
ARIS110D	//	Install ISQL
ARIS120D	//	Install ISQL
ARIS130D	//	Install ISQL

Figure 36. The parameters for ARIS71ED

Expected return code is 0.

Note:

- The ARIS71ED job runs the application server in single user mode. Ensure that it runs in the DB2 Server for VSE partition as described in "Preparation Step 3: Set Up the VSE Environment".
- Procedure ARIS080D installs the DB2 Server for VSE online support, which you need to run ISQL or any of your own interactive applications.
- "Installation Step 3: Generate the Starter Database" procedure ARIS050D granted CONNECT authority to ALLUSERS. This allows the DB2 Server for VSE online support to implicitly connect users. See the *DB2 Server for VSE & VM Database Administration* manual for more information on implicit CONNECT.
- Procedure ARIS360D loads the FIPS flagger into the database. For more information on the FIPS flagger, see the *DB2 Server for VSE & VM Application Programming* manual.

3.5 Installation Step 5: Reload CCSID-Related Phases Package

Job name is ARIS71WD.

This step is mandatory.

Job control member ARIS71WD, contains the job control statements to load the CCSID-related phases package into the database. Procedure ARIS175D reloads the CCSID-related phases package in the database by running the application server in single user mode against that database.

There are no non-global parameters for ARIS71WD job.

Expected return code is 4.

3.6 Installation Step 6: Selecting National Language Support

Job name is ARIS71HZ.

This step is optional.

This step will install a national language for DB2 Server for VSE, and optionally load the ISQL Help Text for that language. The following steps will be performed:

- Enlarge Help Text Dbspace.
- "Install" Language.
- Verify Installation.

Parameter Name	Default value	Description
PAGES	8192	Number of pages acquired for the HELPTEXT DBSpace. Default value 8192 is enough to define 2 languages.

Figure 37. The parameters for ARIS71HZ

Expected return code is 0.

3.6.1 Install Language and Help Text

The ARIS71JZ Z-type member calls the ARIS380D PROC-type member that was modified according to the parameters specified in ARISIVAR file when you started the Installation Step (Chapter 3). If you have modified the parameters used in ARIS380D (Figure 39 on page 40) in ARISIVAR file after executing Installation Step 1, you might need to update ARIS380D file manually before submitting ARIS71JZ.

This is only necessary if the Help Text Dbspace is not large enough to hold the addition of this language. As supplied, DB2 Server for VSE has 8192 pages assigned for the PUBLIC.HELPTEXT dbspace. This is sufficient for the Help Text for 3 languages.

Language List:

Language	Short Name
Mixed English	AME
Uppercase English	UCE
French	FRE
German	GER
Japanese	KAN
Chinese	HAN

Parameter Name	Default value	Description
LANGUAGE	AME	Short form of the language name, taken from the language list.
HELP	NO	If you want only the ISQL help text to be loaded, change value to HELP=ONLY. To install a National language in addition to the Help Text, set HELP=YES. If you do not want Help Text to be loaded keep current value.
CUU	181	Tape drive address.
DEFAULTL	NO	If you want this language to be the default language, set DEFAULTL parameter to YES. Otherwise, set the value to NO.

Figure 38. The parameters for ARIS71JZ

Parameter Name	Default value	Description
NLSLIB	PRD2.DB271 (For AME) Note: There is no '0' at the end of PRD2.DB271.	Language Library. Note: The name of NLSLIB must not exceed 5 characters, since NLS suffix is 3 characters - making library name 8 characters. The NLS suffix will be added during the execution of the program. The suffix is generated by procedure ARIS385D. For LANG=AME library will be PRD2.DB2710 For LANG=FRE library will be PRD2.DB271S03,etc.
CLIB	PRD2.DB2710	The Installation Library

Figure 39. The parameters for ARIS380D

Note: Read "Appendix A: What should you keep in mind."

ARIS71JZ job will perform the following functions:

- Define a sublibrary for the language components
- Linkedit the message repository
- Update SQLDBA.SYSLANGUAGE with language key and language id
- Linkedit language specific parts
- Change the default language if requested
- Load Help text if requested.

Expected return code is 0.

3.7 Installation Step 7: Grant SCHEDULE Authority

Job name is ARIS71FD.

This step is optional.

If the CICS application name specified in the SIT table is DBDCCICS (APPLID=DBDCCICS) and you are using the default password (SQLDBAPW), skip this step.

In "Installation Step 4: Install Optional Database Components", procedure ARIS080D granted SCHEDULE authority to user ID DBDCCICS and assigned it the password SQLDBAPW. DBDCCICS is the default CICS application name (APPLID).

However, if in "Entries Required in DFHSIT", you specified a different CICS application name in the SIT (APPLID=**name**), this **name** should be granted SCHEDULE authority instead. To do this, run job control member ARIS71FD, shown in Figure 40.

The password (**namepw**) specified in the GRANT SCHEDULE command must also be specified in the CIRB and CIRT transactions used to start and stop the DB2 Server for VSE online support.

See "Starting the DB2 Server for VSE Online Support" on page 43 and "Stopping the DB2 Server for VSE Online Support" on page 46. For details on the CICS APPLID, refer to the *CICS* manuals.

Parameter Name	Default value	Description
NAME	DBDCCICS	CICS application name (APPLID=name)
NAMEPW	SQLDBAPW	Password

Figure 40. The parameters for ARIS71FD

Expected return code is 0.

3.8 Installation Step 8: Start the Application Server in Multiple User Mode

Job name is ARIS71GD.

This step is mandatory for the installation process, but optional for the migration process.

Parameter Name	Default value	Description
DBNAME	SQLDS	SQLDS is the RESID of the database to connect to the DBNAME parameter of the database server.

Figure 41. The parameters for ARIS71GD and ARIS71GZ

You should verify the installation by performing this step through "Installation Step 12: Stop the Application Server".

To use the application server in multiple user mode, start it in a partition like a batch job. You can then run applications in other partitions that use DB2 Server for VSE, or you can start CICS transactions that access DB2 Server for VSE.

Note: DB2 Server for VSE has many initialization parameters that it uses to initialize and configure its partition. These parameters are described in detail in the *DB2 Server for VSE System Administration* manual, along with examples of how you can create lists of such parameters and reference them. Ways of using and overriding cataloged procedures for starting the application server are also described in that manual.

IBM-supplied job control member ARIS71GD starts the application server in multiple user mode. Further information on day-to-day operation of DB2 Server for VSE is in the *DB2 Server for VSE & VM Operation* manual. The VSE partition configuration required for DB2 Server for VSE multiple user mode operation is described in "Preparation Step 2: Set Up the VSE Environment".

Note: When DB2 Server started successfully, you will see the following message on the console:

ENTER A PARTITION NUMBER TO START THE OTHER JOBS :

Please, enter any available partition class.

3.9 Installation Step 9: Create CCSID-Related Phases

Job name is ARISCNVD.

This step is mandatory and must be executed while the database server is active.

Parameter Name	Default value	Description
PARMS	SQLDBA/SQLDBAPW/SQLDS	SQLDBA is user id with DBA authority, SQLDBAPW is the connect password, SQLDS is the RESID of the database to connect to the DBNAME parameter of the database server.

Figure 42. The parameters for ARISCNVD

Note: See global parameters for installation.

Expected return code is 0.

3.10 Installation Step 10: Run the Sample Programs to Verify Installation

This step is optional.

You should run the sample application programs to verify that you correctly installed the DB2 Server for VSE system and the Starter Database.

For each language supported by an DB2 Server for VSE preprocessor program application program is supplied that shows how SQL commands can be coded in the preprocessor programs. These sample programs all access and manipulate the DB2 Server for VSE sample tables in a similar manner. Refer to the manual for listings of the sample programs.

IBM also supplies the following DB2 Server for VSE Z-type source members with the job control statements to run the sample programs.

ARIS6ASD preprocesses, assembles, link-edits, and runs the assembler.

See global parameters.

Expected return code is 0.

ARIS6C2D preprocesses, assembles, link-edits, and runs COBOL.

Parameter Name	Default value	Description
COBLIB	CMPLR22.COBVSE	Default library for Cobol compiler

Figure 43. The parameters for ARIS6C2D

See global parameters.

Expected return code is 0.

ARIS6CD preprocesses, assembles, link-edits, and runs C (DO NOT run this job if C is not installed on your system)

Parameter Name	Default value	Description
C-LIB	CMPLR22.CVSE	Default library for C compiler

Figure 44. The parameters for ARIS6CD

See global parameters.

Expected return code is 2.

ARIS6FTD preprocesses, assembles, link-edits, and runs FORTRAN (DO NOT run this job if FORTRAN is not installed on your system)

Parameter Name	Default value	Description
FRTLIB	COMPILE.COMPILE	Default library for Fortran Compiler

Figure 45. The parameters for ARIS6FTD

See global parameters.

Expected return code is 4.

ARIS6PLD preprocesses, assembles, link-edits, and runs PL/I (DO NOT run this job if PL/I is not installed on your system)

Parameter Name	Default value	Description
PLDLIB	COMPILE.COMPILE	Default library for PL/I Compiler

Figure 46. The parameters for ARIS6PLD

See global parameters.

Expected return code is 4.

3.11 Installation Step 11: Run ISQL to Verify Installation

3.11.1 Starting the CICS System

The CICS system needs to be running before you can start DB2 Server for VSE online support. While you do not have to restart the CICS system exclusively for DB2 Server for VSE, you must update both the CICS startup job control and the CICS control tables before you can use DB2 Server for VSE with the CICS system. See "Preparation Step 6" and "Preparation Step 7".

3.11.1.1 Starting the DB2 Server for VSE Online Support:

You can use the CICS CIRB transaction with all its internal default parameters, to start the DB2 Server for VSE online support. The CIRB transaction accepts six positional parameters having the following default values:

password Defaults to SQLDBAPW. This is the password for the CICS APPLID discussed under "Installation Step 7: Grant SCHEDULE Authority".

number of links (NOLINKS) defaults to 3.

default user ID (DEFUID) defaults to CICSUSER.

resource adapter ID (RMID) defaults to 0.

language ID (LANGID) specifies the language that is link-edited and the search order. The default is American English (AMENG).

SERVER-NAME (SERVER-NAME) defaults to SQLDS (or to the system default application server if you have performed "Installation Step 1: Set Up the DBNAME Directory").

Entering CIRB is thus the same as entering:

```
CIRB SQLDBAPW,3,CICSUSER,0,AMENG,SQLDS
```

Refer to the *DB2 Server for VSE System Administration* manual for details about the parameters that can be passed in a CIRB transaction. (That discussion includes a description of how the user IDs DBDCCICS and CICSUSER relate to the DB2 Server for VSE online support.)

If the CIRB transaction fails to run successfully, ensure that:

- The required CICS table updates have been made.
- The CICS system has been restarted **after** the required table updates were made, or RDO was used to update the required tables
- The DFHSIT application name (APPLID) has been granted SCHEDULE authority in the database. (See "Installation Step 7: Grant SCHEDULE Authority".)
- The DB2 Server for VSE sublibrary has been concatenated to the appropriate search chains in the partition in which the CICS system or ICCF runs.
- The application server has been started in multiple user mode.
- All prerequisite service required by DB2 Server for VSE has been applied.
- The CICS restart resynchronization support has been enabled.

3.11.2 Starting ISQL

ISQL runs as a CICS transaction, and is invoked just like any other transaction. Details of the sign-on and exit procedures are in the DB2 Server for VSE & VM Interactive SQL Guide and Reference.

After the CICS terminal has been activated and the DB2 Server for VSE online support has been started, start ISQL by typing:

```
ISQL
```

The system responds with the ISQL sign-on screen, and prompts you to enter your user ID, password and optionally a target database name.

All further actions are handled conversationally between the CICS user and ISQL.

If you cannot log on to ISQL, ensure that:

- The CICS resources were successfully updated during "Preparation Step 6" and Preparation Step 7".
- There is enough CICS dynamic storage for ISQL (900 kilobytes).
- ISQL was installed successfully during "Installation Step 4: Install Optional Database Components".
 - DB2 Server for VSE online support has been started with links to the specified (or default) database.
 - All links managed by DB2 Server for VSE online support have not been used up.
 - All prerequisite service required by DB2 Server for VSE has been applied.

3.11.3 Verify the Installation

If you are signed on to ISQL, you can use it to verify that DB2 Server for VSE is correctly installed and that the Starter Database is successfully installed

To test the Starter Database, execute the following example SQL SELECT command through ISQL:

```
SELECT CREATOR,TNAME FROM SYSTEM.SYSACCESS WHERE CREATOR='SQLDBA'
```

The information displayed is selected from the DB2 Server for VSE catalog table SYSTEM.SYSACCESS. options that were installed.

Figure 47 on page 47 shows the possible rows that may be displayed.


```
CREATOR TNAME
-----
SQLDBA SYSUSERLIST --- SYSTEM.SYSUSERAUTH view
SQLDBA ARIDSQL     --- The DBS utility package
SQLDBA ARIISQL     --- The ISQL package
SQLDBA VPHONE      --- View for sample tables
SQLDBA VEMPLP      --- View for sample tables
SQLDBA ARIFCRD     --- FIPS Flagger package
SQLDBA ARIPDBS     --- DBCS support package
```

Figure 47. Installation Verification Display

To print the display results, enter the ISQL display command:

```
PRINT
```

The successful execution of the PRINT command verifies that SYS098 has been assigned to a VSE/POWER-intercepted printer, or to a real printer. (Refer to "Modifying the CICS Start-Up JCL".)

3.11.4 Stopping ISQL

To end the display and terminate the ISQL session:

Type the ISQL display command:

```
END
```

Type the ISQL session termination command:

```
EXIT
```

3.12 Installation Step 12: Stop the Application Server

3.12.1 Stopping the DB2 Server for VSE Online Support

You can use the CICS CIRT transaction with all its internal default parameters, to stop the DB2 Server for VSE online support. The CIRT transaction accepts three positional parameters, which have the following default values:

password Defaults to SQLDBAPW. This must be the same password as the one specified (or the default) in the CIRB transaction.

mode Defaults to NORMAL. Options are NORMAL or QUICK.

interval Defaults to 30 (seconds). This is a decimal value between 0 and 3600 (seconds).

Entering CIRT is thus the same as entering:

```
CIRT SQLDBAPW,NORMAL,30
```

Refer to the *DB2 Server for VSE System Administration* manual for details about the parameters that can be passed in a CIRT transaction.

3.12.2 Stopping the CICS System

The CICS system need not be stopped when the application server is being shut down; it can continue to process transactions that do not access DB2 Server for VSE. If the CICS system must be stopped, that action can be taken in its normal way; DB2 Server for VSE does not restrict CICS shutdown.

3.12.3 Stopping the Application Server

To stop the application server:

1. Signal the DB2 Server for VSE operator communications routine using the VSE Attention Routine command **MSG Fx** (where **x** is the partition in which the application server is running).
2. In response to message ARI0062A, enter the SQL command **y SQLEND** (where **y** is the reply-id of the partition in which the application server is running).

```
MSG F4
AR 015 1I40I  READY
*F4-004 ARI0062A  SQLDS :
                ENTER AN SQL OPERATOR COMMAND
4 SQLEND
F4 004 ARI0028I DB2 Server IS TERMINATING
F4 004 ARI0065I DB2 Server OPERATOR COMMAND PROCESSING COMPLETE
F4 004 ARI0032I DB2 Server HAS TERMINATED
F4 004 ARI0043I DB2 Server RETURN CODE IS 0
F4 004 EOJ STARTSQL MAX.RETURN CODE=0000
```

Figure 48. Stopping the Application Server

Operator entries are in **BOLD** type.

For more information on the SQLEND command, see the *DB2 Server for VSE System Administration* manual.

3.13 Post-Installation Activities

3.14 Installation Step 13: Add New Users to the Database

This step is optional.

User IDs are usually added to the database after it is installed by executing SQL GRANT commands through ISQL or the DBS utility. The job shown in

Figure 49 on page 49 uses the DBS utility to add a new user ID with DBA authority to the database.

```
// JOB ADD USERIDS
// LIBDEF PROC,SEARCH=(PRD2,DB2710)
// EXEC PROC=ARIS71PL   *-- DB2 Server PRODUCTION LIBRARY ID PROC
// EXEC PGM=ARIDBS,SIZE=AUTO   *-- USE THE DBS UTILITY
CONNECT SQLDBA IDENTIFIED BY SQLDBAPW;
GRANT DBA TO newdba IDENTIFIED BY newdbapw; (1)
/*
/ &
```

Figure 49. Adding New User IDs to the Database

Notes for Figure 49:

- You can supply more than one GRANT statement in the DBS utility SYSIPT input.
 - Refer to the *DB2 Server for VSE & VM SQL Reference* for a complete description of the GRANT command.
 - The application server must be running in multiple user mode in another partition when you run this job. Refer to "Installation Step 9: Start the Application Server in Multiple User Mode" for instructions on how to do this.
- (1) At this time in the installation process, you may want to add a new user ID with DBA authority to the database (as shown above). This new user ID would be responsible for database administration. Replace **newdba** with a new DBA ID and replace **newdbapw** with a new password.

3.15 Installation Step 14: Change the Database Administrator Password

This step is optional for the installation and migration process, but highly recommended.

The user ID SQLDBA is the default user ID under which all DB2 Server for VSE installation jobs are run. It has the default password SQLDBAPW assigned to it. Since it has DBA authority, its use must be carefully controlled. After finishing the DB2 Server for VSE installation and running the sample programs, change this password to one of your own choosing, by entering a GRANT command through either ISQL or the DBS utility.

Figure 50 on page 50 shows a DBS utility job to change the password. The user SQLDBA still has DBA authority, but its password is changed to **newpw**.

```

// JOB ARIS71VD      CHANGE SQLDBA PASSWORD
// LIBDEF PROC,SEARCH=(PRD2.DB2710)
// EXEC PROC=ARIS71PL  *-- DB2 Server PRODUCTION LIBRARY ID PROC
// EXEC PGM=ARIDBS,SIZE=AUTO  *-- USE THE DBS UTILITY
CONNECT SQLDBA IDENTIFIED BY SQLDBAPW;
GRANT CONNECT TO SQLDBA IDENTIFIED BY newpw;  (1)
/*
/ &

```

Figure 50. Job ARIS71VD (Example of Changing the SQLDBA Password in the Database)

Notes for Figure 50:

- **Do not delete user ID SQLDBA from the system.** It was used for the creation of the packages (through PREP) for important programs (such as the DBS utility, the online resource adapter, and ISQL); and if service is applied to any of these programs, the IBM-supplied procedures assume that this user ID with password SQLDBAPW is in the database. Before any of these program packages can be recreated, the password must be changed back to SQLDBAPW.
- The application server must be running in multiple user mode in another partition when you run this job. Refer to *"Installation Step 9: Start the Application Server in Multiple User Mode"*.

(1) Replace **newpw** with a new password.

3.16 Installation Step 15: System Customization Activities

This step lists further administration and customization activities you should consider at this time. These are:

- Install and activate the DRDA Application Server code, and customize the database for distributed processing.
- Install and activate the DRDA Application Requestor code.
- Change the setting of the CHARNAME parameter for the database and initialize the user partition since the default after installation is INTERNATIONAL. The CCSID defaults for the application server are determined when a CHARNAME is chosen.
- Set database options, such as double-byte character set (DBCS) support and character subtype.
- Install additional application servers.
- Set up Stored Procedures.

Refer to the *DB2 Server for VSE System Administration* manual for information to help you define procedures for operating DB2 Server for VSE and for the information you need to perform the activities listed above.

3.16.1 VSE Guest Sharing

This section discusses how to complete the installation of DB2 Server for VSE to enable VSE Guest Sharing. It does not attempt to explain Guest Sharing in detail. For more information on Guest Sharing, refer to the *DB2 Server for VSE System Administration* manual. You can also refer to the IBM VSE/ESA Planning manual.

The term "Guest Sharing" is used because the VSE system is a "guest" of the VM/ESA system and it "shares" the data with the host's application server.

The VSE Guest Sharing installation process requires you to install the complete DB2 Server for VSE product as a guest of a VM/ESA system.

3.16.2 VSE Guest Machine Parameters

The number of links between the VSE guest machine and the VM database is limited by the MAXCONN parameter in the VSE guest machine directory entry. If this parameter is not specified, the default is 16.

Each VSE guest machine partition that uses the VSE guest sharing facility must have an ALLOC R allocation. This allocation must be 40 kilobytes for each DB2 Server for VSE communication link.

SETPFIX LIMIT=40K must also be coded in the JCL.

Online users can access another application server on the VM/ESA systems by supplying a different database name on the SERVER-NAME parameter of the CIRB transaction.

The dbname directory must be coded to include the name of the VM Database. The APPLID field would be coded with the resid of the VM database, the DBNAME parameter. The DBNAME field of the dbname directory should be coded with the server name you would connect to. For example:

```
*****
*TPN
*  |      APPLID
*  |      |
*  |      |      SYSDEFAULT * = system default
*  |      |      |      DBNAME
*  |      |      |      |
*  |      |      |      |      PDEFAULT
*  |      |      |      |      |
*  |      |      |      |      |      PRIVLEGE
*  |      |      |      |      |      |
*  |      |      |      |      |      |      SYSID
*  |      |      |      |      |      |      |
*  |      |      |      |      |      |      |      REMTPN
*  |      |      |      |      |      |      |      |
*  |      |      |      |      |      |      |      |      |
*2..._7.....4_.7.....4_67_9_1..4_6.....
   "6DB SQLMACH   VM_DB
```

Figure 51. DBNAME directory 6.1 format

In an application use

```
CONNECT uid IDENTIFIED BY upass TO VM_DB
```

In CICS, to activate the online resource adapter for the VM database, use

```
CIRB ,,,, VM_DB
```

For information on how VSE batch/ICCF applications access different application servers, refer to the *DB2 Server for VSE System Administration* manual.

4.0 Chapter 4. Migrating an Existing Database

DB2 Server for VSE 7.1.0 supports migration from SQL/DS 3.1.0 and later.

To migrate an existing database to Version 7 Release 1:

1. Read *"Appendix A: How to Use the Job Manager"*.
2. If an earlier release was loaded into the shared virtual area (SVA), remove those earlier phases from the SVA before running the migration Refer to *"DB2 Server for VSE Link Books"* for a list of the phases that are eligible for the SVA.
3. Complete steps in:
 - Chapter 2, Preparing to Install DB2 Server for VSE 7.1:
 - "Preparation Step 2: Set up the VSE Environment"
 - "Preparation Step 3: Allocate DASD for the Distribution Library"
 - "Preparation Step 5: Restore the DB2 Server for VSE Distribution library.
 - "Preparation Step 8: Setup the SQLGLOB and BIND files"
 - Chapter 3, Installing DB2 Server for VSE:
 - "Installation Step 2: Link-Edit the DB2 Server for VSE 7.1 Online Support Components"
4. For each pre-Version 7 Release 1 database, perform all the mandatory steps in this chapter, and all the optional steps that apply to your database. See Figure 52

Note: All of the steps in this chapter run in single user mode.

Attention: In any procedure within any of the steps in this chapter fails to execute successfully, fix the problem and rerun the entire step again before continuing.

<i>Figure 52 (Page 1 of 2). Steps to Migrate an Existing Database to Version 7 Release 1</i>				
Step	Optional	Vs 3.5 & up	Vs 3.4	Description
1	Optional	Manual	Manual	Space Verification and DATE/TIME Option Verification
2	Mandatory	Manual	Manual	Archiving a Database
3	Mandatory	Automated	Manual	Prepare the Database for Migration
4	Mandatory	Automated	Manual	Migrate the DBNAME Directory
5	Mandatory	Automated	Automated	Format the DB2 Server for VSE logs
6	Mandatory	Automated	Automated	Update the DB2 Server for VSE Catalog to the 7.1
7	Mandatory	Automated	Automated	Reload the DBS Utility Package
8	Mandatory	Automated	Automated	Update the DB2 Server for VSE Database
9	Mandatory	Automated	Automated	Migrate the HELP Text Tables

Figure 52 (Page 2 of 2). Steps to Migrate an Existing Database to Version 7 Release 1

10	Optional	Automated	Automated	Reload English Help Text into a Database
11	Optional	Automated	Automated	Reload ISQL into a Database
12	Mandatory	Automated	Automated	Reload CCSID-Related Phases Package
13	Optional	Automated	Automated	Load FIPS Flagger into a Database
14	Optional ¹	Automated	Automated	Determine the Primary Keys to be Recreated
15	Optional	Automated	Automated	Revoke connect Authority from ALLUSERS
16	Mandatory	Automated	Automated	Reset the Password for User SQLDBA
17	Mandatory	Automated	Automated	Start Application Server in multiple user mode
18	Mandatory	Automated	Automated	Create CCSID-Related Phases
19	Mandatory	Manual	Manual	System Customization Activities

Note 1: If you are migrating a database from SQL/DS Vs 3.1 or Vs 3.2, you should run this step

Parameter Name	Default value	Description	Used in member:
PROC1	ARIS61DB	This is the procedure which contains disk labels for the existing database.	All

Figure 53. Description of Global Parameters.

Every Migration Step runs job ARIS71SL and parameters for this job are:

Parameter Name	Default value	Description
CLIB	PRD2.DB2710	Library where you want to catalog any member

Figure 54. Job ARIS71SL (DB2 Server Library Definitions)

4.1 Migration Step 1: Space Verification and DATE/TIME Option Verification

This step is mandatory.

4.1.1 Directory Space

This step is mandatory.

Before you can migrate you should have at least 4 dbspace blocks available in the DB2 Server for VSE directory.

To verify this, start the application server and enter the operator command:


```
SHOW DBCONFIG
```

If the number of "DBSPACE BLOCKS LEFT" is:

Four or more, proceed to "Storage Pool Space" below.

- Less than four, increase the number of available dbspace blocks by reducing the number of internal dbspaces. Refer to the *DB2 Server for VSE System Administration* manual for instructions on adding dbspaces to a database.

If you are migrating, you can also increase the number of available dbspace blocks, by expanding your directory. Refer to the *DB2 Server for VSE System Administration* manual for instructions on how to do this.

Then reissue the SHOW DBCONFIG command, and make sure you have enough dbspace blocks available.

For more information on the SHOW DBCONFIG command, refer to the *DB2 Server for VSE & VM Operation* manual.

4.1.2 Storage Pool Space

Before you migrate, we recommend that each storage pool in your database be less than 90% used and each pool must have at least 30 free pages. To determine the state of your storage pools, start the application server in multiple user mode and enter the operator command:

```
SHOW POOL SUMMARY
```

For more information on the SHOW POOL command, refer to the *DB2 Server for VSE & VM Operation* manual.

If you find a pool above 90% used, you should add one or more dbextents to it. If this is inconvenient, you can avoid the problem until you have completed migration by specifying an SOSLEVEL other than the default when you run job ARIS71PD. Job ARIS71PD is discussed in "Migration Step 6: Update the DB2 Server for VSE Catalog to the 7.1 Level". Refer to the *DB2 Server for VSE System Administration* manual for instructions on adding dbextents.

4.1.3 DATE/TIME Options

Check the values associated with DATE and TIME in SYSTEM.SYSOPTIONS by issuing the following command from ISQL:

```
SELECT * FROM SYSTEM.SYSOPTIONS
```

If VALUE is set to LOCAL and the local date/time exits do not recognize ISO format, VALUE should be set to ISO for the duration of the migration. When you use date/time exits that do not recognize ISO format, SQLCODE -180 is issued when reloading the English Help text. SQLCODE -180 may also occur in later stages of the migration.

4.2 Migration Step 2: Archiving a Database

This step is mandatory.

Archive your database by typing:

```
SQLEND ARCHIVE
```

For more information on the SQLEND command, refer to the *DB2 Server for VSE & VM Operation* manual.

4.3 Migration Step 3: Prepare the Database for Migration

Job name is ARIS71ND.

This step is mandatory.

Before submitting ARISIMGJ to start the Job Manager, you **must**:

- Recatalog the procedure with existing Database identification labels (default value for 6.1 is ARIS61DB) into the Installation library (default value is PRD2.DB2710) - See Figure 77 on page 85.

This procedure is used in all migration jobs - see Figure 53 on page 54.

- Recatalog the procedure which includes library search path for an existing database (default value is ARIS61SL) into the Installation library (default value is PRD2.DB2710) - See Figure 77 on page 85.

This procedure is used in ARIS71ND Z-type member - see Figure 55 on page 57.

- If you plan to reload non-English version of HELP Text into a database, you must manually modify and recatalog ARIS062D PROC-type member. See "Migration Step 10: Reload English HELP Text into a Database."

Start Job Manager - see Figure 76 on page 84.

The ARIS71ND job is shown in Figure 55 on page 57. This job will:

- Reset the logmode to Y.
- Reset the password for SQLDBA to SQLDBAPW, for all remaining steps in this chapter assume that SQLDBA's password is SQLDBAPW.

The parameters for ARIS71ND are:

Parameter Name	Default value	Description
PROC2	ARIS61SL	Library search path for the existing database.
DUALLOG	Y	The DUALLOG parameter defines the number of DB2 Server for VSE logs used (two for dual logs). Change this parameter to N if you require only one log.
OLDPW	SQLDBAPW	Supply current password for SQLDBA.

Figure 55. Job ARIS71ND (Prepare the Database for Migration)

Expected return code is 0.

If you are migrating from releases prior to Version 3.5 you must update ARIS71ND manually to alter the SHAREOPTIONS of the DB2 Server for VSE VSAM Clusters to '4'. See Figure 56

```
* Step 3 - ALTER DB2 Server for VSAM Clusters SHAREOPTIONS
// EXEC PGM=IDCAMS,SIZE=AUTO
  ALTER SQL.BDISK.STARTER.DB.DATA -
    SHAREOPTIONS(4) -
    CATALOG(SQLCAT)
  ALTER SQL.LOGDSK1.STARTER.DB.DATA -
    SHAREOPTIONS(4) -
    CATALOG(SQLCAT)
  ALTER SQL.DDSK1.STARTER.DB.DATA -
    SHAREOPTIONS(4) -
    CATALOG(SQLCAT)
```

Figure 56. Alter DB2 Server VSAM Clusters Shareoptions

Please change SQLCAT to the usercatalog where your dataset was defined.

4.4 Migration Step 4: Migrate the DBNAME Directory

Job name ARISBDID.

This step is mandatory.

ARISBDID (See Figure 31 on page 33) executes VSE/REXX exec ARICCDID, which migrates previous versions (R350, R510 & R610) of the Dbname Directory source file (originally 'ARISDIRD.A') to the new R710 restructured Directory source format.

The output from this Procedure can then be used as input to the new ARICBDID Procedure to create the Dbname Directory Phase (ARICDIRD.PHASE).

Parameter Name	Default value	Description
MIGRATION	YES	This is a migration process
INPUT	mem_name.type	This is the old version Directory Source member to be migrated.
OUTPUTA	mem_name.type	This is the new DBNAME member name Note: There is NO default for either member name.
OUTPUTB	ARISDIRD.A	Member containing defaults for DBNAME
LIB1	PRD2.DB2710	Installation Library, where OUTPUTA will be stored
PLIB	PRD2.DB2xxx	Existing library for old version of DBNAME
COMPILELIB	PRD2.DB2710	Library where PHASE type members cataloged

Figure 57. The parameters for ARISBDID

Expected return code is 0.

4.5 Migration Step 5: Format the DB2 Server for VSE Logs

Job name is ARIS71OD.

This step is mandatory.

To migrate an existing database to Version 7 Release 1, format the DB2 Server for VSE logs.

Parameter Name	Default value	Description
DUALLOG	Y	The DUALLOG parameter defines the number of DB2 Server for VSE logs used (two for dual logs). Change this parameter to N if you re

Figure 58. The parameters for ARIS71OD

It is very important that you run ARIS71OD. Otherwise, you may have problems later when you restore database archives.

If you receive warning message AR12010, you can ignore this message and continue to the next step.

Refer to *DB2 Server for VSE System Administration* manual for installation on logging.

Expected return code is 0.

4.6 Migration Step 6: Update the DB2 Server for VSE Catalog to the 7.1 Level

Job name is ARIS71PD.

This step is mandatory if you are migrating a database from

Vs 5.1 or prior to Vs 5.1. Do **not** execute this step if you are migrating a database from Vs 6.1.

ARIS71PD updates the system catalog.

Parameter Name	Default value	Description
LOGMOD	Y	Specifying a LOGMODE of N has the benefit of avoiding logging. However, not that checkpoints are not triggered for a storage pool full condition with this LOGMODE, so this value should only be used when your storage pools contain a sufficient number of free pages to shadow the work done by migration A LOGMODE of Y or A can be specified so that checkpoints will be triggered during migration, thus releasing shadow pages back to the storage pool for reuse and avoiding the occurrence of a storage pool full condition.
SOSLEVEL	{empty}	If storage pool is more than 90% full, specify an SOSLEVEL according to the percentages of free pages in the storage pools. You must ensure that the SOSLEVEL you choose is lower than or equal to the percentage free in the pool with the least space. For example, if storage pool 1 is 93% used and storage pool 2 is 91% used, a SOSLEVEL of 7 or lower allows a checkpoint to be triggered no matter which storage pool reaches the checkpoint first.

Figure 59. The parameters for ARIS71PD

Note: To determine if any storage pool is over 90% issue the SHOW DBEXTENT prior to migration.

ATTENTION: If any storage pool is above 95% full, it is strongly recommended that one or more dbextents be added rather than specifying a smaller SOSLEVEL. Just specifying a lower SOSLEVEL cannot eliminate the possibility of having a storage pool full condition from occurring, especially when storage pools are approaching 100% full.

Expected return code is 0.

4.7 Migration Step 7: Reload the DBS Utility Package

Job name is ARIS71QD.

This step is mandatory.

Create the DB2 Server for VSE Version 7 Release 1 of the DBS utility package in the database by executing ARIS71QD job.

A return code of 4 is acceptable from procedure ARIS040D and can be ignored. Procedure ARIS040D executes ARISQLDS which in turn runs the application server in single user mode. It creates the package SQLDBA.ARIDSQL in the database.

Accepted return code is 8, **if** it results from SQL 'DROP' statement. Otherwise return code should be 4.

4.8 Migration Step 8: Update the DB2 Server for VSE Database

Job name is ARIS71RD.

This step is mandatory.

The ARIS71RD job does the following:

- Grants SELECT authority for the system catalog to PUBLIC.
- Grants CONNECT authority to ALLUSERS. You can revoke this authority later by performing "Migration Step 15: Revoke CONNECT Authority from ALLUSERS".
- Updates SYSTEM.SYSOPTIONS, ensuring that a row exists in SYSTEM.SYSOPTIONS for each option. If no row exists for a specific option, a new row is inserted, and the default value is used. If a row does exist, the values for that row are not modified.

For every row that exists, you receive a -803 SQLCODE. You can ignore these messages.

While running this job, you may receive informational messages indicating that options are not set up correctly in SYSTEM.SYSOPTIONS. ARIS070D sets up the correct system options, and these messages should no longer occur after it has successfully completed. Refer to the *DB2 Server for VSE & VM SQL Reference* for a description of the valid SYSOPTIONS entries.

- Loads tables for CCSID support.
- Runs the UPDATE STATISTICS command for the SYS0001 dbspace.
- Builds the following sample tables:
 - DEPARTMENT
 - EMPLOYEE
 - PROJECT

- ACTIVITY
- EMP_ACT
- PROJ_ACT
- INVENTORY
- SUPPLIERS
- QUOTATIONS
- PROJECTS
- OPERATION.

Prepare and execute the ARIS71RD job to update the database. A return code of 6 from procedures ARIS070D and ARIS075D is acceptable and can be ignored.

Note:

- Procedure ARIS075D runs three DBS utility jobs. The first one drops the VIEWS SQLDBA.VEMPLP and SQLDBA.VPHONE, the SYNONYMS SQLDBA.INV and SQLDBA.QUO, and all the sample tables if they already exist in the database. The second and third jobs create and load all the sample tables.

You can verify the migrated database by running the supplied sample application programs that use the sample tables. For more information, refer to "Installation Step 10: Run the Sample Programs to Verify Installation".

Expected return code is 6.

4.9 Migration Step 9: Migrate the HELP Text Tables

Job name is ARIS71SD.

This step is mandatory.

ARIS71SD migrates existing HELP Text tables from a previous SQL/DS version to DB2 Server for VSE Version 7 Release 1. It also drops the SQLDBA.SYSLANGUAGE table, and recreates it in the PUBLIC.SYS0001 dbspace. Any entries in SQLDBA.SYSLANGUAGE are lost; when it is recreated, it contains only an entry for mixed case American English.

A DBS utility return code of 6 or lower is acceptable.

This step removes any existing IBM-supplied HELP Text from the database. Any user-supplied HELP Text remains, but you have to restore the appropriate HELP Text language key in order to use it. Refer to the *DB2 Server for VSE System Administration* manual for information.

Acceptable return code is 6.

4.10 Migration Step 10: Reload English HELP Text into a Database

Job name is ARIS71TD.

This step is optional.

If you do not want to load the DB2 Server for VSE HELP Text, skip this step.

You can reload the default version (American English) of the Version 7 Release 1 HELP Text into a database by running the ARIS71TD job.

For the parameters required see "Installation Step 6: Selecting National Language Support, Install Language".

Acceptable return code is 6.

4.10.1 Install Language

Job name is ARIS71JZ.

See "Installation Step 5 - Install Language".

4.11 Migration Step 11: Reload ISQL into a Database

Job name is ARIS71LZ.

This step is optional.

If the database does not contain the ISQL facility, skip this step.

You can Reload ISQL by running ARIS71LZ job.

All steps should end with a return code of 0 through 4.

Note:

- Procedure ARIS120D reloads the ISQL package in the database by running the application server in single user mode against that database.

Expected return code is 0.

4.12 Migration Step 12: Reload CCSID-Related Phases Package

Job name is ARIS71WD.

This step is mandatory.

ARIS71WD contains the job control statements to load the CCSID-related phases package into the database.

Note:

- Procedure ARIS175D reloads the CCSID-related phases package in the database by running the application server in single user mode against that database.

Acceptable return code is 4.

4.13 Migration Step 13: Load FIPS Flagger into a Database

Job name is ARIS71KZ.

This step is optional.

Note:

- Procedure ARIS360D loads the FIPS flagger package in the database by running the application server in single user mode against that database

Acceptable return code is 4.

4.14 Migration Step 14: Determine the Primary Keys to be Recreated

Job name is ARIS711D.

This step is optional.

If you are migrating a database from SQL/DS Version 3 Release 1 or Version 3 Release 2, you should run this step.

This step uses job ARIS711D to list all the primary keys created in SQL/DS Version 3 Release 1 and Version 3 Release 2 which should be dropped and recreated after migrating to Version 7 Release 1. Dropping and recreating these primary keys ensures that the correct CCSID is used for these keys.

DB2 Server for VSE 7.1.0 supports a column CCSID attribute. For primary keys created in earlier SQL/DS Version 3 releases, the value of the CCSID attribute in SYSTEM.SYSKEYCOLS is null. In versions Version 3 Release 4 and later, this null CCSID value is assumed to be the database default for SBCS data. If the column on which the primary key is defined has been defined as FOR MIXED DATA (that is,

the subtype is "M"), the CCSID assumed for the primary key will be incorrect. By dropping and recreating the primary key, the actual nonnull CCSID value is placed in SYSTEM.SYSKEYCOLS and no CCSID value must be assumed. Note that the CCSID value in SYSTEM.SYSKEYCOLS is only used by the system when the primary key column has a field procedure defined on it.

Note:

- Procedure ARIS370D runs two DBS utility jobs. The first job issues a CONNECT command, and the second job lists the primary keys which should be dropped and recreated. The output of the job goes to SYSLST, so be sure your permanent assignments are set as needed.
- Procedure ARIS370D invokes the ARISFKPY macro, which performs the query. The output from the query is a list of all primary keys which satisfy the following criteria:
 - The key is a primary key.
 - A field procedure is defined on the key.
 - The subtype of the column on which the key is defined is "M" (FOR MIXED DATA).
- This list is in order by the creator of the key and then the table on which the key is created. To ensure the correct CCSID is used, drop and recreate the primary keys using the ALTER TABLE statement.

Expected return code is 0.

4.15 Migration Step 15: Revoke CONNECT Authority from ALLUSERS

Job name is ARIS71MZ.

This step is optional.

In "Migration Step 8: Update the DB2 Server for VSE Database", member ARISCTM granted CONNECT authority to ALLUSERS, which allows the DB2 Server for VSE online support to implicitly connect users. (See the *DB2 Server for VSE & VM Database Administration* manual for more information on implicit CONNECT.) To revoke CONNECT authority from ALLUSERS, prepare and execute the job ARIS71MZ.

Note:

- Procedure ARISDBSD runs the application server in single user mode against the identified database.

Acceptable return code is 0.

4.16 Migration Step 16: Reset the Password for User SQLDBA

Job name is ARIS71NZ.

This step is mandatory.

Parameter Name	Default value	Description
NEWPW	NEWPW	The new password for user SQLDBA.

Figure 60. The parameters for ARIS71NZ

Note:

- Procedure ARISDBSD runs the application server in single user mode against the identified database.

Expected return code is 0.

4.17 Migration Step 17: Start the Application Server in multiple user mode

Job name is ARIS71GZ.

This step is mandatory.

See "Installation Step 8: Start the Application Server in Multiple User Mode" for more information.

Expected return code is 0.

4.18 Migration Step 18: Create CCSID-Related Phases

Job name is ARISCNVD.

This step is mandatory and must be executed while the database server is active (See "Migration Step 17: Start the Application Server in multiple user mode").

For ARISCNVD parameters see Installation step 9.

Expected return code is 0.

4.19 Migration Step 19: System Customization Activities

This step lists further administration and customization activities you should consider at this time. These are:

- Rebind your application program packages using the REBIND PACKAGE DBS utility command. If you do not do this, all your application programs will be dynamically preprocessed again at runtime. Dynamic bind preprocessing is only done once. Refer to the *DB2 Server for VSE & VM Database Services Utility* manual for more information.
- Change the setting of the CHARNAME parameter for the database and initialize the user partition since the default after migration is ENGLISH. The CCSID defaults for the application server are determined when a CHARNAME is chosen.
- Set database CCSID support for user tables that existed prior to migration.
- Set database options, such as double-byte character set (DBCS) support and character subtype.
- Drop and recreate any EXPLAIN tables that were created in a previous release. You can use the A-type source member ARISEXP to help you do this.

Users of local date/time exits should reset the values for DATE and TIME in SYSTEM.SYSOPTIONS to LOCAL if they were changed in "Migration Step 1: Space Verification and DATE/TIME Option Verification".

- Set up Stored Procedures to define PSERVERS and cataloging procedures.

Refer to the *DB2 Server for VSE System Administration* manual for information to help you define procedures for operating DB2 Server for VSE and for the information you need to perform the activities listed above.

5.0 Chapter 5. Maintenance Activities

DB2 Server for VSE maintenance includes adding new components (because they were not installed initially) and replacing existing ones (because of service updates). Both types of activities are discussed below. The actions described in this chapter require that DB2 Server for VSE has been installed and that a database has been generated.

The IBM-supplied procedures and source members for installing DB2 Server for VSE components assume that the user ID is SQLDBA, and that the password is SQLDBAPW. If the password has been changed, it should be reassigned before the reinstallation activity. The technique for changing the password is shown when needed in each description below.

Note:

The processing described in this chapter invokes the application server in single user mode with LOGMODE=Y. If the database was last accessed with LOGMODE=A (DB2 Server for VSE archiving on), do an archive and a COLDLOG for the database before proceeding.

5.1 DBS Utility Maintenance

5.1.1 Reloading the DBS Utility Package (SQLDBA.ARIDSQL)

The DBS utility package must be reloaded in all databases if there is a service update to the A-type source member ARIDSQLP. To reload it, prepare and run the job control statements shown in Figure 61.

Refer to the information supplied with each DB2 Server for VSE service update to see if you should take this action.

```
// JOB RELOAD DBS UTILITY
// LIBDEF PROC,SEARCH=(PRD2.DB2710)
// EXEC PROC=ARIS71SL   *-- DB2 Server LIBRARY DEFINITION   (1)
// EXEC PROC=ARIS71DB   *-- CURRENT DATABASE IDENTIFICATION (2)
// EXEC PROC=ARISDBSD   *-- RUN DB2 Server IN SINGLE USER MODE (3)
CONNECT SQLDBA IDENTIFIED BY currentpw;
GRANT CONNECT TO SQLDBA IDENTIFIED BY SQLDBAPW;
/*
// EXEC PROC=ARIS040D   *-- CREATE DBS UTILITY PACKAGE      (4)
// EXEC PROC=ARISDBSD   *-- RUN DB2 Server IN SINGLE USER MODE (5)
CONNECT SQLDBA IDENTIFIED BY SQLDBAPW;
GRANT CONNECT TO SQLDBA IDENTIFIED BY newpw;
/*
/&
```

Figure 61. Reloading the DBS Utility Package

Notes for Figure 61:

- Procedures ARISDBSD and ARIS040D run the application server in single user mode against the identified database.
- (1) Procedure ARIS71SL identifies the DB2 Server for VSE sublibraries.
 - (2) Procedure ARIS71DB identifies the starter database. You can substitute the procedures or job control statements that identify the database being updated.
 - (3) Reset the password for the user ID SQLDBA to SQLDBAPW before executing procedure ARIS040D. The first execution of procedure ARISDBSD changes the password for the user SQLDBA to SQLDBAPW. Supply the current password **currentpw** in the SQL CONNECT command.
 - (4) Procedure ARIS040D creates the package SQLDBA.ARIDSQL in the database from the DB2 Server for VSE A-type source member ARIDSQL P. The user ID SQLDBA must execute this step.

If the database view SQLDBA.SYSUSERLIST exists when you run this step, the step ends with a return code of 0. If this view does not exist, this step ends with a return code of 4.
 - (5) After procedure ARIS040D is executed, you should reset the password for the user SQLDBA to a password of your choice. The second execution of the procedure ARISDBSD changes the password for the user **SQLDBA**. Supply the password of your choice (**newpw**) in the SQL GRANT command.

5.2 Messages and HELP Text Maintenance

5.2.1 Installing the HELP Text after DB2 Server for VSE Installation

If you have already generated a database without the American English HELP Text, you can add it later. To install or reinstall the HELP Text into an existing database, prepare and run the job control statements shown below.

```
// JOB REINSTALL HELP TEXT
// LIBDEF PROC,SEARCH=(PRD2.DB2710)
// EXEC PROC=ARIS71SL    *-- DB2 Server LIBRARY DEFINITION      (1)
// EXEC PROC=ARIS71DB    *-- STARTER DATABASE IDENTIFICATION    (2)
// EXEC PROC=ARISDBSD    *-- RUN DB2 Server IN SINGLE USER MODE (3)
CONNECT SQLDBA IDENTIFIED BY currentpw;
GRANT CONNECT TO SQLDBA IDENTIFIED BY SQLDBAPW;
/*
// EXEC PROC=ARIS059D    *-- ACTIVATE MESSAGES                  (4)
// EXEC PROC=ARIS380D,LANG=AME,HELP=ONLY,CUU=                  (5) (6)
// EXEC PROC=ARISDBSD    *-- RUN DB2 Server IN SINGLE USER MODE (7)
CONNECT SQLDBA IDENTIFIED BY SQLDBAPW;
GRANT CONNECT TO SQLDBA IDENTIFIED BY newpw;
/*
/&
```

Figure 62. Reinstalling the HELP Text into the Database

Notes for Figure 62:

- Procedures ARISDBSD, ARIS059D, and ARIS060D run the application server in single user mode against the identified database.
- (1) Procedure ARIS71SL identifies the DB2 Server for VSE sublibraries.
 - (2) Procedure ARIS71DB identifies the starter database. You can substitute the procedure or job control statements that identify the database being updated.
 - (3) Reset the password for the user SQLDBA to SQLDBAPW before executing procedures ARIS059D and ARIS060D. The first execution of procedure ARISDBSD changes the password for the user SQLDBA to SQLDBAPW. Supply the current password (**currentpw**) in the SQL CONNECT command.
 - (4) Procedure ARIS059D adds a language entry to the SQLDBA.SYSLANGUAGE table. This step must be executed. A return code of 6 is acceptable and can be ignored.
 - (5) Procedure ARIS380D reloads the DB2 Server for VSE ISQL HELP Text into the database. This step must be executed by the user SQLDBA. The source members it reads assume that the password is SQLDBAPW.

The DB2 Server for VSE HELP Text tables SQLDBA.SYSTEXT1, SQLDBA.SYSTEXT2, and SQLDBA.SYSLANGUAGE must exist in the database when you run this procedure.
 - (6) Mount the Help Text tape from the Distribution Material. Code the CUU= with the value of the tape drive address.
 - (7) After procedure ARIS380D is executed, you should reset the password for the user SQLDBA to a password of your choice. The second execution of procedure ARISDBSD changes the password for the user SQLDBA. Supply the password of your choice (**newpw**) in the SQL GRANT command.

5.2.2 Removing Messages and HELP Text from Your DB2 Server for VSE System

To remove the messages and/or the HELP Text after the initial installation, prepare and run the job control statements shown Figure 63 on page 70

Attention:

- Procedure ARIS062D deletes all ISQL HELP next for a specified language, including topics provided by the database administrator.
- Procedure ARIS063D deletes all ISQL HELP Text for ALL languages, including topics provided by the database administrator.

```

// JOB REMOVE HELP TEXT
// LIBDEF PROC,SEARCH=(PRD2.DB2710)
// EXEC PROC=ARIS71SL *-- DB2 Server LIBRARY DEFINITION (1)
// EXEC PROC=ARIS71DB *-- STARTER DATABASE IDENTIFICATION (2)
// EXEC PROC=ARISDBSD *-- RUN DB2 Server IN SINGLE USER MODE (3)
CONNECT SQLDBA IDENTIFIED BY currentpw;
GRANT CONNECT TO SQLDBA IDENTIFIED BY SQLDBAPW;
/*
* Use one or the other of the next two statements, but not both.
* See notes 4 and 5 for a brief description.
// EXEC PROC=ARIS062D *-- REMOVE MESSAGES AND/OR HELP TEXT (4)
// EXEC PROC=ARIS063D *-- DELETE ALL HELP TEXT (5)
// EXEC PROC=ARISDBSD *-- RUN DB2 Server IN SINGLE USER MODE (6)
CONNECT SQLDBA IDENTIFIED BY SQLDBAPW;
GRANT CONNECT TO SQLDBA IDENTIFIED BY newpw;
/*
/&

```

Figure 63. Removing ISQL HELP Text and Messages from the Database

Notes for Figure 63:

- Procedures ARISDBSD, ARIS062D, and ARIS063D run the application server in single user mode against the identified database.

- (1) Procedure ARIS71SL identifies the DB2 Server for VSE service and production libraries.
- (2) Procedure ARIS71DB identifies the starter database. You can substitute the procedure or job control statements that identify the database being updated.
- (3) Reset the password for the user SQLDBA to SQLDBAPW before executing procedure ARIS062D or ARIS063D. The first execution of procedure ARISDBSD changes the password for the user SQLDBA to SQLDBAPW. Supply the current password (**currentpw**) in the SQL CONNECT command.
- (4) Procedure ARIS062D removes the DB2 Server for VSE messages and/or ISQL Help Text from the database. This step must be executed by the user SQLDBA. The source members it reads assume that the password for user ID SQLDBA is SQLDBAPW.

Change ARIS062D before running it to specify which languages you want to delete, and whether the messages are to be deleted too, or just the HELP Text.

Note: The messages for one language **must** remain.

The DB2 Server for VSE HELP Text tables SQLDBA.SYSTEXT1, SQLDBA.SYSTEXT2, and SQLDBA.SYSLANGUAGE must exist in the database when you run this procedure.

- (5) ARIS063D deletes **all** the HELP Text for **all** languages.
- (6) After procedure ARIS062D (or ARIS063D) is executed, you should reset the password for the user SQLDBA to a password of your choice. The second execution of procedure ARISDBSD changes the password for the user SQLDBA. Supply the password of your choice (**newpw**) in the SQL GRANT command.

5.3 Online Resource Adapter Control Maintenance

5.3.1 Installing Online Resource Adapter Control after DB2 Server for VSE Installation

If you have already generated a database without online resource adapter control, you can add it later as follows:

1. Link-edit the online support as described below.
2. Run procedure ARIS080D to grant CONNECT authority to PUBLIC and SCHEDULE authority to the CICS system.
3. Review "Installation Step 6: Grant SCHEDULE Authority" to determine if procedure ARIS080D granted SCHEDULE authority to the correct user ID.

The procedures for installing these tables are found in "Preparation Step 5: Prepare the CICS System for DB2 Server for VSE".

5.3.2 Re-Link-Editing Online Resource Adapter Control

If you must re-link-edit online resource adapter control after the initial installation of DB2 Server for VSE, prepare and run the job control statements shown in Figure 64

Refer to the information supplied with each DB2 Server for VSE service update to see if you should take this action.

```
// JOB RELINK ONLINE RESOURCE ADAPTER CONTROL
// LIBDEF *,SEARCH=(PRD2.DB2710,PRD1.BASE,PRD2.CONFIG),          X
//          CATALOG=PRD2.DB2710                                (1)
// EXEC PROC=ARIS090D    *-- LINK-EDIT ONLINE RESOURCE ADAPTER CONTROL (2)
/*
/ &
```

Figure 64. Re-Link-Editing Online Resource Adapter Control

Notes:

- This job specifies the standard CICS libraries in the LIBDEF search path. If required, modify the job to search your own CICS libraries.
- (1) This job requires that you specify the DB2 Server for VSE sublibrary into which the linkage editor output is cataloged; in this job, the output is cataloged in the PRD2.DB2710 sublibrary. Specify your own if it has a different name. If you have installed a National Language, then specify the sublibrary into which the language was installed in the LIBDEF SEARCH chain (before PRD2.DB2710), and also as the value for the LIBDEF CATALOG parameter.

- (2) Procedure ARIS090D link-edits the DB2 Server for VSE online resource adapter control into the DB2 Server for VSE sublibrary. It must not be changed. This link-edit job will include the CICS interface modules DFHEAI and DFHEAI0 found in the CICS PRD1.BASE sublibrary, or your own CICS libraries.

Restart the CICS system after the link-edit is successfully completed. For information, refer to CICSTUP">"Preparation Step 5: Prepare the CICS System for DB2 Server for VSE".

5.4 ISQL Maintenance

5.4.1 Installing ISQL after DB2 Server for VSE Installation

If you have already generated a database without ISQL, you can add it later as follows:

1. Reload the ISQL package (SQLDBA.ARIISQL).
2. Re-link-edit ISQL.
3. Re-link-edit the ISQL ITRM terminal transaction.
4. Re-link-edit the ISQL ITRX terminal extension.

Instructions for each of these tasks follow immediately.

5.4.2 Reloading the ISQL Package (SQLDBA.ARIISQL)

If you reload the ISQL package SQLDBA.ARIISQL after the initial DB2 Server for VSE installation, prepare and execute the job control statements shown in Figure 65. The package must be reloaded in all applicable databases if there is a service update to A-type source member ARIISQLM.

Refer to the information supplied with each DB2 Server for VSE service update to see if you should take this action.

```
// JOB RELOAD ISQL
// LIBDEF PROC,SEARCH=(PRD2.DB2710)
// EXEC PROC=ARIS71SL    *-- DB2 Server LIBRARY DEFINITION    (1)
// EXEC PROC=ARIS71DB    *-- STARTER DATABASE IDENTIFICATION  (2)
// EXEC PROC=ARISDBSD    *-- RUN DB2 Server IN SINGLE USER MODE (3)
CONNECT SQLDBA IDENTIFIED BY currentpw;
GRANT CONNECT TO SQLDBA IDENTIFIED BY SQLDBAPW;
/*
// EXEC PROC=ARIS120D    *-- RELOAD THE ISQL PACKAGE    (4)
// EXEC PROC=ARISDBSD    *-- RUN DB2 Server IN SINGLE USER MODE (3)
CONNECT SQLDBA IDENTIFIED BY SQLDBAPW;
GRANT CONNECT TO SQLDBA IDENTIFIED BY newpw;
/*
/&
```

Figure 65. Reloading the ISQL Package

Notes for Figure 65:

- The steps executed by procedures ARISDBSD and ARIS120D run the application server in single user mode against the identified database.
- (1) Procedure ARIS71SL identifies the DB2 Server for VSE sublibraries.
 - (2) Procedure ARIS71DB identifies the starter database. You can substitute the procedure or job control statements that identify the database being updated.
 - (3) The password for the user SQLDBA must be reset to SQLDBAPW before procedure ARIS120D is executed. The first execution of procedure ARISDBSD changes the password for the user SQLDBA to SQLDBAPW. Supply the current password (**currentpw**) in the SQL CONNECT command. After procedure ARIS120D is executed, the password for the user SQLDBA should be reset to a password of your choice. The second execution of procedure ARISDBSD changes the password for the user SQLDBA. Supply the password of your choice (**newpw**) in the SQL GRANT command.
 - (4) Procedure ARIS120D reloads the package SQLDBA.ARIISQL into the database from the DB2 Server for VSEA-type source member ARIISQLM. This step must be executed by the user SQLDBA.

This step successfully completes with a return code of 0 through 4.

5.4.3 Re-Link-Editing ISQL

To re-link-edit ISQL after initial installation, prepare and execute the job control statements shown in Figure 66

Refer to the information supplied with each DB2 Server for VSE service update to see if you should take this action.

```
// JOB RELINK ISQL
// LIBDEF *,SEARCH=(PRD2.DB2710,PRD1.BASE,PRD2.CONFIG),          X
// EXEC PROC=ARIS140D    *-- LINK-EDIT ISQL                      (1)
// CATALOG=PRD2.DB2710
// EXEC PROC=ARIS140D    *-- LINK-EDIT ISQL                      (2)
/*
/ &
```

Figure 66. Re-Link-Editing ISQL

Notes for Figure 66:

- This job specifies the standard CICS libraries in the LIBDEF search path. If required, modify the job to search your own CICS libraries.
- (1) This job requires that you specify the DB2 Server for VSE sublibrary into which the linkage editor output is cataloged; in this job, the output is cataloged in the PRD2.DB2710 sublibrary. Specify your own if it has a different name. If you have installed a National Language, then specify the sublibrary into which the language was installed in the LIBDEF

SEARCH chain (before PRD2.DB2710), and also as the value for the LIBDEF CATALOG parameter.

- (2) Procedure ARIS140D link-edits the DB2 Server for VSE ISQL facility into the DB2 Server for VSE library. It must not be changed. This link-edit job will include the CICS interface modules DFHEAI and DFHEAI0 found in the CICS PRD1.BASE sublibrary, or your own CICS libraries.

The CICS system must be restarted after the link-edit is successfully completed. See "Preparation Step 5: Prepare the CICS System for DB2 Server for VSE". Alternatively, you can access the new phase by executing the CICS CEMT master command after the link-edit is successfully completed. Refer to the CICS manuals for information on this command.

5.4.4 Re-Link-Editing the ISQL ITRM Terminal Transaction

To re-link-edit the ISQL ITRM terminal transaction after initial installation, prepare and execute the job control statements shown in Figure 67. This is required by a service update to the ISQL ITRM terminal transaction program module.

Refer to the information supplied with each DB2 Server for VSE service update to see if you should take this action.

```
// JOB RELINK ISQL ITRM TERMINAL TRANSACTION PROGRAM
// LIBDEF *,SEARCH=(PRD2.DB2710,PRD1.BASE,PRD2.CONFIG),          X
//                   CATALOG=PRD2.DB2710                      (1)
// EXEC PROC=ARIS150D *-- LINK-EDIT ITRM TERMINAL TRANSACTION (2)
/*
/ &
```

Figure 67. Re-Link-Editing the ISQL ITRM Terminal Transaction

Notes for Figure 67:

- This job specifies the standard CICS libraries in the LIBDEF search path. If required, modify the job to search your own CICS libraries.
- (1) This job requires that you specify the DB2 Server for VSE sublibrary into which the linkage editor output is cataloged; in this job, the output is cataloged in the PRD2.DB2710 sublibrary. Specify your own if it has a different name. If you have installed a National Language, then specify the sublibrary into which the language was installed in the LIBDEF SEARCH chain (before PRD2.DB2710), and also as the value for the LIBDEF CATALOG parameter.
- (2) Procedure ARIS150D link-edits the DB2 Server for VSE ISQL facility ITRM terminal transaction module into the DB2 Server for VSE library. It must not be changed. This link-edit job will include the CICS interface modules DFHEAI and DFHEAI0 found in the CICS PRD1.BASE sublibrary, or your own CICS libraries.

The CICS system must be restarted after the link-edit is successfully completed. See "Preparation Step 5: Prepare the CICS System for DB2 Server for VSE". Alternatively, you can access the new phase by executing the CICS CEMT master command after the link-edit is successfully completed. Refer to the CICS manuals for information on this command.

5.4.5 Re-Link-Editing the ISQL ITRM Terminal Extension Program

To re-link-edit the ISQL ITRM terminal extension program after initial installation, prepare and execute the job control statements shown in Figure 68. This is required by a service up date to the ISQL ITRM terminal extension program module.

Refer to the information supplied with each DB2 Server for VSE service update to see if you should take this action.

```
// JOB RELINK ISQL ITRM TERMINAL EXTENSION PROGRAM
// LIBDEF *,SEARCH=(PRD2.DB2710,PRD1.BASE,PRD2.CONFIG),          X
//          CATALOG=PRD2.DB2710                                (1)
// EXEC PROC=ARIS160D    *-- LINK-EDIT ITRM TERMINAL EXTENSION (2)
/*
/ &
```

Figure 68. Re-Link-Editing the ISQL ITRM Terminal Extension Program

Notes for Figure 68:

- This job specifies the standard CICS libraries in the LIBDEF search path. If required, modify the job to search your own CICS libraries.
- (1) This job requires that you specify the DB2 Server for VSE sublibrary into which the linkage editor output is cataloged; in this job, the output is cataloged in the PRD2.DB2710 sublibrary. Specify your own if it has a different name. If you have installed a National Language, then specify the sublibrary into which the language was installed in the LIBDEF SEARCH chain (before PRD2.DB2710), and also as the value for the LIBDEF CATALOG parameter.
- (2) Procedure ARIS160D link-edits the DB2 Server for VSE ISQL facility ITRM terminal extension program module into the DB2 Server for VSE library, and must not be changed. This link-edit job will include the CICS interface modules DFHEAI and DFHEAI0 found in the CICS PRD1.BASE sublibrary, or your own CICS libraries.

The CICS system must be restarted after the link-edit is successfully completed. See "Preparation Step 5: Prepare the CICS System for DB2 Server for VSE". Alternatively, you can access the new phase by executing the CICS CEMT master command after the link-edit is successfully completed. Refer to the CICS manuals for information on this command.

You can use operator commands to search the file for a new copy. See the appropriate CICS manual for details.

5.5 CCSID-Related Phases Maintenance

5.5.1 Reloading the CCSID-Related Phases Package (SQLDBA.ARIRSQR)

The CCSID-related phases package must be reloaded in all applicable databases if there is a service update to A-type source member ARIRSQRM. To reload it, run job control member ARIS71WD shown in Figure 69.

Refer to the information supplied with each DB2 Server for VSE service update to see if you should take this action.

```
// JOB ARIS71WD      RELOAD CCSID-RELATED PHASES PACKAGE
// LIBDEF PROC,SEARCH=(PRD2.DB2710)
// EXEC PROC=ARIS71SL  *--- DB2 Server LIBRARY DEFINITION
// EXEC PROC=ARIS71DB  *--- STARTER DATABASE IDENTIFICATION
// EXEC PROC=ARIS175D  *--- RELOAD CCSID-RELATED PHASES PACKAGE
/*
/ &
```

Figure 69. Reloading the CCSID-Related Phases Package

Notes for Figure 69:

- For procedures ARIS61DB and ARIS61SL, substitute your own procedures or job control statements that identify your current database and the DB2 Server for VSE Version 7 Release 1 sublibrary.
- Procedure ARIS175D reloads the CCSID-related phases package in the database by running the application server in single user mode against that database.

5.5.2 Recreating the CCSID-Related Phases

To recreate the CCSID-related phases after initial installation, execute job ARISCNVD (supplied as a Z-type job control member). You must recreate the CCSID-related phases after any updates are made to the SYSTEM.SYSCCSIDS, SYSTEM.SYSCCHARSETS, or SYSTEM.SYSSTRINGS system catalog tables. Refer to "Migration Step 16: Create CCSID-Related Phases" for details.

5.6 FIPS Flagger Maintenance

5.6.1 Reloading the FIPS Flagger Package (SQLDBA.ARIFCRD)

The FIPS flagger package must be reloaded in all applicable databases if there is a service update to A-type source member ARIFCRDM. To reload it, prepare and run the job control statements shown in Figure 70 on page 77

Refer to the information supplied with each DB2 Server for VSE service update to see if you should take this action.

```
// JOB RELOAD FIPS FLAGGER
// LIBDEF PROC,SEARCH=(PRD2.DB2710)
// EXEC PROC=ARIS71SL   *-- DB2 Server LIBRARY DEFINITION   (1)
// EXEC PROC=ARIS71DB   *-- STARTER DATABASE IDENTIFICATION (2)
// EXEC PROC=ARISDBSD   *-- RUN DB2 Server IN SINGLE USER MODE (3)
CONNECT SQLDBA IDENTIFIED BY currentpw
GRANT CONNECT TO SQLDBA IDENTIFIED BY SQLDBAPW
/*
// EXEC PROC=ARIS360D   *-- RELOAD THE FIPS FLAGGER         (4)
// EXEC PROC=ARISDBSD   *-- RUN DB2 Server IN SINGLE USER MODE (3)
CONNECT SQLDBA IDENTIFIED BY SQLDBAPW
GRANT CONNECT TO SQLDBA IDENTIFIED BY newpw
/*
/ &
```

Figure 70. Reloading the FIPS Flagger Package

Notes for Figure 70:

- The steps executed by procedure ARISDBSD and procedure ARIS360D run the application server in single user mode against the identified database.
- (1) Procedure ARIS71SL identifies the DB2 Server for VSE sublibraries.
 - (2) Procedure ARIS71DB identifies the starter database. For procedure ARIS34DB, you can substitute the procedure or job control statements that identify the database being updated.
 - (3) The password for the user SQLDBA must be reset to SQLDBAPW before procedure ARIS360D is executed. The first execution of procedure ARISDBSD changes the password for the user SQLDBA to SQLDBAPW. You must supply the current password (**currentpw**) for the user SQLDBA in the SQL CONNECT command shown. After procedure ARIS360D is executed, the password for the user SQLDBA should be reset to a password of your choice. The second execution of the procedure ARISDBSD changes the password for the user SQLDBA. Supply the password of your choice (**newpw**) for the user SQLDBA in the SQL GRANT command.
 - (4) The step executed by procedure ARIS360D reloads the package SQLDBA.ARIFCRD into the database from the DB2 Server for VSE A-type source member ARIFCRDM. The step must be executed by the user SQLDBA.

This step is successfully completed with a return code of 0 through 4.

5.7 DB2 Server for VSE Library Maintenance

In a VSE environment, a production sublibrary is required for DB2 Server for VSE.

5.7.1 Replacing DB2 Server for VSE

To replace DB2 Server for VSE:

1. Purge the existing sublibrary as described below.
2. Restore DB2 Server for VSE through MSHP by following "Preparation Step 4: Restore the DB2 Server for VSE Distribution Library".
3. Perform the link-edits in "Installation Step 1: Link-Edit the DB2 Server for VSE 7.1 Online Support Components".

5.7.2 Purging DB2 Server for VSE Libraries

To purge existing sublibraries of all entries relating to DB2 Server for VSE, prepare and execute the job control statements shown in Figure 71

```
// JOB PURGE DB2 Server VSE VERSION 7.1 LIBRARIES
// EXEC LIBR,PARM='MSHP'
ACCESS SUBLIB=PRD2.DB2710          (1)
DELETE ARI*.*
/*
/ &
```

Figure 71. Purging DB2 Server for VSE Libraries

Note for Figure 71:

- (1) The ACCESS statement must contain the name of the sublibrary that contains DB2 Server for VSE. Change this name as required.

5.8 DB2 Server for VSE Link Books

Table 2 shows the relationships between DB2 Server for VSE components, link books, and phase names. Refer to it when re-link-editing DB2 Server for VSE phases.

Note:

1. Only the following DB2 Server for VSE phases are eligible for the VSE shared virtual area (SVA):

ARICDIRD
ARIPRPF
ARIXRDS

ARIDBS
ARIPRPP

ARIPRPA
ARIRBARM

ARIPRPC
ARISQLDS

If you install all of the phases eligible for SVA into the VSE shared virtual area, allocate an additional 4.1 megabytes of storage to the SVA.

Table 2. Link Books for the DB2 Server for VSE Components

<i>Figure 72 (Page 1 of 2). Link Books for the DB2 Server for VSE Components</i>		
Component	Link Book	Phases
DB2 Server for VSE Copyright	None	\$\$\$COSQL
DBSS / DSC	ARISLKDD ARISLKMMD	ARISQLDS ARICMOD
VSE Dependent Functions	ARISLKED	ARISD00D ARISD01D ARISD10D ARISD11D ARISD12D ARISD13D ARISD14D ARISD15D ARISD16D ARISD20D ARISD21D ARISD22D ARISD23D ARISD24D ARISD25D ARISD26D ARISD30D ARISD31D ARISD32D ARISD33D ARISD34D
RDS with DRDA	ARISLKRA	ARIXRDS
RDS without DRDA	ARISLKRD	ARIXRDS
User Exit Router	ARISLKXD	ARIXSXR
DBMS	ARISLK1D	ARISDBMS
Assembler Preprocessor	ARISLKAD	ARIPRPA
Flagger Semantic Routines	ARISLK4D	ARIFFVL
Flagger View Analysis Routines	ARISLK5D	ARIFBVL
Flagger LGP tables modules	ARISLK7D	ARIFF00 ARIFS00 ARIFB00
C Preprocessor	ARISLK6D	ARIPRPB
COBOL Preprocessor	ARISLKCD	ARIPRPC
PL/I Preprocessor	ARISLKPD	ARIPRPP
FORTTRAN Preprocessor	ARISLKTD	ARIPRPF
DBS Utility	ARISLKUD	ARIDBS
Batch Resource Adapter	ARISLKBBD	ARIRBARM
Online Resource Adapter	ARISLKZD	ARI0OLRM
DBNAME Directory Generator	ARISLK8D	ARICBDID
DBNAME Directory Services	ARISLKDA	ARICDIRD
APPC-to-XPCC Exchange Transaction	ARISLK9D	ARICAXED
Trace Formatter	ARISLKFD	ARIMTRA
Directory Expander	ARISLKQD	ARIMEXBD
Online Resource Adapter Control (ENABLE/DISABLE CICS Resource Adapter)	ARISLKYD	ARIRCONT
ISQL Mainline Transaction	ARISLKID	ARIISQL
ITRM Terminal Transaction program	ARISLKJD	ARIITRM
ITRM Terminal Extension Program	ARISLKLD	ARIITRX

<i>Figure 72 (Page 2 of 2). Link Books for the DB2 Server for VSE Components</i>		
Abend Checking Support for LE/VSE	None	ARICABC
Message Repository (American English)	None	ARIMS001
DRDA2 Support	ARISLKVD ARISLKOD ARISLKND ARISLKWD	ARICDEBD ARICDRAD ARICDAXD ARICDR2
COBOL II Dynamic Support	None	ARIPADR4 ARIPADR5 ARIPRDI ARISSMA Note: Note: You can use Z-type source member ARIS51LP to create these Phases.
CCSID-Related Phases	ARISLKQZ ARISLKRZ ARISLKSZ	ARIRRFC ARIRRFSD ARIRRFSD
CBND Mainline Transaction	ARISLKBA	ARIPCBND
CBND sub-transaction	ARISLKCA	ARIPCB2D
SQLGLOB File Default Setting Program	ARISLKGZ	ARICGDEF
ISQL Package Conversion Program	ARISLKBZ	ARICIQBD

6.0 Appendix A. How to Use the Job Manager

IMPORTANT: READ THIS APPENDIX BEFORE STARTING THE INSTALLATION.
--

6.1 Overview of Installation and Migration

This section is an introduction to the installation of DB2 Server for VSE Version 7 Release 1 (7.1) and the migration of existing databases to 7.1. At the beginning of chapters 2 through 4, you can find an outline of the preparation, installation and migration steps in each chapter.

An installation aid is supplied to help with the installation and migration processes. Some steps in Chapters 2 through 4 utilize this aid, and some are performed manually.

6.2 Installation

If you are installing DB2 Server in a VSE system for the first time, follow the steps in Chapter 2, Preparing to install DB2 Server for VSE 7.1, and Chapter 3, Installing DB2 Server for VSE. You do not perform any of the steps in Chapter 4, Migrating an Existing Database.

6.3 Migration

If you are migrating from a previous release, follow the relevant steps in Chapter 2 on Preparation, and the Migration steps in Chapter 4. Of course, you might follow the installation process to build a starter database for initial application testing, and then perform the migration process for your existing databases.

As part of your preparation to migrate your existing database to the DB2 Server for VSE Version 7 Release 1, you should review the Appendix in the *DB2 Server for VSE System Administration* manual that discusses the differences between your existing system, and Version 7 Release 1.

6.4 Optional Steps

Not all of the steps in the installation and migration processes are mandatory. Depending on how you want to install DB2 Server for VSE, you may decide to not perform some optional steps. Also, depending on how you want to migrate any existing databases, you may choose to omit certain optional steps.

6.5 The Job Manager

The Job Manager is a set of REXX Exec, Job Control members, and parameter tables, to assist in the DB2 Server for VSE Installation and Migration processes. REXX program ARISIMGR controls the overall job flow, based on the contents of the job list control tables (supplied as Z-type members). There are job lists for Preparation steps (ARISITBP), for Installation steps (ARISITBI), and for Migration steps (ARISITBM).

The Job Manager selects the job control member from the job list, extracts the member from the library, modifies the JCL, submits the job, evaluates the execution, posts the results, and then repeats the process. Modifications to the job control members are based on substituting variables in the JCL, using the parameters in ARISIVAR (a Z-type member).

6.5.1 How Parameter Substitution Works

The Job Manager reads variables stored in ARISIVAR (a Z-type member).

Before starting the Job Manager:

1. Punch and modify the sample ARISIVAR from your installation library.
2. Re-catalog ARISIVAR to your installation library.

Note:

- Make sure to preserve the structure of ARISIVAR member.
- You do not need to update parameters for a step, you are not planning to execute.

The parameter table (see ARISIVAR a Z-type member) has one line for each parameter for each job. The lines of the parameter table are in the following format:

Job name	The job name that requires Parameter(s)
Parameter name	The variable name in the job JCL
Value of the parameter	The value of the parameter that can be changed

Figure 73. The description of parameters in ARISIVAR

The parameter table also has one line for each global parameter. These parameters are used in more than one job, but apply only within the start/end group being processed.

Parameter name	GLOBAL (constant keyword)
Parameter name	This name appears in a JCL for the job
Value of the parameter	This is actual value of the global parameter, which can be changed

Figure 74. The description of Global parameters in the ARISIVAR

6.5.2 How Job List Works

The job list is used by the Job Manager to determine the jobs required by each step (Preparation/ Installation or Migration).

Job's name	Name of member in the distribution library
Job's type	Type of member in the distribution library
Return code	<ul style="list-style-type: none"> RC = 'X' - job did not complete successfully or has not run before. RC=number, job has run and RC contains the return code of the job.
MAXRC	MAXRC maximum return code allowed for this job to continue the installation process.
Is job Optional?	O - Optional, M - Mandatory (for Installation part)
Is job Optional?	O - Optional, M - Mandatory (for Migration part)
Is input required?	<ul style="list-style-type: none"> YES - input required (get variables from ARISIVAR) NO - input is not required. <p>Note: If the only required parameter is installation library name or a global variable, then input marked as 'NO'</p>
Stop Job Manager?	<ul style="list-style-type: none"> YES - stop the execution of the Job Manager after this step. NO - continue the execution of the Job Manager.

Figure 75. Description of each column in a job list

Note: Every parameter in a job list must be in upper case, separated from other parameters by one blank space.

Here is an example of a job list for the Preparation Step:

```
ARIS71JD Z X 4 0 M YES NO
```

In the example, ARIS71JD is a Z type member, which was not executed yet. The maximum return code allowed for ARIS71JD is 4. ARIS71JD is Optional step in Preparation for Installation, but mandatory step in Preparation for Migration. The ARIS71JD requires parameters from ARISIVAR and the execution of the Job Manager will not stop after this step.

As ARIS71JD is submitted to your VSE system, the Job Manager will compare the maximum return code from the execution to MAXRC. If the job completes with a return code greater than MAXRC, the Job Manager stops.

6.5.2.1 How to Run All Jobs Again:

If you have multiple databases and want to execute Preparation, Installation, or Migration Step again this section will explain how to do it. You can choose one of the following:

1. Punch a Job List corresponding to the step you want to execute:
 - ARISITBP - Job List for Preparation Step
 - ARISITBI - Job List for Installation Step
 - ARISITBM - Job List for Migration Step

Change the "Return Code" fields (See Figure 75 on page 83) for all jobs with "X" and re-catalog the Job list to the installation library.

WARNING: When changing the records in the file, note that the fields must be separated by only one blank.

2. See Figure 77 on page 85.

6.5.3 Starting the Job Manager

IMPORTANT: Modify ARISIVAR Z-type member with the appropriate parameters. If you subsequently change ANY ARISIVAR global variables you MUST restart the Job Manager.

After successful modification of ARISIVAR control table, punch and submit job control member ARISIMGJ.Z from the distribution library, which will start execution of Job Manager.

```
* $$ JOB JNM=ARISIMGJ,CLASS=x (1)
* $$ LST CLASS=V,DEST=(,userid) *modify accordingly
// JOB ARISIMGJ JCL TO START MANAGER EXEC
// LIBDEF *,SEARCH=(PRD2.DB2710) *modify accordingly
// EXEC REXX=ARISIMGR
/*
/&
* $$ E0J
```

Figure 76. Starting the Job Manager

- (1) For CLASS specify any available partition to run the Job Manager.

Note: ARISSTDL Z-type member must run in background partition, thus for the Preparation Step do not submit the Job Manager to run in background partition. See Figure 77 on page 85:

Note: ARISIMGJ Job will always complete with the return code of 0. You must check the return code of the executed job and rely on the messages from the Job manager to make sure that the execution was successful.
See "How the Job Results are Evaluated".

6.5.3.1 User Interface:

```
F4 0004 *****
F4 0004     PREPARE FOR INSTALLATION/MIGRATION PROCESS
F4 0004 *****
F4 0004 ENTER INSTALLATION LIBRARY NAME (PRD2.DB2710  default) (1)
F4-0004
4
F4 0004 YOU HAVE SELECTED  PRD2.DB2710
F4 0004 PRESS ENTER TO CONTINUE OR ENTER ANY OTHER KEY TO
F4 0004 MODIFY YOUR SELECTION:
F4-0004
4
F4 0004 WHICH CLASS WILL YOU USE TO RUN THE PROCESS ? (4  default) (2)
F4-0004
0
F4 0004 YOU HAVE SELECTED  0
F4 0004 PRESS ENTER TO CONTINUE OR  ENTER ANY OTHER KEY TO
F4 0004 MODIFY YOUR SELECTION:
F4-0004
4
F4 0004 PLEASE SELECT ONE OF THE FOLLOWING :
F4 0004 FOR PREPARATION....  ENTER (P)
F4 0004 FOR INSTALLATION...  ENTER (I)
F4 0004 FOR MIGRATION.....  ENTER (M)
F4-0004
4 p
F4 0004 IF PREPARATION FOR:
F4 0004 INSTALLATION... PLEASE ENTER (I)
F4 0004 MIGRATION..... PLEASE ENTER (M)
F4-0004
4 i
F4 0004 DO YOU WANT TO EXECUTE ALL JOBS? {Y|N-default} (3)
F4-0004
4 n
F4 0004 IF YOU WANT TO START FROM A SPECIFIC JOB ENTER 1 (4)
F4 0004 IF YOU WANT TO EXECUTE ONLY ONE STEP  ENTER 2 (Default) (5)
F4-0004
4 2
F4 0004 ENTER THE JOB NAME YOU WANT TO EXECUTE (ex. ARIS71JD):
F4-0004
4 aris71jd
F1 0001 1Q47I  F4 ARIS71JD 00021 FROM (JCL) , TIME=12:45:32
BG 0000 * ** JOB JNM=ARIS71JD,CLASS=0,DISP=D
BG 0000 * ** LST CLASS=V,DISP=D,DEST=(,XXXXXXX)
BG 0000 // JOB ARIS71JD DEFINE DB2710 PROGRAMS AND TRANSACTIONS
```

Figure 77. Sample user answers when running the Job Manager

Notes for Figure 77:

- (1) The installation library name, which is specified here, is included in library search path for all jobs as the parameter - LIBNAME.

```
// JOB name
// LIBDEF PROC,SEARCH=(%%LIBNAME%%)
```
- (2) **For Preparation Step** - answer 0 (BG partition). **Note:** the BG partition must be available.
For Installation/ Migration Steps - specify any available partition that has enough size to start the DB2 startup database
- (3) Enter **'YES'** if you want to run all jobs within the current step (Preparation/ Installation/ Migration).
Note: the Job Manager will skip all jobs which were run successfully. The first job it will submit will be a job which failed in previous execution or which was never run before.
The default answer is **'NO'**.
- (4) Enter **'1'** if you want the Job Manager to start from a particular job and continue execution of all jobs which follow the specified one.
Note: this choice is useful if you have to execute some jobs twice, even if the execution of the jobs was successful.
- (5) The default answer is **'2'** - to execute only one job.

6.5.4 Execution of Jobs Submitted by the Job Manager

On the console during the execution of job you should see the following:

```
F4 0001 1Q47I F4 name_of_submitted_job 00025 FROM
(ARISIMGR) , TIME=11:39:33
F4 0004 // JOB name_of_job comment from submitted job
DATE 11/12/1999, CLOCK 11/39/33
* more comments from submitted_job (if available)
F4 0004 EOJ name_of_job MAX.RETURN CODE=0000
DATE 11/12/1999, CLOCK 11/39/36, DURATION 00/00/03
F4 0004 EOJ NO NAME
DATE 11/12/1999, CLOCK 11/39/37
F4 0001 1Q34I F4 WAITING FOR WORK
F1 0001 1Q34I LST WAITING FOR WORK ON 00E
F4-0004 *****
F4-0004 * JOB: name_of_job EXECUTED SUCCESSFULLY (1)
F4-0004 *****
F4-0004 JOB MANAGER COMPLETED SUCCESSFULLY (2)
F4-0004 EOJ JCL MAX.RETURN CODE=0000
BG-0000
```

Figure 78. Console output from the Job Manager

(1) This message will always appear if submitted job executed successfully.

The possible error messages are:

- 'ERROR! RETURN CODE FROM LAST STEP WAS xxx'
- 'JOB WAS CANCELED'
- 'READ CONSOLE FOR DETAILS.'

(2) **If error occurs you must investigate, correct the error and restart the Job Manager.**

6.5.5 How the Job Results are Evaluated

What do you look for:

- Messages from the Job manager (ARISIMGJ). If it was terminated, read console and check your reader to make sure you understand what went wrong, correct the error, and restart Job Manager.
- Messages from submitted jobs.
 - Some jobs have error checking inside the JCL. In such situations Job Manager will wait for an user response to continue or to stop the installation process.
 - Other jobs that terminate abnormally will produce readable output on the console and send the console output file to your reader. Please read the file to determine what went wrong.
 - Some jobs will not terminate until there is a console response from the user. If no response was received after 30 seconds, Job Manager will output a warning message on the console and wait for your response.
- If the return code allowed for a job was greater than zero, it is your responsibility to check whenever this code was expected or if occurred because of some kind of error. This is very important for Z-type member ARIS71DD. Please read the console output for this job and make sure no errors are found.

<p>IMPORTANT: Always verify if the execution of the last job was successful. If the Job Manager stops its execution, before proceeding to another step, make sure that no errors occurred and that you executed all mandatory jobs for the step.</p>

6.5.6 What Should You Keep in Mind

As soon as you start the Job Manager for Installation or Migration Steps, it will update and recatalog three members: **ARIS71DB**, **ARIS71SL** and **ARIS380D**

Note: If you need to make any changes to ARIS71DB, ARIS71SL or ARIS380D after starting the Job Manager for Installation or Migration Steps, you must do it **manually**.

ARIS71DB Contains the labels for the VSAM files used for the Starter Database. This member will be updated using parameters you specified for ARIS71CD Z-type member. The parameters needed are:

- DBCAT
- DIRFILE

- LOGFILE
- EXTFILE

ARIS71SL This member will be updated using following parameters:

- Default Installation Library, which you specify when starting the Job Manager (default is PRD2.DB2710)
- CLIB - see Figure 54 on page 54

ARIS380D This member will install a language. See "Chapter 3: Install Language". If you need to install more than one language you need to modify this procedure manually.

6.6 The Disclaimer

The Job Manager is supplied as an installation aid for DB2 Server for VSE, and is not intended to be used as a general purpose monitoring tool. Any use of the Job Manager, other than Preparation, Installation, and Migration for DB2 Server for VSE is not supported.

7.0 Appendix B. Techniques Used for Installation

The following are techniques used in some of the DB2 Server for VSE installation procedures and members:

- Embedding database identification statements
- Embedding DB2 Server for VSE library identification statements
- Using READ MEMBER statements
- Running the DBS utility in single user mode
- Suppressing preprocessor output.

7.1 Embedding Database Identification Statements

The IBM-supplied procedure ARIS71DB contains the DLBL statements that identify the components of the starter database. No program is executed by this procedure. It is executed first in the example job control members to embed the database DLBL statements needed by DB2 Server for VSE (program ARISQLDS).

You can replace the references to ARIS71DB with actual database DLBL statements, or with references to your own procedures set up for this purpose.

7.2 Embedding DB2 Server for VSE Library Identification Statements

The IBM-supplied procedure ARIS71SL contains the library identification (LIBDEF) statements for most of the installation steps for a database. The IBM-supplied procedure ARIS71PL contains the LIBDEF statements for normal use of DB2 Server for VSE.

The LIBDEF statements in procedures ARIS71SL and ARIS71PL are not unique to a particular database. They are included whenever a set of DB2 Server for VSE libraries is needed.

You can replace the references to ARIS71SL and ARIS71PL with your own LIBDEF statements, or with references to your own procedures set up for this purpose.

7.3 Using the READ MEMBER Statement

DB2 Server for VSE can read input from a source member with a statement of the form:

```
READ MEMBER member-name[.member-type] [(NOCONT)]
```

Note: The square brackets [] indicate an optional parameter.

member-name

Specifies a source member in the DB2 Server for VSE library.

member-type

Specifies the source member type. The default is ".A". For example, either **BOOK1** or **BOOK1.A** is correct.

NOCONT Specifying NOCONT prevents READ MEMBER from continuing to read from SYSIPT. It also ensures that the EOF indicator is returned. If NOCONT is specified, subsequent records are read from SYSIPT after the end of member

A READ MEMBER statement:

- Can occur anywhere between byte 1 and byte 71 of a SYSIPT record.
- Is accepted only if it occurs immediately after an EXEC statement or another READ MEMBER statement.
- Is accepted after a SCHEMA or RELOAD PACKAGE command if the INFILE specified is SYSIPT. The NOCONT option is required to properly end the file.
- Is accepted after a DATALOAD command if the INFILE specified is (*). An ENDDATA command is required at the end of the input data records, whenever the end of data is inside the member or in SYSIPT.
- Must not follow other SYSIPT data records. However, SYSIPT data records can follow it if the NOCONT option is not specified.
- Is not intended to be used outside of the DB2 Server for VSE process. Using READ MEMBER to include members with SQL INCLUDE statements results in errors.

You can place SYSIPT data immediately after an EXEC statement and not READ MEMBER statement.

7.4 Running the DBS Utility in Single User Mode

The job control example shown in Figure 79 on page 91 starts the application server in single user mode (SYSMODE=S). When the application server is initialized, it passes control to the application program specified by the PROGNAME parameter (in this situation, the DBS utility program ARIDBS).

During the DB2 Server for VSE installation process, the DBS utility is run without DB2 Server for VSE logging (LOGMODE=N). All other DB2 Server for VSE initialization parameters are allowed to default.

```

// JOB START SINGLE
// LIBDEF PROC,SEARCH=(PRD2.DB2710)
// EXEC PROC=ARIS71DB   *-- STARTER DATABASE IDENTIFICATION
// EXEC PROC=ARIS71PL   *-- DB2 Server LIBRARY DEFINITION
.
Optional statements for the application program,
such as TLBL and DLBL statements.
.
// EXEC ARISQLDS,SIZE=AUTO,PARM='SYSMODE=S,LOGMODE=N,PROGNAME=ARIDBS'
.
SYSIPT input to the DBS utility application program.
.
/*
/&

```

Figure 79. Example of Running the DBS Utility in Single User Mode

Note:

For procedure ARIS71DB, you can substitute your own procedure or job control statements, to start the application server using your own database.

7.5 Suppressing Preprocessor Output

SYSPCH and SYSLST output from the DB2 Server for VSE Assembler preprocessor is suppressed during the database install action process. It is not required because only access modules are being built for the database. Assignment and label information for SYSPCH is not needed when the SYSPCH output is suppressed. The assignment and label information is only required for output to disk file.

Preprocessor parameters NOPRINT (NOPR) and NOPUNCH (NOPU) are used. Refer to the *DB2 Server for VSE & VM Application Programming* manual for a complete description of the preprocessor parameters.

Preprocessor diagnostic messages are always written to SYSLST.

8.0 Appendix C. Procedures Provided by IBM

This appendix lists the procedures provided by IBM for your use. Any procedures not documented in this manual are included in the *DB2 Server for VSE System Administration* manual.

Procedure	Purpose
ARISIMGR	Rexx Job Manager
ARISDBSD	Run the DBS Utility in DB2 Server for VSE Single User Mode
ARIS030D	Generate the Starter Database
ARIS040D	Create the DBS Utility Package
ARIS050D	Finish Database Generation
ARIS055D	Load Sample Table and Routines
ARIS059D	Activate the Messages for Language xxxx
ARIS060D	Install ISQL HELP Text into the Database
ARIS061D	Migrate the HELP Text Tables
ARIS062D	Deactivate a Language and/or Delete HELP Text for a Specific Language
ARIS063D	Delete all HELP Text for all Languages
ARIS070D	Update the DB2 Server for VSE System
ARIS075D	Drop, Recreate, and Load the Sample Tables
ARIS080D	Grant SCHEDULE Authority to DBDCCICS
ARIS090D	Link-edit Online Resource Adapter Control
ARIS110D	Create/Grant ISQL Tables/Authorizations
ARIS120D	Reload the ISQL Package
ARIS130D	Complete the Installation of ISQL
ARIS140D	Link-edit ISQL
ARIS150D	Link-edit ISQL ITRM Terminal Transaction
ARIS160D	Link-edit ISQL ITRM Terminal Extension Program
ARIS170D	Link-edit DB2 Server for VSE Batch Resource Adapter
ARIS175D	Reload the CCSID-related Phases Package
ARIS180D	Link-edit DB2 Server for VSE Trace Formatter
ARIS185D	Link-edit DB2 Server for VSE Directory Expander
ARIS190D	Link-edit DB2 Server for VSE DBSS/DSC

ARIS250D	Add and Delete Dbextents
ARIS71FC	Sample File Control Table Entries for SQLBIND and SQLGLOB
ARIS71DB	Starter Database Identification Statements
ARIS71PL	DB2 Server for VSE Production Library Definition
ARIS71SL	DB2 Server for VSE Optional Service/Production Library Definition
ARIS360D	Load FIPS flagger
ARIS370D	List Primary Keys to be Dropped and Recreated
ARIS380D	User entry for NLS Installation
ARIS385D	Procedure to install NLS and Load Help Text
ARIS390D	Load initial record to SQLGLOB VSAM file
ARIS395D	Load initial record to SQLBIND VSAM file

9.0 Appendix D. A-Type Source Members

This appendix identifies the members that are distributed as DB2 Server for VSE A-type source members. The members contain sample input used during installation and migration.

Member	Contents
ARIDSQLP	Source Code of the DBS Utility Package
ARIFCRDM	FIPS Flagger Package
ARIISQLM	ISQL Package
ARIPREPF	Prep parm file for preparing DBSU at installation
ARIRCAN	User Cancel Exit Support Macro
ARIRMAR	User Cancel Exit Support Macro
ARIRSQRM	CCSID-related Phases Package
ARISADD	Sample Input to Add/Delete Dbextent Function
ARISAMDB	SQL Statements to be Executed by the DBS Utility to Build Sample Tables
ARISAMPI	SQL Statements to be Executed by the DBS Utility to Load the Sample ISQL Routines into the Database
ARISCAT	Required Input to Database Generation
ARISCMDB	DBS Utility Commands to Drop Sample Tables
ARISCON	SQL CONNECT Command to be Executed by the DBS Utility
ARISCTM	Database Catalog Migration Authorization Updates
ARISCTMP	System Catalog SYSTEM.SYSOPTIONS Updates
ARISDBG	Control Statements to Generate the Starter Database (Input to ARIS030D)
ARISDBU	SQL Statements to be Executed by the DBS Utility to Finish Database Generation (Input to ARIS050D)
ARISDIRD	Directory of all DBNAMEs and TPNs in the VSE system
ARISDTM	Commands to Update Datetime Defaults
ARISEXP	DBS Utility Input to Create the New EXPLAIN Tables
ARISFPKY	SQL Statements Used by the DBS Utility to List Primary Keys to be Dropped and Recreated
ARISI20	Input to ARIS110D (ISQL Installation)
ARISI21	Input to ARIS130D (ISQL Installation)
ARISMMDB	Commands that Create Manufacturing Sample Tables
ARISS001	Commands to Add American English Entry on SQLDBA.SYSLANGUAGE table

ARISTCF	Commands to the DBS Utility for Installing the Chinese Help Text (Input to ARIS060D)
ARISTC1	Commands to the DBS Utility for Installing the Chinese Help Text (Input to ARIS060D)
ARISTC3	Commands to the DBS Utility for Installing the Chinese Help Text (Input to ARIS060D)
ARISTFF	Commands to the DBS Utility for Installing the French Help Text (Input to ARIS060D)
ARISTF1	Commands to the DBS Utility for Installing the French Help Text (Input to ARIS060D)
ARISTF3	Commands to the DBS Utility for Installing the French Help Text (Input to ARIS060D)
ARISTGF	Commands to the DBS Utility for Installing the German Help Text (Input to ARIS060D)
ARISTG1	Commands to the DBS Utility for Installing the German Help Text (Input to ARIS060D)
ARISTG3	Commands to the DBS Utility for Installing the German Help Text (Input to ARIS060D)
ARISTJF	Commands to the DBS Utility for Installing the Japanese Help Text (Input to ARIS060D)
ARISTJ1	Commands to the DBS Utility for Installing the Japanese Help Text (Input to ARIS060D)
ARISTJ3	Commands to the DBS Utility for Installing the Japanese Help Text (Input to ARIS060D)
ARISTUF	Commands to the DBS Utility for Installing the Uppercase English Help Text (Input to ARIS060D)
ARISTU1	Commands to the DBS Utility for Installing the Uppercase English Help Text (Input to ARIS060D)
ARISTU3	Commands to the DBS Utility for Installing the Uppercase English Help Text (Input to ARIS060D)
ARISTXF	Commands to the DBS Utility for Installing the Mixed English Help Text (Input to ARIS060D)
ARISTX1	Commands to the DBS Utility for Installing the Mixed English Help Text (Input to ARIS060D)
ARISTX3	Commands to the DBS Utility for Installing the Mixed English Help Text (Input to ARIS060D)
ARIS6ASD	Sample Assembler Language Application Program to Manipulate the Sample Tables (see note below)
ARIS6CBD	Sample COBOL Application Program to Manipulate the Sample Tables (see note below)
ARIS6CD	Sample C Application Program to Manipulate the Sample Tables (see note below)
ARIS6FTD	Sample FORTRAN Application Program to Manipulate the Sample Tables (see note below)
ARIS6PLD	Sample PL/I Application Program to Manipulate the Sample Tables (see note below)
ARIUXDT	User Date Conversion Routine
ARIUXIT	User Exit Router Routine
ARIUXTM	User Time Conversion Routine
FP102CY	Sample field procedure for cultural sorting for the Cyrillic code page (Regions: Russia, Bulgaria, Serbia and Montenegro).

FP870L2 Sample field procedure for cultural sorting for the Latin 2 code page (Regions: Slovenia, Poland and Romania).

Note:

Members ARIS6ASD, ARIS6CD, ARIS6CBD, ARIS6FTD, and ARIS6PLD are shown in the *DB2 Server for VSE & VM Application Programming*. They serve as coding examples for application programmers.

You can punch the A-type members listed in this appendix by using the JCL statements shown in Figure 80. Replace **XXXXXXXX** with the name of a member.

```
// JOB PUNCH
* * * * *
*
* PURPOSE: JOBSTREAM TO PUNCH OUT MEMBER XXXXXXXX.A
*
* * * * *
// EXEC LIBR,PARM='MSHP'
ACCESS SUBLIB=PRD2.DB2710
PUNCH XXXXXXXX.A
/*
/ &
```

Figure 80. Example of JCL Required to Punch A-Type Members

10.0 Appendix E. Z-Type Source Members

This appendix identifies the members that are distributed as DB2 Server for VSE Z-type source members. The members contain sample JCL. Any members not documented in this manual are included in the *DB2 Server for VSE System Administration* manual.

Member	Contents
ARISIMGJ	Job Control to Start Job Manager
ARISIVAR	Control Table with parameters
ARISITBP	Control Table with list of jobs for Preparation Step
ARISITBI	Control Table with list of jobs for Installation Step
ARISITBM	Control Table with list of jobs for Migration Step
ARISBDID	DBNAME Directory Generation Job Control
ARISCNVD	Job Control to Refresh CCSIDs-Related Phases
ARISGDEF	Job Control to set SQLGLOB file default value
ARISSTDL	Job Control to update labels for the new datasets
ARISIQBD	Job Control to generate ISQL bind file
ARIS6ASD	DB2 Server for VSE Sample Assembler Program Job Control
ARIS6CBD	DB2 Server for VSE Sample COBOL Program Job Control
ARIS6CD	DB2 Server for VSE Sample C Program Job Control
ARIS6C2D	DB2 Server for VSE Sample COBOL II Program Job Control
ARIS6FTD	DB2 Server for VSE Sample FORTRAN Program Job Control
ARIS6PLD	DB2 Server for VSE Sample PL/I Program Job Control
ARIS71AD	Job Control to prepare for installation and restore the Distribution Library
ARIS71BD	Job Control to Do DB2 Server for VSE Link-Edits
ARIS71CD	Job Control to Define the VSAM Master Catalog and the VSAM Data Sets
ARIS71DD	Job Control to Generate and Install Starter Data Base
ARIS71ED	Job Control to Install Optional DB2 Server for VSE Components
ARIS71FD	Job Control to Optionally Grant SCHEDULE Authority to CICS
ARIS71GD	Job Control to Start DB2 Server for VSE in Multiple User Mode
ARIS71HD	Job Control to Add and Delete Dbextents
ARIS71HZ	Job Control to Enlarge HELPTEXT Dbspace
ARIS71ID	Job Control to Increase the Size of the Directory

ARIS71JD	Job Control to Define CICS Programs and Transactions
ARIS71JZ	Job Control to Install National Language
ARIS71KD	Job Control to Define CICS DB2 for VSE DRDA Programs and Transactions for CICS
ARIS71ND	Job Control to Cold Log and Change the Password for User SQLDBA
ARIS71OD	Job Control to Format the DB2 Server for VSE Logs
ARIS71PD	Job Control to Create the Version 6 Release 1 System Catalog
ARIS71QD	Job control to Create the DBS Utility Package
ARIS71RD	Job Control to Update the DB2 Server for VSE System
ARIS71SD	Job Control to Migrate the Help Text Tables
ARIS71TD	Job Control to Reload the English Help Text
ARIS71VD	Job Control to Change the Password for User SQLDBA
ARIS71WD	Job Control to Reload the CCSID-Related Phases Package
ARIS711D	List Primary Keys to be Dropped and Recreated
ARIS712D	Enable DRDA Server Support
ARIS713D	Remove DRDA Server Support
ARIS714D	Linkedit LE/VSE Abend Checking Support
ARIS715D	Job Control to Enable DRDA AR Support
ARIS716D	Job Control to Remove DRDA AR Support
ARIS717D	Job Control to Define VSAM Preprocessor Bind File
ARIS718D	Job Control to define SQLGLOB VSAM file
ARIS719D	Job Control to define BINDWKF VSAM file
ARIS71GZ	Job Control to Start DB2 Server for VSE Migration in Multiple User Mode
ARIS71KZ	Load Fips Flagger
ARIS71LZ	Reload ISQL
ARIS71MZ	Revoke allusers connect
ARIS71NZ	Reset SQLDBA Password

You may punch the Z-type source members presented in this appendix using the JCL in Figure 81 on page 99. Replace **XXXXXXXX** with the name of a member.

```
// JOB PUNCH ZTYPE
* * * * *
*
* PURPOSE: JOBSTREAM TO PUNCH OUT MEMBER XXXXXXXX.Z
*
* * * * *
// EXEC LIBR,PARM='MSHP'
ACCESS SUBLIB=PRD2.DB2710
PUNCH XXXXXXXX.Z
/*
/ &
```

Figure 81. Example of JCL Required to Punch Z-Type Members

11.0 Appendix F. Additional CICS and VSE Updates for the DB2 Server System

Chapters 2 and 3 of this manual presented the basic CICS and VSE requirements for DB2 Server for VSE. This appendix describes additional entries you may choose to make. Only the CICS and VSE entries related to DB2 Server for VSE are described here; for information about CICS entries to control access to ISQL, see the *DB2 Server for VSE System Administration* manual.

This appendix is not a tutorial on CICS or VSE installation and customization. For complete descriptions of product usage, refer to the applicable CICS and VSE manuals.

11.1 Additional Updates Required for the CICS Monitoring Facility

If DB2 Server for VSE will be used in an online environment, and if your system will use the CICS Monitoring Facility, update these CICS tables:

DFHJCT	Journal Control Table
DFHMCT	Monitor Control Table
DFHFCT	File Control Table
DFHSIT	System Initialization Table.
DFHTCT	Terminal Control Table

These entries are described in the following sections.

11.1.1 DFHJCT Entries

Define a journal used for the CICS system log in the DFHJCT. Specify JFILEID=SYSTEM in a DFHJCT TYPE=ENTRY macro.

Also, define a journal used to record the monitoring facility output data in a DFHJCT TYPE=ENTRY macro as a user journal. Specify a JFILEID value between 02 and 99. Specify FORMAT=SMF for the user journal so that the SMF block format is used instead of the CICS block format.

Figure 82 on page 101 shows an example of how to code your DFHJCT. Here, a CICS system log is allocated to a 3380 DASD device, and an DB2 Server user journal is assigned to a tape device.

```

DFHJCT TYPE=INITIAL,SUFFIX=jj      (1)
DFHJCT TYPE=ENTRY,                X
      JFILEID=SYSTEM,              X
      BUFSIZE=1024,                X
      BUFSUV=1024,                 X
      JOUROPT=(CRUCIAL,INPUT),     (2) X
      JTYPE=DISK1,                  X
      OPEN=INITIAL,                 X
      DEVADDR=sysxxx,              (3) X
JDEVICE=3380 X
DFHJCT TYPE=ENTRY,                X
      JFILEID=nn,                  (4) X
      BUFSIZE=4096,                X
      BUFSUV=4096,                 X
      FORMAT=SMF,                  X
      JTYPE=TAPE1,                  X
      OPEN=INITIAL,                 X
      DEVADDR=sysyyy,              (5)
      JDEVICE=TAPE
DFHJCT TYPE=FINAL
END DFHJCTBA

```

Figure 82. DFHJCT Examples for CICS Monitoring Facility

Notes for Figure 82:

- CICS journal files must be formatted before use. See the CICS manuals for information on CICS journal files.
- (1) The SUFFIX value **jj** must be supplied in the DFHSIT JCT=**jj** parameter.
 - (2) Use of the **CRUCIAL** parameter causes the CICS system to ABEND if the log is inaccessible. This condition usually occurs because of a permanent I/O error which makes the log unreadable. Consequently, it may not be possible to correctly recover all resources.

An alternative and preferable procedure is not to specify **CRUCIAL**, in which case the operator is notified with a DFH4513 message, and the CICS system continues. The operator should then perform a non-immediate shutdown of the CICS system, but before starting it again with a new log, should backup recoverable resources so the backups are properly synchronized with the new log.
 - (3) **sysxxx** is the logical unit address for the CICS system log journal (JFILEID=SYSTEM) assigned to a 3380 DASD file.
 - (4) The JFILEID value **nn** must be between 02 and 99. This value must also be supplied as the DFHMCT TYPE=RECORD entry DATASET parameter value.
 - (5) **sysyyy** is the logical unit address for the DB2 Server user journal (JFILEID=**nn**) assigned to a tape file.

11.1.2 DFHMCT Entries

Figure 83 on page 102 shows an example of how to code your DFHMCT to activate all the DB2 Server clocks and counters. Refer to the DB2 Server for VSE & VM Performance Tuning Handbook for a description of these clocks and counters.

```

DFHMCT TYPE=INITIAL,SUFFIX=mm           (1)
*
* CLOCK/COUNTER FOR TIME WAITING FOR A LINK
*
DFHMCT TYPE=EMP,ID=(PP,16),CLASS=PERFORM,PERFORM=SCLOCK(1)   (2)
DFHMCT
TYPE=EMP,ID=(PP,17),CLASS=PERFORM,PERFORM=PCLOCK(1)
*
* TIME USER HOLDS A LINK
*
DFHMCT TYPE=EMP,ID=(PP,18),CLASS=PERFORM,PERFORM=SCLOCK(2)
DFHMCT TYPE=EMP,ID=(PP,19),CLASS=PERFORM,PERFORM=PCLOCK(2)
*
* TIME IN DB2 Server for VSE PARTITION
*
DFHMCT TYPE=EMP,ID=(PP,20),CLASS=PERFORM,PERFORM=SCLOCK(3)
DFHMCT TYPE=EMP,ID=(PP,21),CLASS=PERFORM,PERFORM=PCLOCK(3)
*
* DB2 Server FUNCTION COUNTERS (4 COUNTERS) FOR LINK USAGE AND
ALLOCATION
*
DFHMCT
TYPE=EMP,ID=(PP,22),CLASS=PERFORM,PERFORM=(MLTCNT(1,4))
*
* CICS/VS USER JOURNAL
*
DFHMCT
TYPE=RECORD,CLASS=PERFORM,DATASET=nn,MAXBUF=2040,FREQ=100   (3)
DFHMCT TYPE=FINAL
END

```

Figure 83. DFHMCT Example for CICS Monitoring Facility

Notes for Figure 83:

- (1) The DFHMCT TYPE=**INITIAL** macro defines the SUFFIX value **mm** to be used for the DFHSIT MCT parameter value.
- (2) The DFHMCT TYPE=**EMP** macros define clocks and counters to record the DB2 Server monitored events.
- (3) The DFHMCT TYPE=**RECORD** macro identifies the CICS user journal to which the data is to be sent for each class of data being collected (in this case, the performance class). The DATASET value **nn** specified must correspond to the DFHJCT JFILEID value specified for the user journal.

To include support for the CICS Monitoring Facility, use the CICS RDO tool (CEDA):

```

CEDA ADD GROUP(DFHSTAND) LIST(VSELIST)
CEDA ADD GROUP(DFHJRNL) LIST(VSELIST)

```

Replace VSELIST with the value specified for GRPLIST in your DFHSIT or CICS startup JCL.

11.1.3 DFHSIT Entries

The DFHSIT macro must include:

- `CMP=YES` to identify the monitoring program.
- `JCP=2$` to identify journal control programs without dynamic transaction backout.
- `JCT=(jj<,...>)` where `jj` is the SUFFIX parameter value specified in the DFHJCT macro.
- `MCT=mm` where `mm` is the SUFFIX parameter value specified in the DFHMCT macro.
- `MONITOR=PER` to record performance class information. The operator can later use the CSTT transaction to activate or deactivate any of the monitoring classes. For example:

```
CSTT MONITOR,ON=PER
```

11.2 Additional Updates for DB2 Server Accounting

If DB2 Server accounting is to be used, you must:

- Provide CICS Restart Resynchronization capability, as described under "CICS Restart Resynchronization Support".
- Include VSE/ESA job accounting. The parameter `JA=YES` must be specified on the IPL SYS command.

11.3 Additional Updates for CIRB Auto-Initiation

If CICS sequential device support is to be used to auto-initiate the CIRB transaction, update the CICS DFHTCT table.

11.3.1 DFHTCT Entries Required for Card Reader Line Printer Support

When a CRLP (card reader, line printer) device is defined in the DFHTCT, the CIRB transaction can be automatically executed by including the CIRB statement in the CICS startup job stream.

Figure 84 on page 104 shows an example of how you might code your DFHTCT entry for CRLP support.

DFHTCT TYPE=SDSCI,	X
DEVADDR=SYSIPT,	X
DEVICE=2540,	X
DSCNAME=READER	
DFHTCT TYPE=SDSCI,	X
DEVADDR=SYSLST,	X
DEVICE=1403,	X
DSCNAME=PRINTER	
DFHTCT TYPE=LINE,	X
ACCMETH=BSAM,	X
TRMTYPE=CRLP,	X
ISADSCN=READER,	X
OSADSCN=PRINTER,	X
INAREAL=80	
DFHTCT TYPE=TERMINAL,	X
TRMIDNT=SAMA,	X
TRMTYPE=CRLP,	X
TRMSTAT=TRANSCIVE	

Figure 84. DFHTCT Examples for CRLP Support

After the CRLP device has been defined in the DFHTCT, the CIRB statement can be included in the CICS startup job stream. Code it just as you would if entering it from a terminal. Include '\ ' at the end of the statement to indicate the end of data. Following is an example of auto-initiating CIRB using CRLP support.

```
// EXEC DFHSIP,SIZE=nnnnK
CIRB PASSWORD,3,PRODCICS,0\
/*
```

Figure 85. Auto-initiating CIRB using CRLP support

When the CICS system is initialized, the CIRB transaction is automatically invoked. Do not include a CSSF GOODNIGHT statement following the CIRB statement. This allows the CIRB statement to be processed in all CICS startup modes (COLD, AUTO, or EMER).

11.3.2 DFHTCT Entries Required for Sequential DASD Support

When a sequential DASD device is defined in the DFHTCT, the CIRB statement can be read from a sequential DASD data set.

Figure 86 on page 105 shows an example of how you might code your DFHTCT entry for sequential DASD support.

DFHTCT TYPE=SDSCI,	X
DEVADDR=SYS001,	X
DEVICE=2314,	X
DSCNAME=DISKIN1	
DFHTCT TYPE=SDSCI,	X
DEVADDR=SYS006,	X
DEVICE=2314,	X
DSCNAME=DISKOT1	
DFHTCT TYPE=LINE,	X
ACCMETH=SEQUENTIAL,	X
TRMTYPE=DASD,	X
ISADSCN=DISKIN1,	X
OSADSCN=DISKOT1,	X
INAREAL=80	
DFHTCT TYPE=TERMINAL,	X
TRMIDNT=SAMB,	X
TRMSTAT=(TRANSCIVE)	

Figure 86. DFHTCT Examples for Sequential DASD Support

To use sequential DASD support, two sequential DASD data sets must be defined. These can be either Sequential Access Method (SAM) data sets or SAM-managed VSAM data sets.

The input data set (DISKIN1 in Figure 84 on page 104) must contain the CIRB statement. Depending upon the data set type, a utility such as DITTO or VSAM IDCAMS can be used to load the CIRB statement to the input data set. Load the CIRB statement just as you would if entering it from a terminal. Include "\ " at the end the statement to indicate the end of data. The output data set (DISKOT1 in Figure 85 on page 104) contains the messages from the CIRB initialization process.

When DASD data sets are used to simulate a CICS terminal, provide DLBL, EXTENT, and ASSGN job control statements (depending upon the access method). When the CICS system is initialized, the CIRB statement is automatically invoked. Do not include a CSSF GOODNIGHT statement following the CIRB statement. This allows the CIRB statement to be processed in all CICS startup modes (COLD, AUTO, or EMER).

11.4 Additional Updates Required for the Online Resource Adapter DRDA Router Tracing

DB2 Server for VSE uses VSAM files (or VSE/VSAM Space Management for the SAM feature) to store trace records. CICS/VSE treats SAM files as **Extrapartition Transient Data**. Transient data queues are called **destinations**. They must be predefined in a table known as the destination control table (DCT).

Data directed to of from an external destination is called extrapartition data and consists of sequential records that are fixed-length or variable-length, blocked or unblocked. The record format for an extrapartition destination must be defined in the DCT by the system programmer.

Note that Transient data queue definitions point to an associated data definition (DLBL/TLBL) statement in the CICS start-up JCL.

If Online Resource Adapter DRDA Router Tracing will be used in an online environment (for example, the SQLGLOB parameter TRACERA or TRACEDRRM or TRACECONV is ON), the following steps are required for creating trace records:

1. Define the SAM file to CICS. This involves updating the DCT.
2. Add the appropriate TLBL, DLBL, EXTENT and ASSGN JCL statements to the CICS startup JCL to define file ARITRAC.

Figure 87 shows an example of how to code your DFHDCT to define the Resource Adapter trace file to CICS.

```

* Use one of the following SDSCI entries - not BOTH
* This definition is used if tracing to TAPE
DFHDCT  TYPE=SDSCI,      (1)          X
        BLKSIZE=4096,          X
        BUFNO=1,              X
        DSCNAME=ARITRAC,       X
        RECFORM=VARBLK,        X
        DEVICE=TAPE,           X
        DEVADDR=SYS018, (2)          X
        FILABL=STD,            X
        ERROPT=IGNORE,         X
        RECSIZE=4088,          X
        REWIND=UNLOAD,         X
        TYPEFLE=OUTPUT
* This definition is used if tracing to Disk

DFHDCT  TYPE=SDSCI,      (1)          X
        BLKSIZE=4096,          X
        BUFNO=1,              X
        DSCNAME=ARITRAC,       X
        RECFORM=VARBLK,        X
        DEVICE=DISK,           X
        ERROPT=IGNORE,         X
        RECSIZE=4088,          X
        TYPEFLE=OUTPUT

DFHDCT  TYPE=EXTRA,       X
        DESTID=ARIT,          X
        DSCNAME=ARITRAC,       X
        OPEN=INITIAL, (3)       X
        RESIDNT=YES,          X
        RSL=PUBLIC (4)

```

Figure 87. DFHDCT Example

Notes:

- (1) The "TYPE=SDSCI" definitions do not include a **MODNAME=name** parameter. Because this operand is omitted, a standard VSE name is generated for calling the logic module when the DCT is link-edited.
- (2) Code **DEVADDR** with the symbolic unit address. This operand is not required for disk data sets when the symbolic address is provided through the **EXTENT** system control statement.

- (3) **OPEN=DEFERRED** may be used. In this case, the command **CEMT SET QUEUE (ARIT) ENABLED OPEN** must be used to open the file.
- (4) **RSL=0** or **RSL=number** may also be used. In these cases, any transactions defined with **RSLC(YES)** may not be able to access the **ARITRAC** file. See the **CICS/VSE Resource Definition (Macro)** manual for more details.

The output of the Online Resource DRDA Router trace can be directed to either tape or disk.

To direct the output to tape, include a **TLBL** statement in your CICS startup job control for generating a trace. An example of a **TLBL** statement for a trace output file is as follows:

```
// ASSGN SYS018,181  
// TLBL ARITRAC,'DB2.ARITRAC'
```

To direct the output to disk, include a **DLBL**, an **EXTENT**, and an **ASSGN** statement in the CICS startup job control for generating a trace.

The following is an example of the job control required for a trace output DASD file.

```
// ASSGN SYS018,DISK,VOL=&vol,SHR  
// DLBL ARITRAC,'DB2.ARITRAC',0,SD  
// EXTENT SYS018,&vol,1,0,195,90
```

12.0 Bibliography

This bibliography lists publications that are referenced in this manual or that may be helpful.

Related Publications

- DB2 Server for VSE & VM Data Restore, SC09-2991
- IBM SQL Reference, Version 2, Volume 1, SC26-8416
- IBM SQL Reference, SC26-8415

Other Distributed Data Publications

- DRDA: Every Manager's Guide, GC26-3195
- IBM Distributed Data Management (DDM) Architecture, Architecture Reference, Level 3, SC21-9526
- IBM Distributed Data Management (DDM) Architecture, Implementation Programmer's Guide, SC21-9529
- VM/Directory Maintenance Licensed Program Operation and User Guide Release 4, SC23-0437
- IBM Distributed Relational Database Architecture Reference, SC26-4651
- IBM Systems Network Architecture, Format and Protocol
- SNA LU 6.2 Reference: Peer Protocols
- Reference Manual: Architecture Logic for LU Type 6.2
- IBM Systems Network Architecture, Logical Unit 6.2 Reference: Peer Protocols
- Distributed Data Management (DDM) List of Terms

CCSID Publications

- Character Data Representation Architecture, Executive Overview, GC09-2207
- Character Data Representation Architecture Reference and Registry, SC09-2190

C/370 Publications

- IBM C/370 Installation and Customization Guide, GC09-1387
- IBM C/370 Programming Guide, SC09-1399

Communication Server for OS/2 Publications

- Up and Running!, GC31-8189
- Network Administration and Subsystem Management Guide, SC31-8181
- Command Reference, SC31-8183
- Message Reference, SC31-8185
- Problem Determination Guide, SC31-8186

Distributed Database Connection Services (DDCS) Publications

- DDCS User's Guide for Common Servers, S20H-4793
- DDCS for OS/2 Installation and Configuration Guide, S20H-4795

VTAM Publications

- VTAM Messages and Codes, SC31-6493
- VTAM Network Implementation Guide, SC31-6494
- VTAM Operation, SC31-6495
- VTAM Programming, SC31-6496
- VTAM Programming for LU 6.2, SC31-6497
- VTAM Resource Definition Reference, SC31-6498
- VTAM Resource Definition Samples, SC31-6499

CSP/AD and CSP/AE Publications

- Developing Applications, SH20-6435
- CSP/AD and CSP/AE Installation Planning Guide, GH20-6764
- Administering CSP/AD and CSP/AE on VM, SH20-6766
- Administering CSP/AD and CSP/AE on VSE, SH20-6767
- CSP/AD and CSP/AE Planning, SH20-6770
- Cross System Product General Information, GH23-0500

Query Management Facility (QMF) Publications

- QMF General Information, GC26-4713
- QMF VSE/ESA Setup and Usage Guide, GG24-4196
- Managing QMF for VSE/ESA, SC26-3252
- Installing QMF on VSE/ESA, SC26-3254
- QMF Learner's Guide, SC26-4714
- QMF Advanced User's Guide, SC26-4715
- QMF Reference, SC26-4716
- Installing QMF on VM, SC26-4718
- QMF Application Development Guide, SC26-4722
- QMF Messages and Codes, SC26-4834
- Using QMF, SC26-8078
- Managing QMF for VM/ESA, SC26-8219

DL/I DOS/VS Publications

- DL/I DOS/VS Application Programming, SH24-5009

COBOL Publications

- VS COBOL II Migration Guide for VSE, GC26-3150
- VS COBOL II Migration Guide for MVS and CMS, GC26-3151
- VS COBOL II General Information, GC26-4042
- VS COBOL II Language Reference, GC26-4047
- VS COBOL II Application Programming Guide, SC26-4045
- VS COBOL II Application Programming Debugging, SC26-4049
- VS COBOL II Installation and Customization for CMS, SC26-4213
- VS COBOL II Installation and Customization for VSE, SC26-4696
- VS COBOL II Application Programming Guide for VSE, SC26-4697

Systems Network Architecture (SNA) Publications

- SNA Transaction Programmer's Reference Manual for LU Type 6.2, GC30-3084
- SNA Format and Protocol Reference: Architecture Logic for LU Type 6.2, SC30-3269
- SNA LU 6.2 Reference: Peer Protocols, SC31-6808
- SNA Synch Point Services Architecture Reference, SC31-8134

Miscellaneous Publications

- IBM 3990 Storage Control Planning, Installation, and Storage Administration Guide, GA32-0100
- Dictionary of Computing, ZC20-1699
- APL2 Programming: Using Structured Query Language, SH21-1056
- ESA/390 Principles of Operation, SA22-7201

Related Feature Publications


- DB2 Replication Guide and Reference, SC26-9920
- Control Center Operations Guide for VSE, GC09-2992

13.0 Reader's Comments

Program Directory for DB2 Server for VSE Version 7 Release 1, Modification Level 0

You may use this form to comment about this document, its organization, or subject matter. Please understand that your feedback is of importance to IBM, but IBM makes no promises to always provide a response to your feedback.

For each of the topics below please indicate your satisfaction level by circling your choice from the rating scale. If a statement does not apply, please circle N.

RATING SCALE						
very satisfied					very dissatisfied	not applicable
1	2	3	4	5	N	

	Satisfaction					
	1	2	3	4	5	N
Ease of product installation	1	2	3	4	5	N
Time required to install the product	1	2	3	4	5	N
Contents of program directory	1	2	3	4	5	N
Readability and organization of program directory tasks	1	2	3	4	5	N
Necessity of all installation tasks	1	2	3	4	5	N
Accuracy of the definition of the installation tasks	1	2	3	4	5	N
Technical level of the installation tasks	1	2	3	4	5	N
Installation verification procedure	1	2	3	4	5	N
Ease of customizing the product	1	2	3	4	5	N
Ease of migrating the product from a previous release	1	2	3	4	5	N
Ease of putting the system into production after installation	1	2	3	4	5	N
Ease of installing service	1	2	3	4	5	N

- Did you order this product as an independent product or as part of a package?
 - Independent
 - Package

What type of package was ordered?

- CustomPac
 - FunctionPac
 - SystemPac
- System Delivery Offering (SDO)
- Other - Please specify type: _____

- Is this the first time your organization has installed this product?
 - Yes
 - No
- Were the people who did the installation experienced with the installation of VM products using VMSES/E?
 - Yes
 - How many years of experience do they have? _____
 - No
- How long did it take to install this product? _____
- If you have any comments to make about your ratings above, or any other aspect of the product installation, please list them below:

Please provide the following contact information:

Name and Job Title

Organization

Address

Telephone

Thank you for your participation.

Please send the completed form to the following address, or give to your IBM representative who will forward it to the DB2 Server for VSE Development group:

IBM Canada Ltd.
DB2 Server for VSE & VM
2S/240/1150/TOR
1150 Eglinton Avenue East
North York, Ontario, Canada. M3C 1H7

Communicating Your Comments to IBM

DB2 Server for VSE Version 7
VSE/ESA

Publication No. GI10-4999-00

If there is something you like—or dislike—about this book, please let us know. You can use one of the methods listed below to send your comments to IBM. If you want a reply, include your name, address, and telephone number. If you are communicating electronically, include the book title, publication number, page number, or topic you are commenting on.

The comments you send should only pertain to the information in this book and its presentation. To request additional publications or to ask questions or make comments about the functions of IBM products or systems, you should talk to your IBM representative or to your IBM authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

If you are mailing a readers' comment form (RCF) from a country other than the United States, you can give it to the local IBM branch office or IBM representative for postage-paid mailing.

- If you prefer to send comments by mail, use the RCF at the back of this book.
- If you prefer to send comments by FAX, use this number:
 - United States and Canada: 416-448-6161
 - Other countries: (+1)-416-448-6161
- If you prefer to send comments electronically, use the network ID listed below. Be sure to include your entire network address if you wish a reply.
 - Internet: torrcf@ca.ibm.com

Readers' Comments — We'd Like to Hear from You

DB2 Server for VSE Version 7
VSE/ESA

Publication No. GI10-4999-00

Overall, how satisfied are you with the information in this book?

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Overall satisfaction	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

How satisfied are you that the information in this book is:

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Accurate	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Complete	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Easy to find	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Easy to understand	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Well organized	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Applicable to your tasks	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

Please tell us how we can improve this book:

Thank you for your responses. May we contact you? Yes No

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

Name

Address

Company or Organization

Phone No.



Fold and Tape

Please do not staple

Fold and Tape

PLACE
POSTAGE
STAMP
HERE

IBM Canada Ltd. Laboratory
DB2 Server for VSE & VM
2S/240/1150/TOR
1150 EGLINTON AVENUE EAST
NORTH YORK ONTARIO CANADA M3C 1H7

Fold and Tape

Please do not staple

Fold and Tape



Program Number: 5697-F42 5821
5822
5824
6016

Printed in U.S.A.

GI10-4999-00

