

# **Connect:Direct<sup>®</sup> for UNIX**

## **Getting Started Guide**

**Version 4.0**

**Connect:Direct for UNIX Getting Started Guide  
Version 4.0**

**First Edition**

(c) Copyright 1999-2008 Sterling Commerce, Inc. All rights reserved. Additional copyright information is located at the end of this guide.

**STERLING COMMERCE SOFTWARE**

**\*\*\*TRADE SECRET NOTICE\*\*\***

THE CONNECT:DIRECT SOFTWARE ("STERLING COMMERCE SOFTWARE") IS THE CONFIDENTIAL AND TRADE SECRET PROPERTY OF STERLING COMMERCE, INC., ITS AFFILIATED COMPANIES OR ITS OR THEIR LICENSORS, AND IS PROVIDED UNDER THE TERMS OF A LICENSE AGREEMENT. NO DUPLICATION OR DISCLOSURE WITHOUT PRIOR WRITTEN PERMISSION. RESTRICTED RIGHTS.

This documentation, the Sterling Commerce Software it describes, and the information and know-how they contain constitute the proprietary, confidential and valuable trade secret information of Sterling Commerce, Inc., its affiliated companies or its or their licensors, and may not be used for any unauthorized purpose, or disclosed to others without the prior written permission of the applicable Sterling Commerce entity. This documentation and the Sterling Commerce Software that it describes have been provided pursuant to a license agreement that contains prohibitions against and/or restrictions on their copying, modification and use. Duplication, in whole or in part, if and when permitted, shall bear this notice and the Sterling Commerce, Inc. copyright notice. As and when provided to any governmental entity, government contractor or subcontractor subject to the FARs, this documentation is provided with RESTRICTED RIGHTS under Title 48 52.227-19. Further, as and when provided to any governmental entity, government contractor or subcontractor subject to DFARs, this documentation and the Sterling Commerce Software it describes are provided pursuant to the customary Sterling Commerce license, as described in Title 48 CFR 227-7202 with respect to commercial software and commercial software documentation.

These terms of use shall be governed by the laws of the State of Ohio, USA, without regard to its conflict of laws provisions. If you are accessing the Sterling Commerce Software under an executed agreement, then nothing in these terms and conditions supersedes or modifies the executed agreement.

Where any of the Sterling Commerce Software or Third Party Software is used, duplicated or disclosed by or to the United States government or a government contractor or subcontractor, it is provided with RESTRICTED RIGHTS as defined in Title 48 CFR 52.227-19 and is subject to the following: Title 48 CFR 2.101, 52.227-19, 227.7201 through 227.7202-4, FAR 52.227-14, and FAR 52.227-19(c)(1-2) and (6/87), and where applicable, the customary Sterling Commerce license, as described in Title 48 CFR 227-7202 with respect to commercial software and commercial software documentation including DFAR 252.227-7013, DFAR 252,227-7014, DFAR 252.227-7015 and DFAR 252.227-7018, all as applicable.

The Sterling Commerce Software and the related documentation are licensed either "AS IS" or with a limited warranty, as described in the Sterling Commerce license agreement. Other than any limited warranties provided, NO OTHER WARRANTY IS EXPRESSED AND NONE SHALL BE IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR USE OR FOR A PARTICULAR PURPOSE. The applicable Sterling Commerce entity reserves the right to revise this publication from time to time and to make changes in the content hereof without the obligation to notify any person or entity of such revisions or changes.

Connect:Direct is a registered trademark of Sterling Commerce. Connect:Enterprise is a registered trademark of Sterling Commerce, U.S. Patent Number 5,734,820. All Third Party Software names are trademarks or registered trademarks of their respective companies. All other brand or product names are trademarks or registered trademarks of their respective companies.

---

Sterling Commerce, Inc.  
4600 Lakehurst Court Dublin, OH 43016-2000 \*  
614/793-7000

---

# Contents

---

## Chapter 1 About Connect:Direct for UNIX 7

|   |    |
|---|----|
| Server Components . . . . .                                 | 7  |
| Process Manager . . . . .                                   | 7  |
| Command Manager . . . . .                                   | 8  |
| Session Manager . . . . .                                   | 8  |
| File Agent . . . . .  | 8  |
| Connect:Direct Secure+ Option for UNIX . . . . .            | 9  |
| User Interfaces . . . . .                                   | 9  |
| Applications Programming Interface . . . . .                | 9  |
| Command Line Interface . . . . .                            | 9  |
| Sterling Control Center . . . . .                           | 10 |
| Connect:Direct Browser User Interface . . . . .             | 11 |
| Connect:Direct Concepts . . . . .                           | 12 |
| Local and Remote Nodes . . . . .                            | 12 |
| Processes . . . . .   | 12 |
| Transmission Control Queue . . . . .                        | 13 |
| Commands . . . . .  | 14 |
| Network Map . . . . .                                       | 14 |
| User Authorization . . . . .                                | 15 |
| Process Restart . . . . .                                   | 15 |
| Archive Statistics Files . . . . .                          | 17 |
| Sample Processes, Shell Scripts, and API Programs . . . . . | 17 |
| Connect:Direct for UNIX Files . . . . .                     | 19 |
| Connect:Direct for UNIX Configuration Files . . . . .       | 19 |
| Connect:Direct for UNIX Directory Structure . . . . .       | 20 |
| Connect:Direct for UNIX Documentation . . . . .             | 22 |
| About This Guide . . . . .                                  | 22 |
| Task Overview . . . . .                                     | 23 |

---

## Chapter 2 Installing Connect:Direct for UNIX 25

|   |    |
|---|----|
| Before You Begin . . . . .  | 25 |
| Configuration Types . . . . .   | 25 |
| Preparing to Install Connect:Direct for UNIX in a Cluster Environment . . . . .                     | 25 |
| High-Availability Cluster Environments . . . . .  | 26 |
| Load-Balancing Cluster Environments . . . . .   | 26 |
| Preparing to Install Connect:Direct for UNIX on the Linux for zSeries<br>Operating System . . . . . | 28 |
| Installing Connect:Direct for UNIX . . . . .  | 29 |

|  |    |
|--|----|
| Customizing Connect:Direct for UNIX . . . . .  | 32 |
| Setting Up the Connect:Direct for UNIX Server. . . . .                                 | 33 |
| Defining the Connect:Direct Node Name . . . . .  | 34 |
| Defining the Initialization Parameters File. . . . .                                   | 34 |
| Defining the Network Map File . . . . .  | 35 |
| Customizing the User Authorization Information File . . . . .                          | 36 |
| Connect:Direct Creates an Authentication Key File . . . . .                            | 38 |
| Setting Up the Connect:Direct for UNIX Client . . . . .                                | 38 |
| Customizing the Client Configuration File . . . . .                                    | 39 |
| Customizing the Client Authentication Key File . . . . .                               | 39 |
| Configuring Connect:Direct for UNIX Using Root Privilege . . . . .                     | 40 |
| Installing File Agent . . . . .  | 43 |
| Installing Secure+ Option . . . . .  | 47 |
| Configuring SNA Support for Connect:Direct for UNIX . . . . .                          | 51 |
| Defining High-Availability Settings in the Configuration Files . . . . .               | 51 |
| Additional Configuration Requirements in a SunCluster 3.X Environment . . . . .        | 52 |
| Additional Configuration Requirements in a SunCluster 2.2 Environment . . . . .        | 53 |
| Additional Configuration Requirements for IBM HACMP . . . . .                          | 54 |
| Additional Configuration Requirements for Hewlett-Packard<br>MC/ServiceGuard . . . . . | 54 |
| Verifying the Installation . . . . .   | 54 |

---

**Chapter 3 Managing Files with Connect:Direct File Agent** **57**

|   |    |
|---|----|
| Connect:Direct File Agent . . . . .                                       | 57 |
| Running File Agent . . . . .  | 58 |
| File Agent Logging Capabilities. . . . .                                  | 59 |
| File Agent Configuration Interface and Help . . . . .                     | 59 |
| Planning the File Agent Configuration . . . . .                           | 59 |
| Connect:Direct File Agent Configuration Examples. . . . .                 | 63 |
| Detecting a File Added to a Watched Directory on an z/OS System . . . . . | 63 |
| Detecting a File by File Size on a Windows System . . . . .               | 63 |
| Detecting a System Event by Title on a Windows System . . . . .           | 65 |
| Passing the UNIX Pathname for a Detected File to a Process. . . . .       | 66 |

---

**Appendix A Installation Worksheets** **67**

|  |    |
|--|----|
| Installation Worksheet . . . . .   | 68 |
| Customization Worksheet . . . . .  | 68 |
| User Authorization Information File Worksheet. . . . .                               | 69 |
| Remote User Information Record . . . . .   | 69 |
| Local User Information Record . . . . .  | 70 |
| CLI/API Configuration File Worksheet . . . . .                                       | 74 |
| Network Map Remote Node Information File Worksheet<br>(TCP/IP and UDT Only). . . . . | 75 |
| Server Authentication Key File Worksheet . . . . .                                   | 76 |
| Client Authentication Key File Worksheet . . . . .                                   | 76 |

## Appendix B SNA LU6.2 Connectivity 77

---

|   |     |
|---|-----|
| About SNA LU6.2 Connections . . . . .   | 77  |
| Supported Interfaces . . . . .  | 77  |
| Session Support . . . . .   | 77  |
| APPC Requirements . . . . .   | 78  |
| Configuration Requirements . . . . .  | 78  |
| SNA Considerations . . . . .  | 78  |
| Installing and Configuring the AIX SNA Server . . . . .                       | 79  |
| Manually Configuring the AIX SNA Server . . . . .                             | 79  |
| About the Configuration Script . . . . .                                      | 80  |
| Running the Configuration Script . . . . .                                    | 81  |
| HP SNAplus2 Configuration Requirements . . . . .                              | 83  |
| SNAP-IX SNA Gateway Support Configuration Requirements . . . . .              | 83  |
| Brixton 4.1 SNA for Sun Solaris Requirements . . . . .                        | 87  |
| Configuring BrxGMAN Software . . . . .  | 87  |
| Configuring BrxGMI Software . . . . .   | 89  |
| Configuring BrxPU21 Software . . . . .  | 90  |
| Starting BrxGMAN . . . . .  | 91  |
| Sample Brixton BrxPU2.1 Configuration . . . . .                               | 92  |
| SunLink SNA 9.1 for Sun Solaris Configuration Requirements . . . . .          | 93  |
| Sample z/OS Definitions for an LU6.2 Connection . . . . .                     | 98  |
| Token Ring 3174-R Gateway Controller Configuration . . . . .                  | 99  |
| Token Ring 3745 Token Ring Interface Coupler (TIC) Configuration . . . . .    | 101 |
| VTAM Application Definition . . . . .   | 102 |
| VTAM Logmode Table Entries . . . . .  | 102 |
| NTRI Switched Major Node Definition . . . . .                                 | 103 |
| ILU CDRSC Definitions . . . . .   | 103 |
| Connect:Direct Remote Node Entry . . . . .                                    | 104 |
| Special Considerations . . . . .  | 104 |
| Required Changes to the File Specified with the comm.info Parameter . . . . . | 104 |
| Obtaining Traces for the Brixton LU6.2 API and SunLink P2P . . . . .          | 105 |
| Stopping Connect:Direct on SNA Systems . . . . .                              | 105 |
| Connectivity Between IBM pSeries and i5/OS Systems . . . . .                  | 105 |
| AIX SNA Error Messages . . . . .  | 105 |

## Appendix C Connect:Direct for UNIX Manual Pages 107

---

|  |     |
|--|-----|
| Setting Up Connect:Direct for UNIX Manual Pages . . . . .                              | 107 |
| Combining Manual Pages . . . . .   | 107 |
| Displaying Connect:Direct Manual Pages . . . . .                                       | 108 |
| Accessing Connect:Direct Manual Pages . . . . .  | 108 |
| Using MANPATH in the Bourne Shell . . . . .  | 108 |
| Using MANPATH in the C Shell . . . . .   | 108 |
| Accessing Manual Pages on an IBM pSeries or Sun SPARC Platform<br>Using BSDI . . . . . | 109 |

Contents

**Glossary** **111**

---

**Index** **117**

---

---

# About Connect:Direct for UNIX

Connect:Direct links technologies and moves all types of information between networked systems and computers. It manages high-performance transfers by providing such features as automation, reliability, efficient use of resources, application integration, and ease of use. Connect:Direct offers choices in communications protocols, hardware platforms, and operating systems. It provides the flexibility to move information among mainframe systems, midrange systems, desktop systems, and LAN-based workstations.

Connect:Direct is based on client-server architecture. The Connect:Direct server components interact with the user interfaces (API, CLI, Connect:Direct Browser User Interface, and Sterling Control Center) to enable you to submit, execute, and monitor Connect:Direct statements and commands.

---

## Server Components

Connect:Direct has the following server components:

### Process Manager

The Process Manager (PMGR) is the daemon that initializes the Connect:Direct server environment. The PMGR provides the following functions:

- ◆ Initializes Connect:Direct
- ◆ Accepts connection requests from Connect:Direct client APIs and remote nodes
- ◆ Creates Command Manager and Session Manager child Processes to communicate with APIs and remote nodes
- ◆ Accepts requests from Command Managers and Session Managers when centralized Connect:Direct functions are required
- ◆ Stops Connect:Direct

---

**Note:** Any application, including End User Applications (EUA), can run on any computer as long as it can connect to the PMGR.

---

## Command Manager

A Command Manager (CMGR) is created for every API connection that is successfully established. The number of Command Managers that a PMGR can create is system-dependent and limited by the number of file descriptors available for each UNIX Process. The number of file descriptors set up by the UNIX operating system may affect Connect:Direct operation. You must define enough file descriptors to handle the number of concurrent Connect:Direct sessions allowed, which can be as many as 999.

The CMGR provides the following functions:

- ◆ Executes commands sent by the API and sends the results back to the API
- ◆ Carries out the Connect:Direct authentication procedure, in conjunction with the API, to determine access to Connect:Direct
- ◆ Interacts with the PMGR when executing commands

## Session Manager

The Session Manager (SMGR) is created and invoked by the PMGR when resources are available and either a Process is ready to run or a remote node requests a connection with a local node. The SMGR provides the following functions:

- ◆ Performs the necessary Connect:Direct work
- ◆ Acts as a primary node (PNODE) and initiates Process execution
- ◆ Acts as a secondary node (SNODE) to participate in a Process initiated by the PNODE

When an SMGR is created to execute a Process submitted to a node, it creates the connection to the remote node. If the SMGR is started by the PMGR to execute local Processes, the SMGR runs each Process on this session until all Processes are completed.

If an SMGR is created because a remote node initiated a connection, the SMGR completes the connection. If the SMGR is started by the PMGR to execute remote Processes, the SMGR executes remote Process steps supplied by the remote SMGR until the remote SMGR completes all of its Processes.

The SMGR depends on the PMGR for Transmission Control Queue (TCQ) services and other centralized services. Refer to the *Transmission Control Queue* on page 13 for an overview of the TCQ.

## File Agent

Connect:Direct File Agent is a feature of Connect:Direct, which provides unattended file management. File Agent monitors *watched* directories to detect new files. When File Agent detects a new file, it either submits a default Process or evaluates the file using rules to override the default Process and to determine which Process to submit. You create rules to submit different Processes based on the following properties:

- ◆ Specific or partial file names
- ◆ File size
- ◆ System events



You create the Processes used by File Agent on Connect:Direct; you cannot create them using File Agent.

To achieve optimum performance, configure File Agent to communicate with the Connect:Direct node where it is installed. File Agent can be installed on UNIX, Windows, and z/OS operating systems. For information to help you plan how to implement File Agent, see the *Managing Files with Connect:Direct File Agent* chapter in your Connect:Direct administration guide or getting started guide. The Connect:Direct File Agent Help contains instructions for configuring File Agent.

## Connect:Direct Secure+ Option for UNIX

The Connect:Direct Secure+ Option application provides enhanced security for Connect:Direct and is available as a separate component. It uses cryptography to secure data during transmission. You select the security protocol to use with Secure+ Option.

To use Connect:Direct Secure+ Option for communications with remote nodes, you must have node records in the Secure+ Option parameters file that duplicate the adjacent node records in the Connect:Direct network map. You can populate the Secure+ Option parameters file from entries defined in an existing network map. For more information about creating the Connect:Direct Secure+ Option parameters file and configuring nodes for Secure+ Option, refer to the *Connect:Direct Secure+ Option for UNIX Implementation Guide*.

---

## User Interfaces

Connect:Direct has the following user interfaces, which enable you to create, submit, and monitor Processes.

### Applications Programming Interface

The UNIX Applications Programming Interface (API) enables you to write programs that work with Connect:Direct. Several API functions are provided to allow an End User Application (EUA) to perform the following tasks:

- ◆ Establish an API connection to the Connect:Direct server
- ◆ Terminate an API connection to the Connect:Direct server
- ◆ Send a command to Connect:Direct
- ◆ Receive responses from commands

### Command Line Interface

The Command Line Interface (CLI) enables you to perform the following tasks:


- ◆ Issue Connect:Direct commands
- ◆ Monitor Processes

The default CLI command prompt is **direct >**. Refer to the *Controlling and Monitoring Processes* chapter in the *Connect:Direct for UNIX User's Guide* for additional information about the CLI.

## Sterling Control Center

Sterling Control Center is a centralized management system that provides operations personnel with continuous enterprise-wide business activity monitoring capabilities for Connect:Direct for z/OS, UNIX, Windows, HP NonStop, and i5OS servers; Connect:Direct Select; and Connect:Enterprise for UNIX and Connect:Enterprise for z/OS servers; and Gentran Integration Suite (GIS). Sterling Control Center enables you to:

- ◆ Manage multiple servers
  - ◆ Group individual servers into server groups for a single view of system-wide activity
  - ◆ View status and statistics on active or completed processing
  - ◆ Suspend, release, stop, and delete Connect:Direct Processes on z/OS, UNIX, Windows, Select, and HP NonStop platforms
  - ◆ Stop Connect:Direct servers on z/OS, Windows, HP NonStop, i5OS, and UNIX platforms.
- ◆ Monitor service levels
  - ◆ View active and completed processes across the servers within your network



- ◆ Receive notification of data delivery events that occur or do not occur as scheduled
- ◆ Define rules that, based on processing criteria, can generate an alert, send an e-mail notification, generate a Simple Network Management Protocol (SNMP) trap to an Enterprise Management System (EMS), run a system command, or issue a server command

- ◆ Monitor for alerts, such as a server failure or a Process not starting on time
- ◆ Create service level criteria (SLCs) that define processing schedules, monitor Processes, files within Processes, and file transfers for compliance with these schedules, and generate alerts when the schedules are not met
- ◆ Analyze key operational metrics
- ◆ Create customized reports to document and analyze processing activity based on criteria you define
- ◆ Validate user authenticity for console-to-engine connections using one or more of four authentication methods, including password validation, host name identification, Windows domain, and TCP/IP address (or three methods in the case of the Web console, which does not support domain authentication)
- ◆ Identify additional Connect:Direct servers that may need to be monitored based on communications with a currently monitored server

Sterling Control Center enhances operational productivity and improves the quality of service by:

- ◆ Ensuring that critical processing windows are met
- ◆ Reducing impact on downstream processing by verifying that expected processing occurs
- ◆ Providing proactive notification for at-risk business processes
- ◆ Consolidating information for throughput analysis, capacity planning, post-processing operational or security audits, and workload analysis
- ◆ Reducing the risk of errors associated with manual system administration, including eliminating individual server logon to view activity, and the need to separately configure each server for error and exception notifications


Sterling Control Center is available for purchase as a separate product. Contact your Sterling Commerce representative to learn more about Sterling Control Center.

## Connect:Direct Browser User Interface

Connect:Direct Browser User Interface allows you to build, submit, and monitor Connect:Direct Processes from an Internet browser, such as Microsoft Internet Explorer.

You can also perform Connect:Direct system administration tasks, such as viewing and changing the network map or initialization parameters, from Connect:Direct Browser. The specific administration tasks that you can perform depend on the Connect:Direct platform that your browser is signed on to and your security level.

Connect:Direct Browser is distributed on CD-ROM with Connect:Direct for z/OS, Connect:Direct for Windows, Connect:Direct for UNIX, and Connect:Direct for HP NonStop. It can also be downloaded from the Sterling Commerce Web site. Connect:Direct Browser is installed on a Web server and can be accessed by administrators and users through a URL. The following example shows the page used to graphically build a Process:



To learn more about Connect:Direct Browser, see the documentation on the Connect:Direct Browser CD-ROM or available online from the Sterling Commerce Documentation Library.

## Connect:Direct Concepts

This section introduces concepts and definitions to help you understand system operations.

### Local and Remote Nodes

Each data transfer involves a local and a remote node. The two servers (local and remote) function together to perform the work. Either Connect:Direct node can initiate the work.

Local and remote node connections are set up in the network map file. Refer to the *Maintaining the Network Map File* chapter in the *Connect:Direct for UNIX Administration Guide* for a description of the network map file.

Connect:Direct must be installed on each node. When Connect:Direct establishes a session between the local node and remote node, the node that initiates the session has primary control (PNODE). The other serves as the partner and has a secondary function (SNODE). The node that initiates the session has primary control, regardless of the direction of information flow. The Process can specify work destined for either the local or remote node. When Connect:Direct establishes a session, the two nodes work together to transfer the information.

### Processes

The Connect:Direct Process language provides instructions for transferring files, running programs, submitting jobs on the adjacent node, and altering the sequence of Process step execution. You can include one or more steps in a Process. A Process consists of a Process definition statement (Process statement) and one or more additional statements. Parameters further qualify Process instructions.

The following table lists Process statements and their functions:

| Process Statement | Function  |
|-------------------|---|
| copy              | Copies files from one node to another.  |
| conditionals      | Alters the sequence of Process execution based on the completion code of previous steps with the <b>if</b> , <b>then</b> , <b>else</b> , <b>endif</b> (end if), <b>goto</b> , and <b>exit</b> statements. |
| process           | Defines general Process characteristics.  |
| run job           | Enables you to specify UNIX commands in a Process. The Process does not wait until the job has finished running before executing the next step in the Process.  |
| run task          | Enables you to specify UNIX commands in a Process. The Process waits until the job has finished running before executing the next step in the Process.  |
| submit            | Starts another Connect:Direct Process to either the local or remote node during execution of a Process.   |
| pend              | Marks the end of a Connect:Direct for UNIX Process.   |

Following is a sample Process:

```

ckpt01 process snode=unix.node
step01 copy from (
        file=file1
        snode
    )
    ckpt=1M
    to (
        file=file2
        disp=new
        pnode
    )
pend;

```

Refer to the Connect:Direct Processes Web site at <http://www.sterlingcommerce.com/documentation/processes/processhome.html> for instructions on building a Process.

## Transmission Control Queue

The Transmission Control Queue (TCQ) controls when Processes run. Connect:Direct stores submitted Processes in the TCQ. The TCQ is divided into four logical queues: Execution, Wait, Timer, and Hold. Processes are run from the Execution queue.

Connect:Direct places a Process in the appropriate queue based on Process statement parameters, such as the **hold**, **retain**, and **startt** parameters.

Connect:Direct runs Processes based on their priority and when the Process is placed in the Execution queue. Processes will run first based on their submitted date, and higher priority Processes are selected for execution ahead of Processes with a lower priority. You can access the queues and manage the Processes through Connect:Direct commands.

Refer to the *Connect:Direct for UNIX User's Guide* for more information on scheduling Processes in the TCQ.

## Commands

You use Connect:Direct commands to submit Processes to the TCQ. You can also use Connect:Direct commands to perform the following tasks:

- ◆ Manage Processes in the queue
- ◆ Monitor and trace Process execution
- ◆ Produce reports on Process activities
- ◆ Stop Connect:Direct operation

The following table lists the commands and their functions:

| Command           | Function   |
|-------------------|--|
| change process    | Changes the status and modifies specific characteristics of a nonexecuting Process in the TCQ. |
| delete process    | Removes a nonexecuting Process from the TCQ.   |
| flush process     | Removes an executing Process from the TCQ.   |
| trace             | Runs Connect:Direct traces.  |
| select process    | Displays or prints information about a Process in the TCQ.                                     |
| select statistics | Displays or prints statistics in the statistics log.   |
| stop              | Stops Connect:Direct operation.  |
| submit            | Submits a Process for execution.   |

For example, the following command submits the Process called **onestep** to the TCQ with a hold status of yes:

```
Direct> submit file=onestep hold=yes;
```


## Network Map

During the transfer of data, the Connect:Direct server where the Process is submitted is the primary node and the secondary node is the remote node (partner). Connect:Direct identifies the remote

nodes that the local node is able to communicate with through the use Connect:Direct network map (or netmap).

The network map includes the names of all the remote nodes that the Connect:Direct local node can communicate with, the paths to contact those remote nodes, and characteristics of the sessions for communication.

The remote Connect:Direct nodes also have network maps for their remote nodes. The following sample displays the corresponding network map entries of UNIX-Dallas, z/OS-Miami, and UNIX-Houston:



## User Authorization

Connect:Direct can authorize local and remote users to perform certain Connect:Direct tasks. In order to use Connect:Direct, each user must have a record defined in the user authorization file, called `userfile.cfg`. Each local user must have a record in the user authorization file, and remote users may be mapped to a local user ID in a proxy relationship.

To provide a method of preventing an ordinary user from gaining root access through Connect:Direct for UNIX, a second access file called the Strong Access Control (SACL) file is created when you install Connect:Direct for UNIX and is named `sysacl.cfg`. The **root:deny.access** parameter, which is specified in the `sysacl.cfg` file, allows, denies, or limits root access to Connect:Direct for UNIX. If the SACL file is deleted or corrupted, access to Connect:Direct is denied to all users.

For more information about specifying user authorizations in the `userfile.cfg` and the `sysacl.cfg` files, see *Maintaining Access Information Files* in the *Connect:Direct for UNIX Administration Guide*.

## Process Restart

Several facilities are provided for Process recovery after a system malfunction. The purpose of Process recovery is to resume execution as quickly as possible and to minimize redundant data

transmission after a system failure. The following Connect:Direct facilities are available to enable Process recovery:

- ◆ **Process step restart**—As a Process runs, the steps are recorded in the TCQ. If a Process is interrupted for any reason, the Process is held in the TCQ. When you release the Process to continue running, the Process automatically begins at the step where it halted.
- ◆ **Automatic session retry**—Two sets of connection retry parameters are defined in the remote node information record of the network map file: short-term and long-term. If you do not specify a value for these parameters in the remote node information record, default values are used from the local.node entry of the network map file. The short-term parameters allow immediate retry attempts. Long-term parameters are used after all short-term retries are attempted. Long-term attempts assume that the connection problem cannot be fixed quickly and retry attempts occur after a longer time period, thus saving the overhead of connection retry attempts.
- ◆ **Checkpoint restart**—This feature is available with the **copy** statement.  
Checkpoint restart can be explicitly configured within a **copy** step through the **ckpt** parameter. (Refer to the Connect:Direct Processes Web site at <http://www.sterlingcommerce.com/documentation/processes/processhome.html>) If it is not configured in the **copy** step, it can be configured in the Initparms through the **ckpt.interval** parameter. (See *Maintaining the Initialization Parameters File* in the *Connect:Direct for UNIX Administration Guide* for more information on this parameter.)
- ◆ **Run Task restart**—If a Process is interrupted when a run task on an SNODE step is executing, Connect:Direct attempts to synchronize the previous run task step on the SNODE with the current run task step. Synchronization occurs in one of the following ways:
  - ◆ If the SNODE is executing the task when the Process is restarted, it waits for the task to complete, and then responds to the PNODE with the task completion status. Processing continues.
  - ◆ If the SNODE task completes before the Process is restarted, it saves the task results. When the Process is restarted, the SNODE reports the results, and processing continues.

If synchronization fails, Connect:Direct reads the **restart** parameter in the **run task** step or the initialization parameters file to determine whether to perform the **run task step** again. The **restart** parameter on the **run task** step overrides the setting in the initialization parameter.

For example, if the SNODE loses the run task step results due to a Connect:Direct cold restart, Connect:Direct checks the value defined in the **restart** parameter to determine whether to perform the **run task** again.

---

**Note:** Run task restart works differently when Connect:Direct for UNIX runs behind a connection load balancer. For more information on the considerations you need to know when running Connect:Direct for UNIX in a load balancing environment, see the *Connect:Direct for UNIX Release Notes*, *Connect:Direct for UNIX Administration Guide*, and the *Connect:Direct for UNIX Getting Started Guide*.

---

- ◆ **Interruption of Process activity when the SNODE is a Connect:Direct for UNIX node**—When the SNODE is a Connect:Direct for UNIX node and the PNODE interrupts Process activity by issuing a command to suspend Process activity, deleting an executing Process, or when a link fails or an I/O error occurs during a transfer, the Process is placed in the Wait queue in WS status.



If Process activity does not continue, you must manually delete the Process from the TCQ. Refer to the *Connect:Direct for UNIX User's Guide* for command syntax and parameter descriptions for the **delete process** command.

---

**Note:** You cannot issue a **change process** command from the SNODE to continue Process activity; the Process can only be restarted by the PNODE, which is always in control of the session.

---

## Archive Statistics Files

Connect:Direct for UNIX provides a utility to archive and purge statistics files. When you configure Connect:Direct for UNIX, you identify when to archive a statistics file by setting the parameter, **max.age**, in the stats record of the initialization parameters file. The **max.age** parameter defines how old a statistics file must be before you want to archive the file.

Once a day, the script called `statarch.sh` is started. This script identifies the statistics files that are equal to the **max.age**. It then runs the `tar` command and the `compress` command to create a compressed archived file of all the statistics records that match the **max.age** parameter. Once the statistics files are archived, these files are purged. For files archived on a Linux computer, the archived statistics files have the `.gz` suffix since these files are compressed with the `gzip` format. Archived files on all other UNIX platforms have the `.Z` suffix to indicate they are compressed using the `compress` format.

The archived files are stored in the directory where the statistics files and TCQ are stored. The shell script, `statarch.sh`, is located in the `ndm/bin` directory. If necessary, modify the script to customize it for your environment.

If you want to restore statistics files that have been archived, run the **statrestore.sh** script. It uses the **uncompress** and **tar** commands to restore all the statistics files in the archive. You supply two arguments to the **statrestore** command. The first argument is the directory path where the statistics files are located and the second argument identifies the archived file name followed by as many archived file names as you want to restore. Below is a sample **statrestore** command:

```
qa160sol: ./statrestore.sh /export/home/users/cd4000/ndm/bin archive1
```

After files are restored, the statistics records can be viewed using the `select statistics` command.

## Sample Processes, Shell Scripts, and API Programs

Connect:Direct provides sample Processes and shell scripts in `d_dir/ndm/src`, where `d_dir` indicates the destination directory of the Connect:Direct software. You can create similar files with a text editor. In addition, instructions for creating sample Processes and shell scripts are in the `README` file in the same directory.

The following table displays the file names of sample Processes. Modify the Processes as required:

| File Name | Type of Process |
|-----------|-----------------|
| cpunx.cd  | copy            |
| rtunx.cd  | run task        |
| rjunx.cd  | run job         |
| sbunx.cd  | submit          |

The following table displays the file names of sample shell scripts. Modify the shell scripts as required.

| File Name         | Type of Shell Script                                    |
|-------------------|---|
| selstat.sh        | select statistics                                       |
| send.sh           | send  |
| recv.sh           | receive   |
| wildcard          | send multiple files to a PDS                            |
| statarch.sh       | archive statistics files                                |
| statrestore.sh    | restore statistics files that have been archived        |
| lcu.sh            | launch the Local Connection Utility tool                |
| spadmin.sh        | launch the Secure+ Option Admin Tool                    |
| spcli.sh          | launch the Secure+ Option CLI (SPCLI)                   |
| spcust_sample1.sh | configure Secure+ Option for the STS protocol           |
| spcust_sample2.sh | configure Secure+ Option for the STS protocol           |
| spcust_sample3.sh | configure Secure+ Option to use the SSL or TLS protocol |

The following table displays the names of sample programs:

| Program Name | Description   |
|--------------|---|
| apicheck.c   | This program submits a Process to copy a file to a remote system. MAXDELAY is used in this example, which means that the program will not finish execution until the file has been transferred. A standard c compiler is used to compile this module. |
| apicheck.C   | Same as apicheck.c, except that it is compiled with one of the C++ compilers listed in the <i>Connect:Direct for UNIX User's Guide</i> .  |

| Program Name    | Description   |
|-----------------|---|
| exit_skeleton.c | This program is a skeleton of a user exit program that works in conjunction with Connect:Direct for UNIX. It demonstrates usage of all three user exits.        |
| exit_skeleton.C | Same as exit_skeleton_c, except that it is compiled with one of the C++ compilers listed in the <i>Connect:Direct for UNIX User's Guide</i> .                   |
| exit_sample.c   | This is the same program as the skeleton user exit program, except that the security exit is demonstrated with code that approximates PassTicket functionality. |
| sdksample.C     | This program exercises various commands using the SDK interface to Connect:Direct for UNIX.   |

## Connect:Direct for UNIX Files

This section describes the configuration files, illustrates the directory structure of Connect:Direct for UNIX, and lists the individual files that are installed.

### Connect:Direct for UNIX Configuration Files

Connect:Direct for UNIX creates the following configuration files during installation and customization. These files are required for the Connect:Direct server to operate correctly.


| Configuration File                  | Description   |
|-------------------------------------|---|
| Initialization parameters file      | Provides information to the server to use at start up. During the installation, you identify the settings necessary for the initialization parameters file.   |
| User authorization information file | Contains the local user information and remote user information record types. You customize this file during installation to map remote user IDs to local user IDs and create remote user information records in the user authorization information file. |
| Strong access control file          | Improves the security of Connect:Direct for UNIX and allows, denies, or limits root access control. This file is created when you install Connect:Direct for UNIX. If the file is deleted or corrupted, access to Connect:Direct is denied to all users.  |
| Network map file                    | Describes the local node and other Connect:Direct nodes in the network. You can define a remote node record for each node that Connect:Direct for UNIX communicates with.   |
| Server authentication key file      | Verifies client API connection requests. Only verified clients are granted a connection.  |

| Configuration File             | Description   |
|--------------------------------|---|
| Client configuration file      | Identifies the port and host name used by a client to connect to Connect:Direct.  |
| Client authentication key file | Identifies Connect:Direct servers that a Connect:Direct client connects to. You can have multiple entries for multiple servers. |

## Connect:Direct for UNIX Directory Structure

The following figure illustrates the Connect:Direct for UNIX directory structure. The directory tree starts at *d\_dir/*, the destination directory where the software is installed. This directory structure provides for multiple nodes on the same network and possibly on the same computer. The directory structure organization enables you to share Connect:Direct programs, such as *cdpmgr* and *ndmcmgr*. If multiple nodes exist, each node must have its own *d\_dir/ndm/cfg/cd\_node/* directory structure for configuration files, where *cd\_node* is the Connect:Direct node name.

**Note:** The secure+ directory is available only when Secure+ Option is purchased and installed.




---

**Note:** See the following figure to view the work directory for a node.

---

A `d_dir/work/cd_node` directory is created for each node. The following figure displays the work directory for multiple nodes and illustrates the working files created for each node, such as TCQ files:




---

## Connect:Direct for UNIX Documentation

See *Connect:Direct for UNIX Release Notes* for a complete list of the product documentation.

### About This Guide

The *Connect:Direct for UNIX Getting Started Guide* is for programmers and network operations staff who install Connect:Direct for UNIX. By reading this document, you gain the knowledge required to install Connect:Direct.

This guide assumes knowledge of the UNIX operating system, including its applications, network, and environment. For LU6.2 connectivity, a proficiency in configuring the SNA package to support independent LU6.2 connections is required.

## Task Overview

The following table guides you to the information required to perform Connect:Direct for UNIX installation tasks:

| <b>Task</b>  | <b>Reference</b>  |
|--|---|
| Understanding Connect:Direct for UNIX  | Chapter 1, <i>About Connect:Direct for UNIX</i>                 |
| Installing Connect:Direct for UNIX   | Chapter 2, <i>Installing Connect:Direct for UNIX</i>            |
| Customizing Connect:Direct for UNIX  | Chapter 2, <i>Installing Connect:Direct for UNIX</i>            |
| Setting up the Connect:Direct for UNIX server  | Chapter 2, <i>Installing Connect:Direct for UNIX</i>            |
| Setting up the Connect:Direct for UNIX client  | Chapter 2, <i>Installing Connect:Direct for UNIX</i>            |
| Creating the Strong Access Control file and changing file permissions on session manager, process manager, command manager, and user manager programs. | Chapter 2, <i>Installing Connect:Direct for UNIX</i>            |
| Installing File Agent  | Chapter 2, <i>Installing Connect:Direct for UNIX</i>            |
| Installing Secure+ Option  | Chapter 2, <i>Installing Connect:Direct for UNIX</i>            |
| Managing files with File Agent   | Chapter 3, <i>Managing Files with Connect:Direct File Agent</i> |
| Recording the information necessary to install and customize Connect:Direct  | Appendix A, <i>Installation Worksheets</i>                      |
| Configuring an LU6.2 connection  | Appendix B, <i>SNA LU6.2 Connectivity</i>                       |
| Accessing and displaying manual pages  | Appendix C, <i>Connect:Direct for UNIX Manual Pages</i>         |





---

# Installing Connect:Direct for UNIX

This section describes the tasks necessary to install and customize Connect:Direct for UNIX. It also describes preparations for installing Connect:Direct for UNIX in a cluster environment and on the Linux for zSeries operating system.

---

## Before You Begin

Before you install Connect:Direct for UNIX, complete the following tasks:

- ◆ Read the *Connect:Direct for UNIX Release Notes* for any additional system requirements and upgrade considerations.
- ◆ Complete the worksheets in Appendix A, *Installation Worksheets*, to identify all information required to perform the installation.

## Configuration Types

Connect:Direct for UNIX requires that you install a server and at least one client location. You can install Connect:Direct for UNIX in two different configurations:

- ◆ Install the server on a local system and the clients on remote systems
- ◆ Install the server and at least one client on a local system and the remaining clients on remote systems

---

**Caution:** Install Connect:Direct for UNIX on a local drive. Do *not* install Connect:Direct for UNIX on a Network File System (NFS) resource.

---

## Preparing to Install Connect:Direct for UNIX in a Cluster Environment

Connect:Direct for UNIX supports clustering software to allow two or more computers to appear to other systems as a single system. All computers in the cluster are accessible through a single IP address. Connect:Direct for UNIX can be installed in two types of clustering environments: high availability and load balancing clustering environments.

## High-Availability Cluster Environments

Consider the following information when planning to use Connect:Direct for UNIX in a high-availability cluster environment.

### Supported High-Availability Cluster Environments

Connect:Direct for UNIX is certified to operate in the following high-availability cluster environments:

- ◆ IBM high-availability cluster multiprocessing (HACMP) environment
- ◆ Hewlett-Packard MC/Service Guard
- ◆ SunCluster versions 2.2, 3.0, and 3.2.

If you plan to install Connect:Direct for UNIX in a high-availability cluster environment, complete the following tasks:

- ◆ Install the clustering software on each computer in the cluster, including setting up a logical host or application package.
- ◆ Create a user with the same name and user ID on each cluster node.
- ◆ Create a Secure+ Option subdirectory on a shared file system on a shared volume group.
- ◆ Ensure that the shared file system is owned by the Connect:Direct user.
- ◆ Install Connect:Direct for UNIX on the shared file system.
- ◆ Perform the procedures necessary to define the high-availability settings and configure the cluster environment.

### Limitations of High-Availability Clusters

When running Connect:Direct for UNIX in a high-availability cluster environment, be aware of the following limitations:

- ◆ If a failure occurs, all Processes being held will be restarted when Connect:Direct is restarted. This includes Processes that are held by the operator as well as Processes held in error. This could cause a security risk.
- ◆ When a Connect:Direct ndmsmgr process associated with a Connect:Direct Process is killed, the Process is not automatically restarted and is put in the Held in Error state. It must be manually restarted; otherwise, the Connect:Direct Process is restarted when the cluster restart occurs.

## Load-Balancing Cluster Environments

In a load-balancing cluster environment, an incoming session is distributed to one of the Connect:Direct for UNIX instances based on criteria defined in the load balancer. Generally, from the point of view of the nodes behind the load balancer, only incoming or SNODE sessions are affected by the load balancer. PNODE, or outgoing sessions, operate the same way as non-cluster Connect:Direct for UNIX PNODE sessions.

### SNODE Server Considerations for Load-Balancing Clusters

Consider the following when planning and setting up the Connect:Direct for UNIX SNODE servers in a load balancing cluster:

- ◆ The servers used for the Connect:Direct for UNIX instances behind the load balancer must all have access to common shared disk storage because of the following:
  - ◆ Any **copy** statement source and destination files for SNODE processes must reside in directories accessible to all servers.
  - ◆ All nodes must have access to a common SNODE work area and that area must be on a cluster file system and not a Network File System (NFS) resource.
  - ◆ All servers must be of the same platform type (for example, all Solaris SPARC or all Linux Intel) and the same Connect:Direct for UNIX version and maintenance level.
- ◆ The system clocks on all servers must be synchronized in order for **copy** checkpoint/restart and **run task** synchronization to work.
- ◆ The administrator user ID used to install Connect:Direct for UNIX must be defined on each server and must be the same user and group number on each server.

### Connect:Direct for UNIX SNODE Setup for Load-Balancing Clusters

Consider the following when planning and setting up the Connect:Direct for UNIX SNODEs in a load-balancing cluster:

- ◆ One Connect:Direct for UNIX node should be installed on each server behind the load balancer.
- ◆ Each node should be installed by the same user ID.
- ◆ Each node should have the same Connect:Direct for UNIX node name.
- ◆ Each node should have the same node-to-node connection listening port.
- ◆ A directory should be established for the shared SNODE work area used by the Connect:Direct for UNIX nodes behind the load balancer. This directory should be owned by the Connect:Direct for UNIX administrator ID and must be accessible to all of the servers behind the load balancer.
- ◆ Each node should specify the same path to the directory used for the shared SNODE work area. Specify this path in the **snode.work.path** parameter of the ndm.path record in the initialization parameter file.

For more information on the initialization parameters file and the **snode.work.path** parameter, see the *Connect:Direct for UNIX Administration Guide*.

### Limitations of Load Balancing Clusters

When running Connect:Direct for UNIX in a cluster environment, be aware of the following limitations:

- ◆ If an incoming session fails and is restarted by the PNODE, then the restarted session may be assigned to any of the instances behind the load balancer and will not necessarily be established with the original SNODE instance.
- ◆ When shared SNODE work areas are configured and the **run task** is on the SNODE, then at restart time, Connect:Direct for UNIX cannot determine whether the original task is still active or not because the restart session may be with a different server. If you set the global run task restart parameters to yes in the initialization parameters file, a task could be restarted even though it may be active on another machine. Therefore, exercise caution when specifying restart=y.

- ◆ Each SNODE instance that receives a session for a given Process creates a TCQ entry for the Process. Each SNODE instance has its own TCQ file, and these files are not shared among SNODE instances. Only the work files created in the shared work area are shared among SNODE instances.
- ◆ When a Process is interrupted and restarted to a different SNODE instance, the statistics records for that Process is distributed between the two SNODE instances involved. As a result, you cannot select all the statistics records for a Process.

## Preparing to Install Connect:Direct for UNIX on the Linux for zSeries Operating System

Connect:Direct for UNIX is distributed on a CD-ROM. Because the Linux for zSeries operating system does not support the CD-ROM drive installation, you must use ftp to transfer installation files from a UNIX or Windows operating system. To transfer the files from a Windows or UNIX platform to the Linux for zSeries operating system, use the following procedure:

1. Create a temporary directory on the computer running Linux for zSeries.
2. Insert the CD-ROM into the appropriate drive on the computer running Windows or UNIX and perform one of the following actions:
  - ◆ From Windows, select **Start > Programs > Accessories > Command Prompt**.
  - ◆ From UNIX, use the mount command to locate the CD-ROM drive.
3. Type the following command, where *ip address* is the IP address of the computer running Linux for zSeries:

```
ftp ip address
```

4. At the prompt, type the user name and password for a user on the computer running Linux for zSeries.
5. At the ftp prompt, set the transfer mode to binary by typing the following command:

```
binary
```

6. Change to the temporary directory you created on the computer running Linux for zSeries by typing the following command, where *temp\_dir* is the directory you created in step 1:

```
cd temp_dir
```

7. To copy the installation script from the CD-ROM to the computer running Linux for zSeries, perform one of the following actions:

- ◆ From Windows, type the following command, where *x* is the location of the CD-ROM drive:

```
put x:\IBMS390_linux\cdinstall cdinstall
```

- ◆ From UNIX, type the following command:

```
put /cdrom/IBMS390_linux/cdinstall cdinstall
```

8. To copy the Connect:Direct cpio file from the CD-ROM to the computer running Linux for zSeries, perform one of the following actions:

- ◆ From Windows, type the following command, where *x* is the location of the CD-ROM drive:

```
put x:\IBMS390_linux\cdunix cdunix
```

- ◆ From UNIX, type the following command:

```
put /cdrom/IBMS390_linux/cdunix cdunix
```

9. To exit the ftp application, type **quit**.

---

## Installing Connect:Direct for UNIX

Observe the following conventions when you install Connect:Direct for UNIX:

- ◆ If a file name contains a semicolon, precede the semicolon with a backslash (\) character; otherwise, the shell interprets the semicolon as the start of a new command. For example, specify the file name SNA;1 as SNA\;1.
- ◆ Acceptable responses to prompts are listed in brackets, where **y** specifies yes, **n** specifies no, and **a** specifies all.
- ◆ The default response is capitalized. Press **Enter** to accept the default value.
- ◆ Do not use colons (:) for values in the installation and customization scripts.
- ◆ Do not use keywords for values.
- ◆ Press **Enter** after each entry to continue.
- ◆ Terminate any procedure by pressing **Ctrl-C**.

To install Connect:Direct for UNIX:

1. Log on to the UNIX system with the privileges required to install software. You can create an account specifically for this purpose.

---

**Caution:** Do not install as root.

---

2. Depending upon how you obtained the product, take one of the following actions:
  - ◆ If you have the product distribution media, select the CD for your platform. Type the following command and press **Enter** to change to the CD-ROM drive and the directory that correspond to the UNIX platform:

```
cd /cdrom/<platform directory>
```

Refer to the following table for the name of the platform directory for each platform.

| UNIX Platform      | Platform Directory Path |
|--------------------|-------------------------|
| HP PA-RISC         | HP_PA-RISC              |
| HP UX Itanium      | HP_Itanium              |
| IBM System pSeries | IBM                     |
| Sun SPARC systems  | Sun_Solaris             |
| Red Hat            | RedHat_linux            |
| SuSE               | SuSE_linux              |
| Linux for zSeries  | IBMS390_linux           |
| Solaris/x86        | Solaris_x86             |

- ◆ If you downloaded the product from the ESD Portal, type the following command and press **Enter** to change to the location of the product download:

```
cd /<location of product download>
```

3. Type the following command to invoke the installation script and press **Enter**:

```
cdinstall
```

The following screen is displayed:

```
=====
Sterling Commerce, Inc.,(TM) Connect:Direct(TM) for UNIX(TM)
Installation Procedure

You are beginning the Connect:Direct for UNIX Installation
Procedure. You will be asked to specify a directory (called
the destination directory) where the Connect:Direct for UNIX
files will be stored.

Please follow the Getting Started Guide and/or Release Notes for the
proper Media Name.

Sterling Commerce, Inc.(TM) and Connect:Direct(TM) are trademarks
of Sterling Commerce, Inc. in the U.S.A. and other countries.

UNIX is a registered trademark of The Open Group
=====

Press ENTER when ready.
```

4. Read the information and press **Enter**. The following screen is displayed:

```

=====
Connect:Direct for UNIX License Agreement.
=====
The license agreement must be accepted for the installation to continue.

Press ENTER to display the agreement.
(Then use the spacebar to page through the agreement.)

```

5. Read the information and press **Enter**. Use the spacebar to page through the license agreement. When you are prompted to accept the License Agreement, press **Enter** if you accept or type **n** and **Enter** to exit the installation. If you accept the License Agreement, the following screen is displayed:

```

Enter the FULL path of the directory where
Connect:Direct for UNIX 4.0.00 will be installed.
You can use $HOME to shorten the name:[$HOME/cdunix]

```

6. Type the path name of the directory where Connect:Direct for UNIX will be installed and press **Enter**.
7. When you are prompted to confirm the installation location, press **Enter**.

---

**Note:** The option for installing Connect:Direct for UNIX SNMP Agent will not display for platforms where this option is not supported.

---

The following screen is displayed:

```

Please select one of the following installation options:

(1) Connect:Direct for UNIX Server and Client(CLI/API)
(2) Connect:Direct for UNIX Server
(3) Connect:Direct for UNIX Client(CLI/API)
(4) Connect:Direct for UNIX File Agent
(5) Connect:Direct Secure+ Option for UNIX
(6) Connect:Direct for UNIX SNMP Agent
(7) EXIT

Enter your choice:[1]

```

8. Do one of the following:
- ◆ Press **Enter** to accept the default and install the Server and Client on the same computer.
  - ◆ Type **2** to install the Server only and press **Enter**.
  - ◆ Type **3** to install the Client only and press **Enter**.

The following screen is displayed:

```

Enter the path "AND filename" where the installation file is mounted or
where the ESD portal download is extracted (e.g. /cdrom/<platform>/cdunix):

```

9. Type the path and filename of the installation file and press **Enter**.

If you selected **1** in step 8 to install the Server and Client, the following screen is displayed. If you selected option **2** or **3**, the screen displays the software that will be installed.

```
Both Connect:Direct for UNIX Server and Client(CLI/API) Version 4.0.00
will be installed in your system. Do you want to continue?:[Y/n]
```

10. Press **Enter** to continue.

If the destination directory does not have enough free disk space, the script suggests you delete enough files to provide the necessary disk space and then exits.

If sufficient disk space is available, the installation script copies files from the distribution media to the destination directory and verifies that the correct number of files and blocks are copied.

The customization script starts automatically when the installation is complete.

---

## Customizing Connect:Direct for UNIX

The customization script starts automatically after the installation is complete to set up the Connect:Direct for UNIX operating environment. It is located in *d\_dir/etc*, where *d\_dir* is the Connect:Direct installation directory, and may be run by itself if needed for future configuration changes. The option you select determines what Connect:Direct for UNIX operating environment is configured: the Connect:Direct for UNIX Server only, the Connect:Direct for UNIX Client only, or the Connect:Direct for UNIX Server and Client.

After you customize the environment, you need to configure Connect:Direct for UNIX for using root privilege to create a Strong Access Control List (SACL) file and to set the owner and permissions of Connect:Direct executables. You must create the SACL file and set the owner and permissions before you can run Connect:Direct for UNIX. See *Configuring Connect:Direct for UNIX Using Root Privilege* for more information about this process.

The customization script displays the following message and prompts you to begin the customization procedure:

```
=====
Sterling Commerce Connect:Direct for UNIX Customization

The customization procedure sets up the Connect:Direct for UNIX
operating environment. In the following, please answer questions
when prompted and when in doubt, enter (?) followed by the ENTER
key for help. To abort the process, enter Control-C.

As a short hand, entering ENTER at the prompt means "yes", or
the default value, if any, will be taken.
=====

Press ENTER when ready.
```



1. Read the information and press **Enter**. Complete the following steps to customize Connect:Direct for UNIX:

```
The customization procedure allows you to create configuration
files for:
```

- (1) Configure the Connect:Direct for UNIX Server.
- (2) Configure the Connect:Direct for UNIX Client.
- (3) Configure the Connect:Direct for UNIX Server and Client.
- (4) Configurations requiring root privilege.
- (5) EXIT.

```
Enter your choice:[3]
```

2. Do one of the following:

---

**Note:** Be sure to select the same configuration you selected during the installation in step 8 on page 31.

---

- ◆ Type **3** to customize the Server and Client on the same computer and press **Enter**.  
If you are installing both the Client and the Server, complete all of the procedures in *Setting Up the Connect:Direct for UNIX Server* and *Setting Up the Connect:Direct for UNIX Client*.
- ◆ Type **2** to customize the Client only and press **Enter**.  
If you are installing the Client only, complete the procedure *Setting Up the Connect:Direct for UNIX Client*.
- ◆ Type **1** to customize the Server only and press **Enter**.  
If you are installing the Connect:Direct for UNIX Server only, complete the procedures in the next section, *Setting Up the Connect:Direct for UNIX Server*.

---

## Setting Up the Connect:Direct for UNIX Server

After you install Connect:Direct for UNIX, you need to define the parameters needed by the Server for startup. If you installed the Server software, the process to customize the Server starts automatically.

To set up the server, perform the following tasks:

- ◆ Define your node name.
- ◆ Define SNA settings, if applicable.
- ◆ Define the initialization parameters file.
- ◆ Define the network map file.
- ◆ Define the user authorization information file.

## Defining the Connect:Direct Node Name

If you selected option 1 or 3 in step 2 of *Customizing Connect:Direct for UNIX* on page 33, the following prompt is displayed:

```
Please enter name of Connect:Direct node you want to customize: <node name>
```

Type the name of the node, up to 16 characters, that you want to customize and press **Enter**. The following message is displayed:

```
Index file has been created for: [/<installation directory>/ndm/cfg/msgfile.cfg]
```

## Defining the Initialization Parameters File

Connect:Direct processes initialization parameters during startup. Some parameters identify files that provide information to the server.

---

**Note:** The option for configuring SNA will not display for platforms where this option is not supported.

---

If you selected option 1 to install only the Server or option 3 to install the both the Server and Client, the following prompt is displayed:

```
If you purchased SNA support for Connect:Direct and SNA is properly installed
on your system, do you want to add the appropriate SNA entry
to your initparm file?:[Y/n]
```

1. If you have SNA configured on your system, press **Enter** to configure SNA in the Connect:Direct initialization parameters file. If you do not use SNA, type **n** and press **Enter** to continue customizing Connect:Direct for UNIX.

The following prompt is displayed:

```
Enter TCP/IP port to listen for a remote connection request:[1364]
```

2. Type the TCP/IP port number that Connect:Direct monitors for requests from remote nodes. If available, use the default port, 1364. If the default port number is being used by another service, use any other available port.

This value is entered into the initialization parameters file in the **comm.info** parameter.

The following prompt is displayed:

```
Enter TCP/IP hostname to listen for a remote connection request:[0.0.0.0]
```

3. Type the hostname or IP address that Connect:Direct Monitors for requests from remote nodes.

If you use 0.0.0.0, Connect:Direct will listen for requests from remote nodes on all network adapters configured on the UNIX server.

This value is entered into the initialization parameters file in the **comm.info** parameter.

The following prompt is displayed:

```
Enter TCP/IP port to listen for a Client connection request:[1363]
```

4. Type the TCP/IP port number that Connect:Direct monitors for requests from Clients. If available, use the default value of **1363**. If the default port number is being used by another service, use any other available port.

This value is entered into the network map file in the **tcp.api** parameter.

The following prompt is displayed:

```
Enter TCP/IP hostname to listen for a Client connection request:[<host name>]
```

5. Type the hostname or IP address that Connect:Direct monitors for requests from Clients.

This value is entered into the network map file in the **tcp.api** parameter.

Connect:Direct creates the network map file and displays the directory path and file name.

## Defining the Network Map File

After you define the initialization parameters file, the customization script creates the network map file and displays the directory path and file name. Connect:Direct adds a remote node record to the network map file. The remote node record is assigned the name of the local node you specified in *Defining the Connect:Direct Node Name*.

---

**Note:** For information on adding remote node records for other nodes, refer to *Maintaining Configuration Files* in the *Connect:Direct for UNIX Administration Guide*.

---

The initialization parameters file and the network map file are created and the path and file name for each file is displayed:

```

=====
A initparm file has been created. This initparm file consists of
initialization parameter records used by Connect:Direct during
startup. To see details about modifying the initparm file,
please refer to the "Maintaining the Initialization Parameter File"
chapter in the Administration Guide.

Initparm file is located at
/<installation directory>/ndm/cfg/<node name>/initparm.cfg
=====

=====
A netmap file has been created. This netmap file contains the
installed Connect:Direct node network definition. For assistance
adding network definitions of other nodes, please refer to
the "Maintaining the Network Map File" chapter in the
Administration Guide.

Netmap file is located at
/<installation directory>/ndm/cfg/<node name>/netmap.cfg.
=====
Press Enter when ready.

```

Press **Enter** to continue. The netmap file is automatically created.

## Customizing the User Authorization Information File

After the user authorization information file is created, you are ready to customize the file. Use this procedure to map remote user IDs to local user IDs and create remote user information records in the user authorization information file.

After the user authorization information file is created, the following screen is displayed:

```

=====
User Authorization file has two types of records: local user
record and remote user record. Refer to the
"Maintaining the User Authorization Information File" chapter in
the Administration Guide for details.

User Authorization file is located at
/<installation directory>/ndm/cfg/<node name>/userfile.cfg
=====

```

The following message is displayed to prompt you to create an authorization information record for a remote user:

```

Insert remote user record? [Y/n]

```

1. Press **Enter** to add a remote user record. The following prompt is displayed:

```
Enter remote userid:
```

2. Type the login name or ID of the remote user and press **Enter**. The following prompt is displayed:

```
Enter remote Connect:Direct node name:
```

3. Type the name of the remote node and press **Enter**. The submitter ID and remote node name become the record name for the remote user information record. The following prompt is displayed:

```
Enter local userid:
```

4. Type the local user ID to which the remote user ID will be mapped and press **Enter**. The local user ID is the UNIX account name. This value is associated with **local.id** in the remote user information record and defines the local user ID used to check security for the remote user. The following prompt is displayed:

```
Insert another remote user record?:[Y/n]
```

5. Do one of the following:
  - ◆ To create another remote user record, press **Enter** and repeat steps 2-4.
  - ◆ Type **n** and press **Enter** if you do not want to create another remote user record.

The following prompt is displayed:

```
Insert local user record?: [Y/n]
```

6. Do one of the following:
  - ◆ If you do not want to create a local user record, type **n** and press **Enter**. Go to *Connect:Direct Creates an Authentication Key File* to continue configuring Connect:Direct for UNIX.
  - ◆ To create a local user record, press **Enter**.

The following prompt is displayed:

```
Enter userid:
```

7. Type the user ID for the local user and press **Enter**. This value is associated with **userid** in the user authorization information file. The following prompt is displayed:

```
Grant administrative authority:[Y/n]
```

8. Press **Enter** to grant administrative authority to the local user ID. All Connect:Direct capabilities that you specify in the local user information record are assigned to the user. This value is assigned to **admin.auth** in the local user information record. The following prompt is displayed:

```
Insert another local user record? [Y/n]
```

9. Do one of the following:
  - ◆ Press **Enter** and repeat this procedure to create another local user record.
  - ◆ Type **n** and press **Enter** to continue to the next task.

### Connect:Direct Creates an Authentication Key File

A server authentication key file verifies connection requests. Only authorized clients are granted a connection. Connect:Direct generates the server authentication key file automatically. After the file is generated, Connect:Direct displays the following message:

```
A server authentication key file has been created. The default
key is CD4UNIX. Please refer to the "Maintaining Client
and Server Authentication Key Files" chapter in the
Administration Guid for details.
=====
Press Enter when ready.
```

Press **Enter** to continue.

---

## Setting Up the Connect:Direct for UNIX Client

After you install and customize Connect:Direct for UNIX Server, you need to define the parameters needed by the Client for startup. To set up the Client, perform the following tasks:

- ◆ Customize the Client configuration file
- ◆ Customize the Client authentication key file

## Customizing the Client Configuration File

The Client configuration file is automatically created during the customization process. Use the following procedure to customize the Client configuration file. After the Client configuration file is created, the following screen is displayed:

```

=====
                Configuring Connect:Direct for UNIX Client
=====

The Client configuration file defines connection information
to the Connect:Direct Server. A network-wide configuration file
with records defining connection information for different
Servers can be set up. Please refer to the "Modifying
the Client Configuration File" chapter in the Administration
Guide.

The Client configuration is located at
/<installation directory>/ndm/cfg/cliapi/ndmapi.cfg.
=====

Enter port of the Connect:Direct Server this Client will connect to:[1363]

```

1. Type the port number of the Server that the Client connects to and press **Enter** when ready. This value is associated with **tcp.port** in the Client configuration file. The following prompt is displayed:

```

Enter hostname of the Connect:Direct Server this Client will connect to:[<node
name>]

```

2. Press **Enter** to accept the host name. This value is displayed in the **tcp.hostname** parameter in the Client configuration file.

## Customizing the Client Authentication Key File

The Client authentication key file identifies all Connect:Direct Servers that this Connect:Direct node connects to. This file is automatically generated during customization. After the file is generated, the following message is displayed:

```

A Client authentication key file has been created. The default
key is CD4UNIX. Please refer to the "Maintaining Client
and Server Authentication Key Files" chapter in the
Administration Guide for details.

```

Press **Enter** to continue.

You will be returned to the customization option selection screen.

---

## Configuring Connect:Direct for UNIX Using Root Privilege

You must have root privilege to do the following:

- ◆ Create a Strong Access Control List (SACL) file. This improves the security of Connect:Direct for UNIX and prevents a user from obtaining root access control.
- ◆ Set the owner and permissions of Connect:Direct executables. This allows you to run Connect:Direct for UNIX.

After you customize the environment, you will be returned to the customization option selection screen.

```
The customization procedure allows you to create configuration
files for:

(1) Configure the Connect:Direct for UNIX Server.
(2) Configure the Connect:Direct for UNIX Client.
(3) Configure the Connect:Direct for UNIX Server and Client.
(4) Configurations requiring root privilege.
(5) EXIT.

Enter your choice:[3]
```

If you know the root password or if a system administrator is standing by who knows the root password, select option 4. If you do not know the root password, but are authorized to gain root authority using `sudo` or a similar utility, type **5** to exit the Connect:Direct for UNIX customization script. The following message is displayed:

```
Exiting Connect:Direct for UNIX customization procedure.

=====
WARNING! The SACL was not properly configured. Please insure
that the SACL is configured properly before continuing, or the
Connect:Direct product will not function properly.

For further details, refer to the Connect:Direct for UNIX
Getting Started Guide.
=====

Press ENTER to continue.
```



Read the information and press **Enter**. Connect:Direct generates the sample.cd file for the purpose of testing the installation. After this file is generated, the following screen is displayed:

```

=====
A sample pnode equal to snode process has been created
to test the Connect:Direct for UNIX installation. It is
located at /<installation directory>/ndm/bin/sample.cd.
More example processes can be found in sub-directory
/<installation directory>/ndm/src.
=====

Connect:Direct for UNIX configuration completed.

Before starting Connect:Direct for UNIX, please
set the environment variable NDMAPICFG to point to the
client configuration file. Please refer to the "Installing
Connect:Direct for UNIX" chapter in the Getting Started Guide
for details.

Thank you for using Connect:Direct for UNIX.
=====
Would you like to return to the installation menu?:[Y/n]

```

To exit the customization, type **n** and press **Enter**.

After you exit the customization script, if you did not select option 4 above, launch cdcust (located in /<product install directory>/etc) using sudo to become root before creating the SACL and setting the owner and permissions of the executables.

---

**Note:** You must create the SACL file and set the owner and permissions of the Connect:Direct executables to run Connect:Direct for UNIX.

---

You must change the file attributes of the Session Manager (*d\_dir/ndm/bin/ndmsmgr*), Process Manager (*d\_dir/ndm/bin/cdpmgr*), Command Manager (*d\_dir/ndm/bin/ndmcmgr*) User Manager (*d\_dir/ndm/bin/ndmumgr*), Statistics Manager (*d\_dir/ndm/bin/cdstatm*), Client Authenticator (*d\_dir/ndm/bin/ndmauthc*), Server Authenticator (*d\_dir/ndm/bin/ndmauths*), and hostid.sh utility program on Linux Intel (*d\_dir/ndm/bin/cd\_hostid*).

Use the following procedure to customize the SACL file and set the owner and permissions of the Connect:Direct executable files. After you launch cdcust, the following prompt is displayed.

```

Enter full path of Connect:Direct destination directory:[$HOME/cdunix]

```

Type the full path of the Connect:Direct destination directory and press **Enter**.

The following screen is displayed:

```
=====
Sterling Commerce Connect:Direct for UNIX Customization

The customization procedure sets up the Connect:Direct for UNIX
operating environment. In the following, please answer questions
when prompted and when in doubt, enter (?) followed by the ENTER
key for help. To abort the process, enter Control-C.

As a short hand, entering ENTER at the prompt means "yes", or
the default value, if any, will be taken.
=====

Press ENTER when ready.
```

Press **Enter** to continue. The following screen is displayed:

```
The customization procedure allows you to create configuration
files for:

(1) Configure the Connect:Direct for UNIX Server.
(2) Configure the Connect:Direct for UNIX Client.
(3) Configure the Connect:Direct for UNIX Server and Client.
(4) Configurations requiring root privilege.
(5) EXIT.

Enter your choice:[3]
```

1. Type **4** and press **Enter**. The following message is displayed:

```
This option will check for the existence and proper minimal
configuration of the Strong Access Control List (SACL). It
will also set required file ownership and permissions for the
Connect:Direct executable files.

Press ENTER when ready.
```

2. Press **Enter** to continue. The following prompt is displayed:

```
Performing configuration tasks that require root authority.

Note to system administrator:

root authority will be used to create or check the following file:

    /<installation directory>/ndm/SACL/sysacl.cfg

used to control user access to Connect:Direct UNIX.

root authority will also be used to set required ownership and permission
settings of Connect:Direct UNIX executables in:

    /<installation directory>/ndm/bin

This option requires root password. Continue?:[Y/n]
```

3. Press **Enter** to continue.
4. If you have already assumed root authority by using a utility such as sudo, press **Enter**. Otherwise, type the root password and press **Enter**.  
If you type the root password incorrectly, a message informs you that the configuration tasks were not completed. Otherwise, a SACL file is created, the owner and permissions of the Connect:Direct executable files are set, and you are returned to the Customization menu.
5. Press **Enter** to continue.
6. Type **5** to exit the Connect:Direct for UNIX customization script.

The following parameters are modified during the customization:

| Parameter                          | Value  | File                                |
|------------------------------------|--|-------------------------------------|
| SNAFILE=/ndm/lib/libcdsna.s        | Defines SunLink as the SNA software  | Initialization parameters file      |
| BRXSNAFILE=/ndm/lib/libcdbrxsna.s  | Defines Brixton as the SNA software  | Initialization parameters file      |
| SNPSNAFILE=/ndm/lib/libcdsnpsna.so | Defines SNAP-IX as the SNA software  | Initialization parameters file      |
| comm.info                          | Identifies the IP address and port that Connect:Direct monitors for requests from remote nodes | Initialization parameters file      |
| tcp.api                            | Identifies the IP address and port monitored by Connect:Direct for requests from clients       | Network map file                    |
| mode.listen                        | Identifies the host used to monitor LU 6.2 connections   | Initialization parameters file      |
| admin.auth                         | Determines if user ID has administrative authority   | User authorization information file |
| tcp.port                           | Specifies port number of the server that the client connects to                                | Client configuration file           |
| tcp.hostname                       | Specifies host name of the server that the client connects to                                  | Client configuration file           |

## Installing File Agent

After completing the Connect:Direct for UNIX installation, you can install File Agent at any time.

**Note:** If you are installing File Agent on Linux for zSeries, you must download the Java 1.5 software from the manufacturer's Web site before continuing the installation.

Complete the following steps to install File Agent.

---

**Note:** If you have completed the Server installation and are still in the installation program, return to the main installation menu and begin with step 9.

---

1. Log on to the UNIX system with the privileges required to install software. You can create an account specifically for this purpose.

---

**Caution:** Do not install as root.

---

2. Depending upon how you obtained the product, take one of the following actions:
  - ◆ If you have the distribution media, select the CD for your platform. Type the following command and press **Enter** to change to the CD-ROM drive and the directory that correspond to the UNIX platform:

```
cd /cdrom/<platform directory>
```

Refer to the following table for the name of the platform directory for each platform:

| UNIX Platform      | Platform Directory Path |
|--------------------|-------------------------|
| HP PA-RISC         | HP_PA-RISC              |
| HP UX Itanium      | HP_Itanium              |
| IBM System pSeries | IBM                     |
| Sun SPARC systems  | Sun_Solaris             |
| Red Hat            | RedHat_linux            |
| SuSE               | SuSE_linux              |
| Linux zSeries      | IBMS390_linux           |
| Solaris/x86        | Solaris_x86             |

- ◆ If you downloaded the product from the ESD Portal, type the following command and press **Enter** to change to the location of the product download:

```
cd /<location of product download>
```

3. Type the following command to invoke the installation script and press **Enter**:

```
cdinstall
```

The following screen is displayed:

```

Sterling Commerce, Inc.,(TM) Connect:Direct(TM) for UNIX(TM)
Installation Procedure

You are beginning the Connect:Direct for UNIX Installation
Procedure. You will be asked to specify a directory (called
the destination directory) where the Connect:Direct for UNIX
files will be stored.

Please follow the Getting Started Guide and/or Release Notes for the
proper Media Name.

Sterling Commerce, Inc.(TM) and Connect:Direct(TM) are trademarks
of Sterling Commerce, Inc. in the U.S.A. and other countries.

UNIX is a registered trademark of The Open Group
=====

Press ENTER when ready.

```

4. Read the information and press **Enter**. The following screen is displayed:

```

=====
Connect:Direct for UNIX License Agreement.
=====
The license agreement must be accepted for the installation to continue.

Press ENTER to display the agreement.
(Then use the spacebar to page through the agreement.)

```

5. Read the information and press **Enter**. Use the spacebar to page through the license agreement. When you are prompted to accept the License Agreement, press **Enter**. The following screen is displayed:

```

Enter the FULL path of the directory where
Connect:Direct for UNIX 4.0.00 will be installed.
You can use $HOME to shorten the name:[$HOME/cdunix]

```

6. Type the path and press **Enter**. The following screen is displayed:

```

WARNING: "<directory path>" : Directory exists

Files in <directory path> could be overwritten by the
installation. Do you want to continue: [Y/n]

```

7. Press **Enter** to continue. The following screen is displayed:

```
Installed components detected in this directory.

A previous version of C:D for UNIX was detected.

Would you like this procedure to detect and upgrade your currently installed
options with minimal interaction?
If yes, the configuration files will be left in place and reused.
If not, the full installation procedure will prompt to either reuse, or purge
and rebuild, each configuration file.

Caution: If you are upgrading from earlier version of C:D for UNIX, existing
Processes in the tcq may encounter conversion error. They will need to be deleted
and resubmitted.

Type y or press Enter to continue with the upgrade procedure, or
type n to run the full installation procedure:[Y/n]
```

8. Type **n** and press **Enter**.

The following installation options menu is displayed:

```
Please select one of the following installation options:

(1) Connect:Direct for UNIX Server and Client(CLI/API)
(2) Connect:Direct for UNIX Server
(3) Connect:Direct for UNIX Client(CLI/API)
(4) Connect:Direct for UNIX File Agent
(5) Connect:Direct Secure+ Option for UNIX
(6) Connect:Direct for UNIX SNMP Agent
(7) EXIT

Enter your choice:[1]
```

9. Select **4** and press **Enter**. The following prompt is displayed:

```
Enter the path "AND filename" where the installation file is mounted or
where the ESD portal is extracted (e.g. /cdrom/<platform>/cdunix):
```

10. Type the full Connect:Direct for UNIX installation path and filename and press **Enter**. You are prompted to confirm the installation.

```
Connect:Direct for UNIX File Agent will be installed
in your system. Do you want to continue?:[Y/n] y
```

11. Press **Enter** to continue. The program determines if enough free space exists to complete the installation.

- ◆ If sufficient space is available, the File Agent installation begins.
- ◆ If the space is insufficient, the program suggests that you delete enough files to provide the necessary disk space and then exits. After you have cleared enough space, restart the installation procedure.

12. After the File Agent installation completes, the following message is displayed:

```
Would you like to return to the installation menu?:[Y/n]
```

13. Press **Enter** to return to the installation menu or press **n** and **Enter** to exit the installation menu.

---

## Installing Secure+ Option

After completing the Connect:Direct for UNIX installation, you can install Secure+ Option at any time.

---

**Note:** If you already have Secure+ Option installed, when you are prompted to upgrade your installation, type **y**.

---

Complete the following steps to install Secure+ Option:

---

**Note:** If you have completed the server installation and are still in the installation program, return to the main installation menu and begin with step 10 of this procedure.

---

1. Log on to the UNIX system with the privileges required to install software. You can create an account specifically for this purpose.

---

**Caution:** Do not install as root.

---

2. Depending upon how you obtained the product, take one of the following actions:
  - ◆ If you have the distribution media, select the CD for your platform. Type the following command and press **Enter** to change to the CD-ROM drive and the directory that correspond to the UNIX platform:

```
cd /cdrom/<platform directory>
```

Refer to the following table for the name of the platform directory for each platform:

| UNIX Platform     | Platform Directory Path |
|-------------------|-------------------------|
| HP PA-RISC series | HP_PA-RISC              |
| HP UX Itanium     | HP_Itanium              |

| UNIX Platform      | Platform Directory Path |
|--------------------|-------------------------|
| IBM System pSeries | IBM                     |
| Sun SPARC systems  | Sun_Solaris             |
| Red Hat            | RedHat_linux            |
| SuSE               | SuSE_linux              |
| Linux zSeries      | IBMS390_linux           |
| Solaris/x86        | Solaris_x86             |

- ◆ If you downloaded the product from the ESD Portal, type the following command and press **Enter** to change to the location of the product download:

```
cd /<location of product download>
```

3. Type the following command to invoke the installation script and press **Enter**:

```
cdinstall
```

The following screen is displayed:

```

Sterling Commerce, Inc.,(TM) Connect:Direct(TM) for UNIX(TM)
Installation Procedure

You are beginning the Connect:Direct for UNIX Installation
Procedure. You will be asked to specify a directory (called
the destination directory) where the Connect:Direct for UNIX
files will be stored.

Please follow the Getting Started Guide and/or Release Notes for the
proper Media Name.

Sterling Commerce, Inc.(TM) and Connect:Direct(TM) are trademarks
of Sterling Commerce, Inc. in the U.S.A. and other countries.

UNIX is a registered trademark of The Open Group
=====

Press ENTER when ready.
```

4. Read the information and press **Enter**. The following screen is displayed:

```

=====
Connect:Direct for UNIX License Agreement.
=====
The license agreement must be accepted for the installation to continue.

Press ENTER to display the agreement.
(Then use the spacebar to page through the agreement.)
```



5. Read the information and press **Enter**. Use the spacebar to page through the license agreement. When you are prompted to accept the License Agreement, press **Enter**. The following screen is displayed:

```
Enter the FULL path of the directory where
Connect:Direct for UNIX 4.0.00 will be installed.
You can use $HOME to shorten the name:[$HOME/cdunix]
```

6. Type the path and press **Enter**. The following screen is displayed:

```
WARNING: "<directory path>" : Directory exists

Files in <directory path> could be overwritten by the
installation. Do you want to continue: [Y/n]
```

7. Press **Enter** to continue. The following screen is displayed:

```
Installed components detected in this directory.

A previous version of C:D for UNIX was detected.

Would you like this procedure to detect and upgrade your currently installed
options with minimal interaction?
If yes, the configuration files will be left in place and reused.
If not, the full installation procedure will prompt to either reuse, or purge
and rebuild, each configuration file.

Caution: If you are upgrading from earlier version of C:D for UNIX, existing
Processes in the tcq may encounter conversion error. They will need to be deleted
and resubmitted.

Type y or press Enter to continue with the upgrade procedure, or
type n to run the full installation procedure:[Y/n]
```

8. Type **n** and press **Enter** to run the full installation procedure.  
9. The following screen is displayed:

```
Connect:Direct for UNIX installation directory specified:
[directory path]

Please select one of the following installation options:

(1) Connect:Direct for UNIX Server and Client(CLI/API)
(2) Connect:Direct for UNIX Server
(3) Connect:Direct for UNIX Client(CLI/API)
(4) Connect:Direct for UNIX File Agent
(5) Connect:Direct Secure+ Option for UNIX
(6) Connect:Direct for UNIX SNMP Agent
(7) EXIT

Enter your choice:[1]
```

10. Type **5** and press **Enter**. The following prompt is displayed:

```
Enter the path "AND filename" where the installation file is mounted or
where the ESD portal download is extracted (e.g. /cdrom/<platform>/cdunix):
```

11. Type the full Connect:Direct for UNIX installation path and filename and press **Enter**. You are prompted to confirm the installation.

```
Connect:Direct Secure+ Option for UNIX 4.0.00 will be
installed on your system. Do you want to continue?:[Y/n]
```

12. Press **Enter** to continue. The program determines if enough free space exists to complete the operation.

- ◆ If sufficient space is available, the Secure+ installation script and cpio files are extracted.
- ◆ If the space is insufficient, the program suggests that you delete enough files to provide the necessary disk space and then exits. After you have cleared enough space, restart the installation procedure.

After the files are extracted, the following screen is displayed:

```
Sterling Commerce, Inc.,(TM) Connect:Direct(TM) Secure+ Option
for UNIX(TM) Installation Procedure

You are beginning the Connect:Direct Secure+ Option for UNIX
Installation Procedure. You will be asked to specify a directory
(called the destination directory) where the Connect:Direct for
UNIX files are stored. The Secure+ Module will be installed in
this same directory where Connect:Direct is installed.

Sterling Commerce, Inc.(TM) and Connect:Direct(TM) are trademarks
of Sterling Commerce, Inc. in the U.S.A. and other countries.

UNIX is a registered trademark of The Open Group

Press ENTER when ready.
```

13. Read the screen and press **Enter**. The following prompt is displayed:

```
You have selected <installation directory> for installation. Do you want to
continue?:[Y/n]
```

14. Press **Enter** to continue. A message is displayed regarding the amount of disk space required to install Secure+ Option for your platform, and then the installation program determines if sufficient space exists:

- ◆ If sufficient space is available, press **Enter** to continue.
- ◆ If the space is insufficient, the script suggests that you delete enough files to provide the necessary disk space and then exits. After you have cleared enough space, restart the installation procedure.

15. A screen is displayed as the files are extracted from the media and the JRE is configured. After the JRE is configured, the following prompt is displayed:

```

Initializing the Secure+ Parmfile.

Please enter name of Connect:Direct node you want to customize:[<node name>]

```

16. Press **Enter** if your node name is displayed. If your node name is not displayed, enter your node name and press **Enter**. The following prompt is displayed:

```

Please enter a passphrase. The passphrase must be at least 32 characters
in length. It is not necessary to remember this passphrase.

```

17. Enter a passphrase of at least 32 random characters and press **Enter**. The installation is complete and the following prompt is displayed:

```

The initialize Secure+ Parmfile operation succeeded.

Would you like to return to the installation menu?:[Y/n]

```

18. Press **Enter** to return to the installation menu or press **n** and **Enter** to exit the installation menu.

---

## Configuring SNA Support for Connect:Direct for UNIX

For LU6.2 connectivity, you must configure SNA support. Refer to Appendix B, *SNA LU6.2 Connectivity* for instructions on modifying both the initialization parameters and network map files.

---

## Defining High-Availability Settings in the Configuration Files

After you install Connect:Direct for UNIX on a shared file system, you must modify some Connect:Direct for UNIX parameters to support a clustering environment. Complete the following procedure to modify the configuration files for a cluster environment:

---

**Note:** You must install Connect:Direct for UNIX on a shared cluster file system to use it in a cluster environment.

---

1. Modify the following parameters:
  - ◆ In the initialization parameters file (`initparm.cfg`), set `:comm.info=0.0.0.0;nnnn:\` where `nnnn` is the number of the listening port you defined during installation.

- ◆ In the `api.parms` record of the NDMAPI configuration file (`ndmapi.cfg`), set `:tcp.hostname=logical_host_ip_name:\` where `logical_host_ip_name` is the virtual address of the cluster.
  - ◆ In the network map file (`netmap.cfg`), set `:tcp.api=logical_host_ip_name;nnnn:\` where `nnnn` is the API port you defined during installation.
2. In the network map file (`netmap.cfg`), set the outgoing address parameter in the `local.node` record to specify the local host IP name or address of the floating address to the following value. The remote node will also use this value for network map checking.

```
:outgoing.address=(host name |nnnnnn.nnn):\
```

3. Modify the following records in the network map file:
  - ◆ Set `:comm.info=logical_host_ip_name;1364:\` to configure the loopback remote node record.
  - ◆ Set `tcp.max.time.to.wait` to a value other than zero and less than the value set in the resource group manager of the cluster software to allow for clean shutdowns.
4. Acquire an asset protection key that includes the CPUs of all computers in the cluster.
5. In the same volume group as the installation file system, create a user data file system that is shared by all cluster nodes.

### Additional Configuration Requirements in a SunCluster 3.X Environment

The High-Availability cluster commands shown below are not intended to be a complete set of instructions for setting up the High-Availability cluster software. Additional steps may be required to complete the configuration of the High-Availability environment. High-Availability cluster expertise is the responsibility of the customer. White papers detailing specific environments, setup steps, and testing of various High-Availability clusters are available on the Support On Demand web site.

In addition to modifying the configuration files, complete the following procedure to set up a SunCluster 3.X cluster:

1. Type the following command to create the cluster resource:

```
scdscreate -V SCI -T cd
```

Use the `V` parameter to define the vendor ID and `T` parameter to define the resource ID.

2. Type the following command to configure the custom resource scripts:

```
scdsconfig
```

3. Edit the `SCI.cd` resource file and change the value of `RT_BASEDIR` as follows:

```
RT_BASEDIR=/opt/SCIcd/bin;
RT_BASEDIR=/global/vol1/sci/cduserk1/3.5.00/suncluster+scripts/SCIcd/bin;
```

## Additional Configuration Requirements in a SunCluster 2.2 Environment

In addition to modifying the configuration files, complete the following steps to complete the SunCluster 2.2 setup:

1. Place the following sample scripts and configuration files in a directory that is available to SunCluster 2.2 software:
  - ◆ cd\_start.sh
  - ◆ cd\_stop.sh
2. Update the scripts as required for your environment.
3. Copy the sample scripts to all nodes in the cluster.
4. Issue the **hareg** command to register the Connect:Direct data service. Refer to the SunCluster documentation for more information. Following is a sample command:

```
hareg -r cd \
  -b /control/scripts/directory \
  -m START_NET=cd_start_net.sh \
  -m STOP_NET=cd_stop_net.sh \
  -m ABORT_NET=cd_abort_net.sh \
  -m START=cd_start.sh \
  -m STOP=cd_stop.sh \
  -m ABORT=cd_abort.sh \
  -t START_NET=60 \
  -t STOP_NET=60 \
  -t START=30 \
  -t STOP=30 \
  -h logicalhost \
  -v 3.3.02
```

5. Complete the following steps if the Connect:Direct for UNIX SNMP Agent is installed on your system:
  - a. Copy /etc/srconf/agt to *d\_dir*/srconf/agt.
  - b. Copy /etc/srconf/mgr to *d\_dir*/srconf/mgr.
  - c. Ensure that the following environment variables are defined in the user's profile:
    - SR\_AGT\_CONF\_DIR=*d\_dir*/srconf/agt
    - SR\_MGR\_CONF\_DIR=*d\_dir*/srconf/mgr
  - d. If the SUN master SNMP agent is activated and in use by another application and is using the default ports of 1361 and 1362, add the following environment variables to the user's profile:
    - SR\_SNMP\_TEST\_PORT=1361 (or other available port)
    - SR\_TRAP\_TEST\_PORT=1362 (or other available port)

## Additional Configuration Requirements for IBM HACMP

In addition to modifying the configuration files, complete the following steps to complete the IBM high-availability cluster multiprocessing (HACMP) setup:

1. Place the following sample scripts and configuration files in a directory that is available to the IBM HACMP software:
  - ◆ cd\_start\_net.sh
  - ◆ cd\_stop\_net.sh
2. Update the scripts as required for your environment.
3. Copy the sample scripts to all nodes in the cluster.
4. Complete the following steps if the Connect:Direct for UNIX SNMP Agent is installed on your system:
  - a. Copy /etc/srconf/agt to *d\_dir*/srconf/agt.
  - b. Copy /etc/srconf/mgr to *d\_dir*/srconf/mgr.
  - c. Ensure that the following environment variables are defined in the user's profile:
    - SR\_AGT\_CONF\_DIR=*d\_dir*/srconf/agt
    - SR\_MGR\_CONF\_DIR=*d\_dir*/srconf/mgr
  - d. Configure the SNMP agent to use ports other than the default ports of 1361 and 1362.
  - e. Add the following environment variables to the user's profile:
    - SR\_SNMP\_TEST\_PORT=1361 (or other available port)
    - SR\_TRAP\_TEST\_PORT=1362 (or other available port)

## Additional Configuration Requirements for Hewlett-Packard MC/ServiceGuard

The HP Solutions Competency Center (SCC) has successfully integrated Connect:Direct for UNIX with MC/Service Guard. The implementation and certification of Connect:Direct for UNIX followed the SCC's high availability Implementation and Certification Process. Refer to the *Implementation and Certification With Hewlett-Packard's MC/ServiceGuard High Availability Software* document located under Product Information on the Support on Demand Web site.

---

## Verifying the Installation

After you complete the installation, perform the following steps to verify the installation:

1. Type the following command to identify the release and platform operating system release for Connect:Direct, where *d\_dir* is the destination directory and *binaryx* is a file in the bin/ directory (for example, **cdpmgr**):

```
% d_dir/etc/cdver d_dir/ndm/bin/[binary1 binary2 ...]
```

2. Log in with the user account under which Connect:Direct was installed.
3. Copy your Connect:Direct for UNIX license key to the `d_dir/ndm/cfg/<node>` directory. The license key file name should be `license.key`.
4. Type the following command to start Connect:Direct for UNIX Server, where `d_dir` is the destination directory and `cd_node` is the Connect:Direct node name.

```
$ d_dir/ndm/bin/cdpmgr -i d_dir/ndm/cfg/cd_node/initparm.cfg
```

5. Do one of the following to set the environment variable `NDMAPICFG` to point to the client configuration file:
  - ◆ If you are using the Bourne or Korn shell, type the following command:

```
$ NDMAPICFG=d_dir/ndm/cfg/cliapi/ndmapi.cfg
$ export NDMAPICFG
```

- ◆ If you are using the C shell, type the following command:

```
% setenv NDMAPICFG d_dir/ndm/cfg/cliapi/ndmapi.cfg
```

6. Type the following command to invoke the Connect:Direct client:

```
$ d_dir/ndm/bin/direct
```

7. Type the following command:

```
Direct> select statistics;
```

Read the statistics information and ensure that the initialization started with no errors. If any errors are displayed, resolve the errors before continuing.

8. Type the following command to submit a sample Process:

```
Direct> submit file=d_dir/ndm/bin/sample.cd;
```

This sample Process copies a binary file named `msgfile.cfg` to the file `cddelete.me` in your HOME directory (your node is both the PNODE and the SNODE). The checkpointing interval is set to 2M and extended compression is used.

9. Type the following **select process** command to monitor data transmission activity:

```
Direct> select process pnumber=1;
```

Connect:Direct generates a report with the Process name and number, user, submitter node, queue, and status.

10. After the Process is complete, type the following **select statistics** command to review the statistics log for the Process:

```
Direct> select statistics pnumber=1;
```

11. Do one of the following:

- ◆ Type the following command to manually shut down the Connect:Direct server:

```
Direct> stop;
```

- ◆ When running Connect:Direct for UNIX with the LU6.2 feature on HP SNA, NCR SNA, Brixton SNA, or SunLink SNA, type the following command to stop Connect:Direct:

```
Direct> stop force;
```

- ◆ Type the following command to quit the Connect:Direct client without shutting down the server:

```
Direct> quit;
```

The client terminates automatically when you stop the server.

Refer to the *Connect:Direct for UNIX User's Guide* for command syntax and parameters.



---

# Managing Files with Connect:Direct File Agent

Connect:Direct File Agent is a component of Connect:Direct that provides unattended file management. Before using Connect:Direct File Agent, you must plan how to configure it to automate file management for your site. After planning what you need to accomplish, configure File Agent to connect to a Connect:Direct server, watch the directories that files of interest will be added to, and submit a specified Connect:Direct Process to the server when a file is detected.

---

## Connect:Direct File Agent

Connect:Direct File Agent provides monitoring and detection capabilities that enhance the automation you accomplish with Connect:Direct Processes. You cannot create Processes with File Agent; however, File Agent variables can be used to pass arguments to a Process. File Agent does not delete, copy, or move files directly, but it helps you accomplish such tasks by submitting the Process you specify in the configuration to the Connect:Direct server. Before you specify a Connect:Direct Process in the File Agent configuration, you must create and test the Processes to ensure that it performs tasks as expected when File Agent submits the Process.

Using the File Agent configuration interface and Help system, you define the *default configuration file* (Default\_Config.ser). The default configuration file defines the Connect:Direct server that Connect:Direct File Agent communicates with; the directory, or directories, that File Agent monitors; and how a file added to a watched directory or a detected system event are processed.

You can configure Connect:Direct File Agent to operate in either of the following ways:

- ◆ Watch for any file to appear in one or more *watched* directories and submit the default Process after detecting the newly added file.
- ◆ Override the default Process specified and apply either *watched file event* rules (Submit Process rule) or *system event* rules that is enabled for the configuration. File Agent applies a *watched file event* rule to a detected file by checking file properties to determine whether criteria specified by the rule are met. A *system event* rule checks whether a system event meets criteria specified by the rule. When all criteria for a rule are met, File Agent submits the Connect:Direct Process associated with that rule.

You can create File Agent rules based on the following properties:

- ◆ Full or partial name of the file detected in a watched directory
- ◆ Size of the file detected in a watched directory
- ◆ System event title
- ◆ System event contents (as included in a stack trace)

You can specify more than one rule in a File Agent configuration; each rule can have File Agent submit a different Process.

---

**Note:** Although you can create multiple rules as part of a File Agent configuration, File Agent processing ends when all criteria for a rule are met. Therefore, you should specify rules so that those with more specific criteria (properties) are listed first in the configuration.

---

For optimum performance, you should configure Connect:Direct File Agent to communicate with the Connect:Direct node where it is installed. You can configure File Agent to use continuous signon and remain connected to the API port for the Connect:Direct server at all times, or configure it to connect to the port only when it needs to. File Agent can be installed on UNIX, Windows, and z/OS operating systems. When you use Connect:Direct with UNIX or Windows, the watched directory is a UNIX pathname or a Windows path to the directory. When you use Connect:Direct with z/OS, the watched directory can be the HFS pathname for a file or a directory, the full MVS data set name, or a partial MVS data set name.

File Agent can monitor multiple directories, including local and network directories. File Agent scans the watched directories you specify in the configuration for newly added files (unless you specify a rule to force other operation). By default, Connect:Direct File Agent scans a watched directory once per minute. For example, if you start File Agent at 1:00 p.m., a file added to that watched directory at 12:55 a.m. is not detected as newly added. If you start File Agent at 1:00 p.m., and a file is placed in the watched directory at 1:01 p.m., then File Agent detects this newly added file. File Agent detects a file only one time, unless the file is accessed and saved with a later timestamp.

Using Connect:Direct File Agent requires an understanding of Connect:Direct Processes, operating systems, and scripting (for regular expression operator use with File Agent rules).

## Running File Agent

You can run File Agent from a UNIX or command line, configure it to start automatically as a Windows Service at system startup, or configure it to run from a Windows shortcut. Use the command line to verify that File Agent is working correctly or to specify an alternate configuration file. After you run File Agent from the command line to verify that File Agent is operating correctly, run it using the method that requires the least user intervention.

When File Agent runs as a Windows service, it is fully automated, requiring little user intervention. On UNIX, you can modify the initialization sequence of the computer to call the `cdfa.sh` script and run Connect:Direct File Agent whenever you restart the computer. On z/OS, you must run the appropriate job to start the File Agent configuration interface, or start or shutdown the File Agent.

Depending on your network and how you use Connect:Direct, there might be more than one File Agent running (on different hosts). The first File Agent that connects to a Connect:Direct server

becomes the File Agent *gate keeper*. The gate keeper port is used to keep track of locations monitored in case multiple File Agents are configured to watch a single directory. The gate keeper ensures that only one File Agent detects a file that appears in a watched directory.

## File Agent Logging Capabilities

File Agent logging capabilities vary by platform. Running File Agent from a command line using the verbose argument turns on File Agent logging when it is available. When you run File Agent as Windows service, no information is logged unless an error occurs.

Connect:Direct File Agent provides the following levels of status information when logging is available on a platform:

- ◆ System log—Shows all system activity. This log is created only when you specify verbose mode or if an error occurs. If you are running verbose mode from the command line, this log information is shown in the command line window. If you are not running in verbose mode, the system log appears in the snaps directory (located in the File Agent installation directory), which is created when the first event occurs.
- ◆ First Failing Status (FFS) log—One or more logs created when an error occurs. The snaps directory is created as needed and contains the FFS logs for any errors encountered by File Agent.

Using trace commands provided for your platform can also help capture details related to File Agent operation.

## File Agent Configuration Interface and Help

Instructions for configuring File Agent are available in the online Help system that you access from the configuration interface. Field-level Help is displayed in the bottom pane of the configuration interface. Clicking **Help** displays the online configuration procedures.

---

# Planning the File Agent Configuration


Before you begin configuring File Agent, you must use Connect:Direct to choose or create the Processes that perform the actions you want to automate. You will need to carefully configure File Agent to connect to the Connect:Direct server and to monitor and detect conditions (such as a file addition to a directory). At detection, Connect:Direct File Agent submits the Process for executing actions that need to be performed in response to those conditions.

Refer to *Connect:Direct File Agent Configuration Examples* on page 63 to review some configuration scenarios that can help you plan your File Agent configuration. When you configure File Agent, it is best to take an incremental approach; that is, first specify the server connection, a default Process, and the watched directories. Run a test from the command line to ensure that the default File Agent configuration is working correctly. After a successful test of the default configuration, you can run the File Agent Configuration Interface again to start building and testing

any File Agent rules that you want to apply, one by one. After you successfully create a default configuration, you can use the file as the basis for other configuration files.

Use the *File Agent Worksheet* on page 61 to gather the information you need to configure File Agent. Contact your system administrator for the site-specific information you will need to establish a connection to the Connect:Direct server. As you complete the worksheet, run the File Agent Configuration Interface and use the File Agent Help system to learn about entering parameters. The Help system and field-level help provide complete descriptions of parameters and arguments you can specify in the configuration file. Make copies of this worksheet if you have to configure File Agent on multiple Connect:Direct servers.

The following diagram illustrates the flow of steps for setting up File Agent for use in a production environment.



## File Agent Worksheet

| <b>Connect:Direct Server Connection Information</b>  |  |
|--|--|
| Userid for API (for connecting to the Connect:Direct server) <b>Required</b><br>Must match the user ID used to submit the default Process.   | <input style="width: 95%;" type="text"/> |
| Password for API (for connecting to the Connect:Direct server) <b>Required</b><br>Must match the password used to submit the default Process.  | <input style="width: 95%;" type="text"/> |
| API host DSN name (name of the host on which the Connect:Direct server is located) <b>Required</b>   | <input style="width: 95%;" type="text"/> |
| API port (default =1363)<br>1–5 digit port number that Connect:Direct File Agent uses to connect to the Connect:Direct server API. <b>Required</b>   | <input style="width: 95%;" type="text"/> |
| Gatekeeper port (default=65530)<br>Port used to track directory monitoring and ensure that multiple File Agents do not monitor a single directory. <b>Required</b>   | <input style="width: 95%;" type="text"/> |
| Gate keeper DNS name (optional)<br>(default=127.0.0.1)   | <input style="width: 95%;" type="text"/> |
| <b>Default Process and Watched Directory Information</b>   |  |
| Watched directories:<br>For Windows and UNIX, one or more valid specifications of paths (Windows) or pathnames (UNIX). For z/OS, one or more fully specified HFS pathnames of a file or directory, or a full or partial MVS data set name. <b>Required</b><br>List one valid entry per line. |  |
| <input style="width: 95%; height: 20px;" type="text"/><br><input style="width: 95%; height: 20px;" type="text"/><br><input style="width: 95%; height: 20px;" type="text"/><br><input style="width: 95%; height: 20px;" type="text"/>   |  |

| <b>Default Process and Watched Directory Information</b>  |  |
|---|--|
| Default Process:<br>Windows and UNIX: Valid path and name of the file that contains the default Process on the Connect:Direct server. _____<br>z/OS: Member Name in DMPUBLIB _____<br><b>Note:</b> If you do not specify a default Process or create a rule, no processing is performed when a file or event is detected. |  |
| Default arguments (See Help for complete list.)<br>Argument string to pass to the default Process in the following format:<br>&FA_XXXX_XXX. _____<br><b>Note:</b> The percent sign (&) and period (.) are required.   |  |
| Error Process: _____  |  |
| Error arguments _____   |  |
| Process class (default=1) <b>Required</b> _____   |  |
| Process priority (default=1) _____  |  |
| Watched file interval (default=1 minute) _____  |  |
| File completion delay (default=1 minute) _____  |  |

---

**Note:** If you are using X Windows, the X11 display variable is used to connect to the GUI server for terminal emulation. The File Agent Configuration Interface will display on the monitor specified for the X11 display variable. If you want to display the File Agent Configuration Interface on a Windows computer, you must specify the network ID of the terminal you want to use for displaying the File Agent Configuration Interface.

---

## Connect:Direct File Agent Configuration Examples

The following examples illustrate three typical scenarios for using Connect:Direct File Agent. Fields that are not required to be set for the operation demonstrated in the example are not included in the tables of configuration parameters. Required fields are indicated by an asterisk(\*) in the File Agent Configuration Interface, and all fields are described in field-level Help. You can use the sample scenarios to become familiar with settings for parameters you must set using the configuration interface in order to accomplish watched directory monitoring and file detection needs.

See the *File Agent Worksheet* on page 61 for a description of the parameters required to establish the connection. The tables of sample data for these scenarios assume that you have already configured the site-specific parameters required to establish a connection to the Connect:Direct server where File Agent is installed. The sample scenarios also assume that the Connect:Direct Processes that will perform tasks associated with Connect:Direct File Agent file detection activities have been created.

### Detecting a File Added to a Watched Directory on an z/OS System

Some users need to access a report file that is expected to be transferred to a location that only administrators can access. File Agent can be configured to perform the processing on a z/OS system:

- ◆ Monitor the watched data set called EASTERN.Q1.REPTS.
- ◆ Submit a default Process called DEFPROC. The default Process has been created to copy a file detected in the watched data set to a specified location for access by users.

| Tab        | Field               | Sample or Description  |
|------------|---------------------|--|
| File agent | Watched directories | Type EASTERN.Q1.REPTS to specify the fully qualified MVS data set name to watch.   |
|            | Default Process     | Type DEFPROC, the member name for the Process in DMPUBLIB.<br><b>Note:</b> If no default Process is specified and the file does not match a rule, then no processing occurs. |

### Detecting a File by File Size on a Windows System

Customer transaction files are regularly transferred into the Windows directory c:\monthend\datafile. Files larger than 1 MB require special processing that will automatically be performed on files in a certain directory.

The sample values in the following table accomplish the following processing:

- ◆ Monitor the watched directory c:\monthend\datafile
- ◆ Apply the rule titled “find big file” to detect files larger than 1 MB.

- ◆ Override the default Process and submit a Process that is associated with the Check file size rule. This fixbigfile.cdp Process will copy a file larger than 1 MB from the c:\monthend\datafile directory to the c:\reprocess directory.
- ◆ Pass the path and file name of the file that meets the criteria for the “find big file” rule to the Process fixbigfile.cdp.

| Tab        | Field or Dialog Box                                      | Actions and Sample Entry   |
|------------|--|--|
| File agent | Watched directories field                                | Specify the directory to watch. Type the directory path for the directory that File Agent will watch:<br><b>c:\monthend\datafiles</b>  |
| Rules      | Create rule dialog box                                   | Click <b>New</b> and type the name you want to give the rule in the field:<br><b>find big file</b><br>Click <b>find big file</b> in the list of rules and click <b>Edit</b> .  |
|            | Match criteria list for rule “find big file”             | Specify the criterion to check for a detected file. Select the default criterion name, <b>Not enabled: system event title matches “ ”</b> and click <b>Edit match</b> .  |
|            | Edit match criterion for rule “find big file” dialog box | <ul style="list-style-type: none"> <li>◆ Click <b>Enabled</b> to enable the criteria you are about to specify.</li> <li>◆ Click <b>Size of the newly arrived file</b></li> <li>◆ Click <b>Matches</b> to display the options for the comparison. Click <b>Greater than</b> to define the how the file size should compare.</li> <li>◆ Type <b>1048576</b> in the <b>Compare size</b> field and click <b>OK</b>.</li> </ul> |
|            | Process name field                                       | Scroll down to view the <b>Submit Process information for watched file event rule “find big file”</b> . Type the directory path and filename for the Process that File Agent is to submit when the rule Find big file results in a match:<br><b>c:\processes\fixbigfile.cdp</b><br>Click <b>Done</b> and then click <b>Save</b> .  |



## Detecting a System Event by Title on a Windows System

`IndexOutOfRangeException` is the title of an event that indicates a number is outside of an expected range. In the following example, File Agent is used to detect an event with `IndexOutOfRangeException` in the title, pass a string (the event title) to a `Connect:Direct Process`, and then submit a `Process` to the `Connect:Direct` server that will perform actions the environment requires for this type of event. In this scenario, the event `IndexOutOfRangeException` could indicate activity that a network administrator should investigate. Because the site uses a `Connect:Direct` mailbox system, the configuration will include the administrator's account to be notified when `Connect:Direct File Agent` submits a `Process` for the `IndexOutOfRangeException` rule.

The sample values in the following table accomplish the following processing:

- ◆ Override the default `Process` and submit `\processfolder\oo_boundserproc.cdp`
- ◆ Send a message to the administrator's mailbox system account after submitting the `oo_boundserproc.cdp` `Process` for the rule.

| Tab          | Dialog Box, Window, or Field   | Description/Example  |
|--------------|--|--|
| <b>Rules</b> | <b>Create rule</b> dialog box  | Type <b>index out of bounds</b> as the name of the rule you are creating.  |
|              | <b>Match criteria list for rule "index out of bounds"</b> window                     | Select the default criteria <b>Not enabled: System event title matches " "</b> and click <b>Edit match</b> .   |
|              | <b>Edit match criterion for rule "index out of bounds"</b> dialog box                | <ul style="list-style-type: none"> <li>◆ Click <b>Enabled</b> to enable the criteria you are about to specify.</li> <li>◆ Click <b>System event title</b> as the criterion to match for the rule.</li> <li>◆ Click <b>Matches</b> on the drop-down field to see the options for comparison to a string.</li> <li>◆ Click <b>Contains</b> to specify how the compare string should relate to a system event title that File Agent detects.</li> <li>◆ Type <b>IndexOutoffBounds</b> as the <b>Compare String</b> to indicate that the system event title should include this string.</li> <li>◆ Click <b>OK</b>.</li> </ul> |
|              | <b>Submit Process information for system event rule "index out of bounds"</b> window | Type information into the fields that will define the <code>Process</code> to submit and the mailbox user to notify after the <code>Process</code> is submitted.   |
|              | <b>Process name</b> field  | Type <code>c:\processfolder\errproc.cdp</code> to specify the path and file name for the <code>Process</code> File Agent submits when a file meets the rule criteria.  |
|              | <b>Notification userid</b> field   | Type <code>adminjim@company.com</code> to specify the user to notify when File Agent submits the <code>Process</code> .  |

## Passing the UNIX Pathname for a Detected File to a Process

Because Connect:Direct File Agent can watch multiple directories for the appearance of a new file, the Connect:Direct Process that File Agent is to submit to the server at the appearance of a new file might need to reference the Windows Path or UNIX pathname for the detected file as part of commands and statements in the Process.

In the following example, a UNIX pathname is passed to the default Process, copynewfile.cdp.

| Tab               | Dialog box, Window, or Field | Sample Entry  |
|-------------------|------------------------------|---|
| <b>File agent</b> | <b>Watched directories</b>   | Type one UNIX pathname per line for each location File Agent is to watch for the appearance of files:<br><b>user/bin/monthend/<br/>quartend/easterndiv/errorfiles<br/>managers/special/reports</b><br>File Agent checks these pathnames for new files.  |
|                   | <b>Default process</b>       | Type the UNIX pathname and filename for the Connect:Direct Process that File Agent is to run when a file appears in any watched directory specified:<br><b>user/bin/admin/copynewfile.cdp</b><br>The pathname where File Agent detected a new file is passed to this Process.   |
|                   | <b>Default arguments</b>     | Type the File Agent variable for passing a UNIX pathname or Windows path, including the leading percent sign (%) and the ending period (.):<br><b>&amp;FAP=%FA_PATH_FOUND.</b><br>In this example, <b>&amp;FAP</b> is the variable to which File Agent will pass the UNIX pathname where the file was detected. <b>%FA_PATH_FOUND.</b> is the File Agent variable used to indicate the information to pass to the Connect:Direct Process. |

---

# Installation Worksheets

Before you begin installing Connect:Direct for UNIX, complete the worksheets in this appendix to help you gather the information you need to complete the installation procedure.

Complete the following worksheets before beginning the installation procedure:

- ◆ *Installation Worksheet* on page 68
- ◆ *Customization Worksheet* on page 68
- ◆ *User Authorization Information File Worksheet* on page 69
- ◆ *CLI/API Configuration File Worksheet* on page 74

Connect:Direct automatically generates the network map and server and client authentication key files. However, you may want to further customize these files. The following worksheets are provided for your convenience:

- ◆ *Network Map Remote Node Information File Worksheet (TCP/IP and UDT Only)* on page 75
- ◆ *Server Authentication Key File Worksheet* on page 76
- ◆ *Client Authentication Key File Worksheet* on page 76

In the following worksheets, host name refers to the TCP/IP computer name, and node name refers to the Connect:Direct node name.

---

## Installation Worksheet

Complete this worksheet to assist you during the installation procedure.

| Parameter  | Value |
|--|-------|
| TCP/IP host name of the computer where the Connect:Direct server is installed              |       |
| Directory or path on which the distribution media will be mounted                          |       |
| Destination directory where Connect:Direct will be installed, including the full path name |       |

---

## Customization Worksheet

Use this worksheet during customization. Refer to the *Customizing Connect:Direct for UNIX* on page 32.

| Parameter  | Default Value | Value to Use |
|--|---------------|--------------|
| Connect:Direct node name you are customizing, up to 16 characters long.  |               |              |
| <b>Initialization Parameters File Information</b>  |               |              |
| TCP/IP port number that the server monitors for an API connection request.   | 1363          |              |
| TCP/IP port number that the server monitors for a remote Connect:Direct connection request:  | 1364          |              |
| <b>Note:</b> Use the default port number, if available. If the default port number is being used by another service, use any other available port. Check the /etc/services file for a list of ports. |               |              |

---

## User Authorization Information File Worksheet

Use this worksheet when you are defining the user authorization information which includes the remote user information records and local user information records.

All Connect:Direct users must have an entry in the user authorization information file.

### Remote User Information Record

Connect:Direct uses the remote user information record to establish a proxy relationship between remote and local user IDs. Remote user IDs are translated to valid local user IDs on the system where you are installing Connect:Direct for UNIX. Connect:Direct also uses the remote and local user information records to determine the functionality of the user IDs that are translated and connected to it through a client using a Connect:Direct API.

Use the following table to create a list of remote user IDs and the local user IDs to which they will be mapped. If necessary, make copies of this page to record additional remote user IDs and local user IDs.

For more information on creating remote user information records and for information on using special generic characters to map remote user IDs, refer to the *Connect:Direct for UNIX Administration Guide*.

| Remote User ID | at | Remote Node Name | mapped to | Local User ID |
|----------------|----|------------------|-----------|---------------|
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |
|                | @  |                  | =         |               |

## Local User Information Record

Use the following table to record the local user ID records to create and the parameters to define. Define the additional parameters by editing the `userfile.cfg` file using any standard UNIX editor.

Default values are shown as capital letters in brackets. Before you begin defining local user information records, make copies of this worksheet for the number of users you plan to create.

| Local User ID | Parameter                | Description  | Value to Assign                           |
|---------------|--------------------------|--|---|
|               | <code>admin.auth</code>  | Determines if the user has administrative authority.<br>y—All the other command parameter capabilities in the local user information record are automatically assigned to this user.<br>n—You must grant specific command parameters individually. |   |
|               | <code>cmd.chgproc</code> | Specifies whether the user can issue the <b>change Process</b> command.<br>y—Allows the user to issue the command.<br>n—Prevents the user from issuing the command.<br>a—Allows all users to issue this command.                                   |   |
|               | <code>cmd.delproc</code> | Specifies whether the user can issue the <b>delete Process</b> command.<br>y—Allows the user to issue the command.<br>n—Prevents the user from issuing the command.<br>a—Allows all users to issue this command.                                   | y   n   a<br>y—Default<br>a—For all users |
|               | <code>cmd.flsproc</code> | Specifies whether the user can issue the <b>flush Process</b> command.<br>y—Allows the user to issue the command.<br>n—Prevents the user from issuing the command.<br>a—Allows all users to issue this command.                                    | y   n   a<br>y—Default<br>a—For all users |

| Local User ID | Parameter    | Description   | Value to Assign  |
|---------------|--------------|---|------------------|
|               | cmd.selproc  | Specifies whether the user can issue the <b>select Process</b> command.<br>y—Allows the user to issue the command.<br>n—Prevents the user from issuing the command.<br>a—Allows all users to issue this command.    |                  |
|               | cmd.selstats | Specifies whether the user can issue the <b>select statistics</b> command.<br>y—Allows the user to issue the command.<br>n—Prevents the user from issuing the command.<br>a—Allows all users to issue this command. |                  |
|               | cmd.stopndm  | Specifies whether the user can issue the <b>stop</b> command.<br>y—Allows the user to issue the command.<br>n—Prevents the user from issuing the command.   |                  |
|               | cmd.submit   | Specifies whether the user can issue the <b>submit Process</b> command.<br>y—Allows the user to issue the command.<br>n—Prevents the user from issuing the command.   |                  |
|               | cmd.trace    | Specifies whether the user can issue the <b>trace</b> command.<br>y—Allows the user to issue the command.<br>n—Prevents the user from issuing the command.  |                  |
|               | descrip      | Permits the administrator to add descriptive notes to the record.   | text string_____ |
|               | name         | Specifies the name of the user.   | user name_____   |
|               | phone        | Specifies the telephone number of the user.   | user phone_____  |

| Local User ID | Parameter          | Description  | Value to Assign |
|---------------|--------------------|--|-----------------|
|               | pstmt.copy         | Specifies whether the user can issue the <b>copy</b> command.<br>y—Allows the user to issue the command.<br>n—Prevents the user from issuing the command.  |                 |
|               | pstmt.copy.ulimit  | Specifies the action to take when the limit on a user output file size is exceeded during a <b>copy</b> operation.<br>The value for this parameter overrides the equivalent value for the <b>ulimit</b> parameter in the initialization parameters file. If a value is not defined in the initialization parameters file, the default is <b>n</b> .<br>y or n or nnnnnnK or nnnnM or nG where nnnnnnK, nnnnM or nG establishes a default output file size limit for all copy operations.<br>K—Thousands of bytes.<br>M—Denotes millions of bytes.<br>G—Denotes trillions of bytes.<br>The maximum value you can specify is 1 terabyte. |                 |
|               | pstmt.download     | Specifies whether the user can download files.<br>y—Allows the user to issue the command.<br>n—Prevents the user from issuing the command.   |                 |
|               | pstmt.download_dir | Specifies the directory to which the user can download files.  |                 |
|               | pstmt.runjob       | Specifies whether the user can issue the <b>run job</b> statement.<br>y—Allows the user to issue the command.<br>n—Prevents the user from issuing the command.   |                 |
|               | pstmt.runtask      | Specifies whether the user can issue the <b>run task</b> statement.<br>y—Allows the user to issue the command.<br>n—Prevents the user from issuing the command.  |                 |



| Local User ID | Parameter        | Description  | Value to Assign |
|---------------|------------------|--|-----------------|
|               | pstmt.submit     | Specifies whether the user can issue the <b>submit</b> statement.<br><b>y</b> —Allows the user to issue the command.<br><b>n</b> —Prevents the user from issuing the command.  |                 |
|               | snode.ovrd       | Specifies whether the user can code the <b>snodeid</b> parameter on the <b>submit</b> command and <b>Process</b> and <b>submit</b> statements.<br><b>y</b> —Allows the user to issue the command.<br><b>n</b> —Prevents the user from issuing the command. |                 |
|               | pstmt.upload     | Specifies whether the user can upload files.<br><b>y</b> —Allows the user to issue the command.<br><b>n</b> —Prevents the user from issuing the command.   |                 |
|               | pstmt.upload_dir | Specifies the directory from which the user can upload files.  |                 |
|               | run_dir          | Specifies the directory that contains the programs and scripts the user can execute.   |                 |
|               | submit_dir       | Specifies the directory from which the user can submit Processes.  |                 |

---

## CLI/API Configuration File Worksheet

Use this worksheet to define the parameters needed to create a client configuration file. Create a separate file for each client attached to the server. Refer to *Connect:Direct for UNIX Administration Guide* for details on modifying the file.

| Parameter   | Default Value | Value To Use |
|---|---------------|--------------|
| Port number of the Connect:Direct for UNIX server to which this client will connect.  | 1363          |              |
| <b>Note:</b> Use the default port number if available. If the default port number is being used by another service, use any other available port. Check the /etc/services file for a list of ports. |               |              |
| Host name of the Connect:Direct for UNIX server to which this API will connect.   |               |              |
| You can also type the IP address of the server.   |               |              |

---

---

## Network Map Remote Node Information File Worksheet (TCP/IP and UDT Only)

The initial network map file containing a local node definition is created for you during the installation procedure; however, you must add a remote node record to the network map for each remote node you will communicate with unless you plan to specify the IP address or host name with the SNODE parameter when you submit a Process.

---

**Note:** You must define a remote node information record for any node you plan to communicate with using UDT. You cannot specify a hostname or IP address for the SNODE in a Process if you are using UDT to communicate with the remote node.

---

Use the information on this worksheet when you modify the network map. Refer to the *Connect:Direct for UNIX Administration Guide* for details on modifying the file.

Make a copy of this worksheet for each remote node in the network.

| Parameter   | Default Value | Value To Use |
|---|---------------|--------------|
| Remote Connect:Direct node name   |               |              |
| Host name or IP address on which the remote Connect:Direct server will run. |               |              |
| Communication port number to call the remote Connect:Direct server:         | <b>1364</b>   |              |
| comm.transport (UDT only)   |               |              |

---

## Server Authentication Key File Worksheet

The initial server authentication key file is created during the installation procedure; however, you can update your key later. Use the information on this worksheet when you modify your key. Refer to the *Connect:Direct for UNIX Administration Guide*, when determining appropriate values.

| Parameter   | Default Value | Value To Use |
|---|---------------|--------------|
| The host name on which the API is executed.<br>An asterisk (*) stands for any host. | *             |              |

Connect:Direct security depends on a key (similar to a password) in a Connect:Direct server and an identical key in each API that communicates with that server. The keys are defined and coordinated by the system administrator of the specific node or nodes, and should be kept secure. Be sure the authentication keys are available during installation, but do not record them on this worksheet or where they can be lost.

---

## Client Authentication Key File Worksheet

The initial client authentication key file is created automatically during the installation; however, you can update your key at a later date. Use the information on this worksheet when you modify the key. Refer to the *Connect:Direct for UNIX Administration Guide*, when determining appropriate values.

| Parameter  | Default Value | Value To Use |
|--|---------------|--------------|
| The host name on which a Connect:Direct is executed.<br>An asterisk (*) stands for any host. | *             |              |

Connect:Direct security depends on a key, similar to a password, in a Connect:Direct server and an identical key in each API that will communicate with that server. The keys are defined and coordinated by the system administrator of the specific node or nodes, and should be kept secure.

Have the authentication keys you will use available during installation, but do not record them on this worksheet or anywhere else that could compromise security.

---

# SNA LU6.2 Connectivity

This appendix instructs you on installing Connect:Direct for UNIX on SNA systems. It assumes that you have already installed an SNA package and that you are familiar with configuring the SNA package to support independent LU6.2 connections.

---

## About SNA LU6.2 Connections

The Connect:Direct for UNIX product supports SNA LU6.2 connections in addition to TCP/IP connections. SNA LU6.2 connectivity is a separately licensed Connect:Direct feature.

For a list of platforms that are supported for LU6.2 connectivity, refer to the *Connect:Direct for UNIX Release Notes*.

### Supported Interfaces

Following is a list of supported interfaces:

- ◆ Token ring
- ◆ Ethernet
- ◆ SDLC
- ◆ X.25 (QLLC)

### Session Support

Connect:Direct for UNIX supports both independent and dependent LU6.2 sessions. Configuring independent LU sessions simplifies the management of communication between nodes and ensures appropriate recovery in some situations. Dependent LU sessions must be managed manually for communications between Connect:Direct nodes and do not recover properly in some situations.

The maximum number of independent LU sessions you configure defines the maximum number of concurrent transfers between nodes. The total number of sessions determines the number of UNIX transfers that can run simultaneously. Type an even number for the maximum number of sessions so that you can divide equally between the number of contention winner and contention loser

sessions. The recommended number of maximum sessions is 8. The recommended number of contention winner sessions is 4. If supported, the recommended number of automatically established sessions is 4.

## APPC Requirements

APPC requirements are described in the following list:

- ◆ Connect:Direct for UNIX uses a fixed transaction program (TP) name, NNV2DTF.
- ◆ Connect:Direct for UNIX uses basic conversations, sync level = confirm, no conversation level security, and no PIP (program initialization parameters).
- ◆ Do not specify the transaction program (TP) name in hexadecimal.

## Configuration Requirements

Configuration requirements are described in the following list:

- ◆ The Connect:Direct for UNIX daemon must start the session manager, the LU6.2 communications component of Connect:Direct for UNIX. The Connect:Direct for UNIX daemon monitors for inbound ALLOCATEs and starts a session manager to handle the Process submitted by the remote node. The SNA communications package cannot start a session manager.
- ◆ Do not configure the TP as dynamically attachable or as an autostart program.
- ◆ Do not configure a path name to a Connect:Direct for UNIX program when you define the TP.
- ◆ For SNA packages that require that you provide a program name for a TP definition, you must type a program name that does not exist.

## SNA Considerations

SNA considerations are listed in the following section:

- ◆ Connect:Direct for UNIX is tested with the following link LU6.2 types. Currently, not all link types are tested on all platforms.
  - ◆ Token ring
  - ◆ Ethernet
  - ◆ SDLC leased line
  - ◆ X.25 (QLLC)
- ◆ Connect:Direct for UNIX, as an LU6.2 conversation partner, supports any defined link type supported by the SNA package manufacturer. There are no special support or configuration requirements in Connect:Direct for UNIX when using different link types to communicate with the remote node.
- ◆ The RU size selected for use with Connect:Direct for UNIX can strongly affect the observed file transfer throughput. Connect:Direct for UNIX is tested with 1K, 2K, and 4K RU sizes, with inbound and outbound pacing set to 7. Use a 1K RU size to confirm basic functionality, and then use 2K and 4K RU sizes while monitoring network congestion. You can realize a significant gain in throughput by increasing RU sizes from 1K to 4K. Increasing the RU size

beyond 4K or increasing the pacing above 7 generally provides marginal improvement, but can severely degrade network performance.

---

**Note:** VTAM resource names must be typed in uppercase.

---

## Installing and Configuring the AIX SNA Server

For AIX SNA support, you must install and configure either the AIX SNA Server/6000 or the eNetwork Communications Server. You can perform the configuration manually or use the Connect:Direct for UNIX configuration script. The script generates a set of communications profiles, which are used by Connect:Direct for UNIX. Review and modify the values in the profile entries to suit your environment.

The following sections provide the parameter definitions required by Connect:Direct for UNIX and a description of the script included with Connect:Direct.

### Manually Configuring the AIX SNA Server

You can manually configure AIX SNA by modifying the values in the default profile entries, as appropriate for your environment; however, Connect:Direct requires that you add a TP profile name with specific parameters.

To add the TP profile name, log in as root and type one of the following commands:

- ◆ For AIX SNA Server/6000

```
mksnaobj -t'local_tp' -c 'basic' -w '/usr/lpp/sna' CDUTPPRO
```

- ◆ For eNetwork Communications Server

```
smitsnaadmin -x define_tp, tp_name='CDUTPPRO' conv_type='BASIC', \  
security_rqd='NO', sync_level='CONFIRM_SYNC_LEVEL', pip_allowed='YES'
```

The following table lists the parameters required by Connect:Direct. You can assign default values to all other parameters.

| Parameter                  | Definition   |
|----------------------------|--------------|
| Profile name               | CDUTPPRO     |
| Conversion type            | basic        |
| Full path to TP executable | /usr/lpp/sna |

---

**Note:** The path must be a valid directory that differs from the Connect:Direct for UNIX installation directory.

---

### About the Configuration Script

If you want to use a script to generate the Connect:Direct for UNIX configuration for AIX SNA Server/6000 support, run the script located in **etc/cdsnacfg**. After running the script, use SMIT to review the configuration to ensure that the profile values are appropriate for your environment. Sample profiles are provided as a reference.

Using the script, you can configure your IBM pSeries workstation for any of the following options:

- ◆ Token ring
- ◆ SDLC leased line

---

**Note:** Do not use the cdsnacfg script to configure more than one connection. The script archives and deletes the current profile entries before adding values required by Connect:Direct.

---

The script issues commands to perform the following tasks:

- ◆ Stop AIX SNA support.
- ◆ Back up the current configuration to **/snadirs/sna\_XXXX.sav**, where **XXXX** is the current month and day.
- ◆ Delete the current AIX SNA profiles. You can restore or merge saved profiles with the **smit importsna** command.
- ◆ Regenerate base profiles.
- ◆ Configure AIX SNA support as required by Connect:Direct.
- ◆ Verify the AIX SNA configuration.
- ◆ Start AIX SNA support.
- ◆ Start the required SNA connections.



## Running the Configuration Script

Complete the following steps to run the configuration script:

1. Log in as root.
2. From the `d_dir/etc` directory, type the following command:

```
# cdsnacfg
```

---

**Note:** The configuration script can run even if messages indicating irregular processing are returned. Read any messages as you proceed through the configuration. Refer to the AIX SNA documentation as required.

---

The following screen is displayed:

```
=====
                Sample AIX SNA Configuration Script
                COPYRIGHT (C) 1983, 1999 Sterling Commerce, Inc.
=====

Stopping SNA Support ... ..
0513-044 The stop of the sna Subsystem was completed successfully.

Backing up current SNA configuration ... ....
The backup file is /usr/lpp/sna/sna_1111.sav .

Deleting current profile entries ... ..

Regenerating base profiles ... ..

Stopping SNA Support again (overriding possible autostart) ...
0513-004 The Subsystem or Group, sna, is currently inoperative.

Build a sample SNA configuration to access an MVS
host with one of the following connections:

    (1). Token Ring
    (2). SDLC Leased Line

    (3). Exit.

Note 1: Host resource names must be entered in uppercase.

Note 2: When the script completes, use SMIT to verify that
        the selected SNA configuration options match your
        communications environment (e.g. NRZ vs. NRZI for
        SDLC, SAP address for Token Ring).

====> Enter your choice here [1]:
```

3. Do one of the following:
  - ◆ Type **1** to select Token Ring as the connection type and press **Enter**. The default is a token ring connection [1]. Go to step 5.
  - ◆ Type **2** to select SDLC Lease Line as the connection type and press **Enter**. Go to the next step.
4. Type the appropriate value for the following prompts or press **Enter** to select the default as listed in the brackets. The token ring adapter name is an AIX SNA assigned name. All other default values are samples that you can modify. For a VTAM host, the Adjacent Control Point Name is the SSCPNAME. Type host resource names in uppercase letters.

```

Please enter Network Name ..... [CDUNET] :
Please enter Adjacent Control Point Name ..... [HOSTTCP] :
Please enter PU name ..... [RS6PU01] :
Please enter Remote Link Address..... [400076543210] :
Please enter XID node ID..... [07143210] :
Please enter local LU name ..... [RS6LU01] :
Please enter remote LU name (C:D MVS APPLID) .. [NDMAPP4] :
Please enter mode name ..... [NDM621K] :
Please enter Token Ring Adapter name ..... [tok0] :
Please enter Token Ring Adapter name ..... [0]

```

5. Type the appropriate value for an SDLC leased line connection or press **Enter** to select the default values in brackets. The Portmaster Adapter/A port name is an AIX SNA assigned name. All other default values are samples that you can modify. For a VTAM host, the Adjacent Control Point Name is the SSCPNAME. Type host resource names in uppercase letters.

```

Please enter Network Name ..... [CDUNET] :
Please enter Adjacent Control Point Name ..... [HOSTTCP] :
Please enter PU name ..... [RS6PU01] :
Please enter PU address (decimal)..... [02] :
Please enter local LU name ..... [RS6LU01] :
Please enter remote LU name (C:D MVS APPLID) .. [NDMAPP4] :
Please enter mode name ..... [NDM621K] :
Please enter Portmaster Adapter/A port name ... [mpq0] :

```

6. Review the messages as the configuration script completes its final steps. If you receive a message that Connect:Direct is unable to determine the installed version of AIX SNA support, then perform the following steps:
  - ◆ Verify your installation with SMIT.
  - ◆ Run `etc/snaver.sh` to test for the correct installation of AIX SNA Server/6000.
  - ◆ Rerun the `cdsnacfg` script.

For special considerations for connectivity between IBM pSeries and i5/OS systems, refer to *Special Considerations* on page 104.

Refer to the AIX SNA Server/6000 documentation for further information about AIX SNA Server/6000.

---

## HP SNAplus2 Configuration Requirements

For HP SNA support, you must install and configure HP SNAplus2API, SNAplus2-Common, and SNAplus2-Link software. Perform the following steps to configure your system:

1. Use a text editor or **xsnapadmin** to create a configuration file named **/etc/opt/sna/sna\_node.cfg**.
2. Add the following entry to the **/etc/opt/sna/sna\_tps** file:

```
[ "NNV2DTF" ]
TYPE=QUEUED-BROADCAST
USERID=XXXXX
```

3. To start the SNA 3.0 support, log in as root and type the following command:

```
snap start
```

4. To validate or modify your configuration, start the local node, log in as root, and type the following command:

```
snapadmin
```

For additional information about configuring for SNAplus2 10.10 connectivity, refer to the Hewlett-Packard documentation.

The following example displays the contents of a file that contains the required Connect:Direct AT&T Servers SNA 3.0 Invokable TP definition. This file, **sna\_tps**, is provided in the directory **d\_dir/etc**.

```
[ "NNV2DTF" ]
TYPE=QUEUED-BROADCAST
```

---

## SNAP-IX SNA Gateway Support Configuration Requirements

For SNAP-IX support, you must install and configure the SNAP-IX SNA server software.

Documentation about SNAP-IX can be found at the following Web site:

<http://www.dataconnection.com/sna/docs.htm> or with the SNAP-IX product.

Perform the following steps to configure SNAP-IX.

1. Log on as root before executing any SNAP-IX commands.
2. Type the following command to start the SNAP-IX SNA Server application:

```
/opt/sna/bin/sna start
```

3. Create a configuration file that defines configuration statements for your system, including the communications protocol. Either use the command line program `/opt/sna/bin/snaadmin` to create or modify the `/etc/opt/sna/sna_node.cfg` configuration file or use the `/opt/sna/bin/X11/xsnaadmin` program to create or modify a configuration file. Refer to the `SNAP_IX` documentation for a description of the available parameters.
4. Type the following command to define the `NNV2DTF` transaction program:

```
/opt/sna/bin/snaadmin
define_tp,tp_name=NNV2DTF,conv_type=BASIC,sync_level=CONFIRM_SYNC_LEVEL,pip_alled=NO
```

Following are sample statements in the file `/etc/opt/sna/sna_tps`, where 'xxxxxx' is a valid user ID.

```
[NNV2DTF]
LUALIAS = ""
DESCRIPTION = ""
USERID = xxxxxx
TIMEOUT = -1
TYPE = QUEUED-BROADCAST
```

Following is a sample configuration statement that is defined in the `SNAP_IX` `sna_node.cfg` file and defines a `SNAP_IX` SNA Server for LU6.2 connectivity between an Ethernet attached SUN Solaris 8 system and an z/OS mainframe. It defines a single independent LU and one `Connect:Direct` node

LU on the mainframe. The VTAM resource names correspond to the samples given in this appendix.

```
[define_node]
cp_alias = CDUPU01
description = Control Point Node
fqcp_name = CDUNET.CDUPU01
node_type = END_NODE
mode_to_cos_map_supp = YES
mds_supported = YES
node_id = <01702160>

[define_ethernet_dlc]
dlc_name = ETHER0
description = Ethernet dlc
neg_ls_supp = YES
initially_active = NO
adapter_number = 0
lan_type = 802_3_DIX

[define_ethernet_port]
port_name = ETSAP0
description = Ethernet Port 0
dlc_name = ETHER0
port_type = PORT_SATF
port_number = 0
max_rcv_btu_size = 1033
[define_ethernet_ls]
ls_name = ETHL0
description = Ethernet Link Station
port_name = ETSAP0
adj_cp_name = <00000000000000000000000000000000>
adj_cp_type = LEARN_NODE
mac_address = <10005ad172fc>
solicit_sscp_sessions = YES
pu_name = ETHL0

[define_partner_lu]
plu_alias = NDMAPP4
description = QC.OS390.V4300 C:D Node
fqplu_name = CDUNET .NDMAPP4
plu_un_name = <0000000000000000>
parallel_sess_supp = YES

[define_local_lu]
lu_alias = CDULU01
list_name = ""
description = Local LU
lu_name = CDULU01
lu_session_limit = 0
pu_name = <0000000000000000>

[define_mode]
mode_name = NDM621K
description = NDM621K
default_ru_size = NO
max_ru_size_upp = 1024
```

```
Sample configuration statement (continued)

[define_mode]
mode_name = NDM622K
description = NDM622K
default_ru_size = NO
max_ru_size_upp = 2048

[define_mode]
mode_name = NDM624K
description = NDM624K
default_ru_size = NO
max_ru_size_upp = 4096

[define_directory_entry]
resource_name = CDUNET .CSDSA01
resource_type = ENCP_RESOURCE
description = MVSA SSCP
parent_name = <00000000000000000000000000000000>
parent_type = ENCP_RESOURCE

[define_directory_entry]
resource_name = CDUNET .CSDSA01
resource_type = LU_RESOURCE
description = (Auto defined - default LU)
parent_name = CDUNET .CSDSA01
parent_type = ENCP_RESOURCE

[define_directory_entry]
resource_name = CDUNET .NDMAPP4
resource_type = LU_RESOURCE
description = QC.OS390.V4300 C:D Node
parent_name = CDUNET .CSDSA01
parent_type = ENCP_RESOURCE

[define_tp]
tp_name = NNV2DTF
description = C:D-UNIX TP
list_name = ""
conv_type = BASIC
security_rqrd = NO
sync_level = NONE
enabled = YES
pip_allowed = NO
tp_instance_limit = 0
```

---

## Brixton 4.1 SNA for Sun Solaris Requirements

For Brixton SNA support, use the procedures in this section to install and configure the Brixton BrxPU2.1 SNA Server.

- ◆ For Brixton SNA support, Connect:Direct for UNIX requires Brixton software packages BrxAPPC, BrxGMAN, BrxGMI, and BrxPU21

| Product | Description                            |
|---------|--|
| BrxGMAN | Brixton Gateway Manager                |
| BRXGMI  | Brixton Graphical Management Interface |
| BrxAPPC | Brixton LU6.2 and CPI-C APIs           |

- ◆ Connect:Direct for UNIX requires that you configure BrxGMAN, BrxGMI, and BrxPU2.1 packages.
- ◆ The BrxGMI (Graphical Management Interface) generates a working configuration that can be altered to match your needs.

---

**Note:** This is not an SNA configuration.

---

### Configuring BrxGMAN Software

Perform the following steps to configure the BrxGMAN software:

1. Type the following commands to run the PU2.1 setup program:

```
# cd /opt/BrxPU21
```

```
# ./brxsetup
```

The following screen is displayed:

```

The installation procedure allows you to install:

(1) Configure BrxGMAN Software.
(2) Configure BrxGMI Software.
(3) Configure BrxPU21 Software.
(4) Configure BrxGMAN Software.
(5) Start BrxGMAN Software.
(6) Start BrxPU21 Software
(7) Stop BrxGMAN Software
(8) Stop BrxPU21 Software
(9) Show BrxGMAN Software
(10) Show BrxPU21 Software

(q) Exit

Enter selection [q] 1

```

2. To configure the BrxGMAN software, type **1** and press **Enter**.

The BrxGMAN configuration file directory root is currently set to `/etc/brixton`. The following prompt is displayed:

```

The BrxGMAN configuration file directory root is currently set to /etc/brixton.
Do you want to change it (Yes/No) [N]?

```

3. Type **n** and press **Enter** to use the default directory.

The BrxGMAN is configured for a site that runs a main DNS Server. The setup script prompts you to change the setting.

```

The BrxGMAN is configured for a site that runs a main DNS server. In this mode, the
main DNS server is configured to handle all resource lookups initially and direct
those that are in the Brixton sub-domain to the BrxGMAN running on this or other
systems.

Do you want to change this setting (Yes/No) [N]?

```

4. Type **n** and press **Enter** to use the default DNS server configuration.

The following screen is displayed. The DNS domain name is currently set to `stercomm.com`.

```

The DNS domain name is currently set to stercomm.com.
Do you want to change it (Yes/No) [N]?

```

5. Type **n** and press **Enter** to use the default DNS domain name.

The following prompt is displayed. The Brixton subdomain name is currently set to `csg`.

```

The Brixton subdomain name is currently set to csg.
Do you want to change it (Yes/No) [N]?

```

6. Type **n** and press **Enter** to use the default Brixton subdomain name.



The following prompt is displayed. BrxGMAN product is set to startup automatically each time your system reboots. The setup script prompts you to change this setting.

```
The BrxGMAN product is set to startup automatically each time your system reboots.
Do you want to change it (Yes/No) [N]?
```

7. Type **n** and press **Enter** to continue to automatically start the BrxGMAN product at startup. The following screen displays a prompt to verify the BrxGMAN configuration:

```
The BrxGMAN can be configured as follows:
  Installation directory           /opt/BrxGMAN
  Working directory                /var/brixton
  Configuration file directory root /etc/brixton
  Brixton DNS configuration        Operate with existing DNS server
  Full DNS domain name             csg.stercomm.com
  Run startup script at boot       YES

Is this configuration correct (Yes/No) [Y]?
```

8. Type **y** and press **Enter** to confirm the configuration.

## Configuring BrxGMI Software

Perform the following steps to configure the BrxGMI software.

The following setup script prompts you to select a task:

```
The installation procedure allows you to install:

(1) Configure BrxGMAN Software.
(2) Configure BrxGMI Software.
(3) Configure BrxPU21 Software.
(4) Configure BrxGMAN Software.
(5) Start BrxGMAN Software.
(6) Start BrxPU21 Software
(7) Stop BrxGMAN Software
(8) Stop BrxPU21 Software
(9) Show BrxGMAN Software
(10) Show BrxPU21 Software

(q) Exit

Enter selection [q] 2
```

1. To configure the BrxGMI software, type **2** and press **Enter**.

The following screen prompts you to change the current Help browser.

```
The BrxGMI help browser is currently set to mosaic.
Do you want to change it (Yes/No) [N]?
```

2. Type **n** and press **Enter** to use the default browser.

The script prompts you to change the working directory.

```
The BrxGMI working directory is currently set to /var/brixton.
Do you want to change it (Yes/No) [N]?
```

3. Type **n** and press **Enter** to use the default BrxGMI working directory.

The script prompts you to verify the configuration.

```
The BrxGMI can be configured as follows:
  Installation directory      /opt/BrxGMI
  Working directory          /var/brixton
  Help browser type         mosaic
  Help browser pathname/image mosaic
  Xterm command path        /usr/bin/X11/xterm

Is this configuration correct (Yes/No) [Y]?
```

4. If the configuration is correct, type **y** and press **Enter**.

## Configuring BrxPU21 Software

Perform the following steps to configure the BrxPU21 software.

The following screen prompts you to select a task:

```
The installation procedure allows you to install:

(1) Configure BrxGMAN Software.
(2) Configure BrxGMI Software.
(3) Configure BrxPU21 Software.
(4) Configure BrxGMAN Software.
(5) Start BrxGMAN Software.
(6) Start BrxPU21 Software
(7) Stop BrxGMAN Software
(8) Stop BrxPU21 Software
(9) Show BrxGMAN Software
(10) Show BrxPU21 Software

(q) Exit

Enter selection [q] 3
```

1. Type **3** to and press **Enter** configure BrxPU21. The setup script prompts you to change the working directory.

```
The BrxPU21 working directory is currently set to /var/brixton.
Do you want to change it (Yes/No) [N]?
```

2. Type **n** and press **Enter**. The setup script prompts you to change the root directory.

```
The BrxPU21 configuration file directory root is currently set to /etc/brixton.
Do you want to change it (Yes/No) [N]?
```

3. Type **n** and press **Enter**. The setup script prompts you to change the startup setting.

```
The BrxPU21 product is set to startup automatically each time
your system reboots.
Do you want to change it (Yes/No) [N]?
```

4. Type **n** and press **Enter**. The setup script prompts you to verify the configuration.

```
The BrxPU21 can be configured as follows:
  Installation directory           /opt/BrxPU21
  Working directory                /var/brixton
  Configuration file directory root /etc/brixton
  Run startup script at boot       YES

Is this configuration correct (Yes/No) [Y]?
```

5. If the configuration is correct, type **y** and press **Enter**.

## Starting BrxGMAN

Perform the following steps to start the BrxGMAN software.

The setup script prompts you to select a task.

```
The installation procedure allows you to install:

(1) Configure BrxGMAN Software.
(2) Configure BrxGMI Software.
(3) Configure BrxPU21 Software.
(4) Configure BrxGMAN Software.
(5) Start BrxGMAN Software.
(6) Start BrxPU21 Software
(7) Stop BrxGMAN Software
(8) Stop BrxPU21 Software
(9) Show BrxGMAN Software
(10) Show BrxPU21 Software

(q) Exit

Enter selection [q] 5
```

1. Type **5** to start the BrxGMAN and press **Enter**.
2. Type the following command to start the Graphical Manager and configure SNA LU6.2 definitions:

```
# ./brxgmi.sh
```

Refer to the Brixton documentation for additional information about configuring the UNIX system for Brixton SNA connectivity.

## Sample Brixton BrxPU2.1 Configuration

Connect:Direct for UNIX supports platforms running Brixton SNA 4.1 Server for LU6.2 connectivity. The following sample displays a sample Brixton 4.1 SNA definition for a token ring-attached workstation. This file template is provided in the directory *d\_dir/etc*. The VTAM resource names correspond to the samples given in this appendix:

```
// Brixton BrxPU2.1 SNA Server Sample Configuration - Connect:Direct for UNIX//
CP
NAME = CDUPU01
NQ_CP_NAME = CDUNET.CDUPU01
;
LU
COMMENT = "LOCAL ILU"
NAME = CDULU01
LUTYPE = 6.2
PACING = 0
SESS_LMT = 8
;
TRLINE
COMMENT = "NCP Token Interface"
NAME = NCPTIC
SOURCE_ADDRESS = X'400050000000'
LAN_RATE = RING_16Mbs
;
PU2
COMMENT = "VTAM PU"
NAME = CDUPU01
LINK_NAME = NCPTIC
MAXDATA = 2057
ROLE = Negotiable
TERMINID = X'05700004'
ALS_CONNECT = Active
LMT_RES = No
ACTPU_SUPPRESS = No
RMTTERMINID = X'05700004'
RMTNQ_CP_NAME = CDUNET.HOSTCP
RMTMACADDR = X'400050000004'
;
PTNR_LU
NAME = NDMAPP4
LOC_LU_NAME = CDULU01
INIT_TYPE = INITIATE_OR_QUEUE
;
```

```

MODE
NAME = NDM624K
PTNR_LU_NAME = NDMAPP4
DLC_NAME = CDUPU01
SND_MAX_RU_LB = 8
RCV_MAX_RU_LB = 8
PREF_SND_RU = 4096
PREF_RCV_RU = 4096
LCL_MAX_SESS_LMT = 8
MIN_CW_SESS = 4
MIN_CL_SESS = 4
CW_AUTOACT_LMT = 4
AUTOINIT_SL = Yes
;

TP
TP_NAME = NNV2DTF
LOC_LU_NAME = CDULU01
CONV_TYPE = BASIC
SYNC_LVL = CONFIRM
PIP = NO
PRIVILEGE = NONE
;

```

---

**Note:** The LU SESS\_LMT must be 2 greater than the MODE LCL\_MAX\_SESS\_LMT.

---

The i5/OS definitions include the following in the DLC directive:

```
RMTNQ_CP_NAME=CDUNET.CP_NAME //Rmt Network Qualified Name
```

After running the Brixton configuration for the i5/OS connection, change the i5/OS device description to match the **Mode\_Name** defined in the Brixton configuration.

---

## SunLink SNA 9.1 for Sun Solaris Configuration Requirements

For SunLink SNA support, use the following procedure to install and configure the SunLink SUNWpu2.1 SNA server software:

- ◆ For SunLink SNA support, configure the following SunLink software packages: SUNWlu62, SUNWgmi, SUNWgman, and SUNWpu21.

| Product  | Description                        |
|----------|------------------------------------|
| SUNWgman | SNA Gateway Manager                |
| SUNWgmi  | SNA Graphical Management Interface |
| SUNWlu62 | SNA Logical Unit Type 6.2          |

| Product  | Description      |
|----------|------------------|
| SUNWpu21 | SNA PU2.1 Server |

- ◆ Connect:Direct for UNIX requires that you configure SUNWgman, SUNWgmi, and SUNWpu21 packages.
- ◆ The SUNWgmi (Graphical Management Interface) generates a working configuration that can be altered to match your needs.

---

**Note:** This is not an SNA configuration.

---

1. Type the following commands to run the PU2.1 setup program:

```
# cd /opt/SUNWPU21
```

```
# ./sunsetup
```

The following screen displays a list of tasks:

```
The installation procedure allows you to install:
```

- ```
(1) Configure GMAN Software.
(2) Configure GMI Software.
(3) Configure PU21 Software.
(4) Start GMAN Software.
(5) Start PU21 Software
(6) Stop GMAN Software
(7) Stop PU21 Software
(8) Show GMAN Configuration
(9) Show GMI Configuration
(10) Show PU21 configuration
```

```
(q) Exit
```

```
Enter selection [q] 1
```

2. Type **1** to configure the SUNWgman software.

The following screen prompts you to change the root directory:

```
The SUNWgman configuration file directory root is currently set to /opt/SUNWgman.
Do you want to change it (Yes/No) [N]?
```

3. Type **n** and press **Enter**.

The setup script prompts you to change the DNS server configuration.

```
The SUNWgman is configured for a site that runs a main DNS server. In this mode,
client systems must be configured to use this system directly to resolve lookups
for resources in the SunLink domain.
```

```
Do you want to change this setting (Yes/No) [N]?
```

4. Type **n** and press **Enter**.

The setup script prompts you to change the DNS domain name.

```
The DNS domain name is currently set to stercomm.com.
Do you want to change it (Yes/No) [N]?
```

5. Type **n** and press **Enter**.

The setup script prompts you to change the startup option.

```
The BrxGMAN product is not set to startup automatically each time your system
reboots.
Do you want to change it (Yes/No) [N]?
```

6. Type **n** and press **Enter**.

The following message prompts you to verify the SUNWgman configuration.

```
The SUNWgman can be configured as follows:
  Installation directory           /opt/SUNWgman
  Working directory                /opt/SUNWgman
  Configuration file directory root /opt/SUNWgman
  SunLink DNS configuration        SUNWgman is primary DNS server
  Full DNS domain name            csg.stercomm.com
  Run startup script at boot       NO

Is this configuration correct (Yes/No) [Y]?
```

7. Do one of the following:

- ◆ If the configuration is correct, type **y** and press **Enter**.
- ◆ If necessary, type new parameters for each option. Type **y** and press **Enter**.

The following screen is displayed:

```
The installation procedure allows you to install:
```

- (1) Configure GMAN Software.
- (2) Configure GMI Software.
- (3) Configure PU21 Software.
- (4) Start GMAN Software.
- (5) Start PU21 Software
- (6) Stop GMAN Software
- (7) Stop PU21 Software
- (8) Show GMAN Configuration
- (9) Show GMI Configuration
- (10) Show PU21 configuration
  
- (q) Exit

```
Enter selection [q] 2
```

8. To configure the SUNWgmi software, type **2**. The following message prompts you to change the current Help browser.

```
The SUNWgman help browser is currently set to mosaic.
Do you want to change it (Yes/No) [N]?
```

9. Type **n** and press **Enter**. The script prompts you to change the working directory.

```
The SUNWgman working directory is currently set to /opt/SUNWgman.
Do you want to change it (Yes/No) [N]?
```

10. Type **n** and press **Enter**. The script prompts you to verify the configuration.

```
The SUNWgman can be configured as follows:
Installation directory      /opt/SUNWgman
Working directory          /opt/SUNWgman
Help browser type          mosaic
Help browser pathname/image mosaic
Xterm command path        /usr/bin/X11/xterm

Is this configuration correct (Yes/No) [Y]?
```

11. Do one of the following:

- ◆ If the configuration is correct, type **y** and press **Enter**.
- ◆ If necessary, type new parameters for each option. Type **y** and press **Enter**.



The setup script prompts you to select a task:

```
The installation procedure allows you to install:
```

- (1) Configure GMAN Software.
- (2) Configure GMI Software.
- (3) Configure PU21 Software.
- (4) Start GMAN Software.
- (5) Start PU21 Software
- (6) Stop GMAN Software
- (7) Stop PU21 Software
- (8) Show GMAN Configuration
- (9) Show GMI Configuration
- (10) Show PU21 configuration

```
(q) Exit
```

```
Enter selection [q] 3
```

12. Type **3** to configure SUNWpu21 and press **Enter**. The setup script prompts you to change the working directory.

```
The SUNWpu21 working directory is currently set to /opt/SUNWpu21.
Do you want to change it (Yes/No) [N]?
```

13. Type **n** and press **Enter**. The setup script prompts you to change the root directory.

```
The SUNWpu21 configuration file directory root is currently set to /opt/SUNWpu21.
Do you want to change it (Yes/No) [N]?
```

14. Type **n** and press **Enter**. The setup script prompts you to change the startup setting.

```
The SUNWpu21 product is not set to startup automatically each time
your system reboots.
Do you want to change it (Yes/No) [N]?
```

15. Type **n** and press **Enter**. The setup script prompts you to verify the configuration.

```
The SUNWpu21 can be configured as follows:
Installation directory           /opt/SUNWpu21
Working directory                 /opt/SUNWpu21
Configuration file directory root /opt/SUNWpu21
Run startup script at boot       YES

Is this configuration correct (Yes/No) [Y]?
```

16. Do one of the following:

- ◆ If the configuration is correct, type **y** and press **Enter**.
- ◆ If necessary, type new parameters for each option. Type **y** and press **Enter**.

The setup script prompts you to select a task.

```
The installation procedure allows you to install:

(1) Configure GMAN Software.
(2) Configure GMI Software.
(3) Configure PU21 Software.
(4) Start GMAN Software.
(5) Start PU21 Software
(6) Stop GMAN Software
(7) Stop PU21 Software
(8) Show GMAN Configuration
(9) Show GMI Configuration
(10) Show PU21 configuration

(q) Exit

Enter selection [q] 4
```

17. Type **4** to start the SUNWgman.

18. Type the following command to start the Graphical Manager and configure SNA LU6.2 definitions.

```
#./sungmi.sh
```

---

## Sample z/OS Definitions for an LU6.2 Connection

This section provides samples of the z/OS NCP and VTAM definitions required for LU6.2 connectivity between Connect:Direct for UNIX and Connect:Direct for z/OS. A sample Connect:Direct for z/OS network map definition is also included.

## Token Ring 3174-R Gateway Controller Configuration

The following figure displays sample line, PU, and LU definitions used by VTAM to define a token ring 3174-R gateway controller for an LU6.2 connection:

```

*****
*          REAL 3174 CONTROLLER, FUNCTIONS AS THE GATEWAY CONTROLLER
*****
D1IRR1  PU ADDR=01,                               *
        DATMODE=HALF,                             *
        MAXDATA=521,                               *
        MAXOUT=7,                                  *
        PACING=2,                                   *
        PUDR=YES,                                   *
        DLOGMOD=SNX32702,                           *
        MODETAB=DALLMTAB,                           *
        USSTAB=LSUSSTAB,                            *
        SSCPFM=USSSCS,                              *
        PUTYPE=2,                                    *
        DISCNT=(NO),                                 *
        SECNET=NO,                                   *
        VPACING=4,                                   *
        XID=YES,                                     *
        ISTATUS=ACTIVE

*
*                                     COAX PORTS
D1IRR102 LU LOCADDR=2, ISTATUS=ACTIVE
D1IRR103 LU LOCADDR=3, ISTATUS=ACTIVE
D1IRR104 LU LOCADDR=4, ISTATUS=ACTIVE
D1IRR105 LU LOCADDR=5, ISTATUS=ACTIVE
D1IRR106 LU LOCADDR=6, ISTATUS=INACTIVE
D1IRR107 LU LOCADDR=7, ISTATUS=INACTIVE
D1IRR108 LU LOCADDR=8, ISTATUS=INACTIVE
D1IRR109 LU LOCADDR=9, ISTATUS=INACTIVE
*
*          FOR LU6.2 ILU
CDULU01 LU LOCADDR=0, DLOGMOD=NDM621K, RESSCB=5, ISTATUS=ACTIVE
CDULU02 LU LOCADDR=0, DLOGMOD=NDM621K, RESSCB=5, ISTATUS=ACTIVE
CDULU03 LU LOCADDR=0, DLOGMOD=NDM621K, RESSCB=5, ISTATUS=ACTIVE
CDULU04 LU LOCADDR=0, DLOGMOD=NDM621K, RESSCB=5, ISTATUS=ACTIVE
*

```

```

*****
*      DOWNSTREAM PU OFF OF THE REAL 3174 GATEWAY CONTROLLER      *
*      INDEPENDENT LU6.2  *
*****
CDUPU01  PU ADDR=02,
          DATMODE=HALF,
          MAXDATA=521,
          MAXOUT=7,
          PACING=2,
          PUDR=YES,
          DLOGMOD=SNX32702,
          MODETAB=DALLMTAB,
          USSTAB=LSUSSTAB,
          SSCPFM=USSSCS,
          PUTYPE=2,
          DISCNT=(NO),
          SECNET=YES,
          VPACING=4,
          ISTATUS=ACTIVE
*
DISPLAY2 LU LOCADDR=2, ISTATUS=ACTIVE
DISPLAY3 LU LOCADDR=3, ISTATUS=ACTIVE

```

The 3174-R token ring gateway requires that the IBM pSeries token ring adapter address match the address configured in the 3174-R.

## Token Ring 3745 Token Ring Interface Coupler (TIC) Configuration

The following figure displays sample line, PU, and LU definitions used by VTAM to define a token ring TIC for an LU6.2 connection:

```

M1IRGPGP GROUP ECLTYPE=PHYSICAL          PHYSICAL GROUP
* NTRI PHYSICAL LINE DEFINITION
M1IRG  LINE  ADDRESS=(1088,FULL),        LAN                *
          LOCADD=400076543210,          'SOFT' ADDRESS FOR TIC *
          MAXTSL=4060,                  RANGE 265 TO 16732     *
          OWNER=SA01,                   MVS OWNS THIS LINE    *
          NPACOLL=YES,                  NPM                   *
          PORTADD=0,                    WHERE ACRS3LGP POINTS TO *
          RCVBUFC=1440,                 RANGE 6*BFRS TO 4095  *
          ADAPTER=TIC2,                 TIC2                  *
          TRSPEED=4,                    SPEED OF LAN          *
          SPAN=(8000)                   NETVIEW OPERAND
M1IRG1  PU   SPAN=(8000)
M1IRG100 LU  ISTATUS=INACTIVE,          IBM RECOMMENDED      *
          SPAN=(8000)                   NETVIEW OPERAND
M1IRGLGP GROUP ECLTYPE=LOGICAL,         LOGICAL GROUP        *
          CALL=INOUT,                   ALLOW DIAL IN AND DIAL OUT *
          NPACOLL=YES,                  NPM                   *
          OWNER=SA01,                   MVS OWNS THIS LINE GROUP *
          PHYPORT=0,                    POINTS TO ACRS3 LINE PORTADD *
          SPAN=(8000),                  NETVIEW OPERAND      *
          TYPE=NCP                       NETWORK CONTROL MODE
M1IRGT00 LINE AUTOCOPY=(35,M1IRGT01,D)
M1IRGP00 PU  NEXT=(M1IRGP01,D)
          ENDAUTO
*****
*          TOKEN RING NTRI SWITCHED SNA DEFINITION          *
*****
M1T2001 VBUILD TYPE=SWNET
CDUPU01  PU  ADDR=01,                    *
          PUTYPE=2,                      *
          DISCNT=NO,                     *
          MAXOUT=7,                      *
          PASSLIM=7,                    *
          ISTATUS=ACTIVE,                *
          IDBLK=071,                    *
          IDNUM=43210,                  *
          SSCPFM=USSSCS,                *
          MODETAB=DALLMTAB,             *
          USSTAB=LSUSSTAB,             *
          DLOGMOD=NDM621K
CDULU01  LU  LOCADDR=0,DLOGMOD=NDM621K,RESSCB=5

```

## VTAM Application Definition

The following figure shows a VTAM application (APPL) definition for an LU6.2 connection between Connect:Direct for z/OS and Connect:Direct for UNIX:

```

NDMAPP4 APPL ACBNAME=NDMAPP4,      VTAM APPLICATION ID      *
      APPC=YES,                    ENABLE TO RUN LU6.2 SESSIONS *
      AUTH=(ACQ,NOCNM,NOPASS,NOPO,NOTSO,VPACE),  APPROXIMATE # OF CONCURRENT SESS *
      EAS=6,                        MODE TABLE NAME        *
      MODETAB=NDMTAB,              NO UNBIND IN SCIP EXIT   *
      SONSCIP=NO,                  NO SRB PROCESSING       *
      SRBEXIT=NO,                  RECEIVE PACING OF 7     *
      VPACING=7,                    MODE TABLE ENTRY       *
      DLOGMOD=NDMLOGM,             PARALLEL SESSIONS CAN BE USED *
      PARSESS=YES,                 # OF CONCURRENT LU6.2 SESSIONS *
      DSESLIM=8,                   # OF LOCAL CONTENTION WINNERS *
      DMINWNL=4,                   # OF REMOTE CONTENTION WINNERS *
      DMINWNR=4,                   # OF AUTOMATIC LU6.2 SESSIONS *
      AUTOSSES=4,                  ALLOW CNOS TO DRAIN SESSIONS *
      DDRAINL=ALLOW,              DEF RESPONSIBILITY FOR LOCAL CNOS*
      DRESPL=ALLOW,
      VTAMFRR=NO

```

## VTAM Logmode Table Entries

The following figure displays a sample mode table entry for an LU6.2 connection using a 1-K RU.

```

* LU6.2 LOGMODE
*
NDM621K  MODEENT LOGMODE=NDM621K,      *
      TYPE=1,                          *
      COS=NJE,                           *
      FMPROF=X'13',                       *
      TS_PROF=X'07',                       *
      PRIPROT=X'B0',                       *
      SECPROT=X'B0',                       *
      COMPROT=X'D0B1',                     *
      RUSIZES=X'8787',      1K SEND AND RECV RUSIZE *
      PSERVIC=X'06020000000000000000300'

```

The following figure displays a sample mode table entry for an LU6.2 connection using a 4-K RU:

```

* LU6.2 LOGMODE
*
NDM624K  MODEENT LOGMODE=NDM624K,      *
      TYPE=1,                          *
      COS=NJE,                           *
      FMPROF=X'13',                       *
      TS_PROF=X'07',                       *
      PRIPROT=X'B0',                       *
      SECPROT=X'B0',                       *
      COMPROT=X'D0B1',                     *
      RUSIZES=X'8989',      4K SEND AND RECV RUSIZE *
      PSERVIC=X'06020000000000000000300'

```

## NTRI Switched Major Node Definition

The following figure displays a sample token ring NTRI switched SNA definition for an LU6.2 connection between Connect:Direct for z/OS and Connect:Direct for UNIX:

```

*
CDUPU    VBUILD TYPE=SWNET
*
CDUPU01  PU      ADDR=01,                X
          PUTYPE=2,                       X
          IDBLK=071,                      X
          IDNUM=54321,                   X
          SSCPFM=USSSCS,                  X
          MODETAB=DALLMTAB,               X
          USSTAB=RSUSSTAB,                X
          DLOGMOD=NDM621K

```

## ILU CDRSC Definitions

The following figure displays a sample VTAM 3.4 CDRSC definition for independent LUs used between Connect:Direct for z/OS and Connect:Direct for UNIX:

```

CDULU    VBUILD TYPE=CDRSC
*
CDULU01  CDRSC  ISTATUS=ACTIVE,          X
                ALSLIST=CDUPU01,        ADJ LINK STATION      X
                MODETAB=DALLMTAB,        LOGON MODE TABLE     X
                DLOGMOD=NDM621K,         LOGON MODE TABLE ENTRY X
                RESSCB=5                  SESSION CONTROL BLOCKS
*
CDULU02  CDRSC  ISTATUS=ACTIVE,          X
                ALSLIST=CDUPU01,        ADJ LINK STATION      X
                MODETAB=DALLMTAB,        LOGON MODE TABLE     X
                DLOGMOD=NDM624K,         LOGON MODE TABLE ENTRY X
                RESSCB=5                  SESSION CONTROL BLOCKS
*
CDULU03  CDRSC  ISTATUS=ACTIVE,          X
                ALSLIST=CDUPU01,        ADJ LINK STATION      X
                MODETAB=DALLMTAB,        LOGON MODE TABLE     X
                DLOGMOD=NDM621K,         LOGON MODE TABLE ENTRY X
                RESSCB=5                  SESSION CONTROL BLOCKS
*
CDULU04  CDRSC  ISTATUS=ACTIVE,          X
                ALSLIST=CDUPU01,        ADJ LINK STATION      X
                MODETAB=DALLMTAB,        LOGON MODE TABLE     X
                DLOGMOD=NDM622K,         LOGON MODE TABLE ENTRY X
                RESSCB=5                  SESSION CONTROL BLOCKS

```

## Connect:Direct Remote Node Entry

The following figure displays a sample UNIX remote node definition for the Connect:Direct for z/OS network map. You must specify an LU6.2 logmode entry:

```
ADJACENT.NODE=(PARSESS=(6, 2) -
  (UNIX.LU62.DALLAS, CDULU01, , LU62) -
  LOGMODE=NDM621K -
  ENVIRONMENT=UNIX)
```

---

## Special Considerations

This section identifies special considerations when configuring LU6.2 connections.

### Required Changes to the File Specified with the comm.info Parameter

This information applies to the following operating systems:

- ◆ HP SNA
- ◆ SNAP-IX

After you install Connect:Direct for UNIX, the file pointed to by the **comm.info** parameter (default name **host11**) is located in the same directory as the configuration files. This file includes communications information for the SNA configuration.

To configure an LU6.2 connection, modify the values for **local\_lu**, **remote\_lu**, and **mode**. These names must correspond to the names defined in the SNA package. The **local\_lu** field is a required field. The following figure displays the contents of the **host11** file:

```
comm.info:\
:local_lu=LOCAL_LU:\
:remote_lu=REMOTE_LU:\
:mode=HOSTMODE:
```

The following figure displays values for **lu** and **mode** that correspond to the sample MVS definitions for an LU6.2 connection as illustrated in *Token Ring 3174-R Gateway Controller Configuration* on page 99.

```
comm.info:\
:local_lu=CDULU01:\
:remote_lu=NDMAPP4:\
:mode=NDM624K:
```



## Obtaining Traces for the Brixton LU6.2 API and SunLink P2P

The **trace comm** command also provides Brixton LU6.2 API and SunLink P2P tracing control.

To activate the Brixton LU6.2 API and SunLink P2P traces, type the following command:

```
trace comm level=2|3|4
```

To deactivate the Brixton and SunLink traces, type the following command:

```
trace comm level=0|1
```

Trace files are created in the directory where Connect:Direct for UNIX is started. Refer to the Brixton documentation and the SunLink documentation for additional details.

## Stopping Connect:Direct on SNA Systems

When running Connect:Direct for UNIX with the LU6.2 on an HP SNA, AT&T Global Information Solutions SNA, or Brixton SNA system, you must issue the following command to stop Connect:Direct:

```
Direct> stop force;
```

## Connectivity Between IBM pSeries and i5/OS Systems

To configure IBM pSeries to i5/OS connections, run the `cdsnacfg` script on the pSeries. You must then modify the default AIX SNA Server/6000 configuration to allow the automatic i5/OS configuration to build the appropriate connections.

To modify the default AIX SNA Server/6000 configuration, type the following commands. PUNAME is the PU name typed in the `cdsnacfg` script.

```
chснаobj -t'sna_dlc_token_ring' -b 'no' trdlc11
chснаobj -t'link_station' -w'token_ring' -y 'trdlc11' -a 'no' PUNAME
```

## AIX SNA Error Messages

AIX SNA return codes are documented in the *AIX SNA Server/6000: Transaction Program Reference* or in the file `/usr/include/luxsna.h`.



---

# Connect:Direct for UNIX Manual Pages

Connect:Direct provides manual pages for the following topics:

- ◆ Process Manager and server (cdpmgr)
- ◆ Translation Table Generator (ndmxt)
- ◆ Message Manager (ndmmsg)

As system administrator, you have the option of combining Connect:Direct manual pages with UNIX manual pages. This chapter describes how to access Connect:Direct manual pages and identifies the commands that display specific manual pages.

---

## Setting Up Connect:Direct for UNIX Manual Pages

The UNIX operating system organizes all Help into manual (man) pages. For syntax and a description of a UNIX command, type the following command, where *command* is the UNIX command.

```
% man command
```

### Combining Manual Pages

Most UNIX systems store online manual pages in /usr/man/man1. Connect:Direct stores its manual pages in *d\_dir*/ndm/man1, where *d\_dir* is the path name to the Connect:Direct installation directory. To combine the manual pages, type the following command to copy the Connect:Direct manual pages into the UNIX manual pages directory:

```
% cp d_dir/ndm/man1/*.1 /usr/man/man1
```

---

**Note:** You must have write privileges to the directory /usr/man/man1 to perform this command.

---

You can also use symbolic links instead of copying the files. Refer to UNIX manual pages for information on using the UNIX **ln** command to create symbolic links.

## Displaying Connect:Direct Manual Pages

Type the following command to access Connect:Direct manual pages that you combined with UNIX manual pages, where *command* can be **cdpmgr**, **ndmxlt**, or **ndmmsg**:

```
% man command
```

---

## Accessing Connect:Direct Manual Pages

The following sections show the commands to display Connect:Direct manual pages on various platforms.

### Using MANPATH in the Bourne Shell

On an HP PA-RISC system, you must set the environment variable, **MANPATH**, to locate the Connect:Direct manual pages.

---

**Note:** The value used for setting **MANPATH** is the typical value used in UNIX systems. Your system can have other localized manual pages that must be included in the search path. Changing **MANPATH** is a function of the system administrator.

---

Type the following command to access Connect:Direct manual pages on an HP PA-RISC using the B shell, where *command* can be **cdpmgr**, **ndmxlt**, or **ndmmsg**:

```
$ MANPATH=/usr/man:/usr/contrib/man:d_dir/ndm/man1
$ export MANPATH
$ man command
```

### Using MANPATH in the C Shell

On an HP PA-RISC system, set the environment variable, **MANPATH**, to locate the Connect:Direct manual pages.

---

**Note:** The value used for setting **MANPATH** is the typical value used in UNIX systems. Your system can have other localized manual pages that must be included in the search path. Changing **MANPATH** is a function of the system administrator.

---

Type the following command to access Connect:Direct manual pages on an HP PA-RISC using the C shell, where *command* can be **cdpmgr**, **ndmxlt**, or **ndmmsg**:

```
% setenv MANPATH /usr/man:/usr/contrib/man:d_dir/ndm/man1
% man command
```

### Accessing Manual Pages on an IBM pSeries or Sun SPARC Platform Using BSDI

Type the following command to access Connect:Direct manual pages on IBM pSeries, or Sun SPARC running the Solaris operating system, if the system is using the BSD version of the **man** command (/usr/ucb/man). The *command* can be **cdpmgr**, **ndmxlt**, or **ndmmsg**.

```
% man -M d_dir/ndm command
```



## A

### **Application Programming Interface (API)**

An application that enables End User Applications (EUAs) and the Connect:Direct Command Line Interface (CLI) to interact with the Connect:Direct software.

## C

### **Client**

The program that makes requests of the Connect:Direct server and accepts the server's responses.

### **Command Line Interface (CLI)**

A program available to submit Connect:Direct Processes and commands from a command line environment.

### **Command Manager (CMGR)**

The program that executes commands sent by the API and sends the results back to the API. In conjunction with the API, the CMGR carries out the Connect:Direct authentication procedure, which determines if the user name and password are authorized to access the system. CMGR interacts with the PMGR when required by command execution.

### **Connect:Direct**

The family of data transfer software products that distributes information and manages production activities among multiple data centers.

### **Connect:Direct Browser User Interface**

As an alternative to submitting Connect:Direct commands through the command line interface, you can use the Connect:Direct Browser User Interface to create, submit, and monitor Processes from an Internet browser, such as Microsoft Internet Explorer or Netscape Navigator. You can also use

the Connect:Direct Browser to perform Connect:Direct system administration tasks, such as viewing and changing the network map or initialization parameters, if you have the appropriate Connect:Direct authority.

### **Connect:Direct for UNIX**

The UNIX implementation of the Connect:Direct product.

### **Connect:Direct Node**

Any computer/workstation running Connect:Direct.

### **Connect:Direct Process**

A series of statements, which can be predefined and stored in a directory, submitted through the API to initiate Connect:Direct for UNIX activity. Examples of Process functions are copying files and running jobs.

## **D**

### **daemon**

The long-running process that provides a service to a client. The PMGR is the Connect:Direct for UNIX daemon.

### **Diagnostic Commands**

Connect:Direct commands that assist in the diagnosis of Connect:Direct software problems.

## **E**

### **End User Application (EUA)**

An application program developed by an end user to accomplish a particular task.

### **Execution Queue**

A logical queue in the TCQ. A Process in the Execution Queue can be transferring data to or from a remote Connect:Direct node or it can be waiting for a connection to the remote Connect:Direct node before it can perform its tasks.



## F

### **File Agent**

An application program and component of Connect:Direct. It scans specified directories searching for the presence of a file. When a file appears in a watched directory, Connect:Direct either submits a Process or performs the action specified by the rules for the file.

## H

### **Hold Queue**

A logical queue in the TCQ. Processes in the Hold Queue are waiting for operator intervention before they move to the Wait Queue for scheduling.

## M

### **Monitoring Commands**

Connect:Direct commands that allow you to display information from the statistics file and the TCQ about Connect:Direct Process execution results.

## O

### **Operational Control Commands**

Connect:Direct commands that allow you to submit a Process, change specific characteristics of a Process in the TCQ, remove executing and nonexecuting Processes from the TCQ, and stop Connect:Direct.

## P

### **Process Manager (PMGR)**

The long-running Connect:Direct server that initializes the Connect:Direct software, accepts connection requests from Connect:Direct APIs and remote Connect:Direct nodes, creates Command Managers and Session Managers, accepts requests from Command Managers and Session Managers where centralized Connect:Direct functions are required, and terminates Connect:Direct software execution.

## **PNODE (Primary Node)**

The Connect:Direct node on which the Process is being executed. The primary node is also called the controlling or source node, but is not always the sending node because PNODE can be the receiver. Every Process has one PNODE and one SNODE. The submitter of a Process is always the PNODE. The PNODE name can be 1–16 characters long.

## **S**

### **Session**

A connection between two Connect:Direct nodes.

### **Session Manager (SMGR)**

Responsible for creating or completing a connection with a remote Connect:Direct node and carrying out the Connect:Direct work to be performed.

### **SNODE (Secondary Node)**

The Connect:Direct node that interacts with the Primary node (PNODE) during Process execution. The Secondary node (SNODE) also can be referred to as the participating, target, or destination node. Every Process has one PNODE and one SNODE. The secondary node is the node participating in Process execution initiated by another node (PNODE). The SNODE name can be 1–16 characters long.

### **Sterling Control Center**

A centralized management system that provides operations personnel with continuous enterprise-wide business activity monitoring capabilities for Connect:Direct z/OS, UNIX, and Windows servers. It manages multiple Connect:Direct servers to suspend, release, and delete Processes, stops Connect:Direct servers, and views detailed statistics on running or completed Processes. It monitors service levels to view Connect:Direct processing across Connect:Direct z/OS, UNIX, and Windows servers within your network and retrieve information about active and completed Processes. It receives notification of data delivery events that occur or do not occur as scheduled and defines rules that, based on processing criteria, can generate an alert, send an e-mail notification, generate a Simple Network Management Protocol (SNMP) trap to an Enterprise Management System (EMS), or run a system command. It monitors for alerts, such as a server failure or a Process not starting on time.

## **T**

### **TCQ Status Value**

A two-letter code assigned to a Process by Connect:Direct when the Process is placed on the TCQ. The status of a Process can be examined with a **select process** command.

**TCQ (Transmission Control Queue)**

A queue that holds all Processes that are submitted to Connect:Direct for UNIX. TCQ contains the following four logical queues:

- ◆ EXECUTION
- ◆ WAIT
- ◆ TIMER
- ◆ HOLD

**Timer Queue**

A logical queue in the TCQ. Processes on the Timer Queue are waiting for a start time before they move to the Wait Queue for scheduling.

**W****Wait Queue**

A logical queue in the TCQ. Processes on the Wait Queue are waiting on a connection to or from the remote Connect:Direct node.



## A

AIX SNA  
  configuration script for Connect:Direct for UNIX 80  
  creating the transaction program profile name 79  
  requirements 79  
API, description 9  
APPC requirements for LU6.2 connectivity 78

## B

Brixton SNA  
  for SUN Solaris support 87

## C

Changing file ownership and permissions 43  
CLI, description 9  
CLI/API configuration file  
  creating 39  
  worksheet 74  
CLI/API, creating a configuration file 39  
Client authentication key file  
  worksheet 76  
Cluster environments 26  
  high-availability and load-balancing 26  
  limitations  
    load-balancing 27  
  preparing to install on 25  
  supported  
    high-availability 26  
    load-balancing 26, 27  
CMGR, description 8  
Command  
  cdinst 30, 48  
  change process 14  
  delete process 14  
  flush process 14  
  for TCQ 14  
  select process 14  
  select statistics 14

  setting up environment variable NDMAPICFG 55  
  setting up environment variable NDMAPICFG, from  
    C shell 55  
  starting the Connect:Direct for UNIX server 55  
  stop 14  
  stop force 56  
  stopping Connect:Direct LU6.2  
    HP SNA system 56  
  submit 14  
  trace 14

Command line interface, overview 9

Command manager, overview 8

Configuration requirements  
  for IBM HACMP 54  
  in a SunCluster 2.2 environment 53, 54  
  in a SunCluster 3.0 environment 52

Configured Security Functions 61, 62

Connect:Direct  
  concepts 12  
  defining initialization parameters file 34

Creating a strong access control list file 40

Customization worksheet 68

Customizing, user authorization information file 36

## D

Defining high-availability settings 51

Definition  
  local node 12  
  remote node 12

Description  
  API 9  
  CLI 9  
  CMGR 8  
  network map 14  
  PMGR 7  
  SMGR 8  
  TCQ 13  
  user authorization 15

**E**

Environment variables, setting up 55

**F**

File

- CLI/API configuration file 39
- client authentication key file 39
- initialization parameters file 34
- network map file 35
- server authentication key file 38
- user authorization information file 36

File Agent Worksheet 61

**H**

High-availability, defining settings 51

**I**

IBM AIX SNA support

- configuration script for Connect:Direct for UNIX 80
- creating the transaction program profile name 79
- requirements 79

IBM HACMP, configuration requirements 54

Initialization parameters file

- customizing 34

Installation

- configuration types 25
- Connect:Direct for UNIX 25
- verifying 54

Installing Connect:Direct on the Linux for zSeries

- operating system 28

**L**

limitations

- high-availability 26

Link types, for LU6.2 connectivity 78

Linux for zSeries operating system, installing on 28

Local node

- definition of 12
- in network map 14

LU6.2 connectivity

- APPC requirements 78
- configuration requirements 78

- configuring 51

- configuring SNA support 98

- creating a remote node information record 35

- for AIX SNA support 79

- for Brixton SNA for Sun Solaris support 87

- link types 78

- recommended pacing values 78

- recommended RU sizes 78

- supported connections 77

**M**

Manual pages

- accessing 108

- combining 107

- displaying combined manual pages 108

- displaying on AT&T GIS systems using BSD 109

- displaying on HP PA-RISC using Bourne shell 108

- displaying on HP PA-RISC using C shell 108

- displaying on IBM pSeries 109

- displaying on SUN Sparc 109

max.age, parameter 17

**N**

Network map file

- creating a remote node information record 35

- description 14

- worksheet 75

**P**

Pacing values, for LU6.2 connectivity 78

PMGR, description 7

Process restart, overview 15

Process statements, listed 13

Process, samples 17

**R**

Remote node

- definition of 12

- in network map 14

Remote node information record

- creating 19

- worksheet 75

RU sizes for LU6.2 connectivity 78

**S**

Sample z/OS definitions for LU6.2 connections  
 ILU CDRSC definitions 103  
 NTRI switched major node definition 103  
 Token Ring 3174-R Gateway Controller  
 Configuration 99  
 Token Ring 3745 Token Ring Interface Coupler (TIC)  
 Configuration 101  
 VTAM application definition 102  
 VTAM logmode table entries 102

Samples  
 Processes 17  
 shell scripts 18  
 z/OS definitions 98

Security  
 client authentication key file 39  
 client authentication key file worksheet 76  
 customizing the user authorization information file 36  
 server authentication key file 38  
 server authentication key file worksheet 76

Server authentication key file  
 created 38  
 worksheet 76

Session manager, overview 8

Setting environment variables, NDMAPICFG 55

Shell script, samples 18

SMGR, description 8

SNA LU6.2 connectivity  
 APPC requirements 78  
 configuration requirements 78  
 creating a remote node information record 35  
 for Brixton SNA for SUN Solaris support 87  
 recommended pacing values 78  
 recommended RU sizes 78  
 sample Brixton BrxPU2.1 configuration 92  
 supported connections 77

Special considerations, connectivity between IBM  
 pSeries and i5/OS systems 105

Sterling Control Center 10, 114

Stopping Connect:Direct, SNA systems 105

Strong access control file, creating 40

Suncluster 2.2, configuration 53, 54

SunCluster 3.0 environment, additional configuration  
 requirements 52

**T**

TCQ, description 13

Terminating a procedure 29

Transaction program profile name, for AIX SNA  
 support 79

**U**

User authorization information file  
 customizing 36  
 description 15  
 Worksheet 69

**V**

Verifying, the installation 54

**W**

Worksheet  
 client authentication key file 76  
 Customization worksheet 68  
 File Agent 61  
 Installation 68  
 installation worksheet 68  
 network map remote node information file 75  
 server authentication key file 76  
 User authorization information file 69





Copyright © 1999-2008  
Sterling Commerce, Inc.  
ALL RIGHTS RESERVED

## STERLING COMMERCE SOFTWARE

\*\*\*TRADE SECRET NOTICE\*\*\*

THE CONNECT:DIRECT UNIX SOFTWARE (“STERLING COMMERCE SOFTWARE”) IS THE CONFIDENTIAL AND TRADE SECRET PROPERTY OF STERLING COMMERCE, INC., ITS AFFILIATED COMPANIES OR ITS OR THEIR LICENSORS, AND IS PROVIDED UNDER THE TERMS OF A LICENSE AGREEMENT. NO DUPLICATION OR DISCLOSURE WITHOUT PRIOR WRITTEN PERMISSION. RESTRICTED RIGHTS.

This documentation was prepared to assist licensed users of the Sterling Commerce Connect:Direct Unix software. The Sterling Commerce Software, the related documentation and the information and know-how it contains, is proprietary and confidential and constitutes valuable trade secrets of Sterling Commerce, Inc., its affiliated companies or its or their licensors (collectively “Sterling Commerce”), and may not be used for any unauthorized purpose or disclosed to others without the prior written permission of Sterling Commerce. The Sterling Commerce Software and the information and know-how it contains have been provided pursuant to a license agreement which contains prohibitions against and/or restrictions on its copying, modification and use. Duplication, in whole or in part, if and when permitted, shall bear this notice and the Sterling Commerce, Inc. copyright legend.

U.S. GOVERNMENT RESTRICTED RIGHTS. This software and related documentation are "commercial items" as defined in 48 C.F.R. 2.101. As and when provided to any agency or instrumentality of the U.S. Government or to a U.S. Government prime contractor or a subcontractor at any tier ("Government Licensee"), the terms and conditions of the customary Sterling Commerce commercial license agreement are imposed on Government Licensees per 48 C.F.R. 12.212 or 48 C.F.R. 227.7202 through 227.7202-4, as applicable, or through 48 C.F.R. 52.244-6.

Portions of the Sterling Commerce Software may include products, or may be distributed on the same storage media with products, ("Third Party Software") offered by third parties ("Third Party Licensors"). Sterling Commerce Software may include Third Party Software covered by the following copyrights: Copyright © 1997-2005 Certicom Corp. Copyright © 1999-2004 Hewlett-Packard Development Company. Copyright © IBM Corporation, 1998, 2007. Copyright © 2001-2007, The Board of Trustees of the University of Illinois. Copyright © 1995-2005 Jean-loup Gailly and Mark Adler. Copyright © 1998-2008 The OpenSSL Project. Copyright © 1996, 2004 Oracle Corporation. Copyright © 1992-2004 SNMP Research International, Inc. Copyright © 2007 Sun Microsystems, Inc. All rights reserved by all listed parties.

This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit. (<http://www.openssl.org/>). This product includes cryptographic software written by Eric Young

(eay@cryptsoft.com). This product includes software the copying and distribution of which is done with the permission of SNMP Research International, Inc. This product contains Runtime Modules of IBM(r) 32-bit SDK for AIX(tm), JAVA(tm) 2 Technology Edition, Version 5 Copyright © IBM Corporation, 1996-2005.

References in this manual to Sterling Commerce products, programs, or services do not imply that Sterling Commerce intends to make these available in all countries in which Sterling Commerce operates.

Printed in the United States of America

#### WARRANTY DISCLAIMER

The Sterling Commerce Software and this related documentation are licensed either "AS IS" or with a limited warranty, as described in the Sterling Commerce license agreement. Other than any limited warranties provided, **NO OTHER WARRANTY IS EXPRESSED AND NONE SHALL BE IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR USE OR FOR A PARTICULAR PURPOSE.** The applicable Sterling Commerce entity reserves the right to revise this publication from time to time and to make changes in the content hereof without the obligation to notify any person or entity of such revisions or changes.

This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit. (<http://www.openssl.org/>). This product includes cryptographic software written by Eric Young (eay@cryptsoft.com). This product includes software the copying and distribution of which is done with the permission of SNMP Research International, Inc.

As set forth in the README file located in the Connect:Direct installation directory ("Read Me file"), certain of the Third Party Licensors assert specific terms with respect to their respective products. Such terms shall only apply as to the specific Third Party Licensor product and not to those portions of the product derived from other Third Party Licensor products or to the Sterling Commerce Software as a whole. Except as otherwise described in the README file, the Third Party Software is provided 'AS IS' AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. FURTHER, IF YOU ARE LOCATED OR ACCESSING THIS SOFTWARE IN THE UNITED STATES, ANY EXPRESS OR IMPLIED WARRANTY REGARDING TITLE OR NON-INFRINGEMENT ARE DISCLAIMED. Additionally, certain Third Party Licensor product terms and information are set out below. Such terms shall only apply as to the specific Third Party Licensor product and not to those portions of the product derived from other Third Party Licensor products or to the Sterling Commerce Software as a whole.

These terms of use shall be governed by the laws of the state of Ohio, USA, without regard to its conflict of laws provisions. If you are accessing this documentation or the related Sterling Commerce Software under an executed agreement, then nothing in these terms and conditions supersedes or modifies the executed agreement, except as set forth under the section titled "Oracle Software".

Not that only the JRE license information for the specific JRE system on which the Sterling Software and Third Party Software is installed will be available in the specified directory.

## HEWLETT PACKARD

The Sterling Commerce Software is distributed on the same storage media as the Hewlett-Packard Software which contains Java Runtime Environment 1.6 for HP 9000 PA-RISC and HP-UX Integrity, Copyright © 1999-2007 Hewlett-Packard Development Company (collectively the “HP JRE Software”). All Rights Reserved. Additional license information is located at `<Connect:Direct install dir>/jre/LICENSE` and applies only to the HP JRE Software and not to the Sterling Commerce Software or to any other Third Party Software. The HP JRE Software includes the following notice: "Some third-party code embedded or bundled with the [HP JRE] Software is licensed to you under terms and conditions as set forth in the THIRDPARTYLICENSEREADME.txt file. In addition to any terms and conditions of any third party license identified in the THIRDPARTYLICENSEREADME.txt file, the disclaimer of warranty and limitation of liability provisions contained in the “AS IS” Warranty Statement shall apply to all code distributed as part of or bundled with the [HP JRE] Software.”

US Government Rights Notice. Confidential Computer Software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor’s standard commercial license.

You will only find the JRE license information for the HP JRE Software in the specified directory if the Sterling Software and Third Party Software are installed on a HEWLETT PACKARD system.

## IBM

The Sterling Commerce Software is distributed on the same storage media as the IBM software which contains Java Runtime Environment 1.6 for AIX and Linux zSeries, Copyright © 1998-2007 IBM Corporation (collectively “IBM JRE Software”). All Rights Reserved. Other copyright acknowledgements may be found in the ‘Notices’ file in the IBM JRE Software.

U.S. Government Users Restricted Rights- Use, duplication or disclosure restricted by the GSA ADP Schedule Contract with the IBM Corporation.

You will only find the JRE license information for the IBM JRE Software in the specified directory if the Sterling Software and Third Party Software are installed on an IBM system.

## OPENSSL SOFTWARE

The Sterling Commerce Software includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org/>), ("OpenSSL Software"). The OpenSSL Software is subject to the following license terms:

Copyright (c) 1998-2008 The OpenSSL Project. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. All advertising materials mentioning features or use of this software must display the following acknowledgment: "This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit. (<http://www.openssl.org/>)"
4. The names "OpenSSL Toolkit" and "OpenSSL Project" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact [openssl-core@openssl.org](mailto:openssl-core@openssl.org).
5. Products derived from this software may not be called "OpenSSL" nor may "OpenSSL" appear in their names without prior written permission of the OpenSSL Project.
6. Redistributions of any form whatsoever must retain the following acknowledgment:  
"This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org/>)"

THIS SOFTWARE IS PROVIDED BY THE OpenSSL PROJECT ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE OpenSSL PROJECT OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

This product includes cryptographic software written by Eric Young ([ey@cryptsoft.com](mailto:ey@cryptsoft.com)). This product includes software written by Tim Hudson ([tjh@cryptsoft.com](mailto:tjh@cryptsoft.com)).

## Original SSLeay License

Copyright © 1995-1998 Eric Young ([EAY@cryptsoft.com](mailto:EAY@cryptsoft.com)) All rights reserved.

This package is an SSL implementation written by Eric Young ([ey@cryptsoft.com](mailto:ey@cryptsoft.com)). The implementation was written so as to conform with Netscapes SSL.

This library is free for commercial and non-commercial use as long as the following conditions are aheared to. The following conditions apply to all code found in this distribution, be it the RC4, RSA, lhash, DES, etc., code; not just the SSL code. The SSL documentation included with this distribution is covered by the same copyright terms except that the holder is Tim Hudson ([tjh@cryptsoft.com](mailto:tjh@cryptsoft.com)).

Copyright remains Eric Young's, and as such any Copyright notices in the code are not to be removed.

If this package is used in a product, Eric Young should be given attribution as the author of the parts of the library used.

This can be in the form of a textual message at program startup or in documentation (online or textual) provided with the package.

Redistribution and use in source and binary forms, with or without are met:

1. Redistributions of source code must retain the copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. All advertising materials mentioning features or use of this software must display the following acknowledgement:

"This product includes cryptographic software written by Eric Young ([ey@cryptsoft.com](mailto:ey@cryptsoft.com))"  
The word 'cryptographic' can be left out if the routines from the library being used are not cryptographic related :-).

4. If you include any Windows specific code (or a derivative thereof) from the apps directory (application code) you must include an acknowledgement:

"This product includes software written by Tim Hudson ([tjh@cryptsoft.com](mailto:tjh@cryptsoft.com))"

**THIS SOFTWARE IS PROVIDED BY ERIC YOUNG ``AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.**

The license and distribution terms for any publically available version or derivative of this code cannot be changed. i.e. this code cannot simply be copied and put under another distribution license [including the GNU Public License.]

## ORACLE HELP SOFTWARE

The Sterling Commerce Software is distributed with or on the same storage media as the Oracle Help for Java Software provided by Oracle Corporation, Copyright (c) 1996, 2004 Oracle Corporation ("Oracle Software"). The License relating to the Oracle Software is included in the directory file located at: <Connect:Direct install dir>/Third\_Party\_Licenses. The Oracle Software license terms do not permit distribution of the Oracle Software independent of the Sterling Commerce Software by Sterling Commerce licensees. Note that Oracle USA, Inc. is a third party beneficiary of the software license between Sterling Commerce and you (including the organization on whose behalf you are accessing the software), as the licensee. The Oracle Software license applies only to the Oracle Software which is the subject of the directory identified above and does not apply to the Sterling Commerce Software or to any other Third Party Software.

### Restricted Rights

The Oracle Software is provided under restricted rights. If you are (or if you distribute a license to) the United States government, the Oracle Software, including documentation, shall be considered commercial computer software and you will place a legend, in addition to applicable copyright notices, on the documentation, and on the media label, substantially similar to the following:

#### NOTICE OF RESTRICTED RIGHTS

Programs delivered subject to the DOD FAR Supplement are 'commercial computer software' and use, duplication, and disclosure of the programs, including documentation, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement. Otherwise, programs delivered subject to the Federal Acquisition Regulations are 'restricted computer software' and use, duplication, and disclosure of the programs, including documentation, shall be subject to the restrictions in FAR 52.227-19, Commercial Computer Software-Restricted Rights (June 1987). Oracle Corporation, 500 Oracle Parkway, Redwood City, CA 94065.

## SUN MICROSYSTEMS

SUN, Sun Microsystems, the Sun logo, Solaris, Java, Jini, Forte, J2SE, and iPlanet and all related trademarks, service marks logos and other brand designations that are referred to or displayed in the Sterling Commerce Software or the related documentation are trademarks or registered trademarks of Sun Microsystems, Inc. The Sterling Commerce Software is distributed on the same storage media as the JAVA (tm) 2 Runtime Environment (J2RE) Standard Edition, Version 1.6 for Solaris-Sparc, Solaris-i586 and Linux-i586, Copyright © 2007 Sun Microsystems, Inc. (collectively "Sun JRE Software"). All Rights Reserved.

The license terms for the Sun JRE Software are located at <Connect:Direct install dir>/jre1.6.0\_03 for Sun SPARC, Sun x86, and Linux and at <Connect:Direct install dir>/jre for AIX, HP-UX Itanium, and HP-UX PA-RISC. The Sun JRE Software includes the following notice: "Additional copyright notices and license terms applicable to portions of the Sun JRE Software are set forth in the THIRDPARTYLICENSEREADME.txt file. In addition to any terms and conditions of any third party open source/freeware license identified in the THIRDPARTYLICENSEREADME.txt file, the disclaimer of warranty and limitation of liability provisions in paragraphs 5 and 6 of the Binary Code License Agreement shall apply to all Sun JRE Software in this distribution."

The Sun JRE Software license terms for also require the inclusion of the following notice: "This product includes code licensed from RSA Security, Inc. Some portions licensed from IBM are available at <http://oss.software.ibm.com/ico4j/>."

Government Rights – Commercial Software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements. Use is subject to license terms. This distribution may include materials developed by third parties.

You will only find the JRE license information for Sun JRE Software in the specified directory if the Sterling Software and Third Party Software are installed on a SUN system.

## UDT SOFTWARE

The Sterling Commerce Software includes UDT 3.3 software (the file name of the product downloaded from SourceForge.net is UDT.SDK.3.3.bsd\_lic.tar[1]) licensed by the Board of Trustees of the University of Illinois ("UDT Software"). Other versions of UDT 3.3 were licensed under the LGPL. The UDT Software is subject to the following license terms:

Copyright © 2001-2007, The Board of the Trustees of the University of Illinois. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of the University of Illinois nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING , BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR

A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## ZLIB SOFTWARE

All source code, binaries, documentation and other files distributed with the zlib 1.2.3 Software are subject to the following license terms, and are held under the following copyright notice, unless otherwise noted within the individual files.

zlib.h -- interface of the 'zlib' general purpose compression library  
version 1.2.3, July 18th, 2005

Copyright (C) 1995-2005 Jean-loup Gailly and Mark Adler

This software is provided 'as-is', without any express or implied warranty. In no event will the authors be held liable for any damages arising from the use of this software.

Permission is granted to anyone to use this software for any purpose, including commercial applications, and to alter it and redistribute it freely, subject to the following restrictions:

1. The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required.
2. Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software.
3. This notice may not be removed or altered from any source distribution.

Jean-loup Gailly      Mark Adler  
jloup@gzip.org      madler@alumni.caltech.edu