

# Connect:Direct®

## Problem Isolation Guide

**Connect:Direct Problem Isolation Guide  
Twentieth Edition**

(c) Copyright 1984-2005 Sterling Commerce, Inc. All rights reserved. Additional copyright information is located at the end of the release notes.

**STERLING COMMERCE SOFTWARE**

**\*\*\*TRADE SECRET NOTICE\*\*\***

THE CONNECT:DIRECT SOFTWARE ("STERLING COMMERCE SOFTWARE") IS THE CONFIDENTIAL AND TRADE SECRET PROPERTY OF STERLING COMMERCE, INC., ITS AFFILIATED COMPANIES OR ITS OR THEIR LICENSORS, AND IS PROVIDED UNDER THE TERMS OF A LICENSE AGREEMENT. NO DUPLICATION OR DISCLOSURE WITHOUT PRIOR WRITTEN PERMISSION. RESTRICTED RIGHTS.

This documentation, the Sterling Commerce Software it describes, and the information and know-how they contain constitute the proprietary, confidential and valuable trade secret information of Sterling Commerce, Inc., its affiliated companies or its or their licensors, and may not be used for any unauthorized purpose, or disclosed to others without the prior written permission of the applicable Sterling Commerce entity. This documentation and the Sterling Commerce Software that it describes have been provided pursuant to a license agreement that contains prohibitions against and/or restrictions on their copying, modification and use. Duplication, in whole or in part, if and when permitted, shall bear this notice and the Sterling Commerce, Inc. copyright notice. As and when provided to any governmental entity, government contractor or subcontractor subject to the FARs, this documentation is provided with RESTRICTED RIGHTS under Title 48 52.227-19. Further, as and when provided to any governmental entity, government contractor or subcontractor subject to DFARS, this documentation and the Sterling Commerce Software it describes are provided pursuant to the customary Sterling Commerce license, as described in Title 48 CFR 227-7202 with respect to commercial software and commercial software documentation.

These terms of use shall be governed by the laws of the State of Ohio, USA, without regard to its conflict of laws provisions. If you are accessing the Sterling Commerce Software under an executed agreement, then nothing in these terms and conditions supersedes or modifies the executed agreement.

Where any of the Sterling Commerce Software or Third Party Software is used, duplicated or disclosed by or to the United States government or a government contractor or subcontractor, it is provided with RESTRICTED RIGHTS as defined in Title 48 CFR 52.227-19 and is subject to the following: Title 48 CFR 2.101, 52.227-19, 227.7201 through 227.7202-4, FAR 52.227-14, and FAR 52.227-19(c)(1-2) and (6/87), and where applicable, the customary Sterling Commerce license, as described in Title 48 CFR 227-7202 with respect to commercial software and commercial software documentation including DFAR 252.227-7013, DFAR 252,227-7014, DFAR 252.227-7015 and DFAR 252.227-7018, all as applicable.

The Sterling Commerce Software and the related documentation are licensed either "AS IS" or with a limited warranty, as described in the Sterling Commerce license agreement. Other than any limited warranties provided, NO OTHER WARRANTY IS EXPRESSED AND NONE SHALL BE IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR USE OR FOR A PARTICULAR PURPOSE. The applicable Sterling Commerce entity reserves the right to revise this publication from time to time and to make changes in the content hereof without the obligation to notify any person or entity of such revisions or changes.

Connect:Direct is a registered trademark of Sterling Commerce. Connect:Enterprise is a registered trademark of Sterling Commerce, U.S. Patent Number 5,734,820. All Third Party Software names are trademarks or registered trademarks of their respective companies. All other brand or product names are trademarks or registered trademarks of their respective companies.

---

Sterling Commerce, Inc.  
4600 Lakehurst Court Dublin, OH 43016-2000 \*  
614/793-7000

---

# Contents

## **Part I      General Information**

### **Chapter 1    About Connect:Direct**

### **Chapter 2    Problem Reporting Procedures**

Reporting the Problem .....	11
Gathering Data to Isolate the Problem .....	11
Additional Supporting Data .....	12
Session-related Problems .....	12
Abends or Hangs .....	12
Miscellaneous Problems .....	12
Resolving the Problem .....	13
Escalating a Problem Resolution .....	13

### **Chapter 3    Basic Troubleshooting Methods**

Reviewing Connect:Direct Messages .....	15
Interactive Use of the Connect:Direct Message Facility .....	16
Connect:Direct OS/390.....	16
Connect:Direct for VM/ESA .....	16
Connect:Direct for VSE/ESA .....	16
Abend Messages .....	16
Examining Output from Connect:Direct Select Commands .....	17
SELECT STATISTICS Command .....	18
Connect:Direct IUI Select Statistics Screen for OS/390 .....	18
Verifying File Attributes .....	19
Overriding Connect:Direct Initialization Parameters .....	19
Overriding Connect:Direct OS/390 Initialization Parameters .....	19
Overriding Connect:Direct for VM/ESA Initialization Parameters .....	20
Overriding Connect:Direct for VSE/ESA Initialization Parameters .....	20

**Part II Common Errors**

**Chapter 4 Initialization Errors**

Determining Initialization Errors ..... 23

**Chapter 5 Asset Protection Errors**

Determining License Violations..... 41

**Chapter 6 Signon and IUI/API Errors**

Determining Signon Errors ..... 61

**Chapter 7 Security Errors**

Determining Security Errors ..... 73

**Chapter 8 Connect:Direct DTF Session-Establishment Errors**

**Chapter 9 Connect:Direct DTF Out-of-Storage Abends**

**Chapter 10 Allocation and Open Errors**

**Chapter 11 Transmission Errors**

**Chapter 12 Operator Interface Errors**

**Part III Diagnostic Tools**

**Chapter 13 Dumps**

Information Requested by Customer Support ..... 101

Connect:Direct Data Transmission Facility (DTF) Dumps ..... 102

    Connect:Direct OS/390 DTF Dumps (CDSVCDMP, SYSMDUMP, and SYSABEND) 102

        Capturing Multiple DTF SVC Dumps Using CDSVCDMP ..... 103

        Turning Off the SVC Dump ..... 103

        Changing Dump Options ..... 103

    Connect:Direct for VM/ESA DTF Dump (GCS Dump)..... 104

    Connect:Direct for VSE/ESA DTF Dump (PARTDUMP) ..... 104

Connect:Direct Interactive User Interface (IUI) Dumps ..... 105

    Connect:Direct OS/390 IUI Dumps ..... 105

    CMS Address Space Dump (Connect:Direct for VM/ESA Only)..... 105

SVC Dumps..... 106

DMBATCH Dumps ..... 106

VSAM File Dumps..... 106

Connect:Direct OS/390 VSAM File Dump ..... 106  
 Connect:Direct for VM VSAM File Dump ..... 107  
 Connect:Direct for VSE/ESA VSAM File Dump ..... 107  
 DTF Snap Dump Facility ..... 107  
     Command Syntax ..... 107  
     Using Snap Dump Commands ..... 108  
         Displaying a Hexadecimal Dump Format ..... 108  
         Displaying the Resource Address Table ..... 108  
         Displaying Task Control Area Information ..... 108  
         Displaying DTF Program Information ..... 108  
 Suppressing Dumps for Specific Abend Codes ..... 109

**Chapter 14 Connect:Direct Traces**

Guidelines for Running Traces ..... 111  
 Security Traces ..... 111  
 Connect:Direct Function Traces ..... 113  
     DEBUG Initialization Parameters ..... 115  
         Example of Running a Merged Trace ..... 115  
         Connect:Direct for VSE/ESA ..... 116  
         Connect:Direct for VM/ESA ..... 116  
     Examples of Connect:Direct Trace Output Using DEBUG Parameter ..... 117  
         COPY Routine Trace ..... 117  
         I/O Buffer Trace ..... 117  
         Long RPL Trace ..... 118  
         Short RPL Trace ..... 119  
     Connect:Direct MODIFY Command ..... 119  
     Examples of MODIFY Commands ..... 120  
         Connect:Direct OS/390 ..... 120  
         Connect:Direct for VM/ESA ..... 121  
         Connect:Direct for VSE/ESA ..... 121  
     Using MODIFY Commands Through the Batch Interface ..... 121  
 Connect:Direct Automatic Traces ..... 122  
     Examples of Automatic Connect:Direct Traces ..... 123  
         RPLERRCK Sample Output ..... 124  
         CDLOG Sample Output Showing Session Failure ..... 124  
         CDLOG Sample Output Showing Successful Completion ..... 124  
         ESTAE Sample Output ..... 124  
         NDMCMDS Sample Output ..... 125  
         LOSTOUT Sample Output ..... 125  
         DMCOPYRT Sample Output ..... 125  
         DMVSOPEN Sample Output ..... 126

**Chapter 15 Tracing Network Traffic**

VTAM Line and Buffer Traces ..... 127

**Index**



# Part I

---

## General Information





---

# About Connect:Direct

Connect:Direct is peer-to-peer file-based integration middleware optimized for assured delivery, high-volume and secure data exchange within and between enterprises. It is optimized for high performance and moves files containing any type of data (text, structured such as EDI, binary, image, etc.) across multiple platforms, disparate file systems and disparate media (tape, disk, etc.)

The *Connect:Direct Problem Isolation Guide* is for users who manage and monitor Process status and data transfer with Connect:Direct for the following platforms:

- ❖ IBM OS/390
- ❖ IBM Virtual Machine/Enterprise System Architecture (VM/ESA)
- ❖ IBM Virtual Storage Extended/Enterprise System Architecture (VSE/ESA)

This guide assumes knowledge of the applicable operating system, including its applications, network, and environment. If you are not familiar with the operating systems, refer to the appropriate library of manuals.



---

# Problem Reporting Procedures

This chapter describes the following:

- ❖ Reporting problems
- ❖ Data to have available
- ❖ Problem resolution procedures
- ❖ Escalating problem resolution

---

## Reporting the Problem

Report problems to IBM support at [http://www.ibm.com/support/entry/portal/open\\_service\\_request](http://www.ibm.com/support/entry/portal/open_service_request).

---

## Gathering Data to Isolate the Problem

To expedite the diagnostics process, prepare the following information for the Customer Support representative before calling Sterling Commerce:

- ❖ Version, release, maintenance level, and operating system for the Connect:Direct products being used on both nodes. For example, Connect:Direct OS/390 4.3.00 PUT4301 with Connect:Direct for Tandem NonStop Kernel 3.2.00.
- ❖ Details describing the complete scenario, including:
  - ◆ Commands that are issued, with exact syntax and order.
  - ◆ Files or devices that are involved. Note the file contents and the type of file (such as DCB file attributes, GDG, Tape, SMS, striped, compressed).
  - ◆ Interface that you used, such as batch interface, IUI, or operator interface.
  - ◆ Error messages for *both* nodes.
  - ◆ System logs for *both* nodes, including any messages generated while the problem occurred. Check the SYSLOG for Connect:Direct OS/390 nodes. For Connect:Direct for VM/ESA nodes, review the VM/ESA console log from the Connect:Direct virtual machine. Examine the VSE/ESA console log (SYSLOG) for Connect:Direct for VSE/ESA nodes.

- ♦ Which side is PNODE/SNODE.
- ♦ The direction of the data transfer.
- ♦ What connection protocol you are using (LU0, LU6.2, IBM TCP/IP, TCPAccess).
- ♦ If a Connect:Direct OS/390 node is a Connect:Direct/Plex or stand alone server.
- ♦ Connect:Direct Process.
- ♦ Statistics information for both nodes.

---

**Note:** Be prepared to recreate the problem. Problem recreation is the responsibility of the customer as Sterling Commerce cannot duplicate all customer environments.

---

## Additional Supporting Data

Problem determination can be involved and can require extensive research. We ask you to gather some of the following supporting documentation to help analyze the problem. Not all of this information is applicable to all problems or all operating environments.

## Session-related Problems

For session-related problems, supply the following:

- ❖ SYSLOGs
- ❖ Connect:Direct statistics for both nodes
- ❖ RPLERRCK output
- ❖ ESTAE output
- ❖ VTAM definitions
- ❖ APPLID definitions
- ❖ Logmode table entry
- ❖ Class of Service (COS) entry
- ❖ D NET VTAM display
- ❖ Connect:Direct traces
- ❖ Network map information

You can use your network management software or VTAM commands to isolate any session-related problems.

## Abends or Hangs

For abends or hangs, supply the following:

- ❖ SVC dump
- ❖ SYSLOGs
- ❖ Connect:Direct Traces

## Miscellaneous Problems

For other miscellaneous problems, supply the following:

- ❖ Detailed statistics from both nodes, including ALLOC information
- ❖ SYSLOGs, Connect:Direct Joblog
- ❖ Copy of the Connect:Direct Process

- ❖ File attributes for the FROM and TO files for both nodes
- ❖ Traces for both Connect:Direct and VTAM
- ❖ Connect:Direct initialization parameters
- ❖ ESTAE DD output
- ❖ I/O device types
- ❖ Statistics files
- ❖ Network map information
- ❖ Release levels of the software from both Connect:Direct nodes, operating system, VTAM, and other software involved

---

## Resolving the Problem

If Sterling Commerce Customer Support cannot resolve the problem during your initial call, the problem is documented as a case in a problem-tracking system and is assigned a reference number. Refer to this number when forwarding any supporting documentation or calling for updates.

Security Level	Definition
Severity 1	Production system is down; requires immediate attention. For example, excessive abnormal termination.
Severity 2	A major problem or question; the product operates but is severely restricted. For example, an incorrect response from a frequently used command.
Severity 3	A non-critical issue is encountered with the product, but the majority of functions are still usable. For example, an incorrect response from an infrequently used command.
Severity 4	A minor problem or question that does not affect product function. For example, the text of a message is misspelled.

All cases are prioritized based on severity, as follows: During or immediately after the initial issue is reported, a Sterling Commerce Customer Support representative requests appropriate information needed to research your case. Every effort is made to minimize requests for more information. Trained resources research and resolve cases on a timely basis. You are informed of the resolution status at agreed-upon intervals while the case is still open.

When the problem is resolved and you have accepted the resolution, the case is closed. Brief service evaluation surveys are sent to you occasionally so that we can obtain your feedback.

---

## Escalating a Problem Resolution

If our normal support cycle does not produce the results you require or your issue has changed in severity, you can escalate the case. To escalate a case, contact the technician responsible for your problem, state your concerns, and request that the case be escalated.



---

# Basic Troubleshooting Methods

This chapter describes the basic troubleshooting methods that you can use for problem isolation. Preliminary actions you can take to isolate the problem include:

- ❖ Reviewing Connect:Direct messages
- ❖ Examining output from Connect:Direct SELECT commands
- ❖ Verifying file attributes
- ❖ Overriding Connect:Direct initialization parameters

---

## Reviewing Connect:Direct Messages

As you research a problem, note any messages issued by Connect:Direct. Look specifically for messages displayed by the API through the IUI or batch interface (DMBATCH). If an error occurred in a file transfer, look at messages for any Processes executing at that time for both nodes.

Also, check for messages in the JES log for OS/390, virtual machine's console log for VM/ESA, and hard copy file for VSE/ESA.

Connect:Direct messages contain short and long text to explain the error. Connect:Direct OS/390, VM/ESA, and VSE/ESA only display the short text when an event occurs. The following information is displayed for each message if you request the long text:

- ❖ Module issuing the message
- ❖ Short and long message texts
- ❖ System action as a result of the message situation
- ❖ User response to correct the situation

---

**Note:** For OS/390 or VM/ESA, press **PF1** to display the longer explanation if the message is an ISPF/PDF message.

---

## Interactive Use of the Connect:Direct Message Facility

This section describes how you can display long-text messages for Connect:Direct OS/390, VM/ESA, and VSE/ESA.

### Connect:Direct OS/390

For Connect:Direct OS/390, display the long text message through the IUI by either of the following methods:

- ❖ Use the SELECT MESSAGE command in the command line interface.
- ❖ Type **M** at the CMD prompt and press **Enter**.
- ❖ Access the PRIMARY OPTIONS MENU and type the MSG option at the CMD prompt.
- ❖ Type **=M** from any Connect:Direct screen at the CMD prompt in the ISPF Interface and press **Enter**. The long text for the current message is displayed.

---

**Note:** Installations with ISPF/PDF or TSS/PFD can modify the ISPF/PDF (or TSS/PFD) PRIMARY OPTION MENU to access the Connect:Direct message facility. Refer to the Connect:Direct installation guide applicable to your environment for instructions.

---

### Connect:Direct for VM/ESA

For Connect:Direct for VM/ESA, display messages by using the SELECT MESSAGE command in the command line interface.

### Connect:Direct for VSE/ESA

For Connect:Direct for VSE/ESA, display messages in long form on the console by entering the console reply number, **!m**, and the Connect:Direct message identifier at the command line.

Following is an example.

```
24 !m SVSG001I
```

Refer to the *Connect:Direct for VSE/ESA User's Guide* for use of the batch interface.

## Abend Messages

Some user abend messages are stored in the Connect:Direct message file. To access them, insert the abend message ID in place of a Connect:Direct message ID.

For example, to display the description of user abend U0075 perform the following:

1. Access the PRIMARY OPTIONS MENU in the IUI.
2. Select the MSG option.
3. Select option 1.



4. Type **U0075** on the message ID line and press **Enter**.

```

Connect:Direct (TM) MESSAGE DISPLAY

MESSAGE ID==>U0075
MODULE ==>DMINIT
DATE=> 2003/05/06
TIME=> 10:05
=====

SHORT TEXT==> Connection services initialization failure.
LONG TEXT:
  LINE 1 ==> An error has occurred while initializing VTAM connection
  LINE 2 ==> services. ESTAE output should give a return code and error
  LINE 3 ==> flag.
  LINE 4 ==>
  LINE 5 ==> Verify the applid does not have a password associated with it
  LINE 6 ==> in the LOCAL.NODE definition of the Network Map.
  LINE 7 ==>
  LINE 8 ==>
  LINE 9 ==> SYSTEM ACTION: ABEND the initialization of Connect:Direct.
  LINE 10 ==>
  LINE 11 ==> RESPONSE: Verify that the applid is varied active and there is
  LINE 12 ==> not a VTAM password specified in the Network Map.

COMMAND ==>_____ ENTER 'DIR' TO DISPLAY THE DIRECTORY

```

System abend messages appear in:

- ❖ the JES log for OS/390
- ❖ the virtual machine's console log for VM/ESA
- ❖ the hard copy file for VSE/ESA

They do not appear in the Connect:Direct message file. Refer to the appropriate operating system manuals if you require further details.

---

## Examining Output from Connect:Direct Select Commands

Problem determination and resolution is often as simple as gathering output from the Connect:Direct SELECT commands and examining the output for obvious errors. A description of the commands follows:

Command	Description
SELECT NETMAP	Displays or prints the definitions of nodes with which Connect:Direct can communicate.
SELECT PROCESS	Displays or prints information about Connect:Direct Processes in the TCQ. You can use this command before or during Connect:Direct Process execution.
SELECT STATISTICS	Displays or prints statistics from the statistics log. Use this command only after executing a Connect:Direct Process.
SELECT TASK	Selects, displays, or prints the list of all active users, Processes, and tasks within Connect:Direct.
SELECT TYPE	Displays or prints type records from the Type file.

All of the Connect:Direct SELECT commands are documented in the *Connect:Direct User's Guide* appropriate to your platform.

## SELECT STATISTICS Command

The SELECT STATISTICS command is one of the most useful commands for problem determination. This section provides a brief overview of the SELECT STATISTICS command. For more detailed information, refer to the *Connect:Direct User's Guide* for your platform.

If an error occurred during a file transfer, issue the SELECT STATISTICS command on both the PNODE and SNODE to review the statistics for the Process. Process statistics are stored in the Connect:Direct statistics log. You can request them by either using the IUI Select Statistics (SS) screen, if applicable, or issuing the Connect:Direct SELECT STATISTICS command.

The statistics log records the following types of information for Connect:Direct Processes:

- ❖ Function requested (COPY, RUN TASK, RUN JOB, SUBMIT)
- ❖ Process name and number
- ❖ Start and stop times, and date of the function
- ❖ Completion code
- ❖ Messages associated with the Process
- ❖ Location and ID of the user requesting Connect:Direct services
- ❖ Sending and receiving file names
- ❖ Amount of data sent and received
- ❖ Security violations
- ❖ All Connect:Direct WTO messages, allocation information, and mount requests

---

**Note:** WTO messages are created during Connect:Direct Process execution to document the execution steps and are stored in the Connect:Direct statistics file. This type of message is an excellent debugging tool for determining a Connect:Direct execution failure.

---

The optional parameters associated with the SELECT STATISTICS command enable you to define the search criteria and the form in which the report is presented.

## Connect:Direct IUI Select Statistics Screen for OS/390

The Select Statistics screen provides a convenient, easy method for issuing the SELECT STATISTICS command. Use the fields to specify statistics selection criteria. The selection criteria enable you to determine what records to select from the statistics log, limit the statistics to a certain period of time, or limit the statistics to a certain Process. The selection criteria also allow Connect:Direct to select the requested statistics from the file more efficiently.

The SELECT STATISTICS screen displays general Connect:Direct Process information.

- ❖ To display the requested information in a formatted report, type a D in the CMD field and press Enter.
- ❖ To print the formatted report, type a P in the CMD field and press Enter. The output is sent to your TSO sysout.
- ❖ For a summary report display, type an S in the CMD field and press Enter.
- ❖ To view your statistics file in an unformatted display, type FIL or F in the CMD field and press Enter.
- ❖ The SELECT STATISTICS screen also enables you to exclude certain types of information from being displayed. Type a Y in any of the following fields and press Enter.
  - ♦ **MEMBERS** - Statistics generated for each partitioned data set (PDS) member
  - ♦ **WTO** - WTO (Write to Operator) messages
  - ♦ **–WTO** - All statistics other than WTO messages

When statistics are requested by Sterling Commerce Customer Support, do not exclude any information. Set all the fields listed to N. Customer Support must receive all the information available to solve the problem.

---

## Verifying File Attributes

If a problem occurs during a file transfer, verifying the accuracy of the file attributes can often resolve the problem. Review the following file attribute parameters for the file being transmitted when the error occurred. Check both the input and output files specified in your Connect:Direct Processes:

- ❖ Logical record length (LRECL)
- ❖ Block size (BLKSIZE)
- ❖ Record format (RECFM)
- ❖ File organization (DSORG)
- ❖ File disposition (DISP)
- ❖ Unit containing the file (UNIT)
- ❖ Volume serial number (VOLSER)
- ❖ Storage for allocating new files (SPACE)
- ❖ Optional processing code (OPTCD)
- ❖ Length of keys used in file (KEYLEN)
- ❖ Number of blocks or tracks to search for available space (LIMCT)

For a detailed description of these parameters, see the Connect:Direct Processes Web site at <http://www.sterlingcommerce.com/Documentation/processes/processhome.html>.

---

## Overriding Connect:Direct Initialization Parameters

Initialization parameters are set up during installation. When an error occurs, it may be necessary to alter these initialization parameters. For example, refresh the TCQ if Processes are hanging and the queue becomes corrupted. This section describes methods for overriding Connect:Direct initialization parameters for Connect:Direct OS/390, VM/ESA, and VSE/ESA.

### Overriding Connect:Direct OS/390 Initialization Parameters

You can override individual initialization parameters for Connect:Direct OS/390 by specifying the override on the EXEC statement in the startup job stream as shown in the following figure.

---

**Note:** **Connect:Direct OS/390 only:** In a Connect:Direct/Plex, you can only override initialization parameters allowed in the local initialization parameters file. Use the PARM= keyword in the EXEC statement at system startup.

In a Connect:Direct/Stand-alone Server environment, however, you can override global initialization parameters with the PARM= keyword in the EXEC statement.

---



## Part II

---

## Common Errors



---

# Initialization Errors

This chapter describes the causes of common errors associated with initialization of Connect:Direct.

---

## Determining Initialization Errors

While Connect:Direct is initializing, you see the following series of messages that show the sequence of events during initialization. If an initialization error occurs, note the last message issued. The problem most likely occurred during the step indicated by the last message or on the step indicated by the next message that should have been issued.

```
SITA001I Connect:Direct initialization begun
SITA002I Connect:Direct parameter file allocated and open
SITA120I Keyword INITPARM Value Overridden:UPPER.CASE1
SITA120I Keyword INITPARM Value Overridden:DEBUG1
SITA022I Loading Connect:Direct modules
SITA601I The TCP server modules are loaded2
SITA067I MESSAGE file is open
SITA628I SNMP Trap Agent Initialization Complete3
SITA023I Initializing Connect:Direct storage
SITA024I Building the TCA chain
SITA026I Creating the system tasks (master and timer)
SITA025I Building the ECB address list
SITA027I Building the DDN table
SITA068I AUTHORIZATION file is open
SITA134I TYPE DEFAULTS file is open
SITA069I NETWORK MAP file is open
SITA074I CHECK POINT file is open
SITA030I PCQ/TCQ being built
SITA068I AUTHORIZATION file is open
SITA134I TYPE DEFAULTS file is open
SITA069I NETWORK MAP file is open
SITA074I CHECK POINT file is open
SITA030I PCQ/TCQ being built
```

*Continued*

```

SITA400I Enqueueing TCX for ESF processing
SITA401I Dequeueing TCX for ESF processing
SITA029I Statistics facility being initiated
SSTL026I Statistics File Pair 03 is now active
SSTL019I Statistics facility successfully initialized
SITA034I VTAM services being initiated APPLID = M1CDD729
SITA035I ABEND/ESTAE exit being initialized
SITA036I Connect:Direct v.r.mm for OS/390 PUT 0000 Initialization Complete
STCP021I TCP/IP IUCV INTERFACE INITIALIZED2
STCP025I TCP/IP HOST IDENTIFICATION IS nnn.n.n.n2
STCP001I ISSUING TCP/IP SOCKET CALL2
STCP002I ISSUING TCP/IP BIND SOCKET2
STCP018I TCP/IP PORT NUMBER IS 72242
STCP003I Connect:Direct NOW LISTENING FOR CONNECTIONS2
SSNS001I SNS TCP/IP interface initializing4
SSNS002I SNS TCP/IP issuing AOPEN for SNS Subsystem ID ACSS4
SSNS003I SNS TCP/IP port number is 13704
SSNS004I SNS TCP/IP Issuing TBIND for port4
SSNS005I SNS TCP/IP Connect:Direct now listening for connections4
STCO009I IBM OES TCP/IP Server Subtask Attached5
STCO010I IBM OES TCP/IP Interface Initializing5
STCO001I IBM OES TCP/IP Issuing SOCKET Call5
STCO002I IBM OES TCP/IP Issuing BIND SOCKET Call5
STCO014I IBM OES TCP/IP Port Number is 41995
STCO003I IBM OES TCP/IP Issuing LISTEN SOCKET Call5
STCA009I IBM OES TCP/IP API Server Subtask Attached6
STCA010I IBM OES TCP/IP API Interface Initializing6
STCA001I IBM OES TCP/IP API Issuing SOCKET Call6
STCA002I IBM OES TCP/IP API Issuing BIND Socket Call6
STCA014I IBM OES TCP/IP API Port Number is 41986
STCA003I IBM OES TCP/IP API Issuing LISTEN Socket Call6
SITA028I Secure+ Initialization Complete7
SITA046I Secure+ Initialization Complete8

```

<sup>1</sup> This message is displayed only if an initialization parameter value is overridden in the startup JCL.

<sup>2</sup> This message is displayed only if IBM TCP/IP is used.

<sup>3</sup> This message is displayed only if SNMP=YES.

<sup>4</sup> This message is displayed only if SNS Interlink TCPAccess is used.

<sup>5</sup> This message is displayed only if IBM TCP/IP Open Edition Sockets Interface (OES) is used.

<sup>6</sup> This message is displayed only if IBM TCP/IP API OES is used.

<sup>7</sup> This message is displayed only if the limited export version of Secure+ is installed and active.

<sup>8</sup> This message is displayed only if the export version of Secure+ is installed and active.

---

**Note:** In addition to the initialization errors described in this chapter, you may see two different error messages in traces, which are also related to initialization:

- ❖ If you receive a return code of **4** when you stop Connect:Direct, be sure to review the NDMLOG for SITA995I messages indicating obsolete parameters. Once you remove the parameters, these messages no longer appear in the NDMLOG trace.
  - ❖ If you receive a return code of **8A** in the RPLERRCK trace when you start Connect:Direct and you have multiple TCP/IP stacks defined, the message, *No such device or address (STCO999E)*, appears in the trace. If you have only one TCP/IP stack defined, this is normal and no cause for alarm. If you are in an environment where multiple TCP/IP stacks are defined, you will want to investigate the situation and make sure the correct TCP stack is specified.
-



## Possible Error Messages

### Abend S0Cn

### Probable Cause

One or more NSSs (Named Saved Segments and Named Saved Systems) for VSAM, GCS, and VTAM overlap their page ranges.

### Action to Take

Relocate VSAM, GCS, or VTAM segments as needed so that no overlaps exist among these NSSs.

### Data to Collect

Collect the following data:

❖ NSS display

To display NSS information, you must have a privilege class of E (systems programmer). Type the following command to display all NSSs.

```
QUERY NSS ALL MAP
```

Type the following command to display a single NSS.

```
QUERY NSS NAME segment MAP
```

---

**CONDITION:**        **Connect:Direct does not initialize because of inadequate storage (GETMAIN/GETVIS or FREEMAIN/FREEVIS request failed).**

---

### Possible Error Messages

SITA037I	SITA042I	SITA043I	SITA044I	SITA045I	SITA047I
SITA049I	SITA050I	SITA078I	SITA080I	SITA096I	SITA097I
SITA098I	SITA099I	SITA122I			

### Probable Cause

Inadequate address space is allocated to the Connect:Direct DTF region.

### Action to Take

Review both the short text and long text Connect:Direct messages. Check the Connect:Direct startup job stream and the amount of storage allocated to the Connect:Direct region by checking the region parameter on the job card for Connect:Direct OS/390.

For Connect:Direct for VM/ESA, issue a CP QUERY VIRTUAL STORAGE command to determine the size of your virtual storage.

For Connect:Direct OS/390 and VM/ESA, increase the storage for the Connect:Direct address space. (In some cases, system exits can limit availability of above-the-line storage. Check with your internal Technical Support group about storage limits.)

For Connect:Direct for VSE/ESA, issue a GETVIS *xx* command, where *xx* is the partition identifier for the partition in which Connect:Direct is running.

### Data to Collect

Collect the following data:

- ❖ Connect:Direct error message
- ❖ Region/partition size

---

**CONDITION:**        **An error occurs while allocating or opening the Connect:Direct initialization parameters file.**

---

### Possible Error Messages

SITA063I	SITA070I	SITA121I	SITA123I	SITA291I	SITA292I
SITA293I	SITA294I	SITA501I	SITA502I	SITA505I	

### Probable Cause

The Connect:Direct initialization parameters file does not exist, or the parameter on the EXEC statement is specified incorrectly.

### Action to Take

Review both the short text and long text Connect:Direct messages. For Connect:Direct OS/390, look at the Connect:Direct startup JCL for the EXEC statement. Ensure that the specified initialization parameters data set exists and is correct.

For Connect:Direct for VM/ESA, the initialization parameters file is on the OSRUN parameter. Check the DMGSCMAP STARTUP file for Connect:Direct for VM/ESA.

For Connect:Direct for VSE/ESA, the input parameters are usually stored as SYSIPT in the job stream after the JCL.

### Data to Collect

Collect the following data:

- ❖ Connect:Direct startup JCL
- ❖ DMGSCMAP STARTUP file

---

**CONDITION:**        **Connect:Direct does not initialize because of initialization parameter errors.**

---

### Possible Error Messages

SITA003I	SITA014I	SITA018I	SITA021I	SITA038I	SITA039I
SITA040I	SITA041I	SITA063I	SITA071I	SITA072I	SITA073I
SITA079I	SITA082I	SITA083I	SITA084I	SITA085I	SITA086I
SITA087I	SITA088I	SITA089I	SITA091I	SITA092I	SITA093I
SITA094I	SITA095I	SITA104I	SITA105I	SITA106I	SITA148I
SITA201I	SITA202I	SITA213I	SITA214I	SITA215I	SITA216I
SITA217I	SITA220I	SITA221I	SITA222I	SITA223I	SITA224I
SITA225I	SITA226I	SITA227I	SITA228I	SITA230I	SITA231I
SITA232I	SITA233I	SITA234I	SITA242I	SITA250I	SITA251I
SITA252I	SITA253I	SITA254I	SITA260I	SITA261I	SITA262I
SITA263I	SITA270I	SITA271I	SITA272I	SITA273I	SITA280I
SITA281I	SITA282I	SITA283I	SITA285I	SITA286I	SITA287I
SITA300I	SITA506I	SITA507I	SITA508I	SITA509I	SITA510I
SITA511I	SITA512I	SITA513I	SITA514I	SITA515I	SITA516I
SITA517I	SITA518I	SITA540I			

### Probable Cause

Syntax errors or errors in the values specified exist for one or more Connect:Direct initialization parameters.

### Action to Take

Review both the short text and long text Connect:Direct messages. Note the Connect:Direct messages that you see on the console during initialization. There is a message to indicate the reason for the error. Verify that any comments preceding parameters are closed out. Refer to the appropriate Connect:Direct installation guide for the valid parameter values. Correct the parameter in the Connect:Direct initialization parameters file, and restart Connect:Direct.

### Data to Collect

Collect the following data:

- ❖ Connect:Direct error message
- ❖ Initialization parameters file

---

**CONDITION:**        **Connect:Direct does not initialize because of an error with one of the Connect:Direct VSAM files: the message file, authorization file, type file, network map file, statistics file, checkpoint file, or TCQ file.**

---

### Possible Error Messages

SITA055I	SITA056I	SITA057I	SITA059I	SITA060I	SITA061I
SITA062I	SITA064I	SITA065I	SITA066I	SITA075I	SITA076I
SITA077I	SITA100I	SITA101I	SITA102I	SITA103I	SITA110I
SITA111I	SITA112I	SITA113I	SITA130I	SITA131I	SITA132I
SITA133I	SITA160I				

### Probable Cause

An error occurred while opening the file, or VSAM encountered a physical or logical error. The VSAM file cannot be defined and loaded correctly, the name of the file might be specified incorrectly, or the file might be corrupted.

### Action to Take

Review both the short text and long text Connect:Direct messages. Verify that the name of the file is specified correctly in the initialization parameters file. Also, verify that the file is defined correctly to VSAM and loaded as described in the appropriate Connect:Direct installation guide.

### Data to Collect

Collect the following data:

- ❖ Connect:Direct messages
- ❖ Any messages issued by the VSAM AMS Interface Program (IDCAMS for OS/390 and VSE/ESA; AMSERV for VM/ESA) when the Connect:Direct VSAM file was defined and loaded

---

**CONDITION:**        **Connect:Direct does not initialize because of errors with VTAM initialization.**

---

### Possible Error Messages

SITA004I	SITA005I	SITA048I	SITA051I	SITA052I	SITA053I
SITA054I	SITA090I	user abend U0075			

### Probable Cause

The Connect:Direct DTF APPLID is defined incorrectly, the APPLID logmode table is incorrect or is not found, the DTF APPLID has a VTAM password associated with it, or the Connect:Direct DTF APPLID is not active.

### Action to Take

Review both the short text and long text Connect:Direct messages. Ensure that the DTF APPLID is active. Ensure that the APPLID specified in the LOCAL.NODE entry of the network map is correctly specified and is defined to VTAM. Check the ESTAE output for additional error information. If a VTAM password is associated with the Connect:Direct APPLID, remove it, and do not refer to it in the Connect:Direct network map.

### Data to Collect

Collect the following data:

- ❖ ESTAE output
- ❖ Connect:Direct network map
- ❖ APPLID definition
- ❖ Logmode table entry

---

**CONDITION: Security Environment Invalid for Connect:Direct.**

---

## Possible Error Messages

SITA997I

## Probable Cause

The thread-level security is not valid between Connect:Direct and UNIX System Services.

## Action to Take

If your installation implemented Program Access to Datasets (PADS) functionality within your security system (such as RACF, TSS, ACF2), include the Connect:Direct datasets in your Program Control List (PCL).

---

**CONDITION:**        **Connect:Direct does not initialize because of an error in the statistics log.**

---

## Possible Error Messages

<b>SSTI004I</b>	<b>SSTI005I</b>	<b>SSTI006I</b>	<b>SSTI007I</b>	<b>SSTI008I</b>
<b>SSTI009I</b>	<b>SSTI010I</b>	<b>SSTI011I</b>	<b>SSTI012I</b>	<b>SSTI013I</b>
<b>SSTI014I</b>	<b>SSTI015I</b>	<b>SSTI016I</b>	<b>SSTI017I</b>	<b>SSTI018I</b>
<b>SSTI019I</b>	<b>SSTI020I</b>	<b>SSTI021I</b>	<b>SSTI022I</b>	

SITA059I and user abend U0070 follow one of the previous error messages.

## Probable Cause and Action to Take

The cause and necessary action to take depend on the SSTIxxxI message as explained in the following sections.

### SSTI004I

File pair ESDS data set has invalid CI SIZE.

#### Probable Cause

The ESDS CI SIZE is less than 2048. The minimum acceptable CI SIZE for this data set is 2048.

#### Action to Take

Review both the short text and long text Connect:Direct messages. Delete and redefine the file pair ESDS data set and ensure a CI SIZE that is greater than or equal to 2048.

### SSTI005I

Invalid KSDS data set type in file pair.

#### Probable Cause

Review both the short text and long text Connect:Direct messages. While verifying the KSDS data set, it was found that the data set type was not KSDS.

#### Action to Take

Verify that the statistics file pair KSDS data set is correctly allocated. If no allocation is correct, delete and redefine the KSDS data set.

### SSTI006I

Invalid KSDS data set key length.



## Probable Cause

The key length of the file pair KSDS data set is invalid.

## Action to Take

Review both the short text and long text Connect:Direct messages. Refer to the platform-specific Connect:Direct installation and administration guide for the correct length.

## **SSTI007I**

Invalid file pair KSDS data set key offset.

## Probable Cause

The key offset for the KSDS data set is not 0.

## Action to Take

Review both the short text and long text Connect:Direct messages. Delete and redefine the KSDS with the correct key offset.

## **SSTI008I**

File pair has empty ESDS but non-empty KSDS.

## Probable Cause

The ESDS data set is empty, but the KSDS data set has data in it. One possible reason is that the ESDS data set was reset, but the KSDS was not.

## Action to Take

Review both the short text and long text Connect:Direct messages. The ESDS and KSDS data sets must both be empty or must both contain data. Either delete and redefine the KSDS data set, restore the ESDS data set, or specify STAT.INIT=COLD. Connect:Direct opens both data sets with reset at initialization time.

## **SSTI009I**

File pair has empty KSDS but non-empty ESDS.

## Probable Cause

The KSDS data set is empty, but the ESDS data set has data in it. One possible reason is that the KSDS data set was reset, but the ESDS was not.

## Action to Take

Review both the short text and long text Connect:Direct messages. Both KSDS and ESDS data sets must be empty or contain data. Either delete and redefine the ESDS data set, restore the KSDS data set, run batch utility DMSTBKEY to rebuild the KSDS data set, or specify STAT.INIT=COLD. Connect:Direct then opens both data sets with reset at initialization time.

## SSTI010I

Error reading the file pair KSDS control record.

### Probable Cause

While attempting to read the KSDS control record, an error code was returned.

### Action to Take

Review both the short text and long text Connect:Direct messages. Verify that the KSDS data set is correctly defined. Register 15 contains the VSAM GET return code. To reuse the data set, specify STAT.INIT=COLD in the Connect:Direct initialization parameters and restart Connect:Direct.

## SSTI011I

KSDS control record ESDS name does not match.

### Probable Cause

The KSDS control record contains the name of the matching or paired ESDS data set. When the KSDS and ESDS data set names are built by Connect:Direct at initialization time based on STAT.DSN.BASE, the ESDS data set name that the system built did not match the ESDS data set name in the KSDS control record.

### Action to Take

Review both the short text and long text Connect:Direct messages. Do one of the following:

- ❖ Run batch utility DMSTBKEY to rebuild the KSDS data set control record
- ❖ Delete and redefine both KSDS and ESDS data sets
- ❖ Specify STAT.INIT=COLD (Connect:Direct opens all file pairs with RESET.)

## SSTI012I

KSDS control record ESDS CI SIZE do not match.

### Probable Cause

The KSDS control record contains the CI SIZE of the matching or paired ESDS data set. The CI SIZE from the KSDS control record is not equal to the CI SIZE of the paired ESDS data set that is opened.

### Action to Take

Review both the short text and long text Connect:Direct messages. Verify that the statistics file pair is correctly identified with the STAT.DSN.BASE and STAT.FILE.PAIRS initialization parameters. If the CI SIZE of the ESDS file has changed, you must run the DMSTBKEY batch utility to rebuild the information in the key-sequenced cluster.

## SSTI013I

Error reading the ESDS control record.

### Probable Cause

While attempting to read the ESDS control record, an error code was returned.

### Action to Take

Review both the short text and long text Connect:Direct messages. Verify that the ESDS data set is correctly defined. Register 15 contains the VSAM GET return code. To reuse the data set, specify STAT.INIT=COLD in the Connect:Direct initialization parameters and restart Connect:Direct.

## SSTI014I

Invalid ESDS control record.

### Probable Cause

Connect:Direct read the first record in the ESDS data set; however, it was not the control record. Either the file is not a Connect:Direct statistics file, or the file was corrupted after being written by Connect:Direct.

### Action to Take

Review both the short text and long text Connect:Direct messages. Verify that the statistics file pair is correctly defined using the STAT.DSN.BASE and STAT.FILE.PAIRS initialization parameters. If the file was corrupted and it is the KSDS cluster of the pair, then the information can be rebuilt by running the DMSTBKEY batch utility for the file pair. If the file was corrupted and it is the ESDS cluster of the pair, then the statistics information in the file pair is lost. In this case, both files of the pair must be empty before Connect:Direct initializes successfully. Specify STAT.INIT=COLD in the initialization parameters to initialize successfully.

## SSTI015I

Invalid file pair sequence.

### Probable Cause

The files that comprise the statistics file pair list are not arranged in chronological order. Connect:Direct requires that all non-empty statistics file pairs be ordered chronologically based on the date and time of the oldest data in each pair.

---

**Note:** Although Connect:Direct processes the statistics file pair list in a circular or *wrap around* method, the first file pair in the list does not always contain the oldest data.

---

Connect:Direct verifies the order using the following steps:

1. Connect:Direct locates the file pair containing the oldest data.
2. From that point, Connect:Direct examines each non-empty file pair in the list. If the oldest data is not located in the first file pair, when the search reaches the last file pair in the list, it wraps to the beginning of the list. Each successive non-empty file pair must have a later date than the previous pair.

Connect:Direct always maintains statistics records in strict chronological order. If the records are not in chronological order at initialization, Connect:Direct assumes that the list or the files are incorrectly altered since Connect:Direct last wrote them.

## Action to Take

Review both the short text and long text Connect:Direct messages. Verify that the statistics file pair list is correctly defined using the STAT.DSN.BASE and STAT.FILE.PAIRS initialization parameters. If the reason for the problem is not apparent, it might be necessary to archive or copy all ESDS file pairs to preserve the current statistics data. Then delete and redefine all statistics file pair clusters.

## SSTI016I

WARNING: KSDS of file pair may be too small.

## Probable Cause

The size of the key-sequenced cluster of the file pair named is less than 10% of the size of the associated entry sequenced cluster. This condition can lead to premature filling of the key-sequenced cluster and wasted space in the entry-sequenced cluster.

## Action to Take

Review both the short text and long text Connect:Direct messages. Examine the SSTS005I message issued when the file pair fills to determine the amount of the file Connect:Direct was able to use. Set the key-sequenced cluster to 15% of the size of the entry-sequenced cluster.

## SSTI017I

WARNING: KSDS of file pair may be too large.

## Probable Cause

The size of the key-sequenced cluster of the file pair named is more than 30% of the size of the associated entry-sequenced cluster. This condition can lead to premature filling of the entry-sequenced cluster and wasted space in the key-sequenced cluster.

## Action to Take

Review both the short text and long text Connect:Direct messages. Examine the SSTS005I message issued when the file pair fills to determine the amount of the file Connect:Direct was able to use. Set the key-sequenced cluster to 15% of the size of the entry-sequenced cluster.

## SSTI018I

File pair WHERE condition found.

## Probable Cause

During statistics initialization, a warning may have been issued specifying the KSDS dataset is either too small or too large. This message contains the FILE PAIR where this situation occurred.

## Action to Take

None.

### **SSTI019I**

No active file pair found.

## Probable Cause

Statistics initialization could not determine which of the statistics file pairs was the active pair. The ESDS of each pair contains a status flag that indicates which pair is active. The active flag was not found in any of the ESDS clusters.

## Action to Take

Review both the short text and long text Connect:Direct messages. Archive or copy all ESDS file pairs to preserve the current statistics data. Then delete and redefine all statistics file pair clusters.

### **SSTI020I**

More than one file pair active.

## Probable Cause

For any given sequence of statistics file pairs, only one set can be active at a time. During Connect:Direct statistics initialization, more than one set was found to be active. This condition occurs when mixing old file pairs with current ones.

## Action to Take

Review both the short text and long text Connect:Direct messages. Empty the files by deleting and redefining the file pairs. None of the file pairs are active. Another alternative is to set STAT.INIT=COLD forcing Connect:Direct to open each set of file pairs with RESET at initialization time. If you are interested in retaining the data in the files, archive them first, then continue with one of the previous two methods.

### **SSTI021I**

More than one file pair is both not complete and not empty.

## Probable Cause

The mixing of old file pair data sets with current file pairs can cause this result. Another cause is incorrect modification of file pairs between executions of Connect:Direct.

## Action to Take

Review both the short text and long text Connect:Direct messages. Verify that the statistics file pair list is correctly defined using the STAT.DSN.BASE and STAT.FILE.PAIRS initialization parameters, and restart Connect:Direct. You can also use the STAT.INIT=COLD startup parameter.

**SSTI022I**

Invalid ESDS data set type in file pair.

**Probable Cause**

While verifying the ESDS data set, it was determined that the data set type was not ESDS.

**Action to Take**

Review both the short text and long text Connect:Direct messages. Verify that the statistics file pair ESDS data set is correctly allocated. If the data set is not correctly allocated, delete and redefine the ESDS data set

---

**CONDITION:**      **TCQ.THRESHOLD parameter not defined**

---

### **Possible Error Messages**

**SITA186I      TCQ.THRESHOLD Parameter Error**

### **Probable Cause**

If you receive these messages during initialization, the TCQ.THRESHOLD parameter is not specified.

### **Action to Take**

Specify the TCQ.THRESHOLD parameter as YES, NO or a defined percentage value in the range 0-99.

### **Data to Collect**

None





# Asset Protection Errors

This chapter lists possible asset protection errors, error messages, probable causes, actions to take, and data to collect.

---

### Determining License Violations

Asset protection verification occurs at initialization and periodically throughout the day. Possible error messages are listed in the sections that follow.

---

**CONDITION:**        **Connect:Direct initialization terminates with a message indicating the APDSN is not specified.**

---

### **Possible Error Message**

**SITA3371**

### **Probable Cause**

The required initialization parameter APDSN is not specified in the initialization parameter file.

### **Action to Take**

Update your initialization parameter file with the APDSN parameter and specify the data set name of your Asset Protection Key (APKey) file. If you do not have an APKey file, go to Customer Support on the Sterling Commerce Web site at [www.sterlingcommerce.com](http://www.sterlingcommerce.com) and request one.

### **Data to Collect**

Collect the following data:

- ❖ Display of the Connect:Direct initialization parameter
- ❖ APKey data set name

---

**CONDITION:**        **Connect:Direct initialization terminates with a message indicating an Asset Protection Failure.**

---

### **Possible Error Message**

**SITA338I**

### **Probable Cause**

An asset protection error occurred during initialization. Another asset protection message is issued with the details of the error.

### **Action to Take**

View the other message issued, and take the appropriate action for that message.

### **Data to Collect**

Collect the following data:

- ❖ Asset Protection error message

**CONDITION:**        **Connect:Direct initialization terminates with a message indicating the number of licensed copies is exceeded.**

---

### **Possible Error Message**

**SITA339I**

### **Probable Cause**

The asset protection system determined that initialization of Connect:Direct exceeds the number of servers licensed by the APKey file named in the initialization parameter file.

### **Action to Take**

View the APKey file to determine the number of servers that can be initialized. If this number needs to be increased, contact Sterling Commerce for a new APKey file that increases the number of servers.

### **Data to Collect**

Collect the following data:

- ❖ Number of servers from the APKey file
- ❖ Display of the APKey file

---

**CONDITION:**      **Connect:Direct initialization terminates with a message indicating that storage allocation failed.**

---

### **Possible Error Message**

**SITA340I      SITA341I      SITA342I**

### **Probable Cause**

The asset protection system was not able to allocate required storage and cannot continue.

### **Action to Take**

Increase the storage size defined to the Connect:Direct region. Contact Sterling Commerce if the problem persists.

### **Data to Collect**

Collect the following data:

- ❖ Connect:Direct Initialization JCL

**CONDITION:**        **Connect:Direct initialization message indicating the number of servers was exceeded but the initialization continues.**

---

### **Possible Error Message**

**SITA343I**

### **Probable Cause**

The number of servers defined by the APKey file exceeds the maximum that Connect:Direct can manage. The number of servers is set to the maximum of 32 servers.

### **Action to Take**

Contact Sterling Commerce for a corrected or new APKey file.

### **Data to Collect**

Collect the following data:

- ❖ Display of the APKey file

---

**CONDITION:**        **Connect:Direct message indicating the APKEY file was refreshed.**

---

### **Possible Error Message**

**SITA344I**

### **Probable Cause**

A MODIFY INITPARM command was issued, and, as a result, the asset protection system has processed the APDSN specified in the initialization parameter file.

### **Action to Take**

None

### **Data to Collect**

Collect the following data:

❖ None

**CONDITION:**        **Connect:Direct initialization terminates with a message indicating that Secure+ is not allowed.**

---

### **Possible Error Message**

**SITA345I**

### **Probable Cause**

The SECURE.DSN initialization parameter is specified, but the APKey file does not support Secure+.

### **Action to Take**

Correct your initialization parameter file or contact Sterling Commerce for an APKey that enables Secure+.

### **Data to Collect**

Collect the following data:

- ❖ Display of the APKey file



---

**CONDITION:**      **Connect:Direct initialization message indicating that  
MAXPROCESS was restricted by asset protection.**

---

### **Possible Error Message**

**SITA346I**

### **Probable Cause**

The APKey file indicates that the copy of Connect:Direct being used is a limited-use license and is restricting the number of concurrent Processes.

### **Action to Take**

Contact Sterling Commerce if this message is received in error.

### **Data to Collect**

Collect the following data:

- ❖ Connect:Direct initialization messages
- ❖ Display of the APKey file

**CONDITION:**        **Connect:Direct initialization terminates with a message indicating an invalid keyword.**

---

### **Possible Error Message**

**SITA3471**

### **Probable Cause**

The CONCURRENT-SESSIONS keyword in the APKey does not specify a valid value.

### **Action to Take**

Contact Sterling Commerce for a corrected APKey file.

### **Data to Collect**

Collect the following data:

- ❖ Display of the Connect:Direct initialization parameter file
- ❖ Display of the APKey file

---

**CONDITION:**        **Connect:Direct initialization terminates with a message indicating unauthorized program modifications have occurred.**

---

### **Possible Error Message**

**APSM000E**

### **Probable Cause**

The asset protection system has determined that possible tampering of the asset protection system occurred.

### **Action to Take**

Contact Sterling Commerce if you feel this message is issued incorrectly.

### **Data to Collect**

Collect the following data:

- ❖ Display of the Connect:Direct initialization parameter file
- ❖ Display of the APKey file

---

**CONDITION:**        **Connect:Direct initialization terminates with a message indicating the APKey file is not for this system.**

---

### **Possible Error Message**

**APSM001E**

### **Probable Cause**

The asset protection keyword identified in the text of the message is not valid for this Connect:Direct or is being executed on an unauthorized CPU.

The APKey file was generated with a CPUID that has an LPAR indicator that is not 00.

### **Action to Take**

Contact Sterling Commerce if you feel this message is issued incorrectly or for a corrected APKey file.

### **Data to Collect**

Collect the following data:

- ❖ Display of the Connect:Direct initialization parameter file
- ❖ Display of the APKey file

---

**CONDITION:**        **Connect:Direct initialization terminates with a message indicating the APKey is not valid for a specified number of days.**

---

### **Possible Error Message**

**APSM002E**

### **Probable Cause**

The APKey file contains an ACTIVATION-DATE keyword, and this APKey file is not valid until that date.

### **Action to Take**

Contact Sterling Commerce if you feel this message was issued in error.

### **Data to Collect**

Collect the following data:

- ❖ Display of the Connect:Direct initialization parameter file
- ❖ Display of the APKey file

**CONDITION:**        **Connect:Direct initialization terminates with a message indicating the APKey is not valid.**

---

### **Possible Error Message**

**APSM008E**

### **Probable Cause**

The digital signature in the APKey is not valid.

### **Action to Take**

Contact Sterling Commerce for a corrected APKey file.

### **Data to Collect**

Collect the following data:

- ❖ Display of the Connect:Direct initialization parameter file
- ❖ Display of the APKey file

---

**CONDITION:**        **Connect:Direct initialization terminates with a message indicating the APKey has expired.**

---

### **Possible Error Message**

**APSM009E**

### **Probable Cause**

The asset protection system determined that the APKey is expired.

### **Action to Take**

Contact Sterling Commerce for a new APKey file.

### **Data to Collect**

Collect the following data:

- ❖ Display of the Connect:Direct initialization parameter file
- ❖ Display of the APKey file

**CONDITION:**        **Connect:Direct initialization warning message that the APKey file is expired.**

---

### **Possible Error Message**

**APSM010E**

### **Probable Cause**

The asset protection system has determined that the APKey is expired.

### **Action to Take**

Contact Sterling Commerce if you feel this message was issued in error or to get a new APKey file.

### **Data to Collect**

Collect the following data:

- ❖ Display of the Connect:Direct initialization parameter file
- ❖ Display of the APKey file



---

**CONDITION:**        **Connect:Direct initialization warning message that the APKey file will expire.**

---

## **Possible Error Message**

**APSM011E**

## **Probable Cause**

The asset protection system has determined the APKey expires within 30 days. This message is issued three times a day starting 30 days before the expiration date specified in the APKey file.

## **Action to Take**

Contact Sterling Commerce if you feel this message is issued incorrectly or to get a new APKey file.

## **Data to Collect**

Collect the following data:

- ❖ Display of the Connect:Direct initialization parameter file
- ❖ Display of the APKey file

---

**CONDITION:**        **Connect:Direct message indicating the APKey file is not valid.**

---

### **Possible Error Message**

**APSM015E**

### **Probable Cause**

While processing a refresh of the APKey file from a MODIFY INITPARMS command, the asset protection system determined the AP keyword or the APKey file is not valid. The previous AP settings are retained, but the APKey file is not refreshed. Connect:Direct continues to function.

### **Action to Take**

Contact Sterling Commerce if you feel this message was issued in error.

### **Data to Collect**

Collect the following data:

- ❖ Display of the Connect:Direct initialization parameter file
- ❖ Display of the APKey file

---

**CONDITION:**        **Connect:Direct initialization warning message that indicates initialization used an emergency key.**

---

### **Possible Error Message**

**APSM998I**

### **Probable Cause**

The APKey file contains an EMERGENCY-KEY keyword. The emergency key expires within a very short time.

### **Action to Take**

Contact Sterling Commerce if you feel this message was issued in error or if you need to get a new APKey file.

### **Data to Collect**

Collect the following data:

- ❖ Display of the Connect:Direct initialization parameter file
- ❖ Display of the APKey file



---

# Signon and IUI/API Errors

This chapter provides information that can help you to determine the cause of signon and IUI/API errors.

---

## Determining Signon Errors

Signon errors keep you from accessing Connect:Direct. IUI/API problems prevent you from successfully submitting a Process or executing a command.

This chapter describes the following types of signon and IUI/API errors:

- ❖ ISPF/PDF or TSS/PFD signon failures can be caused by a variety of problems. Errors signing onto the IUI through the ISPF or TSS interface can include VTAM problems, security problems, or ISPF or TSS problems. Refer to Chapter 7, *Security Errors* for a description of common security errors.
- ❖ IUI/API Connect:Direct session failures occur when the IUI/API cannot establish a session with the DTF. A session failure usually means you will be unable to sign on to Connect:Direct.
- ❖ SELECT command errors occur while issuing SELECT STATISTICS, SELECT PROCESS, SELECT NETMAP, SELECT USER, SELECT TYPE, and SELECT TASK commands from the IUI, batch, or operator interface.

---

**Note:** You can diagnose most IUI/API problems by running an API-to-DTF session trace. See Chapter 14, *Connect:Direct Traces* for information on how to run this trace.

---

---

**CONDITION:**        **Signon to the IUI is denied, with message “Error during ACB open.”**

---

## Possible Error Messages

**SVTB002I**

## Probable Cause

The interactive applid that Connect:Direct is trying to use for signon is not active, is in an unacceptable state, or is not correctly defined to VTAM.

## Action to Take

Review both the short text and long text Connect:Direct messages. Allocate NDMCMDS to display error messages to your terminal. NDMCMDS shows all actual Connect:Direct commands issued to the DTF, including resolution of symbolics. It can be particularly helpful to debug Connect:Direct commands through the IUI or through DMBATCH if you are having signon problems, syntax errors, and so forth.

For Connect:Direct OS/390, type the following on your command line.

```
TSO ALLOC FI(NDMCMDS) DA(*)
```

For Connect:Direct for VM/ESA, type the following on your command line.

```
CMS FILEDEF NDMCMDS T
```

Retry the signon. The display echoed to your screen shows you the applid receiving the open failure. Use your network management software to display that applid and ensure its state is **ACTIV** or **CONCT**. If it is not, use a VTAM command to change it between inactive and active again.

If the applid is unknown to VTAM, check your network map to ensure the applid is named correctly.

## Data to Collect

Collect the following data:

- ❖ NDMCMDS output
- ❖ Applid status display
- ❖ Applid definitions
- ❖ Network map

---

**CONDITION:**        **Signon to the IUI is denied, with no error messages.**

---

### **Possible Error Messages**

None

### **Probable Cause**

Your TSO or TSS profile specifies the NOWTPMSG option, which inhibits some error output from being displayed to the terminal.

### **Action to Take**

Review both the short text and long text Connect:Direct messages. For OS/390, change to the WTPMSG option by typing **TSO PROF WTPMSG**. With the WTPMSG option, error messages are displayed at the terminal. Retry the operation (sign on).

### **Data to Collect**

None

---

**CONDITION:        Signon is denied, because Connect:Direct is not active.**

---

## Possible Error Messages

**SVTB004I    SCIA011I**

## Probable Cause

The Connect:Direct you are attempting to sign on to is not active.

## Action to Take

Review both the short text and long text Connect:Direct messages. Ensure that Connect:Direct has completed initialization before attempting a signon. Allocate NDMCMDS to display additional information about the session failure. NDMCMDS shows all actual Connect:Direct commands issued to the DTF, including resolution of symbolics. It can be particularly helpful to debug Connect:Direct commands through the IUI or through DMBATCH if you are having signon problems, syntax errors, and so forth.

For OS/390 check to see that the network map is specified correctly on the ISPF menu and that the network map is correctly loaded, as described in the installation guide for your product.

Try to sign on through the DMBATCH interface to isolate the problem.

## Data to Collect

Collect the following data:

- ❖ NDMCMDS output
- ❖ Network map
- ❖ Connect:Direct initialization parameters
- ❖ For OS/390 the ISR@PRIM panel

## Possible Error Messages

**STAA004I**

## Probable Cause

The number of interactive users on Connect:Direct has reached the limit set in the MAXUSERS parameter.

## Action to Take

Review both the short text and long text Connect:Direct messages. Check the MAXUSERS parameter in the Connect:Direct initialization parameters data set. If it is commented out, the default is six users. Report this error to your Connect:Direct administrator, and determine whether you need to increase the value of this parameter.



## Data to Collect

Collect the following data:

- ❖ Connect:Direct initialization parameters

---

**CONDITION:**        **The SELECT command is issued successfully and completes with a successful return code and message, but no output is produced.**

---

### Possible Error Messages

SAFF000I	SAFF014I	SAFK000I	SAFL000I	SAFL010I	SCBB000I
SCBL000I	SCBO000I	SCBP000I	SCBQ000I	SCBX000I	SOPA000I
SOPA011I	SOPE000I	SOPS001I			

### Probable Cause

It is likely that Connect:Direct is having trouble allocating the temporary data set that contains the output from the SELECT command. For Connect:Direct VM/ESA, the output is written to a file on your A-disk named NDMAPI LISTING.

### Action to Take

Review both the short text and long text Connect:Direct messages. For Connect:Direct OS/390 specify a UNIT and VOLSER for the temporary data set, and SPACE information. You can specify UNIT and VOLSER on the SIGNON DEFAULTS panel of the IUI or use the TEMPDSN parameter on your signon command for batch. Note that a UNIT type of VIO is not acceptable.

For Connect:Direct VM/ESA, ensure your A-disk has enough space for the results of the SELECT command.

### Data to Collect

Collect the following data:

- ❖ List of the SELECT commands that produce output and those not producing output
- ❖ Any error messages

---

**CONDITION:**        **Select commands return with no output and a message indicating no output was available from the command.**

---

## Possible Error Messages

SOPA010I    SOPB012I

## Probable Cause

For the SELECT PROCESS and SELECT STATISTICS commands, it is likely that the userid issuing the command is defined as a *general user* by the stage 2 security exit, indicating that the user is only allowed to see the command output for Processes submitted by that same userid.

## Action to Take

Review both the short text and long text Connect:Direct messages. Check to see that the userid is defined with the ability to select Process/statistics for Processes not submitted by that userid.

## Data to Collect

Collect the following data:

- ❖ Authorization for the userid
- ❖ Statistics file

**CONDITION:**       **Signon failed with the message “SRF must signon to the LOCAL node only.”**

---

## Possible Error Messages

**SCBA501I**

## Probable Cause

An SRF from a remote location attempted to logon to a node other than the defined local node in the SRF Network Map data set. This error only occurs within the Connect:Direct OS/390 Sysplex Requester Facility from a remote signon.

## Action to Take

Review both the short text and long text Connect:Direct messages. Attempt the SIGNON command again by specifying the local node as the destination node.

## Data to Collect

Collect the following data:

- ❖ Output from NDMCMDS
- ❖ Copy of the SRF Network Map

---

**CONDITION:**        **Signon failed with a message “Signon failed. The DTF may be down or inactive.”**

---

## **Possible Error Messages**

**SCBA502I**

### **Probable Cause**

A SIGNON command was attempted for an SRF from a remote location while the DTF is down or initializing. ESF signon is not possible in this situation.

### **Action to Take**

Review both the short text and long text Connect:Direct messages. Attempt the SIGNON command again after the DTF is fully initialized.

### **Data to Collect**

None

---

**CONDITION:**        **Signon failed with a message “Signon failed. No more SRF signons available.”**

---

## **Possible Error Messages**

**SCBA503I**

## **Probable Cause**

An SRF attempted to signon to Connect:Direct. This attempt exceeded the allowable number of concurrent SRFs.

## **Action to Take**

Review both the short text and long text Connect:Direct messages. Attempt the SIGNON command again later. If this problem continues, contact Sterling Commerce to inquire about increasing the number of licensed SRFs.

## **Data to Collect**

None

---

**CONDITION:**      **Multi-session signon failed for a remote SRF.**

---

### **Possible Error Messages**

SCIA002I

### **Probable Cause**

A multi-signon attempt was made from a remote SRF. Multi-session signons are not possible from a remote SRF.

### **Action to Take**

Do not attempt a multi-signon from a remote SRF.

### **Data to Collect**

None





# Security Errors

Security errors can show up at signon, at Process start, or at any step of a Process. In general, a return code of 8 means that the error occurred on the PNODE, and a return code of C means the error occurred on the SNODE. This chapter tells you how to determine the cause of security errors.

---

### Determining Security Errors

Many Connect:Direct security-related messages begin with the prefix RACF. This fact does not mean that RACF was necessarily involved with the failure. It is merely a naming convention for Connect:Direct message identifiers.

Often, it is helpful to run a security trace to determine exactly where and why a security failure occurred. See Chapter 14, *Connect:Direct Traces* in this manual for information on security traces.

The following pages list possible security errors, error messages, probable causes, actions to take, and data to collect.

---

**CONDITION:** At signon, from either batch or the IUI, you receive the Connect:Direct message RACF097I, “The Stage 1 Signon exit has failed.” The signon is denied.

---

## Possible Error Messages

### RACF097I

#### Probable Cause

The Stage 1 Signon exit, DMCXSIGN, cannot be found.

In the Connect:Direct OS/390 IUI, verify that DMCXSIGN is in the LINKLIST or in ISPLLIB of your signon CLIST and not in a STEPLIB.

For Connect:Direct VM/ESA, verify that the FILEDEF for the LOADLIB includes DMCXSIGN. You must specify the LOADLIB in a GLOBAL for your userid in order for Connect:Direct to find the Stage 1 Signon Exit.

#### Action to Take

Review both the short text and long text Connect:Direct messages. If you are receiving the message during signon to the IUI, run a batch job after verifying that DMCXSIGN is available to the job (through STEPLIBs, the linklist, or globals). For either batch or interactive signon, allocate SECURITY. See Chapter 14, *Connect:Direct Traces* for instructions. You will be able to view the progression of BLDLs, along with output showing where Connect:Direct looked for DMCXSIGN and the results from the search.

#### Data to Collect

Collect the following data:

- ❖ Output written to the SECURITY DD when you allocated SECURITY as described in Chapter 14, *Connect:Direct Traces*.

---

**CONDITION:**      **You are unable to successfully link to a minidisk through Connect:Direct VM/ESA.**

---

### Possible Error Messages

SDMK020E	SDMK022E	SDMK052E	SDMK053E	SDMK070E
SDMK071E	SDMK073E	SDMK078E	SDMK101E	SDMK102E
SDMK103E	SDMK104E	SDMK105E	SDMK106E	SDMK107E
SDMK108E	SDMK109E	SDMK110E	SDMK111E	SDMK112E
SDMK113E	SDMK114E	SDMK115E	SDMK116E	SDMK117E
SDMK118E	SDMK119E	SDMK137E	SDMK139E	SDMK153E
SDMK199E	SMDK298E	SDMK331E	*SDMKxxxE	*SHCPxxxE
*SRPIxxxE				

### Probable Cause

The security subsystem on the VM/ESA node has refused the request to link to the disk. The SDMKG-prefixed messages are the Connect:Direct translation of CP messages. For more information, type **Help** and the message ID. For example, type **HELP DMK020E** or **HELP HCP020E** from native CMS.

### Action to Take

Review both the short text and long text Connect:Direct messages. Check your link mode in your Process. If you are using R, for example, try RR, which does not deny your link if another user is linked READ to the disk. Ensure that the userid you are using to make the link (the SNODEID, the ID on the PNODE, or the SECURITY ID in the Connect:Direct VM/ESA authorization file) is given authority to make the link.

If all seems correct, run a security trace on the Connect:Direct VM/ESA node to see that the userid and link password are correct. See Chapter 14, *Connect:Direct Traces* for information on security traces.

### Data to Collect

Collect the following data:

- ❖ Output from the security trace
- ❖ A copy of the LINK parameter from your Process

---

**CONDITION:**      **You attempt to perform a Connect:Direct function, and receive a message that says you are not authorized to perform that function.**

---

### Possible Error Messages

SCBB001I	SCBC030I	SCBD001I	SCBE001I	SCBF001I	SCBF063I
SCBF064I	SCBG001I	SCBH001I	SCBI001I	SCBJ001I	SCBK005I
SCBL001I	SCBN001I	SCBO001I	SCBP001I	SCBR002I	SCBS001I
SCBT005I	SCBU003I	SCBV001I	SCBW001I	SCBX001I	SCBY001I
SCPA008I	SFIA002I	SFIA003I	SRJA014I	SRTA008I	SSUB100I

### Probable Cause

If you are running a Stage 2 security exit, your userid is defined using an authorization bit mask that does not include the function you are attempting. A security trace will show you the general category of Connect:Direct user assigned to your userid (administrator, operator, or general user). See Chapter 14, *Connect:Direct Traces* for more information about how to initiate a security trace. If you are using the Connect:Direct authorization file, the functional authority of your userid does not include the function you are trying to perform.

### Action to Take

Review both the short text and long text Connect:Direct messages. Have the Connect:Direct administrator at your site ensure that your userid has the authority necessary to perform the function, either by updating your userid record in the Connect:Direct authorization file or by assigning the authority within the Stage 2 security exit.

### Data to Collect

Collect the following data:

- ❖ Output from a security trace showing the validation of your authority to perform the Connect:Direct function

---

**CONDITION:**      **On a COPY step, you are denied access to a data set or file.**

---

## Possible Error Messages

RACF095I

### Probable Cause

The security subsystem either on your node (RC=8) or the remote node (RC=C) has denied your userid access to the data set.

### Action to Take

Review both the short text and long text Connect:Direct messages. Ensure that your userid has the correct access to the data set. If you continue getting this message, run a security trace. See Chapter 14, *Connect:Direct Traces* for more information about how to initiate a security trace. It might be necessary to use a PNODEID or SNODEID statement to send a valid userid and password to the security system.

### Data to Collect

Collect the following data:

- ❖ Output from a security trace

**CONDITION:**       **When signing on to Connect:Direct or submitting a Process to another node, you receive message SAFA002I, “The user record was not found in the Authorization Data Set.”**

---

## Possible Error Messages

**SAFA002I**

## Probable Cause

If you are using the Connect:Direct authorization file for security, it is important to remember that the key to that file is a combination of userid and node name. For example, if you are signed on to node CDA with userid USERA and transmitting to node CDB (not using an SNODEID override), the authorization file on CDB must have an entry for the userid USERA and node CDA.

## Action to Take

Review both the short text and long text Connect:Direct messages. Check the appropriate Connect:Direct authorization file and verify that the correct userid/node combination is specified. User records in the Connect:Direct authorization file can be added or modified with the Insert User or Update User commands.

## Data to Collect

Collect the following data:

- ❖ Output from a security trace. See Chapter 14, *Connect:Direct Traces*.

---

# Connect:Direct DTF Session-Establishment Errors

Connect:Direct DTF session-establishment errors prevent a successful connection between two Connect:Direct systems. This chapter explains the most common causes of DTF session-establishment errors, actions to take, and the types of data you need to collect to troubleshoot the error.

---

**CONDITION:**        **An attempt to establish a session with another Connect:Direct session fails. (See the following four possible causes and associated actions.)**

---

## Possible Error Messages

**SVTM026I    SVTM045I    SVTM053I    SVTM104I**

## Probable Cause

The links that connect the two Connect:Direct systems are not active, or an error has occurred on the links.

## Action to Take

Review both the short text and long text Connect:Direct messages. Use your network management software to determine the status of the links used for system-to-system communication. Reactivate the links.

## Data to Collect

Collect the following data:

- ❖ If you are unable to determine the problem, run a session manager, RPLOUT, and separate-trace-per-task trace. For information on these traces, refer to Chapter 14, *Connect:Direct Traces*.

————— OR —————

## Possible Error Messages

**SVTM026I**

## Probable Cause

The cross-domain resource definition for the remote Connect:Direct system is not active.

## Action to Take

Review both the short text and long text Connect:Direct messages. Use your network management software to determine the status of the Connect:Direct cross-domain manager and cross-domain resource definitions used in communicating with other Connect:Direct locations. Reactivate the cross-domain resource manager or cross-domain resources.

## Data to Collect

Collect the following data:

- ❖ If you are unable to determine the problem, run a session manager, RPLOUT, and separate-trace-per-task trace. For information on these traces, refer to Chapter 14, *Connect:Direct Traces*.

————— OR —————



## Possible Error Messages

SNAS0801 SVTM026I

### Probable Cause

The VTAM applid for the remote Connect:Direct system is not active.

### Action to Take

Review both the short text and long text Connect:Direct messages. Use your network management software to determine the status of the applid for the remote Connect:Direct system. Ensure the remote Connect:Direct has initialized. Reactivate the VTAM applid, or initialize the remote Connect:Direct.

### Data to Collect

Collect the following data:

- ❖ If you are unable to determine the problem, run a session manager, RPLOUT, and separate-trace-per-task trace. (For information on these traces, refer to Chapter 14, *Connect:Direct Traces*.)

————— OR —————

## Possible Error Messages

SCCS028I | STAA005I

### Probable Cause

The maximum number of secondary sessions is reached on the secondary Connect:Direct system.

### Action to Take

Review both the short text and long text Connect:Direct messages. Determine the number of active VTAM sessions for the secondary location. Use your network management software to issue **D NET,ID=applid,E** (VTAM applid) at the secondary location site. Ensure that the maximum number of secondary sessions is sufficient for your requirements.

### Data to Collect

Collect the following data:

- ❖ If you are unable to determine the problem, run a session manager, RPLOUT, and separate-trace-per-task trace. For information on these traces, refer to Chapter 14, *Connect:Direct Traces*.



---

# Connect:Direct DTF Out-of-Storage Abends

DTF out-of-storage abends occur during heavy Connect:Direct activity or during phases when the DTF has run for a long period of time. This chapter explains the most common causes of DTF out-of-storage abends, actions to take, and the types of data to collect.

---

**CONDITION:**        **An out-of-storage abend occurs in the DTF. (See the following two possible causes and associated actions.)**

---

### Possible Error Messages

user abend U0500      user abend U0501      system abend SxOA      system abend Sx78

### Probable Cause

If this condition occurs only during heavy Connect:Direct activity, you may need to modify the initialization parameters or the DTF REGION parameter.

### Action to Take

Review both the short text and long text Connect:Direct messages. Limit the number of Processes that can run at one time using the MAXPRIMARY, MAXSECONDARY, and MAXPROCESS initialization parameters. Also, examine the MAXSTGIO initialization parameter to determine if it can be decreased. The REGION size in the DTF JCL may need to be increased to allow more concurrent Processes.

### Data to Collect

Collect the following data:

- ❖ Try to determine which subpool is growing
- ❖ Dump taken after controlled tests when all DTF activity has ended
- ❖ The Connect:Direct log
- ❖ Connect:Direct initialization parameters
- ❖ Connect:Direct STC (started task) JCL
- ❖ Source for any user exits

\_\_\_\_\_ OR \_\_\_\_\_

### Probable Cause

If this condition appears to be a "storage creep" and occurs after the DTF is active for a long time (not necessarily running many Processes immediately), you can take several actions.

### Action to Take

- ❖ Examine all RUNTASK programs and ensure that for every file opened, a CLOSE and a FREEPOOL is also done.
- ❖ Examine any user exits for GETMAIN macros and verify that FREEMAIN macros are issued for each of those areas.
- ❖ Examine any RUNTASK programs for GETMAIN macros and ensure FREEMAIN macros are issued for each area.

- ❖ Try to pinpoint the type of Processes or other DTF activity that causes the problem:
  - ◆ Does this occur only during a COPY?
  - ◆ Does this occur when a specific Process is run? What does the Process do?
  - ◆ Does this occur when a certain command is issued? What is the command?
- ❖ If you cannot determine a specific Process, command, or other activity that causes the storage creep, run a typical batch of processes/commands that runs when the abend occurs. Before the out-of-storage abend occurs, go to the ADMIN MD panel and QUIESCE Connect:Direct. For example, if the abend usually occurs after 10 hours of activity, quiesce after about eight hours.
- ❖ If you did determine that a certain Process or command causes the problem, submit that Process or issue the command several times (the number of times depends on how long it takes before you get to the abend). For example, if it occurs after the Process runs 100 times, run it 90 times in your tests. Get a dump of the DTF address space after all DTF activity is finished.

## Data to Collect

Collect the following data:

- ❖ Dump taken after controlled tests after all DTF activity ended
- ❖ The Connect:Direct log
- ❖ Connect:Direct initialization parameters
- ❖ Connect:Direct STC JCL
- ❖ Source for any user exits



---

# Allocation and Open Errors

Allocation and open errors involve the source or destination files. This chapter describes errors in which the allocation or opening of a file fails, and the action to take and types of data you need to collect to troubleshoot the error.

---

**CONDITION:**      **A failure occurs while trying to allocate a user file.**

---

## Possible Error Messages

SDAA001I   SDAA004I   SDAA005I   SDAA048I

## Probable Cause

Connect:Direct received an error while doing the allocation of a file or data set.

## Action to Take

Review both the short text and long text Connect:Direct messages. Check the SYSLOG, console, or Connect:Direct statistics for the text of the SDAA004I and SDAB005I messages. The SDAA004I message contains the allocation parameters used by Connect:Direct. If an error exists, the ERR=*nnnn* field of the SDAB005I message contains non-zeroes, and error text follows. Use the Connect:Direct message facility to look up the error, which has a format of SDE*nnnn*I, where *nnnn* is the number in the ERR field. The operating system dynamic allocation routine returns the ERR value.

---

**Note:** Connect:Direct initialization parameters (ALLOC.CODES and ALLOC.RETRIES) determine which allocation errors, if any, cause a Process that fails on an allocation error to be retried.

---

## Data to Collect

Collect the following data:

- ❖ Connect:Direct allocation string (found in the WTO records in the statistics file)
- ❖ the Connect:Direct Process involved
- ❖ SDAA004I message output
- ❖ SDAB005I message output



---

**CONDITION:**        **Connect:Direct for VM/ESA console receives message 4228I  
open error X'76'.**

---

## Possible Error Messages

4228I    open error X'76'

## Probable Cause

If you receive these messages during initialization and the files that receive the open errors are Connect:Direct files, it is likely that the last termination of Connect:Direct VM/ESA was abnormal and Connect:Direct was unable to properly close the files before it terminated. If you receive this message at user signon, you are attempting to open the network map file that is already open.

## Action to Take

Review both the short text and long text Connect:Direct messages. These files verified automatically and opened, usually without user intervention. If they do not automatically open, then delete and redefine the files using the AMSERVs and LOAD EXECs provided with Connect:Direct VM/ESA. Receiving this message at user signon is normal and does not cause any problems.

## Data to Collect

None

**CONDITION:**        **The TCQ file has reached the defined threshold value.**

---

### **Possible Error Messages**

**SPQL003I**    **TCQ file is now below the defined threshold of &VAR.**

### **Probable Cause**

The number of VSAM file CIs used has reached the defined threshold.

### **Action to Take**

Reduce the number of Processes in the TCQ, or increase the size of the TCQ. Refer to the *Global Initialization Parameters* section of the *Connect:Direct OS/390 Administration Guide* for more information.

### **Data to Collect**

None

# Transmission Errors

Transmission errors include consistency problems within communication components that can occur during Process execution. The errors can occur within communication components such as VTAM, NETEX™, IBM Network Control Program (NCP), or links.

This chapter lists possible transmission errors, error messages, probable causes, actions to take, and data to collect to troubleshoot an error.

---

**CONDITION:**        **An error occurs during the Process execution initiation. (See the following two possible causes and associated actions.)**

---

### Possible Error Messages

**SVTM041I (SNASYNC1: Session abnormally terminated)**

### Probable Cause

The session or link was lost before Process execution began.

### Action to Take

Review both the short text and long text Connect:Direct messages. Use your network management software to determine the status of the link, cross-domain definitions, and applids used in the system-to-system communication. Activate the link, cross-domain definitions, or applids as required, and restart the Process.

### Data to Collect

None

————— OR —————

### Possible Error Messages

**SVTM053I (Session acquire failure)**

### Probable Cause

A protocol error occurred within the Connect:Direct system.

### Action to Take

Review both the short text and long text Connect:Direct messages. If the problem persists, use the VTAM buffer and I/O trace facility to gather problem determination data. Also, request a session manager trace and an RPL trace.

### Data to Collect

Collect the following data:

- ❖ Output from session manager
- ❖ Output from RPL traces

---

**CONDITION:**      **An unrecoverable error (send or receive error) occurs within the system-to-system session while a Process executes. (See the following three possible causes and associated actions.)**

---

## Possible Error Messages

**SVTM045I**

### Probable Cause

An I/O error within the primary or secondary node causes Connect:Direct to send a negative response to the other location.

### Action to Take

Review both the short text and long text Connect:Direct messages. Accompanying Connect:Direct messages indicate the type of error that caused the send or receive session to fail. Check your network management software for VTAM sense codes, then find the reason the sense code was issued. Correct the problem if possible and retry the Process.

In some cases, you need a VTAM buffer or an I/O trace of the error. You may need a backup copy of the file if a file I/O error caused send or receive error. If the error is temporary, retrying the Process might clear up the difficulty.

### Data to Collect

Collect the following data:

❖ Output from the VTAM buffer or I/O trace

————— OR —————

## Possible Error Messages

**SVTB020I, followed by a U4095 abend**

### Probable Cause

A Connect:Direct system shuts down with either the IMMEDIATE or FORCE parameter specified on the STOP CD command.

### Action to Take

Review both the short text and long text Connect:Direct messages. Restart the Connect:Direct system

### Data to Collect

None

————— OR —————

## Possible Error Messages

<b>SVTM042I</b>	<b>SVTM043I</b>	<b>SVTM044I</b>	<b>SVTM045I</b>	<b>SVTM046I</b>
<b>SVTM047I</b>	<b>SVTM048I</b>	<b>SVTM049I</b>	<b>VTAM sense code 0870</b>	
			<b>VTAM sense code 800A</b>	

In some cases, you need a VTAM buffer or an I/O trace of the error. You may need a backup copy of the file if a file I/O error caused a send or receive error. If the error is temporary, retrying the Process might clear up the difficulty.

## Probable Cause

An error occurs within one of the communication components (VTAM, NCP, or link).

## Action to Take

Review both the short text and long text Connect:Direct messages. The communication component containing the error issues error messages. Various VTAM and NCP definitions are incompatible with Connect:Direct operations. Refer to the *Selecting RU Sizes* section in the appropriate Connect:Direct installation guide for more information.

## Data to Collect

Collect the following data:

- ❖ VTAM definitions
- ❖ NCP definitions

---

# Operator Interface Errors

Operator interface errors occur while you are using the operator interface to issue commands to Connect:Direct. You can find more information on the operator interface in the *Connect:Direct Console Operator's Guide*.

This chapter lists possible operator interface errors, error messages, possible causes, actions to take, and data to collect to troubleshoot an error.

**CONDITION:**        **When issuing operator interface commands, you get a “task busy” message.**

---

## Possible Error Messages

**IEE342I Modify rejected - task busy**

## Probable Cause

An error in the MCS.SIGNON parameter in the Connect:Direct initialization parameters.

## Action to Take

Ensure that the MCS.SIGNON parameter reflects a valid userid-password combination with Connect:Direct operator authority and that the network map is correctly specified on the MCS.SIGNON parameter. Remove comments from this parameter.

## Data to Collect

Collect the following data:

- ❖ Connect:Direct initialization parameters
- ❖ SYSLOG output



---

**CONDITION:**        **When issuing operator interface commands, you get “user not authorized” messages.**

---

### Possible Error Messages

SCBB001I	SCBC030I	SCBD001I	SCBE001I	SCBF001I	SCBF063I
SCBF064I	SCBG001I	SCBH001I	SCBI001I	SCBJ001I	SCBK005I
SCBL001I	SCBN001I	SCBO001I	SCBP001I	SCBR002I	SCBS001I
SCBT005I	SCBU003I	SCBV001I	SCBW001I	SCBX001I	SCBY001I
SCPA008I	SFIA002I	SFIA003I	SRJA014I	SRTA008I	SSUB100I

### Probable Cause

The userid attempting to issue the operator interface commands is not authorized to issue them.

### Action to Take

Review both the short text and long text Connect:Direct messages. Check the userid specified in the MCS.SIGNON parameter of the Connect:Direct initialization parameters file. Determine whether that userid has the authority to issue the command. If you believe it does, run a security trace to determine why the user cannot issue the command.

See Chapter 14, *Connect:Direct Traces* for information on how to run the trace.

### Data to Collect

Collect the following data:

- ❖ Connect:Direct initialization parameters
- ❖ Security trace



# Part III

---

## Diagnostic Tools



A Connect:Direct abend can occur when a system failure or system error exists or when the FORCE parameter is used with the STOP CD command.

When an abend is reported, Customer Support searches the problem tracking database for any similar problems. Often the abend is a known bug or a common error, and a solution is readily available. Otherwise, they need a full SVC dump for diagnosing abends.

---

### Information Requested by Customer Support

When you call to report an abend, Sterling Commerce Customer Support attempts to determine the type of abend and locate the module in which the abend occurred. If support personnel cannot locate a reference to the abend, they might request the following to diagnose the abend:

- ❖ Send a complete dump, not a snap dump.
- ❖ If the abend is caused by a specific Connect:Direct Process, support personnel may request a copy of the Process and the statistics associated with that Process. If the Process has symbolics, include the symbolic substitution data. Also, ensure that the statistics records include WTO records.

---

**Note:** Include statistics from both Connect:Direct nodes.

---

If the abend occurred while executing a Process that has previously executed successfully, determine what changes were made, either in the operating system or within Connect:Direct, since executing and do the following:

- ❖ Send console logs for both Connect:Direct nodes.
- ❖ Note whether the abend caused either Connect:Direct node to terminate.
- ❖ If the abend can be recreated, provide details.
- ❖ Send a copy of the system log and network error log for both operating systems, which can indicate any unusual situations occurring with the operating system or network at the time of the abend.

---

**Note:** A system log is always required when analyzing an abend. It is preferable to review the log for both systems; however, it is essential for the system reporting the abend. When one of the nodes is not an OS/390, VM/ESA, or VSE/ESA, check the output files for Connect:Direct.

---

- ❖ Send RPLERRCK DD output to review I/O errors and other information.
- ❖ Send ESTAE DD output to review abend conditions and some special I/O conditions.

If several abends occur simultaneously, send the dump from the first abend. Usually, subsequent abends result from the original abend.

When sending a dump on tape, send the JCL that created the tape. DSN, VOLSER, LABEL, and DCB attributes are needed to facilitate tape unloading. If available, send a printout of the tape management product display of the VOLSER.

---

**Note:** If you are sending a tape with more than one file, ensure that the JCL that created the tape references the correct file in the LABEL= parameter. This reference ensures that a previous file is not inadvertently overlaid.

---

You can send dumps to Sterling Commerce on tape or over the Internet. To send dumps over the Internet, contact Sterling Commerce Customer Support for instructions.

The remainder of the chapter discusses the various dumps that might be requested by Sterling Commerce Customer Support for problem determination and resolution. Also provided are instructions for producing these dumps. Dumps described in this section include:

- ❖ Connect:Direct Data Transmission Facility dumps, which include SYSMDUMP, CDSVCDMP, and SYSABEND dumps, VM Group Control Services (GCS) address space dumps, and VSE PARTDUMP dumps.
- ❖ Connect:Direct Interactive User Interface dumps, which include OS/390 Time Sharing Option (TSO) address space dumps and VM Conversational Monitor System (CMS) address space dumps.
- ❖ SVC dumps
- ❖ Batch dumps
- ❖ IBM Virtual Storage Access Method file dumps
- ❖ DTF Snap Dump Facility

---

## Connect:Direct Data Transmission Facility (DTF) Dumps

A Connect:Direct Data Transmission Facility (DTF) dump is generated when an abend occurs. The dump contains the contents of the Connect:Direct address space, which is copied into one or more of the data sets that you specify by ddname in the DTF JCL (CDSVCDMP, SYSABEND, or SYSMDUMP).

The DTF dump is also referred to as a GCS dump for Connect:Direct for VM and PARTDUMP for Connect:Direct for VSE/ESA.

The following sections describe how to create a dump of the DTF for each Connect:Direct environment.

### Connect:Direct OS/390 DTF Dumps (CDSVCDMP, SYSMDUMP, and SYSABEND)

When an abend occurs, Connect:Direct produces an SVC dump with all of the information for the address space, regardless of whether the abend occurred in the main task or a User Exit subtask. Unless otherwise specified in the JCL, the dump is written to the standard SVC dump data set, SYS1.DUMPxx. You can specify an alternate data set by using the CDSVCDMP DD statement in the JCL.

You can write debug information to the ESTAE DD by setting the debug trace bit in the initialization parameters to 00000001. For more information, see the ESTAE initialization parameter definition in the *Connect:Direct OS/390 Installation Guide*.

---

**Note:** If the system attempts to take an SVC dump and fails with: \*ERROR\* Unable to take an SVC dump; reason: 0B, the dump analysis and elimination (DAE) component of the operating system found an earlier dump of this problem already exists.

---

You can turn off the SVC dump by modifying your JCL. For more information, see the *Turning Off the SVC Dump* section below.

## Capturing Multiple DTF SVC Dumps Using CDSVCDMP

You can use CDSVCDMP to capture multiple DTF SVC dumps. A dump is created for each abend and written to a separate data set. You can specify whether the dumps are written to the SYS1.DUMPxx data sets or to unique user-specified data sets.

To write dumps to user-specified data sets, you must create a data set name for each dump that can occur. The first data set name must end with .SYSMDP00. Each additional data set name must end with .SYSMDPnn, where nn is a consecutive number up to a value of 99. For example, if you want to create enough data sets to write five dumps, create five data set names beginning with xxxx.yyyy.SYSMDP00 and ending with xxxx.yyyy.SYSMDP04.

You must define the data sets with the same attributes as your SYS1.DUMPxx data sets. The data sets must be preallocated and on the same disk volume.

To record multiple SVC dumps, set the JCL statement for CDSVCDMP as follows.

```
//CDSVCDMP DD DSN=XXXX.YYYY.SYSMDP00,DISP=SHR
```

The first dump is written to the .SYSMDP00 data set. When an additional abend occurs, a dump is written to the next data set, .SYSMDP01. Each additional abend creates a dump to the next .SYSMDPnn data set as long as abends occur and enough .SYSMDPnn data sets are available. If an abend occurs and all data sets are full, the dump is not created and a message is issued stating that all .SYSMDPnn data sets are full.

You do not have to empty or reset these dump data sets. When the DTF is initialized, and you are using the .SYSMDPnn data sets, Connect:Direct writes over the existing data in the data sets. If you want to save the existing data, save the data sets using a different data set name before you restart Connect:Direct.

## Turning Off the SVC Dump

If you want to turn off the SVC dump, place the following statement in your DTF JCL.

```
//CDSVCDMP DD DUMMY
```

## Changing Dump Options

For the SDATA parameter specify SDATA=(ALLSDATA). If SDATA=(ALLSDATA) is not an acceptable default for your system, ensure that the PARMLIB member corresponding to the ddname in the JCL for the DTF specifies, at a minimum, the following.

```
SDATA=(IO, SWA, CB, ENQ, TRT, ERR, DM)
```

For the PDATA parameter for IEADMPxx and IEAABDxx, specify PDATA=(ALLPDATA).

---

**Note:** PDATA is not an option for member IEADMRxx.

---

If you cannot specify ALLPDATA, at a minimum, include PSW, REGS, SA, JPA, SPLS, and SUBTASKS. Refer to the IBM documentation.

If you are unable to change the PARMLIB member, issue an operator command to change the dump options.

The following steps guide you in issuing operator commands to change dump options:

1. Issue the command DISPLAY DUMP,OPTIONS to list the dump options currently in effect.
2. Issue the command CHNGDUMP SET to change the options.
3. Issue the CHNGDUMP DEL or CHNGDUMP RESET command to reset the options after recreating the dump.

If the correct dump options are specified in one of the PARMLIB members, change the ddname in the JCL for the DTF to reference the ddname corresponding to that member.

For further information on changing dump options, refer to the applicable IBM manuals.

## Connect:Direct for VM/ESA DTF Dump (GCS Dump)

Create VM dumps using the CP VMDUMP command and format them using IPCSDUMP on VM/SP or DUMpload on a VM/XA system. They must be in machine-readable format for DUMPSCAN. VMDUMP is the required format. You must process dumps by IPCS or DUMpload, prior to sending to Sterling Commerce.

Use the following procedures when producing a GCS dump:

1. From the GCS (DTF) machine, type the following.

```
#CP VMDUMP 0.END FORMAT GCS DSS *DUMPID
```

The dump is routed to the reader (RDR) of the virtual machine that is defined as the DUMP RECEIVER in the GCS CONFIG file. A message indicating the abend is displayed on the GCS console. This message signals that the dump is complete and in the reader. You can use the DUMPID field to append a description of the problem. The DUMPID field can contain 1 to 100 characters.

2. Type the VM Interactive Problem Control System command **IPCSDUMP** on VM/SP or DUMpload on a VM/XA or VM/ESA system to format the dump into a PRBxxxxx DUMP file. You are prompted for additional information which Connect:Direct uses to generate a PRBxxxxx REPORT file. Dump both of these files to tape using VMFPLC2 or TAPE.
3. Append the GCS NUCMAP to the dump, or send it in a separate file to allow support representatives to map into system code.
4. Also include the GCS console log, PROFILE GCS file, and the DMGCSMAP STARTUP file.
5. Indicate if the dump is from a VM/SP, VM/XA, or VM/ESA system.

## Connect:Direct for VSE/ESA DTF Dump (PARTDUMP)

To create the dump when the DTF cancels, request PARTDUMP on the OPTION job control statement in the startup job stream.



Add the following to the Connect:Direct startup JCL to create a dump.

```
//OPTION LOG,PARTDUMP
```

The specifications on the OPTION job control statement determine the kind of dump created.

---

**Note:** If you cancel Connect:Direct for VSE/ESA with ESTAE=YES, an abnormal termination exit always generates a dump.

---

## Connect:Direct Interactive User Interface (IUI) Dumps

When the Connect:Direct IUI abends, a system dump might be required for problem resolution. The following sections describe how to create a dump of the IUI for each Connect:Direct environment.

### Connect:Direct OS/390 IUI Dumps

To obtain a dump of the TSO address space, allocate a SYSUDUMP, SYSABEND, or SYSMDUMP ddname, and run the ISPF/PDF with the TEST option.

To send a dump of the IUI to a data set, allocate SYSUDUMP, SYSABEND, or SYSMDUMP with DISP=MOD to account for the two dumps that Connect:Direct produces.

To recreate an abend of the IUI to produce a dump, perform the following steps:

1. Ensure that SYSUDUMP, SYSABEND, or SYSMDUMP is allocated.
2. Reinvoke ISPF with the **ISPF TEST** command.
3. To dynamically allocate a SYSUDUMP ddname, type the following TSO command where *filename* is a valid TSO name that has LRECL=121 and RECFM=VBA.

```
TSO ALLOC F(SYSUDUMP) DA(filename) MOD
```

Specify **DISP=MOD**, so that ISPF does not overwrite the dump. Ensure adequate space is allocated for the data set. Generally, 15 cylinders on a 3380 device is enough space for an IUI dump.

4. When the abend message is displayed, press **ENTER** to produce a dump. Two dump messages (and dumps) are produced. Press **PF3/END** to bypass the dump.

### CMS Address Space Dump (Connect:Direct for VM/ESA Only)

Create VM dumps using the VMDUMP command and format them using IPCSDUMP on VM/SP or DUMpload on a VM/XA system. You must put them in machine-readable format for DUMPSCAN. VMDUMP is the required format. Process dumps by IPCS or DUMpload before you send them to Sterling Commerce.

To create a dump of the CMS address space, type the following command from CP read mode.

```
VMDUMP 0.END FORMAT CMS DSS *DUMPID
```

The dump is routed to the reader (RDR) of the virtual machine where the abend occurred. You can use the DUMPID field to append a description of the problem. DUMPID can be from 1-10 characters.

Use the VM Interactive Problem Control System command IPCSDUMP or DUMpload to process the dump and create a problem report. Also, include the CMS NUCMAP with the dump.

---

## SVC Dumps

If you take an SVC dump, copy the dump to a tape and mail it to Sterling Commerce. Include the DCB attributes of the tape data set and the DSN, VOLSER, and LABEL parameters specified when you created the tape. Sterling Commerce Customer Support formats the dump for you. Also, specify the system the dump was taken on (ESA, XA, and so forth).

---

## DMBATCH Dumps

For DMBATCH dumps, ensure the JCL that executes DMBATCH contains a SYSUDUMP, SYSABEND, or SYSMDUMP DD statement. Refer to the discussion on DTF dumps beginning on page 102 to ensure that the appropriate dump options are specified for the corresponding ddname in the JCL for DMBATCH.

---

## VSAM File Dumps

If a problem occurs when using a Connect:Direct VSAM file, you might need a dump of the VSAM file for problem resolution. The following sections describe how to create a dump of the VSAM file for each Connect:Direct environment.

### Connect:Direct OS/390 VSAM File Dump

To dump a Connect:Direct OS/390 VSAM file, use the IBM Access Method Services (AMS) PRINT command. If you send an IDCAMS PRINT of the TCQ, include the TCX file.

Refer to the sample job stream in the following example for creating a Connect:Direct OS/390 VSAM dump.

```
//XXXXXX JOB (1111), PROGRAMMER, NOTIFY=TSOID, CLASS=D, MSGCLASS=X,
//          MSGLEVEL=(1,1)
//PRINT EXEC PGM=IDCAMS
//SYSPRINT DD SYSOUT=*
//SYSIN DD *
PRINT INDATASET(DUMP1.OS390.VSAM1)
DUMP
```

To copy a VSAM file to tape, use the IDCAMS REPRO command. You must include the DCB parameters, RECFM=F, DSORG=PS for the data set created on the tape. In the LRECL and BLKSIZE parameters for the dataset created, you must reflect the size specified for the RECORDSIZE parameter used when you defined the file.

For example, if the Connect:Direct statistics file was initially defined with RECORDSIZE (4089 4089), copy the Connect:Direct statistics file by typing the following DCB parameters in the DD statement in the JCL.

```
//OUTDD DD DSN=TAPE.STAT.FILE,
DCB=(LRECL=4089, BLKSIZE=4089, RECFM=F, DSORG=PS)
```

## Connect:Direct for VM VSAM File Dump

To create a dump of a Connect:Direct for VM VSAM file, perform the following steps:

1. Issue a CMS DLBL command to define the VSAM Master Catalog that contains an entry for the VSAM file you want to dump. Following is an example.

```
DLBL IJSYSCT V DSN MASTCAT (PERM)
```

2. Issue the following CMS DLBL command to define the VSAM file to be dumped. Change **fm** to the file mode of the VSAM disk containing the VSAM file. Change filename to the file name of the VSAM file you want to dump.

```
DLBL SRCFILE fm DSN filename (CAT IJSYSCT)
```

3. Create the following input file to be used by the IBM VM Access Method Services (AMSERV) named PRINT AMSERV. Leave column one blank as shown in the following example.

```
PRINT INFILE ( SRCFILE ) DUMP
```

4. Issue the following CMS command to run AMSERV.

```
AMSERV PRINT
```

## Connect:Direct for VSE/ESA VSAM File Dump

To create a dump of a Connect:Direct for VSE/ESA VSAM file, use the IDCAMS AMS PRINT command.

```
// DLBL IJSYSUC,'vsam catalog id',,VSAM
// DLBL SRCFILE,'filename',,VSAM
// EXEC IDCAMS,SIZE=AUTO
PRINT INFILE(SRCFILE) DUMP
/*
```

---

## DTF Snap Dump Facility

The Snap Dump facility enables you to display, in hexadecimal format, the contents of a storage location in an active DTF. The following paragraphs describe the use of the commands and the format of the output as a result of invoking this facility. To use this facility, add a DD statement with the name CDDUMPR to the DTF startup procedure. Assign the output to SYSOUT or SYSLST.

### Command Syntax

Use the operator command interface to type the following command for Connect:Direct OS/390.

```
F jobname,DUMP,type,[parameter1],[parameter2],[parameter3]
```

Use the operator command interface to type the following command for Connect:Direct for VSE/ESA.

```
nn DUMP,type,[parameter1],[parameter2],[parameter3]
```

The following table describes the command syntax in the preceding example.

Command	Description
DUMP	Indicates a snap dump if you request some location of an active DTF.
type	Identifies the classification of the storage to display.
parameter	Indicates the type of information displayed. It also specifies how the information is displayed.

## Using Snap Dump Commands

The following examples describe different uses for the Snap Dump facility.

### Displaying a Hexadecimal Dump Format

The following command provides a method to display in hexadecimal dump format the contents of the storage starting at location **addr1**. Determine the extent of the storage by either an ending address at **addr2** or by a length indicated by **value**.

```
DUMP,MEM,START=addr1,[END=addr2],[LEN=value]
```

### Displaying the Resource Address Table

The following command displays the complete Resource Address Table (RAT).

```
DUMP RAT
```

### Displaying Task Control Area Information

The following command provides two types of output. The **LIST** parameter provides a list of summary information for each of the active Task Control Areas in the system. The **ID=** parameter provides a dump of all the information for a specific Task Control Area.

```
DUMP TCA,[LIST],[ID=taid]
```

### Displaying DTF Program Information

The following command provides information about the programs comprising the DTF. The **LIST** parameter provides a line of summary information for each of the programs loaded by the initialization of the DTF. To obtain a complete dump of a program, code the **ID=** parameter with the name of the module you want to dump.

```
DUMP PGM,[LIST],[ID=name]
```

---

## Suppressing Dumps for Specific Abend Codes

Use the following procedure if you want to suppress the dump for specific abend codes.

1. Add the abend code for which you want to suppress dumps to the abend codes list defined in the ABEND.CODES.NODUMP parameter. Following is an example:
2. Set the ABEND.RUNTASK parameter to ABEND.CODES.NODUMP

```
ABEND.CODES.NODUMP => (SX37 SX13 U0728 SXD9 S9FC)
ABEND.RUNTASK => ABEND.CODES.NODUMP
```



---

# Connect:Direct Traces

You can perform some problem isolation and diagnostics by running traces. A trace is a sequential recording of program events during execution. Generally, trace output is useful only as a diagnostic tool for the Sterling Commerce Customer Support staff because most of the output is meaningful only with access to the source code.

The following sections describe how to run the different types of traces:

- ❖ Guidelines for running traces
- ❖ Security traces
- ❖ Connect:Direct function traces
- ❖ Connect:Direct automatic traces

---

## Guidelines for Running Traces

When running traces for Sterling Commerce Customer Support personnel, it is important to remember the following:

- ❖ Limit Connect:Direct activity while running traces.
- ❖ Use merged traces. That is, run separate traces for each affected task merged into a single output file.
- ❖ Trace the simplest case possible.
- ❖ Disable traces upon completion. They generate considerable overhead.

---

## Security Traces

Sterling Commerce Customer Support staff use a security trace to debug security problems. The trace shows:

- ❖ Fields from the security control block
- ❖ Messages
- ❖ Return codes from the security system itself such as RACF, CA-TOP SECRET, and VMSECURE
- ❖ Data set names, if verifying data sets

## ❖ Exact userids and passwords

---

**Note:** The security trace may include userids and unencrypted passwords. Therefore, use it selectively and only to pinpoint a problem.

To prevent a remote node's security from discovering and then using Signon dummy passwords to gain access to a primary node, you can use the REMOTE.DUMMY.PASSWORD initialization parameter. See Appendix A, *Global Initialization Parameters*, in the *Connect:Direct OS/390 Administration Guide*.

---

To start a security trace, complete the following steps:

1. Specify TEST=YES as a parameter in your security exit source and reassemble and link-edit the exit.
2. For Connect:Direct OS/390 in the Connect:Direct startup JCL, allocate a DD for SECURITY, either to SYSOUT or to a data set on DASD. SYSOUT is preferred.

For Connect:Direct for VM/ESA, put a FILEDEF for SECURITY in the Connect:Direct PROFILE GCS, either to disk or to DUMMY. If you use DUMMY, spool the console before starting Connect:Direct for VM/ESA.

3. To allocate the security trace from the IUI, enter the following command appropriate for your operating environment.

TSO ALLOC FI(APISECUR) DA(*)	/* FOR OS/390 */
FILEDEF SECURITY TERMINAL	/* FOR VM/ESA */

4. If Connect:Direct is active, stop Connect:Direct. Restart it with the modified JCL startup job, and recreate the problem.

For details on security, refer to the Connect:Direct installation guide for your operating environment.



The following figure shows a portion of a security trace produced on the local node.

```

09:35:01:37 SITA523I SECURITY INITIALIZED
=====
AT ENTRY:SQCBREQC=80
SQCLASS=40
SQSTAT=20
SQSINWK=001FFBD8
UNODE#=000D UNODE=SC.OS390.DALLAS
UID#=0006 UID=JSMITH UID=C1D9C8D6 C1F14040
UPWD#=0008 UPWD=COWBOY UPWD=C9E4C940 40404040
SID#=0006 SID=JSMITH SID=C1D9C8D6 C1F14040
SPWD#=0008 SPWD=COWBOY SPWD=C9E4C940 40404040
NEWPSWD#=0000 NEWPSWD= NEWPSWD=40404040 40404040
SQPACCT#=0000 SQSACCT=0000
CURRENT REQUEST= ** SIGNON **
@@@ STAGE1 PW @@@*****
** USER IS ADMINISTRATOR **
*****
*****
AT FINAL EXIT:
SECURITY SYSTEM RETCODE=00000000
SECURITY EXIT RETCODE=00000000
*****
=====
AT ENTRY:
SQCBREQC=40
SQCLASS=90
SQSTAT=00
SQSINWK=00211BD8
UNODE#=000D UNODE=SC.OS390.DALLAS
UID#=0006 UID=JSMITH UID=C1D9C8D6 C1F14040
UPWD#=0008 UPWD=COWBOY UPWD=C9E4C940 40404040
SID#=0006 SID=JSMITH SID=C1D9C8D6 C1F14040
SPWD#=0003 SPWD=COWBOY SPWD=C9E4C940 40404040
NEWPSWD#=0000 NEWPSWD= NEWPSWD=40404040 40404040
SQPACCT#=0000 SQSACCT=0000
CURRENT REQUEST= ** DATASET VERIFY **
DATASET NAME=ACCT.DATA
SQINOUT=IN
CURRENT NODE=***PNODE***
*****
DATASET VERIFY SUCCESSFUL, RC=00000000
DATASET NAME=ACCT.DATA
VOLSER= M80004
INITIAL DISP=SHR
NORMAL DISP=KEEP
ABNORMAL DISP=KEEP
SQINOUT=IN
*****
*****
AT INTERMEDIATE EXIT:
SECURITY SYSTEM RETCODE=00000000
SECURITY EXIT RETCODE=00000000
*****
=====

```

Annotations on the right side of the trace:

- Usersids and passwords (bracketed next to UID, UPWD, SID, SPWD, NEWPSWD)
- Signon (bracketed next to CURRENT REQUEST= \*\* SIGNON \*\*)
- Use authorization set (bracketed next to \*\* USER IS ADMINISTRATOR \*\*)
- Return codes (bracketed next to RETCODE=00000000)
- Usersids and passwords (bracketed next to UID, UPWD, SID, SPWD, NEWPSWD)
- Data set verification (bracketed next to DATASET VERIFY SUCCESSFUL, RC=00000000)
- Return codes (bracketed next to RETCODE=00000000)

## Connect:Direct Function Traces

Connect:Direct contains various internal traces for diagnosing problems and recording events. Based on the trace specified, the Connect:Direct trace output is directed to various ddnames. You can enable these traces using one of the following methods:

- ❖ Modify the Connect:Direct startup job stream to include the trace files and ddnames for trace output and add the DEBUG parameter to the initialization parameter data set. The traces are turned on during Connect:Direct initialization and continue running until turned off by the MODIFY command or until Connect:Direct is terminated.
- ❖ Issue the Connect:Direct MODIFY command to set DEBUG bits. The trace starts when you issue the MODIFY command.

- ❖ Reduce the amount of trace information by restricting a trace to a Process (MODIFY Debug = parameter) or a specific node (NODETRACE.ON parameter). See *Connect:Direct MODIFY Command* on page 119 for more information about these parameters.

The following table shows the available function traces for Connect:Direct OS/390, VM/ESA, and VSE/ESA, with their respective DEBUG settings, and the ddnames used for output

DEBUG Setting	Trace Type	Output DD	Pseudo DLBL (Connect:Direct for VSE/ESA only)
80000000	COPY Routine and RUN TASK trace	RADBDD01	RADBDD01
10000000	Full TPCB/SYMBOLICS from DMCBSUBM	DMCBSUBM	DMCBSUB
08000000	Session manager trace	RADBDD05	RADBDD05
04000000	Separate trace per task (Example: "R0000005" to trace TASK 5)	Rnnnnnnn	Rnnnnnnn
02000000	API session trace	RADBDD07	RADBDD07
01000000	DMGCSUB trace	RADBDD08	RADBDD08
00800000	NETEX task termination disconnect trace	NTXTRACE	N/A
00400000	TCQSH from DMCOPYRT	DMCOPYRT	DMCOPYR
00200000	Make each SVC dump unique	N/A	N/A
00040000	GETMAIN/FREEMAIN trace	RADBDD16	RADBDD16
00008000	I/O buffer trace	RADBDD21	RADBDD21
00004000	WTO all dynamic allocation parameters	RADBDD22	RADBDD22
00002000	Connect:Direct/Plex traces		
	ACTION queue manager trace	CDPLXACT	N/A
	CKPT queue manager trace	CDPLXCKP	N/A
	TCQ queue manager trace	CDPLXTCQ	N/A
	STATS queue manager trace	CDPLXSTA	N/A
	First REQUEST queue manager trace	CDPLXREQ	N/A
	Second and subsequent REQUEST queue manager trace. For example, "CDPLXR03" traces the third queue manager. The number of queue manager traces is based on the maximum number of servers from the asset protection (APKEY) file.	CDPLXRnn	N/A
	JOIN queue manager trace	CDPLXJOI	N/A
00001000	Workload Balancing trace	CDPLXWLB	N/A
00000080	RPL trace - long	RPLOUT	RPLOUT
00000040	RPL trace - short	RPLOUT	RPLOUT
00000020	Version 2 session trace	RADBDD33	RADBDD33
00000008	Logon exit trace	RADBDD35	RADBDD35

DEBUG Setting	Trace Type	Output DD	Pseudo DLBL (Connect:Direct for VSE/ESA only)
00000004	Logon Process or trace	RADBDD36	RADBDD36
00000002	SCIP exit trace	RADBDD37	RADBDD37
00000001	SNMP trace	SCTRAPDD	N/A

## DEBUG Initialization Parameters

Various settings on the `DEBUG=xxxxxxxx` initialization parameter turn on a specific trace option or any combination of options. In the syntax for the `DEBUG` initialization parameter, `xxxxxxxx` represents the `DEBUG` setting in hexadecimal.

You can place trace `DD` statements in the system without slowing down `Connect:Direct` performance if you do not turn on the trace by specifying the `DEBUG` parameter.

With `VSE/ESA`, file names (equivalent to `ddnames`) are limited to seven characters. Any `Connect:Direct OS/390` `ddname` that is eight characters long is truncated when referenced in `Connect:Direct for VSE/ESA`. For instance, `RPLERRCK` is `RPLERRC` for `Connect:Direct for VSE/ESA`. The exceptions occur with `Connect:Direct OS/390` `ddnames` prefixed with `RADBDD` and `R00000`. For `Connect:Direct for VSE/ESA`, the prefixes are `RADBDD` and `R0000`.

For problems with `SNA` or `NETEX` connections, use the following four function traces merged into a single output file.

- ❖ Session manager trace
- ❖ Separate trace per task trace
- ❖ Long RPL trace
- ❖ `COPY` routine trace

---

**Note:** If the problem occurs during file transfer or session establishment of node connections, run the trace on both the sending and receiving nodes.

---

Because Sterling Commerce Customer Support personnel often request these types of traces, the following example shows how to run them.

## Example of Running a Merged Trace

To start the session manager, separate-trace-per-task, RPL long, and `COPY` routine traces, add the `DEBUG` parameter to the initialization parameter data set. `DEBUG` bits are listed in the table on page 114.

The `DEBUG` setting for the session manager trace is `X'08000000'`. The separate trace per task setting is `X'04000000'`, the `COPY` routine setting is `X'80000000'`, and the RPL long setting is `X'00000080'`. To specify all four traces merged into a single output file, add the four settings together. For example, the initialization parameter file contains the following.

```
DEBUG=8C000080
```

Next, allocate the appropriate `ddnames` for the trace output. Refer to the table on page 114. To run separate traces per task, it is not necessary to allocate the individual `DDs` for the session manager, `COPY` routine, and `RPL` traces. These are dynamically allocated.

When running a separate trace for every task active on Connect:Direct, the number of DDs allocated for the separate trace per task depends on the level of activity on Connect:Direct at the time of the trace.

## Connect:Direct for VSE/ESA

For Connect:Direct for VSE/ESA, add the following lines to the startup JCL for Connect:Direct.

```
*****
*
* NOTE: The SYS numbers used are an example.  You may use ANY
*
* UN-USED SYS number in the CD:VSE/ESA partition...
*
* Also, the SYS number MUST be part of the FILEID and MUST
*
* be the same in the FILEID as the ASSGN statement. Do NOT
*
* change SYSOUT in the FILE-ID. POWER uses this to route the
*
* output to the POWER SYSLST output for the job.
*****
// DLBL RADBD01,'SYSOUT.SYS050'
// DLBL RADBD05,'SYSOUT.SYS050'
// DLBL RPLOUT,'SYSOUT.SYS050'
// DLBL RPLERRC,'SYSOUT.SYS050'
// DLBL ESTAE,'SYSOUT.SYS050'
// DLBL NDMCMDS,'SYSOUT.SYS050'
// DLBL R000005,'SYSOUT.SYS050'
// DLBL R000006,'SYSOUT.SYS050'
// DLBL R000007,'SYSOUT.SYS050'
// DLBL R000008,'SYSOUT.SYS050'
// DLBL R000009,'SYSOUT.SYS050'
// DLBL R000010,'SYSOUT.SYS050'
// ASSGN SYS050,SYSLST
```

Refer to the *Connect:Direct for VSE/ESA Installation and Administration Guide* for further details on the MODIFY command for Connect:Direct for VSE/ESA.

## Connect:Direct for VM/ESA

For Connect:Direct for VM/ESA, add the following lines to the Connect:Direct PROFILE GCS.

```
FILEDEF R0000005 DISK R05 TRACE A
FILEDEF R0000006 DISK R06 TRACE A
FILEDEF R0000007 DISK R07 TRACE A
FILEDEF R0000008 DISK R08 TRACE A
FILEDEF R0000009 DISK R09 TRACE A
FILEDEF R0000010 DISK R10 TRACE A
FILEDEF R0000011 DISK R11 TRACE A
FILEDEF R0000012 DISK R12 TRACE A
FILEDEF R0000013 DISK R13 TRACE A
FILEDEF R0000014 DISK R14 TRACE A
FILEDEF R0000015 DISK R15 TRACE A
```

You can also send this output to the terminal on VM/ESA by changing DISK FN FT FM in the preceding example to DUMMY.

With those two modifications made, bring the Connect:Direct DTF down and back up in order to activate the traces. Because of the extensive overhead involved in running the traces, it is best to try only the functions you need to trace, then bring your DTF back down and deactivate the traces by removing the DEBUG parameter.

As long as you do not have any bits turned on with DEBUG, you can leave the FILEDEFS (or DD statements) in your startup job without activating any traces. You can then use the MODIFY command to turn the bits on interactively.

Refer to the *Connect:Direct for VM/ESA Installation and Administration Guide* for further details on the MODIFY command for Connect:Direct for VM/ESA.

## Examples of Connect:Direct Trace Output Using DEBUG Parameter

The figures in this section show some of the types of trace output that you can request using the DEBUG parameter with the appropriate DD or DLBL allocated.

### COPY Routine Trace

For Connect:Direct OS/390, add the ddname to the Connect:Direct job stream for the trace output as follows.

```
RADBDD01
```

Specify the DEBUG setting as follows.

```
DEBUG=80000000
```

The following figure shows sample output from the COPY routine trace.

```
DMCOPYRT      DMENTER      EP=00074A68   TAID=P   TASK=7
TARTNCD1      =            00000000
TAMSGID1      =            SCPA000I
SUBPGM        DMCPLSND   R14=50074FC2
SUBPGM        SEND-OPEN-NON-RESTART
R14=4007E750
SUBPGM        CALLFH      R14=6007EFB8
ESUBPGM       CALLFH
SUBPGM        BLDCPCB     R14=5007F2EA
SUBPGM        INFORTH    R14=400891F0
ESUBPGM       CALLFH
ESUBPGM       INFORTN
ESUBPGM       BLDCPCB
SUBPGM        CALLFH      R14=7007F36C
ESUBPGM       CALLFH
****NAME=S#MEMO
SUBPGM        CALLFH      R14=4007F586
ESUBPGM       CALLFH
ESUBPGM       SEND-OPEN-NON-RESTART
SUBPGM        CHECK-DESCR  R14=4007E78C
SUBPGM        SNDFMH71    R14=400802A6
SUBPGM        CALLFMH     R14=5008A3BC
ESUBPGM       CALLFMH
ESUBPGM       SNDFMH71
SUBPGM        RCVFMH71    R14=400802E0
**GETMEM FOR VTFMH@ IN RCV71 ADDR=00198890
**FREEMEM FOR VTFMH@ IN MAINLINE ADDR=0019D0E0
DMCOPYRT      DMRETURN
```

### I/O Buffer Trace

For Connect:Direct OS/390, add the ddname to the Connect:Direct job stream for the trace output as follows.

```
RADBDD21
```

Specify the DEBUG setting as follows.

```
DEBUG=00008000
```

The following figure shows sample output from the I/O buffer trace.

IN BUFF:	LEN-	3,120	BLK#-	1	
95899587	40899586	96999481	A3899695		*positioning information with *
81934084	81A38140	A49589A3	40404040		*each logical data unit *
99844096	99408293	9683925D	40848597		*(record or block) depending *
93A485A2	40A29785	83898689	85844089		*on the values specified in the *
40404040	40404040	40404089	9589A389		*initialization parameters *
A38599A2	40819584	40A38885	40949684		*and the mode the file *
89958740	A3998195	A2868599	99858440		*is being transferred in *
85839699	84409496	A4854096	99408293		*(record mode or block mode.) *
99844094	96848540	89A240A4	A2858440		*file is being reblocked, that is *
00404040	40404040	40404089	A2408285		*not equal the input *
99899587	40A39981	95A29489	A2A28996		*block size. Block mode is used *
A4A397A4	A3408293	96839240	40404040		*if the sending and *
849685A2	409596A3	408598A4	819340A3		*receiving files have identical *
89A9854B	4040C293	96839240	94968485		*block sizes.
40404040	40404040	404040A3	888540A2		
A5899587	40868993	85A24088	81A58540		
A289A985	A24B4040	40404040	40404040		

### Long RPL Trace

For Connect:Direct OS/390, add the ddname to the Connect:Direct job stream for the trace output as follows.

RPLOUT

Specify the DEBUG setting as follows.

DEBUG=00000080

The following figure shows sample output from the long RPL trace.

```

09:35:01:76 SITA523I RPLOUT INITIALIZED
12:56:12:56 *** V T A M R E C V *** TATASKNO: 5 TAID: P PNAME=PROC2VM PNUM=357
12:56:12:57 RECEIVE DATA
FMH HEADER IN RU
ONLY IN CHAIN
REQUEST DEFINITE RESPONSE
CHANGE DIRECTION
SYSTEM SENSE=0000 USER SENSE=0000
DATA LENGTH= 66
00000000 42700012 81030000 E2C34BE5 D44BC4C1 D3D3C1E2 40404040 31401015 10704772 *.....SC.VM.DALLAS ..... *
00000020 28A0100 20000000 0008E2C3 4BD4E5E2 4BC4C1D3 D3C1E240 40400000 00000000 *.....SC.OS390.DALLAS ..... *
00000040 0000 ..... *
12:56:12:72 *** V T A M S E N D *** TATASKNO: 5 TAID: P PNAME=PROC2VM PNUM=357
SEND POSITIVE RESPONSE
SYSTEM SENSE=0000 USER SENSE=0000
12:56:12:74 SEND COMPLETED
SEND
SYSTEM SENSE=0000 USER SENSE=0000
DATA LENGTH= 0
12:56:12:83 *** V T A M S E N D *** TATASKNO: 5 TAID: P PNAME=PROC2VM PNUM=357
SEND DATA
FMH HEADER IN RU
ONLY IN CHAIN
REQUEST DEFINITE RESPONSE
12:56:12:97 SEND COMPLETED
SEND
SYSTEM SENSE=0000 USER SENSE=0000
DATA LENGTH= 66
00000000 42700312 000320F5 E2C34BD4 E5E24BC4 C1D3D3C1 E2404040 31103012 20502862 *.....5SC.OS390.DALLAS .....&.. *
00000020 28A0100 A0000000 0008E2C3 4BD4E5E2 4BC4C1D3 D3C1E240 40400000 00000000 *.....SC.OS390.DALLAS ..... *
00000040 0000 ..... *
12:56:13:65 *** V T A M S E N D *** TATASKNO: 5 TAID: P PNAME=PROC2VM PNUM=357
SEND DATA
FMH HEADER IN RU
ONLY IN CHAIN
CHANGE DIRECTION
12:56:13:68 SEND COMPLETED
SEND
SYSTEM SENSE=0000 USER SENSE=0000
DATA LENGTH= 118
00000000 76720112 300000F5 D7D9D6C3 F2E5D440 F0F0F0F0 F0F3F5F7 E2C34BD4 E5E24BC2 *.....5PROC2VM 00000357SC.OS390.B *
00000020 D6E2E3D6 D5404040 D1E2D4C9 E3F14040 E2C34BE5 D44BC4C1 D3D3C1E2 40404040 *OSTON JSMIT1 SC.VM.DALLAS *
00000040 D5E5D4C4 F1F24040 D1E2D4C9 E3F24040 8A7F4F1D 615BA3EB 09EABA98 615BA3EB *NVMD12 JSMIT2 ."/.$t....q/$t. *
00000060 928E4398 615AA2EA 40404040 40404040 00000000 0000 *k .q/!s. .... *
    
```

## Short RPL Trace

For Connect:Direct OS/390, add the ddname to the Connect:Direct job stream for the trace output as follows.

RPLOUT

Specify the DEBUG setting as follows.

DEBUG=00000040

The following figure shows sample output from the short RPL trace.

```

- 10:07:53:44          OFFER ERROR NRBSTAT=          500
- 10:10:54:53          OFFER ERROR NRBSTAT=          500
- 10:13:54:53          OFFER ERROR NRBSTAT=          500
  10:16:02:01          *** V T A M   S E N D ***          TATASKNO:  6  TAID:    I
    SEND DATA
    ONLY IN CHAIN
  10:16:02:01          SEND COMPLETED
    SEND
    SYSTEM SENSE=0000          USER SENSE=0000
    DATA LENGTH=497
00000000          C4E2D500.....          7E7E7E7E7E7E7E7E *DSN.&l= = = = = *
00000000          7E7E7E7E.....          7E7E7E7E7E7E7E7E *= = = = = *
  10:26:45:82          *** V T A M   R E C V ***          TATASKNO:  7  TAID:    P
  10:26:45:82          RECEIVE DATA
    FMH HEADER IN RU
    ONLY IN CHAIN
    REQUEST DEFINITE RESPONSE
    SYSTEM SENSE=0000          USER SENSE=0000
    DATA LENGTH=
00000000          42
00000020          2A700012.....79700016          00806022 *. . . . a . . . . NDM.CHAS40
                                28A0010E00000000          1026
  10:26:45:84          *** V T A M   S E N D ***          TATASKNO:  7  TAID:    P
    SEND DATA
    FMH HEADER IN RU
    ONLY IN CHAIN
    REQUEST DEFINITE RESPONSE
  10:26:45:85          SEND COMPLETED
    SEND
    SYSTEM SENSE=0000          USER SENSE=0000
                                DATA LENGTH=  4
00000000          4750112

```

## Connect:Direct MODIFY Command

The Connect:Direct MODIFY command yields the same types of traces as the DEBUG initialization parameter. Unlike the initialization parameter, however, the MODIFY command does not require you to bring down and restart the DTF. The trace starts when you issue the MODIFY command to turn on the trace bits, provided the DD is allocated. However, for VSE/ESA, include the DLBLs in the start-up JCL rather than attempting dynamic allocation. The following table describes the parameters of the MODIFY command that relate to traces.

Connect:Direct MODIFY Command	Action
MODIFY BITS.ON=X'xxxxxxxx'	The specified debugging bits are turned on in the Connect:Direct resource address table.
MODIFY BITS.OFF=X'xxxxxxxx'	The specified debugging bits are turned off in the Connect:Direct resource address table.
MODIFY CLOSE=ddname	The ddname is closed in the DTF. For Connect:Direct for VSE/ESA: ddnames are the pseudo DLBL file names.

† The batch and IUI formats are shown for the DYN parameter. The batch DYN parameter uses an equal sign before and quotes around the dynamic allocation string. The IUI DYN parameter does not use an equal sign before or quotes around the dynamic allocation string.

Connect:Direct MODIFY Command	Action
MODIFY DDNAME=(ddname,nn)	All trace information generated as a result of the MODIFY.BITS.ON setting is directed to the ddname specified, based on the Connect:Direct taskid specified as <i>nn</i> . This specification provides a consolidated trace of all activity associated with the specified task. The ddname format is R0000nn, where <i>nn</i> is the taskid.
MODIFY DEBUG=xxxxxxxx	Replace system-wide debugging bits with the specified debugging bits.
MODIFY DYN = 'dynamic allocation string' (batch)†	Using the specified allocation string, dynamic allocation is invoked in the DTF.
MODIFY DYN = dynamic allocation string (IUI)†	Using the specified allocation string, dynamic allocation is invoked in the DTF. This definition only applies to the MODIFY (TRACE) COMMAND panel in the IUI.
MODIFY LOG.PRINTER=OFF   ON   luname	Specify whether the log printer is turned off or on or whether the LU name has changed. If you specify a new LU name, the old log printer is disconnected and the new one is attached.
MODIFY MODDIR.TRACE=YES	Request a module trace.
MODIFY NODE.TRACE.ON=(node name, debug bits)	Request a trace on one or more specified nodes, up to 15 at one time. The node name is the 1–16 character name of the node on which the trace runs. The debug bits are the 8-character DEBUG bits setting. See the BITS.OFF=X'nnnnnnnn' BITS.ON=X'nnnnnnnn' parameter in the table on page 114 for a listing of debug bits.
MODIFY NODE.TRACE.OFF=(node name)	Turn off a trace set by the NODE.TRACE.ON parameter.
MODIFY SESSIONS=Q   R (WHERE (NODE=nodename   *))	To prevent the start of new sessions, specify MODIFY SESSIONS=Q. To resume sessions and allow the start of new sessions as required, specify MODIFY SESSIONS=R. The default value is MODIFY SESSIONS=R. The where (NODE=) parameter enables you to suspend or resume processing on one or more nodes to a maximum of 15 nodes.
MODIFY WHERE(SERVER=server name)	Specify which Connect:Direct Plex member the MODIFY command applies to. The servername is the 1–8 character name assigned to a Connect:Direct/Server by the CDPLEX.SERVER initialization parameter.

† The batch and IUI formats are shown for the DYN parameter. The batch DYN parameter uses an equal sign before and quotes around the dynamic allocation string. The IUI DYN parameter does not use an equal sign before or quotes around the dynamic allocation string.

## Examples of MODIFY Commands

This section shows examples of MODIFY commands for Connect:Direct OS/390, VM/ESA, and VSE/ESA.

### Connect:Direct OS/390

The following MODIFY commands set the bits to turn on a short send/receive trace and to dynamically allocate the ddname RPLOUT.

```
MODIFY BITS.ON=X'00000040'
MODIFY DYN='DD=RPLOUT,DSN=A985467.PRINT,DISP=SHR,FREE=CLOSE'
```



After running the trace, the following MODIFY commands close the ddname RPLOUT and turn off the short send/receive trace.

```
MODIFY CLOSE=RPLOUT
MODIFY BITS.OFF=X'00000040'
```

### Connect:Direct for VM/ESA

The following MODIFY commands set the bits to turn on the dynamic allocation trace and invoke dynamic allocation in the DTF to allocate the ddname RADBDD24 to the file R24 S A.

```
MODIFY BITS.ON=X'00001000'
MODIFY DYN='DD=RADBDD24,DSN="R24 S A"'
```

After running the trace, use the following MODIFY commands to close the ddname RADBDD24, unallocate the DD, and turn off the dynamic allocation trace.

```
MODIFY CLOSE=RADBDD24
MODIFY DYN='UNALLOC DD=RADBDD24'
MODIFY BITS.OFF=X'00001000'
```

### Connect:Direct for VSE/ESA

The following MODIFY command sets the bits to turn on a session manager trace.

```
MODIFY BITS.ON=X'08000000'
```

After running the trace, use the following MODIFY command to turn off the session manager trace.

```
MODIFY BITS.OFF=X'08000000'
```

---

**Note:** You can use the command TRACE interchangeably with the MODIFY command.

---

### Using MODIFY Commands Through the Batch Interface

In Connect:Direct OS/390 and VM/ESA, you can issue the MODIFY command interactively through the IUI or the batch interface, DMBATCH.

To use MODIFY commands from the batch interface, include them in a batch job stream.

For example, if using OS/390, submit the following job to turn on the merged COPY routine and DMGCBSUB traces.

```
//TRACEON JOB (1111), 'TRACES', NOTIFY=JSMITH, CLASS=O,
//          REGION=1024K, MSGCLASS=X
//STEP01   EXEC PGM=DMBATCH, PARM= 'YYSLYYY'
//STEPLIB  DD DSN=$CD.CD.LINKLIB, DISP=SHR
//DMPUBLIB DD DISP=SHR, DSN=JSMITH.CNTL
//          DD DISP=SHR, DSN=JSMITH.PROCESS.LIB
//DMMSGFIL DD DISP=SHR, DSN=JSMITH.CD1.MSG
//DMNETMAP DD DISP=SHR, DSN=JSMITH.CD1.NETMAP
//DMPRINT  DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//NDMLOG   DD SYSOUT=*
//SYSIN    DD *
          SIGNON NETMAP=JSMITH.CD1.NETMAP USERID=(JSMITH)
          MODIFY BITS.ON=X'81000000'
SUBMIT PROC=ACCTSEPT
          SIGNOFF
```

To turn off the trace, submit the following job.

```
//NOTRACE JOB (1111), 'TRACES', NOTIFY=JSMITH, CLASS=O,
//          REGION=1024K, MSGCLASS=X
//STEP01   EXEC PGM=DMBATCH, PARM= 'YYSLYYY'
//STEPLIB  DD DSN=$CD.CD.LINKLIB, DISP=SHR
//DMPUBLIB DD DISP=SHR, DSN=JSMITH.CNTL
//          DD DISP=SHR, DSN=JSMITH.PROCESS.LIB
//DMMSGFIL DD DISP=SHR, DSN=JSMITH.CD1.MSG
//DMNETMAP DD DISP=SHR, DSN=JSMITH.CD1.NETMAP
//DMPRINT  DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//NDMLOG   DD SYSOUT=*
//SYSIN    DD *
          SIGNON NETMAP=JSMITH.CD1.NETMAP USERID=(JSMITH)
          MODIFY BITS.OFF=X'81000000'
          SIGNOFF
```

See the platform-specific Connect:Direct user's guide for a description of DMBATCH, and the installation and administration guide for a description of the MODIFY command.

---

## Connect:Direct Automatic Traces

You can activate some internal Connect:Direct traces without using the DEBUG bits. Activate these traces during normal Connect:Direct operation. Others traces are useful mostly for problem diagnosis. You can activate each of these automatic Connect:Direct traces by having a DD statement or FILEDEF in the Connect:Direct startup JCL, except for NDMCMDS, which is allocated in the JCL for DMBATCH or through the IUI.

Some of the most useful automatic traces are:

- ❖ DMCOPYRT provides a display of the TCQSH control block from the DMCOPYRT program.
- ❖ DMVSOPEN contains information related to the allocation of the target data set.
- ❖ ESTAE captures information on I/O errors; VTAM connection errors; abend control blocks; open and close errors; TCQ/TCX errors on add, update, and so forth; LU1 printer errors; and statistics file write errors. Always allocate ESTAE.

- ❖ CDESTAE contains various I/O errors from the statistics facility. Always allocate CDESTAE.
- ❖ RPLERRCK captures VTAM send and receive errors. Always allocate RPLERRCK.
- ❖ NDMCMDS shows all actual Connect:Direct commands issued to the DTF, including resolution of symbolics. It can be particularly helpful to debug Connect:Direct commands through the IUI or through DMBATCH if you are having signon problems, syntax errors, and so forth.
- ❖ NDMLOG contains a chronological log of Connect:Direct events.
- ❖ CDLOG contains allocation information

The following table shows the ddnames you can use in the startup JCL for Connect:Direct for mainframe platforms.

---

**Note:** With VSE/ESA, file names (equivalent to ddnames) are limited to seven characters. Any Connect:Direct ddname that is eight characters long is truncated when referenced in Connect:Direct for VSE/ESA. For instance, RPLERRCK is RPLERRC for Connect:Direct for VSE/ESA

---

DDNAME	Contents of File
DEVTRACE	Traces UCB open and close activity.
DMCOPYRT	Formats the TCQSH control block.
DMGEVENT	Traces Event Services activity.
DMVSOPEN	Formats the allocation block.
ESTAE	Abend diagnostics on various abend conditions and I/O errors. Allocate this name by including in the Connect:Direct startup JCL.
CDESTAE	Diagnostics on various I/O errors from the statistics facility. Allocate this name by including in the Connect:Direct startup JCL.
IGWTRACE	Traces PDSE program objects load to unload activity.
LOSTOUT	Lost term exit trace. For Connect:Direct for VM/ESA, use it in GCS only.
NDMAPI	Used for diagnostics on session errors with the API.
NDMCMDS	IUI/Application Program Interface (IUI/API) commands passed to Connect:Direct. Also use it for diagnostics on session errors with the API. For Connect:Direct for VM/ESA, use it in both GCS and CMS.
NDMLOG	Messages that are routed to ROUTCDE.NORM.
CDLOG	Allocation information.
NDMMSG	(Connect:Direct for VM/ESA) Message file handler errors. Use it in both GCS and CMS.
NDMRPL	(Connect:Direct for VM/ESA) VTAM errors between the GCS API and the DTF. Use it in GCS only.
RPLERRCK	Formatted RPL on error condition only. Allocate this name by including in the Connect:Direct startup JCL.
SCKFILEH	(Connect:Direct for VM/ESA) Message file handler errors. Use it in both GCS and CMS.

## Examples of Automatic Connect:Direct Traces

The following examples show some of the types of trace output that is directed to specified ddnames as certain Connect:Direct events occur.

## RPLERRCK Sample Output

The output for RPLERRCK in the following figure shows a session error.

```

15:35:11:13 SITA523I RPLERRCK INITIALIZED
VTAM SEND ->MAY 9TH, 2003 AT 15:53:45
SNODE=SC.VM.DALLAS PNODE=SC.OS390.BOSTON
PNAME=TAPETEST PNUM=353 TATASKNO=7
TATASKNO: 7 TAID: P
*** RPL @ 0020B398 ***
RPLID =00 RPLSTYP =20 RPLREQ =23
RPLLEN2 =70 RPLPLHPT=4009D57E RPLECB =001BE80C
RPLFDBWD=00100900 RPLRTNCD=10 RPLFDB2 =0900
RPLRH3 =20 RPLSRTP=0A RPLCHN =10
RPLVTFL2=0D RPLCNTDF=80 RPLCNTDC=00
RPLCNTSC=00 RPLURH =0BB220 RPLOPT1 =29
RPLRLEN =00000076 RPLBUFL =00001000 RPLOPT5 =90
RPLOPT6 =30 RPLOPT7 =54 RPLOPT8 =90
RPLOBSQV=0000 RPLBSQV=0000 RPLOBSQ =80
RPLIBSQ =80 RPLSEQNO=0002 RPLEXTDS=40
RPLACTIV=00 RPLSSEI =00 RPLSSMI =00
RPLUSNSI=0000 RPLUSFLD=001BE680 RPLOPT9 =00
RPLOPT10=20 RPLOPT11=80 RPLOPT12=21
RPLSSEO =00 RPLSSMO =00 RPLUSNSO=0000
RPLSIGDA=00000000 RPLEXSCH=00
**ERROR**:
UNCONDITIONAL TERMINATE OR CHARACTER-CODED LOGOFF RECEIVED
RECEIVE
FMH HEADER IN RU
ONLY IN CHAIN
ASYNCHRONOUS
CHANGE DIRECTION
RETURN CODE 10
FEEDBACK CODE 0900
SYSTEM SENSE INBOUND OUTBOUND
USER SENSE 0000 0000
VTAM DATA LENGTH = 118
VTAM BUFFER =
001FD000 08710112 03000000 0416E2C8 00500048 00000572 00004040 40404040 40404040 *.....SH.&..... *
001FD020 E2E3C5D7 F1404040 15533731 0090239F 00000000 E2C3D7C1 F0F0F0C9 D7404040 *STEP1 .....SCPA000IP*
001FD040 0090239F 15533692 40404040 20404040 00F8E2C4 E2C4C5E2 C3D90292 800180C0 *... ..k . . .8SDSDESCR.k...{*
001FD060 80000008 91444040 40404040 40404040 40404040 4040 *....j.*

```

## CDLOG Sample Output Showing Session Failure

The CDLOG output in the following figure shows a session failure during Process transmission.

```

SVTM055I SESSION ESTABLISHED WITH SNODE=CD.NY (002)
SVTM036I PROCESS STARTED TEST ( 19) SNODE=CD.NY(002)
SVTM022I SENDRU: SEND OF VTAM RU FAILED
SVTM045I RPLERRCK: CD/CD SESSION FAILURE
SVTM049I SNDFMH74: FMH_74 SEND ERROR

```

## CDLOG Sample Output Showing Successful Completion

The CDLOG output in the following figure shows that Process PAYRL ended successfully.

```

SVTM055I SESSION ESTABLISHED WITH SNODE=CD.NY(002)
SVTM036I PROCESS STARTED PAYRL ( 20) SNODE=CD.NY(002)
SVTM052I
COPY COPY PAID ( 20) SNODE=CD.NY (002) COMPLETED 00000000/SCPA000I
SVTM037I PROCESS ENDED PAYRL ( 20) SNODE=CD.NY(002)
SVTM056I SESSION TERMINATED WITH SNODE=CD.NY(002)

```

## ESTAE Sample Output

The ESTAE output in the following figure shows that the signon interactive applid was not active or did not exist.

```

OPEN OF ACB RC=00000008 APPLID=NDMDD19
*** ACBERFLG=5A ***
NO MATCHING APPLID ENTRY EXISTS OR IS NOT ACTIVE

```

## NDMCMDS Sample Output

The sample output for NDMCMDS in the following figure shows the output from a successful API Process submission.

```

STR#= 57 STR= SIGNON NETMAP=JSMITH.PUF8.NETMAP USERID=(RSMITH)ESF=YES
      CD/API VER.RLSE.MOD= 10,700 PUT0000
STR#= 51 STR= SUB PROC=ACCTSEPT &DISP=RPL HOLD=YES NEWNAME=JOHN
STR#= 117 STR=
STEP01 COPY FROM(DSN=JSMITH.ACF2.INFO) TO(DSN='ACF2 INFO'
LINK=(JSMI,WJSMI,W,191) DCB=(BLKSIZE=0) DISP=RPL)
STR#= 97 STR=STEP02 COPY FROM(DSN=JSMITH.CNTL SELECT=U7SVC)
TO(DSN='!SPOOL JSMI U7SVC EXAMPLE" DISP=RPL)
STR#= 70 STR=NOTIFY RUN TASK(PGM=DMNOTFY2
PARM=(GOOD,JSMITH.TEMP.DELETE,JSMITH) )
STR#= 6 STR= PEND
STR#= 9 STR= SIGNOFF

```

## LOSTOUT Sample Output

The following figure shows sample output from the Lost Term Exit Trace (LOSTOUT). The fields in the trace are as follows:

- ❖ **R2**—VTAM application control block (ACB)
- ❖ **R3**—Communications ID (CID) of the session.
- ❖ **R4**—Connect:Direct user field
- ❖ **R5**—Reason code indicating why the exit was entered

```

LOSTERM ENTERED
R2=000EE800
R3=6552653F
R4=000FA558
R5=00000018 LOSTERM ENTERED
R2=000EE800
R3=6552653F
R4=000FA558
R5=00000010

```

For more information, refer to the IBM *VTAM Programming* manual.

## DMCOPYRT Sample Output

The following figure shows sample output from the DMCOPYRT trace.

```

TCQSH:
00074C00                                03F2E2C8  00500048 0000054E 00004040 40404
040 * .2SH.&.....+.. *
TCQSH:
00074C20 40404040 E2E3C5D7 F1404040 09010686 0094126F 00000000 E2C3D7C1 F0F0F
0C9 * STEP1 ...f.m.?....SCPA000I *
0006BBA0                                03F2E
2C8 * .2SH *
00074C40 D7404040 0094126F 09010522 40404040 20404040 00F8E2C4 E2C4C5E2 C3D90
292 *P .m.?.... .8SDSDESCR.k *
0006BBC0 00500048 0000054E 00004040 40404040 40404040 E2E3C5D7 F1404040 09010
686 *.&.....+.. STEP1 ...f *

```

## DMVSOPEN Sample Output

The following figure shows sample output from the DMVSOPEN trace.

```
DMVSOPEN: AFTER ALLOPRFL
DAPARM#=008D
DAPARM =
ALLOC          DD=NDM0017  TSODSN=NO RETURN=(DSORG,DEVTYPE) DSN='PROFILE EXEC' DI
SP=(SHR      ) LINK=(AWINS1,ALL,RR,0191) UN
IT=(          ,DEFER)
DMVSOPEN: AFTER ALLOPRFL
DAPARM#=00C6
DAPARM =
ALLOC          DD=NDM0018  TSODSN=NO RETURN=(DSORG,DEVTYPE) DSN='!SPOOL AWINS1 PR
OFILE EXEC4' DISP=(NEW      ,KEEP      ,
DCB=(BLKSIZE=00063,DSORG=PS  ,LRECL=00063,RECFM=V  ) UNIT=(.....,DEFER)
```

---

# Tracing Network Traffic

This chapter describes how to use VTAM line and buffer traces to trace network traffic and record such events as supervisor calls and start I/O operations.

---

## VTAM Line and Buffer Traces

VTAM line and buffer traces are VTAM options that trace network traffic and record such events as supervisor calls and start I/O operations.

The following sections describe how to start VTAM line and buffer traces for Connect:Direct OS/390, VM/ESA, or VSE/ESA.

### Connect:Direct OS/390 VTAM Trace

Refer to the following example when starting VTAM line and buffer traces for Connect:Direct OS/390. For complete instructions, refer to your IBM manuals.

1. Activate the Generalized Trace Facility (GTF), an operating system trace facility that VTAM uses to store captured trace data for printing by a GTF print utility. you must activate the GTF before you can actually capture any trace data, although you can turn on the VTAM traces first. Type the following command.

```
S GTF.stepname
```

---

**Note:** The command to activate the GTF may be customized for your environment. Verify this command with appropriate personnel at your site.

---

2. After entering the command, the response number is displayed in the system log. Type the response number and trace options as follows.

```
nn,TRACE=RNIO,USR  
nn,U
```

3. Begin the VTAM trace by using your network management software. Type the following command.

```
F NET,TRACE,TYPE=BUF,ID=node  
F NET,TRACE,TYPE=IO,ID=node
```

4. Run the test cases or Processes to ensure that the problem occurred while the trace was active.
5. Stop the VTAM trace and the GTF when the trace is complete. Type the following command.

```
F NET,NOTRACE,TYPE=BUF,ID=node
F NET,NOTRACE,TYPE=IO,ID=node
```

6. Stop the GTF when the trace is complete. Type the following command.

```
P stepname
```

7. Format the VTAM buffer trace results using either ACFTAP, the GTF command in IPCS, or AMDPRDMP (if pre-ESA).
8. Print or browse the VTAM buffer trace results using ISPF/PDF utilities.

## Connect:Direct VM/ESA VTAM Trace

Complete the following steps to start the VTAM line and buffer trace for Connect:Direct for VM/ESA. For more information about using TRSTART, TRSOURCE, and TRSAVE, see the *IBM VM/ESA CP Command and Utility Reference* manual.

1. Set up the VM/ESA GCS/Control Program (GCS/CP) environment for the trace by creating a GCS EXEC called TRSTART GCS on the VTAM 191 disk.

The following is a sample EXEC. Change userid to the userid whose reader receives the trace file. Change sysname to the system name of the GCS machine running Connect:Direct for VM/ESA.

```
CP TRSOURCE ID trace_id TYPE GT FOR VMGROUP sysname
CP TRSAVE ID trace_id TO user_id
CP TRSOURCE ENABLE ID trace_id
ETRACE GTRACE GROUP
```

2. To execute the EXEC, type the following command.

```
TRSTART
```

3. Begin the VTAM trace by issuing the following command.

```
VTAM F [NET,]TRACE,ID=vtamid,TYPE=tracetype
```

4. Run the test cases or Processes.
5. Stop the VTAM trace by issuing the following command. Note that NET is optional.

```
VTAM F [NET,]NOTRACE,ID=vtamid,TYPE=tracetype
```

6. Shut down the GCS/CP trace environment by creating a GCS EXEC called TRSTOP GCS on the VTAM 191 disk. The following is a sample EXEC.

```
CP TRSOURCE DISABLE ID trace_id
ETRACE GTRACE OFF
```



- To execute the EXEC, type the following command.

```
TRSTOP
```

- After the EXEC completes execution, a message is displayed verifying that the file containing the trace results was sent to the reader specified when you set up your environment.
- Format the trace output using the TRACERED and ACFTAP utilities.
- Print or browse the VTAM buffer trace results.

## Connect:Direct for VSE/ESA VTAM Trace

Complete the following steps to start the VTAM line and buffer trace for Connect:Direct for VSE/ESA.

- Issue the VTAM MODIFY TRACE command as shown in the following example. Note that the ndmappl is the application ID (APPLID) for the Connect:Direct DTF.

```
MODIFY NET,TRACE,TYPE=BUF,ID=ndmappl
```

- Run the test cases or Processes.
- Stop the VTAM trace by issuing the following command.

```
MODIFY NET,NOTRACE,TYPE=BUF,ID=ndmappl
```

- Print the VTAM trace by running a batch job to execute program TPRINT. Running this job also flushes any in-memory buffers for the buffer trace into the disk trace file.

```
* $$ JOB JNM=TPRINT,CLASS=V,DISP=K,USER='name'
* $$ LST CLASS=A,DISP=D
// JOB TPRINT PRINT THE VTAM TRACE DATASET
// EXEC TPRINT,SIZE=512K
/*
/&
* $$ EOJ
```

Normally, information in the DLBL, EXTENT, and ASSGN statements is not in your job stream, but in the STDLABEL area. If your installation requires these statements in the job stream, use the following sample statements and place them between the JOB and EXEC statements.

```
// DLBL TRFILE,'your.trace.fileid',1999/365,SD
// EXTENT SYS001,packid,1,0,nnnn,mmm
// ASSGN SYS001,DISK,VOL=packid,SHR
```

- ❖ In the DLBL statement, change *your.trace.fileid* to your actual VTAM Trace File-ID.
- ❖ In the EXTENT statement, change *packid* to the VOLSER of the volume on which the trace file resides. Change *nnnn* to the starting track number and *mmm* to the number of tracks of your VTAM trace file.
- ❖ In the ASSGN statement, change *packid* to the VOLSER of the volume on which the trace file resides.

The following message is displayed on the console.

```
5K07A SNAPSHOT MODE TPRINT? ENTER Y OR N
```

5. Type No to the previous prompt using the following information where id is the outstanding VSE/ESA REPLID.

```
id N
```

The following message is displayed on the console.

```
5K05A ENTER TRACE PRINT OPTIONS OR 'CANCEL'
```

6. Respond with the trace print options.

```
id PRINT BUF=ALL
```

## A

ABEND.CODES.NODUMP 109  
ABEND.RUNTASK 109  
Abends  
  description 101  
  diagnosing 101  
  DTF, out-of-storage 83  
  messages 16  
  multiple, Connect:Direct OS/390 103  
  Run Task 102  
  user exit 102  
Address space 26, 102  
API session trace 61  
Asset protection 41  
Automatic Connect:Direct Trace, Examples 123  
Automatic traces 122

## B

Batch dumps 102, 106

## C

Case escalation 13  
CD.KEY initialization parameter 41  
CD.NODE initialization parameter 41  
CDESTAE trace 123  
CDLOG trace 123  
CDSVCDMP, Connect:Direct OS/390 102  
Connect:Direct for VM/ESA  
  dumps  
    CMS address space 105  
    VSAM file 107  
  traces 128

Connect:Direct for VSE/ESA  
  dumps 107  
  traces 129  
Connect:Direct messages 15  
Connect:Direct OS/390  
  dumps  
    DTF 102  
    IUI 105  
    VSAM file 106  
  traces 127  
Connect:Direct Process statistics 18  
Connect:Direct Select command  
  common errors 66  
  output 17  
COPY routine trace 115, 117

## D

DD names 123  
DEVTRACE trace 123  
Diagnostic methods  
  output from Connect:Direct Select command 17  
  overriding initialization parameters 19  
  reviewing messages 15  
  traces 111  
  verifying file attributes 19  
Diagnostic requirements 11  
DMBATCH dumps 102, 106  
DMCOPYRT trace 122, 123, 125  
DMGEVENT trace 123  
DMVSOPEN trace 122, 123, 126  
DTF  
  dumps 102  
  out-of-storage abends 83  
  Snap Dump facility 107  
DTF Snap Dump Facility, VSAM file 102

## Dumps

batch 102, 106  
 CDSVCDMP 102  
 DMBATCH 102, 106  
 DTF 102  
 DTF Snap Dump 107  
 GCS 102  
 general 101  
 IUI 105  
 multiple DTF, Connect:Direct OS/390 103  
 PARTDUMP 102  
 requirements 101  
 sending of 102  
 SVC 102, 106  
 SYSABEND 102  
 SYSDUMP 102  
 types of 102  
 VSAM file 102, 106

**E**

## Error messages

abends 16  
 description 15

## Errors

RACF 73, 74  
 Select command 66  
 statistics log 32

ESTAE trace 122, 123, 124

**F**

File attributes 19

**G**

Gathering data for problem determination 11

GCS dumps 102

**I**

I/O buffer trace 117

IGWTRACE trace 123

Inadequate storage 26

Incident resolution 13

Initialization messages 23

## Initialization parameters

CD.KEY 41

Initialization parameters (*continued*)

CD.NODE 41  
 file 27  
 MCS.SIGNON 97  
 overriding 19

Interactive use of message facility 15

## IUI

dumps 105  
 errors 61  
 signon error 62, 63

**L**

License Violations 41

Line and buffer traces 127

LOSTOUT trace 123, 125

**M**

MCS.SIGNON initialization parameter 97

Merged trace 115

Message facility, interactive use of 15

## Message IDs

4228I 89  
 APSM000E 51  
 APSM001E 52  
 APSM002E 53  
 APSM008E 54  
 APSM009E 55  
 APSM010E 56  
 APSM011E 57  
 APSM015E 58  
 APSM998I 59  
 IEE342I 96  
 open error X'76' 89  
 RACF095I 77  
 RACF097I 74  
 SAFA002I 78  
 SAFF000I 66  
 SAFF014I 66  
 SAFK000I 66  
 SAFL000I 66  
 SAFL010I 66  
 SCBB000I 66  
 SCBB001I 76, 97  
 SCBC030I 76, 97  
 SCBD001I 76, 97  
 SCBE001I 76, 97  
 SCBF001I 76, 97

Message IDs (*continued*)

SCBF063I 76, 97  
 SCBF064I 76, 97  
 SCBG001I 76, 97  
 SCBH001I 76, 97  
 SCBI001I 76, 97  
 SCBJ001I 76, 97  
 SCBK005I 76, 97  
 SCBL000I 66  
 SCBL001I 76, 97  
 SCBN001I 76, 97  
 SCBO000I 66  
 SCBO001I 76, 97  
 SCBP000I 66  
 SCBP001I 76, 97  
 SCBQ000I 66  
 SCBR002I 76, 97  
 SCBS001I 76, 97  
 SCBT005I 76, 97  
 SCBU003I 76, 97  
 SCBV001I 76, 97  
 SCBW001I 76, 97  
 SCBX000I 66  
 SCBX001I 76, 97  
 SCBY001I 76, 97  
 SCCS028I 81  
 SCIA011I 64  
 SCPA008I 76, 97  
 SDAA001I 88  
 SDAA004I 88  
 SDAA005I 88  
 SDAA048I 88  
 SDMK020E 75  
 SDMK022E 75  
 SDMK052E 75  
 SDMK053E 75  
 SDMK070E 75  
 SDMK071E 75  
 SDMK073E 75  
 SDMK078E 75  
 SDMK101E 75  
 SDMK102E 75  
 SDMK103E 75  
 SDMK104E 75  
 SDMK105E 75  
 SDMK106E 75  
 SDMK107E 75  
 SDMK108E 75  
 SDMK109E 75  
 SDMK110E 75  
 SDMK111E 75  
 SDMK112E 75

Message IDs (*continued*)

SDMK113E 75  
 SDMK114E 75  
 SDMK115E 75  
 SDMK116E 75  
 SDMK118E 75  
 SDMK119E 75  
 SDMK137E 75  
 SDMK139E 75  
 SDMK153E 75  
 SDMK199E 75  
 SDMK298E 75  
 SDMK331E 75  
 SDMKxxxE 75  
 SFIA002I 76, 97  
 SFIA003I 76, 97  
 SHCPxxxE 75  
 SITA003I 28  
 SITA004I 30  
 SITA014I 28  
 SITA018I 28  
 SITA021I 28  
 SITA037I 26  
 SITA038I 28  
 SITA039I 28  
 SITA040I 28  
 SITA041I 28  
 SITA042I 26  
 SITA043I 26  
 SITA044I 26  
 SITA045I 26  
 SITA047I 26  
 SITA048I 30  
 SITA049I 26  
 SITA050I 26  
 SITA051I 30  
 SITA052I 30  
 SITA053I 30  
 SITA054I 30  
 SITA055I 29  
 SITA056I 29  
 SITA057I 29  
 SITA059I 29  
 SITA060I 29  
 SITA061I 29  
 SITA062I 29  
 SITA063I 27, 28  
 SITA064I 29  
 SITA065I 29  
 SITA066I 29  
 SITA070I 27  
 SITA071I 28

Message IDs (*continued*)

SITA072I 28  
SITA073I 28  
SITA075I 29  
SITA076I 29  
SITA077I 29  
SITA078I 26  
SITA079I 28  
SITA080I 26  
SITA082I 28  
SITA083I 28  
SITA084I 28  
SITA085I 28  
SITA086I 28  
SITA087I 28  
SITA088I 28  
SITA089I 28  
SITA090I 30  
SITA091I 28  
SITA092I 28  
SITA093I 28  
SITA094I 28  
SITA095I 28  
SITA096I 26  
SITA097I 26  
SITA098I 26  
SITA099I 26  
SITA100I 29  
SITA101I 29  
SITA102I 29  
SITA103I 29  
SITA104I 28  
SITA105I 28  
SITA106I 28  
SITA110I 29  
SITA111I 29  
SITA112I 29  
SITA113I 29  
SITA121I 27  
SITA122I 26  
SITA123I 27  
SITA130I 29  
SITA131I 29  
SITA132I 29  
SITA133I 29  
SITA148I 28  
SITA160I 29  
SITA201I 28  
SITA202I 28  
SITA213I 28  
SITA214I 28  
SITA215I 28

Message IDs (*continued*)

SITA216I 28  
SITA217I 28  
SITA220I 28  
SITA221I 28  
SITA222I 28  
SITA223I 28  
SITA224I 28  
SITA225I 28  
SITA226I 28  
SITA227I 28  
SITA228I 28  
SITA230I 28  
SITA231I 28  
SITA232I 28  
SITA233I 28  
SITA234I 28  
SITA242I 28  
SITA250I 28  
SITA251I 28  
SITA252I 28  
SITA253I 28  
SITA254I 28  
SITA260I 28  
SITA261I 28  
SITA262I 28  
SITA263I 28  
SITA270I 28  
SITA271I 28  
SITA272I 28  
SITA273I 28  
SITA280I 28  
SITA281I 28  
SITA282I 28  
SITA283I 28  
SITA285I 28  
SITA286I 28  
SITA287I 28  
SITA291I 27  
SITA292I 27  
SITA293I 27  
SITA294I 27  
SITA300I 28  
SITA337I 42  
SITA338I 43  
SITA339I 44  
SITA340I 45  
SITA341I 45  
SITA342I 45  
SITA343I 46  
SITA344I 47  
SITA345I 48

Message IDs (*continued*)

SITA346I 49  
 SITA347I 50  
 SITA501I 27  
 SITA502I 27  
 SITA505I 27  
 SITA506I 28  
 SITA507I 28  
 SITA508I 28  
 SITA509I 28  
 SITA510I 28  
 SITA511I 28  
 SITA512I 28  
 SITA513I 28  
 SITA514I 28  
 SITA515I 28  
 SITA516I 28  
 SITA517I 28  
 SITA518I 28  
 SITA540I 28  
 SNAS080I 81  
 SOCN 25  
 SOPA000I 66  
 SOPA010I 67  
 SOPA011I 66  
 SOPB012I 67  
 SOPE000I 66  
 SOPS001I 66  
 SRJA014I 76, 97  
 SRPIxxxE 75  
 SRTA008I 76, 97  
 SSTI004I 32  
 SSTI005I 32  
 SSTI006I 32  
 SSTI007I 33  
 SSTI008I 33  
 SSTI009I 33  
 SSTI010I 34  
 SSTI011I 34  
 SSTI012I 34  
 SSTI013I 35  
 SSTI014I 35  
 SSTI015I 35  
 SSTI017I 36  
 SSTI018I 36  
 SSTI019I 37  
 SSTI020I 37  
 SSTI021I 37  
 SSTI022I 38  
 SSUB100I 76, 97  
 STAA004I 64  
 STAA005I 81

Message IDs (*continued*)

SVTB002I 62  
 SVTB004I 64  
 SVTB020I 93  
 SVTM026I 80, 81  
 SVTM041I 92  
 SVTM042I 94  
 SVTM043I 94  
 SVTM044I 94  
 SVTM045I 80, 93, 94  
 SVTM046I 94  
 SVTM047I 94  
 SVTM048I 94  
 SVTM049I 94  
 SVTM053I 80, 92  
 SVTM104I 80  
 Sx78 84  
 SxOA 84  
 U0075 30  
 U0500 84  
 U0501 84  
 U4095 93  
 VTAM sense code 0870 94  
 VTAM sense code 800A 94

## Messages

abends 16  
 description 15  
 initialization 23  
 WTO 18

Modify command 119

Multiple abends, Connect:Direct OS/390 103

**N**

NDMAPI trace 123

NDMCMDS trace 123, 125

NDMLOG trace 123, 124

NDMMSG trace 123

NDMRPL trace 123

**O**

Open errors 39, 89, 90

Overriding initialization parameters 19

**P**

PARTDUMP 102

Problem isolation 11  
 Problem reporting 11  
 Problem resolution 13  
 Process statistics 18  
 Product corrections 13

## R

RACF errors 73, 74  
 RAT (Resource Address Table) Snap Dump 108  
 RPL trace 115, 118, 119  
 RPLERRCK trace 123  
 Run Task abends 102

## S

SCKFILEH trace 123  
 Security traces 111  
 Select command  
   common errors 66  
   output 17  
 Select Statistics 18  
 Separate trace per task trace 115  
 Session manager trace 115  
 Severity levels 13  
 SITA186I 39  
 Snap Dump  
   command syntax 107  
   DTF 107  
   DTF program information 108  
   hexadecimal format 108  
   Resource Address Table 108  
   Task Control Area 108  
 SPQL003I 90  
 Statistics log error 32  
 Storage, inadequate 26  
 Support requirements 11, 101  
 Suppressing Dumps for Specified Abend Codes 109  
 SVC dumps 102, 106  
 SYSABEND 102  
 SYSMDUMP 102  
 System abend messages 17

## T

TCA (Task Control Area) Snap Dump 108  
 TCQ 90  
 TCQ.THRESHOLD 39

### Traces

API session 61  
 automatic  
   CDESTAE 123  
   CDLOG 123  
   DD names 123  
   DEVTRACE 123  
   DMCOPYRT 122, 123  
   DMGEVENT 123  
   DMVSOPEN 122, 123  
   ESTAE 122, 123, 124  
   IGWTRACE 123  
   LOSTOUT 123  
   NDMAPI 123  
   NDMCMDS 123, 125  
   NDMLOG 123, 124  
   NDMMSG 123  
   NDMRPL 123  
   RPLERRCK 123  
   SCKFILEH 123  
   summary of 122  
 Examples of Automatic 123  
 function  
   COPY routine 115, 117  
   I/O buffer 117  
   RPL 115, 118, 119  
   separate trace per task 115  
   session manager 115  
 merged 115  
 Modify command 119  
 security 111  
 VTAM line and buffer 127

### Troubleshooting methods

Connect:Direct Select command 17  
 file attributes 19  
 initialization parameters 19  
 messages 15  
 running traces 111

## U

User abend messages 16  
 User exit abends 102



**V**

VSAM file dumps 102, 106

VTAM line and buffer traces 127

**W**

WTO messages 18

