

Connect:Direct for Windows

Getting Started Guide

4.5.01

Sterling Commerce
An IBM Company

Contents

Prepare for Installation.....	4
Prepare for the Installation of Connect:Direct for Windows.....	4
Requirements for Copying Files To and From Network Servers.....	4
Configure Windows User Privileges.....	5
Customize a Connect:Direct Logon Account.....	5
Configure TCP/IP Connectivity.....	6
Connect:Direct for Windows Installation Worksheet.....	6
Install and Configure Database Software.....	7
Automate the Connect:Direct for Windows Installation.....	7
Configure SNA Connectivity.....	7
SNA Configuration Worksheet.....	8
Sample SNA Configuration.....	8
Sample Connect:Direct for z/OS Network Map Entries	9
XCA Token Ring: Switched Net Definitions.....	9
XCA Token Ring: Independent LU Definition.....	10
XCA Token Ring: Major Node Definition	11
Sample Connect:Direct APPLDEF	12
Sample Connect:Direct MODEENTS (Mode Definitions)	12
Sample VTAM Start Options (ATCSTRxx)	13
z/OS Network Map Example for VTAM.....	14
Windows Network Map Example.....	14
Access SNA Server Configuration Listing	15
Access Communications Server Configuration Listing.....	18
SNA Server/Host Configuration Worksheet.....	18
Get Support for Sterling Products.....	19
Connect:Direct for Windows Documentation.....	19
Install Connect:Direct for Windows.....	20
Install Connect:Direct for Windows: Overview.....	20
Connect:Direct for Windows Installation Icons.....	20
Apply a Temporary or Permanent License Key.....	21
Start the Installation.....	21
Install Connect:Direct Server and Requester.....	22
Complete the Connect:Direct for Windows and Secure+ Option Installation.....	22
Upgrade Connect:Direct for Windows.....	24
Add Connect:Direct for Windows Components.....	24
Repair Connect:Direct for Windows Components.....	24
Remove Connect:Direct for Windows Components.....	25
Install Requester Only.....	25
Install Connect:Direct File Agent.....	25
Uninstall Connect:Direct for Windows.....	26
Add Initialization Parameters to Support Firewall Navigation.....	26
Firewall Configuration Example.....	27
Automate Installation.....	28
About Silent Installations.....	28

Customize Initialization Information for a Silent Installation.....28
CD_SRVR.INI Parameter Values.....29
Customize Connect:Direct for Windows Configuration Information.....31
Run a Silent Installation.....31
Perform an Unattended Uninstallation.....32

Prepare for Installation

Prepare for the Installation of Connect:Direct for Windows

Before you install Connect:Direct for Windows, make sure the following tasks are complete:

- Make sure system meets product hardware and software requirements
- Define users for Windows
- Configure and test TCP/IP or SNA connectivity as needed
- Install and configure SQL Server or SQL Server Express for database support
- Install and configure SNMP as needed
- If you plan to use NT Broadcast to send user notification messages, ensure that NT Broadcast is configured
- Complete installation worksheets

Requirements for Copying Files To and From Network Servers

When you are ready to create Processes, be aware that Connect:Direct allows you to share information across computers. All of the data does not have to be on the Connect:Direct server. Observe the following requirements to enable copying files among network servers:

- Files to copy must reside on a file server accessible by Connect:Direct for Windows.
- You must provide a valid user ID and password for the file server where the files reside. Use a local node ID when you submit a Process on the local node and a remote node ID when you submit a Process on a remote node. Supply information as part of the process statement or the submit command or use the Login Connection Utility to provide this information.
- If a Process has multiple copy steps, the local node ID or remote node ID parameter must be appropriate for each file server from which, or to which you transfer a file. This method is necessary because the parameters apply to the Process as a whole and not to individual copy steps.
- Specify the Universal Naming Convention (UNC) form of the file name if the file is not on a drive directly connected to the same Windows server as Connect:Direct. If the file is on the Windows server where Connect:Direct is installed, you can specify the drive letter. The UNC name format is:

```
\\servername\share point name\filename
```

- The servername is the Windows server where data resides.
- The share point name is the name under which the remote Windows server shares the directory you want to access.
- The filename specifies the name of the file and any subdirectories.

Configure Windows User Privileges

Connect:Direct for Windows must be installed by a Windows administrator. However, ongoing administration only requires that the administrator is a member of the Windows Users group and is defined in the Connect:Direct User Authorities with administrative privileges based on the admin template.

After Connect:Direct for Windows is installed, attach to Connect:Direct for Windows as sysadmin and add a user as a Connect:Direct for Windows administrator (for example, cdadmin) with the user right, Log on locally. Then, delete sysadmin from the Connect:Direct for Windows User Authorities.

Refer to Microsoft Windows system documentation for instructions on setting up an administrator account. Refer to the *Connect:Direct for Windows System Guide* for information on configuring user authorities.

Customize a Connect:Direct Logon Account

Connect:Direct for Windows is installed under the local System account.

To create a custom account, assign the account the following privileges:

- Log on as service—Set this privilege to allow a Windows service to run in the context of the specified user instead of running in the context of the local system account.
- Replace a process level token—Turn on this privilege to allow Connect:Direct for Windows to submit Processes on behalf of logged on users.
- Be a member of the Local Administrator Group—If you want to allow the node to update its entry in Active Directory, the account must also be a member of the Enterprise Admin group.
- Secure+ directory—Give the account full permissions to the Secure+ directory.

Note: These privileges are stored locally, even if the computer is a member of a domain. As a result, privileges cannot be set on the domain controller and granted to all computers on the domain.

Note: Enabling the option, Allow service to interact with desktop when running Connect:Direct under the local System account, presents a security risk and may allow access to services that interact with the desktop.

After you create the account, you assign it as the account for Connect:Direct. To identify the custom logon account:

1. Select **Start > Settings > Control Panel > Administrative Tools > Services**.
2. Double-click the Connect:Direct server.
3. Click the Log On tab.
4. Select **This account to identify the custom logon account**.
5. Type the account name to use for logging onto Connect:Direct, or click Browse and double-click the user account.
6. Type the password in the **Password** and **Confirm password** fields.

7. Click **OK**.

Configure TCP/IP Connectivity

To enable TCP/IP connectivity, configure each computer with a valid IP address, IP subnet, and IP gateway. If the communications partner is on another subnet or network and a firewall is between the communications partner and the Windows computer, verify that the Access Control Lists (ACLs) are correctly configured. Contact your Firewall/Security Administrator for more information on configuring the ACLs for your firewall.

Connect:Direct for Windows Installation Worksheet

Complete this worksheet before you install Connect:Direct for Windows.

Decision	Choices	Additional Information
What Connect:Direct software to install?	<ul style="list-style-type: none"> • Connect:Direct Requester • Connect:Direct Server • Connect:Direct Secure+ Option 	
Choose the installation directory (where X represents the drive letter.)	<ul style="list-style-type: none"> • Accept the default installation directory - X:\Program Files\Sterling Commerce\Connect:Direct 4.5.00 • Change the installation directory • Install on a network drive • Place an icon on a desktop to perform the installation the first time the application is opened. 	
Name the Connect:Direct node - The default local node name is the name of the Windows computer.		<p>Note: To change the local node name after the product is installed, you must reinstall Connect:Direct for Windows.</p>
Location of the license management file.		You will also need to identify the number of sessions you are licensed for.
Identify the database software	<ul style="list-style-type: none"> • SQL Express Server • Microsoft SQL Server—Windows Authentication 	If security is implemented on Microsoft SQL Server—Windows Authentication, create a valid user ID and password and a CREATE TABLE privilege within the database.
Identify TCP/IP communication information		Identify Node-to-Node IP Address, Node-to-Node Port, User Interface IP Address, User Interface Port
Identify UDT communication information		Identify Node-to-Node IP Address, Node-to-Node Port, User Interface IP Address, User Interface Port

Decision	Choices	Additional Information
Identify additional components	<ul style="list-style-type: none"> • APPC Connectivity - SNA. Identify LU Name, Net ID, Mode Name. • Process Notification. Specify NT Broadcast or SMTP. If SMTP, specify Host Address, Host Port (default is 25), and Sender. • Load an Existing Network Map. Identify the fully qualified pathname for the MAP.CFG. • Load Existing User Authorities. Identify the Fully qualified pathname for the USER.CFG. 	

Install and Configure Database Software

The database logs Process statistics, internal messages, and the Process control queue. Determine which software to use as the database software.

- To use SQL Server, install it on the local computer, a network drive, or remote computer accessible from the local Connect:Direct node.
- To use SQL Server Express, run the SQLServer2008ExpressSP1.exe program located in the CD NT v. 4.5.01 \Server and Requester folder.

Automate the Connect:Direct for Windows Installation

You can automate Connect:Direct for Windows installations using an initialization (INI) file. Implement automated installations by specifying a path to the INI file from the command line of the Windows setup. See *About Silent Installations* for information about automating installations.

Configure SNA Connectivity

If you plan to use SNA network communications connectivity with Connect:Direct, install and configure SNA before installing Connect:Direct for Windows. Use the *SNA Configuration Worksheet* to identify the parameters necessary to configure SNA.

In addition, create an active connection between the local and remote nodes. Connect:Direct for Windows requires the following information for the local and remote SNA networks in order to configure a peer- or host-based partner SNA connection:

- Network name
- Mode name (local system only)
- Control point name
- Node ID
- Network address (remote system only)

- LU name and LU alias name (these names may be the same value; Connect:Direct uses the LU alias name)

Note: Connect:Direct for Windows supports only independent LU6.2.

Refer to the *SNA Server/Host Configuration Worksheet* when mapping SNA connection parameters between Connect:Direct for Windows and a host system.

Note: Consult the SNA product documentation or contact your SNA vendor for any questions about configuring the SNA communications software.

SNA Configuration Worksheet

Use this worksheet to identify the parameters necessary to configure SNA. Make copies of this worksheet for each SNA configuration. See the *z/OS Network Map Example for VTAM* for SNA Server configuration examples.

Node	Information Needed	Additional Information
Local Node	Decide the following: <ul style="list-style-type: none"> • Connect:Direct Node Name • LU Alias Name Get the following information from your SNA administrator: <ul style="list-style-type: none"> • LU Name • Network Name • Mode Name • Control Point Name • Node ID 	The LU Alias name is a user-defined name that references the LU name defined in the local SNA network. This value can be the same as the actual LU name.
Remote Node	Get the following information from your trading partner: <ul style="list-style-type: none"> • Connect:Direct Node Name • LU Alias Name Get the following information from your SNA administrator: <ul style="list-style-type: none"> • LU Name • Network Name • Control Point Name • Node ID • Network Address 	The LU Alias name is a user-defined name that references the LU name defined in the remote SNA network. This value can be the same as the actual LU name. Obtain that information from the SNA administrator of the remote system.

Sample SNA Configuration

This section illustrates a sample SNA configuration used to connect to Connect:Direct for z/OS. You provide the following SNA resource definitions during the Microsoft SNA configuration. These values are derived from VTAM definitions supporting connections between Connect:Direct for z/OS and Connect:Direct for Windows. Contact the VTAM administrator for the values you need to specify during SNA configuration.

Windows	Parameter Value	z/OS
Remote LU Name	= M1CDXY2B	=APPLID
Local LU Name	= M1R01LUA	=LU NAME
Network Name	= CSDNET	=NETID
Mode Name	= NDM624K	=MODEENT
Remote Control Point Name	= CSDSA01	=SSCPNAME
Local Control Point Name	= M1RPU01	=PU NAME
Local Connect:Direct Node Name	= SS.DUB.USER1	=ADJACENT.NODE
Remote Connect:Direct Node Name	= CDNT0001	=LOCAL.NODE
Local Node ID	= 0716200D	=XID
Remote Network Address	= 4000 7000 6200	=MAC Address

Sample Connect:Direct for z/OS Network Map Entries

The following sample illustrates Connect:Direct for z/OS network map entries for Windows SNA software running Connect:Direct for Windows.

```

*****
*
*           Connect:Direct NETWORK MAP
*
*****
*
* LOCAL NODE
*****
LOCAL.NODE   = ((SS.DUB.USER1 M1CDXX2B,, SUPERUSR)
                TCQ= (USER1.R210.TCX
                    USER1.R210.TCQ)
                )
*
ADJACENT.NODE = (PARSESS = (10 2)
                (CDNT0001, M1R01LUA, LU62)
                ENVIRONMENT=NT
                LOGMODE=NDM624K
                )

```

XCA Token Ring: Switched Net Definitions

The following sample illustrates the major node definitions for an XCA device.

```

*****
*
*
* XCA TR   DEFINITION
*
*
* CHANGE LOG
*

```

```

*
*****
M1R01PU  VBUILD TYPE=SWNET,                                X
          MAXGRP=1,                                       MAXIMUM NUMBER OF UNIQUE GRPNM   X
          MAXNO=1                                         MAXIMUM NUMBER OF UNIQUE DIALNO
*
***
M1RPU01  PU      ADDR=01,                                X
          PUTYPE=2,                                       X
          ISTATUS=ACTIVE,                                 X
          DBLK=071,                                       X
          IDNUM=6200D,                                    X
          PASSLIM=8,                                       X
          DLOGMOD=NDM624K,                                 X
          MODETAB=DALLMTAB,                               X
          SSCPFM=USSSCS,                                  X
          USSTAB=LSUSSTAB,                               X
          PACING=7,                                       X
          VPACING=7,                                       X
          DISCNT=(NO),                                    X
          MAXDATA=521,                                    X
          MAXPATH=2,                                      X
          MAXOUT=8
*
M1RPTH0D PATH  GRPNM=M1XG516D,                            X
              DIALNO=001111111111D  DUMMY
*M1ROLUA LU  LOCADDR=0, DLOGMODE=NDM6241C
*3270
*
M1R01LU2 LU  LOCADDR=2,DLOGMOD=D4A3290
M1R01LU3 LU  LOCADDR=3,DLOGMOD=D4A3290
*
*LU 6.2  ILU
*

```

XCA Token Ring: Independent LU Definition

The following sample illustrates the Independent LU definitions included as Cross Domain Resources.

```

*****
VTAM 3.4 CDRSC DEFINITIONS FOR INDEPENDENT LU'S          *
* 6.2 ILU DEFINITION - XCA TR ACCESS                     *
*CHANGE LOG:                                             *
*                                                         *
*                                                         *
*                                                         *
*****
M1R01CDS VBUILD TYPE=CDRSC
*
M1R01CDS VBUILD TYPE=CDRSC
          ALSLIST=M1RPU01,                                ADJ LINK STATION                 X
          MODETAB=DALLMTAB,                                LOGON MODE TABLE                X

```

```

          DLOGMOD=NDM624K,          LOGON MODE TABLE ENTRY          X
          RESSCB=5 SESSION CONTROL BLOCKS
M1R01LUB CDRSC ISTATUS=ACTIVE,          X
          ALSLIST=M1RPU01, ADJ LINK STATION          X
          MODETAB=DALLMTAB, LOGON MODE TABLE          X
          DLOGMOD=NDM624K,          LOGON MODE TABLE ENTRY          X
          RESSCB=5          SESSION CONTROL BLOCKS
*
M1R01LUB CDRSC ISTATUS=ACTIVE,          X
          ALSLIST=M1RPU01,          ADJ LINK STATION          X
          MODETAB=DALLMTAB,          LOGON MODE TABLE          X
          DLOGMOD=NDM624K,          LOGON MODE TABLE ENTRY          X
          RESSCB=5          SESSION CONTROL BLOCKS
*
M1R01LUC CDRSC ISTATUS=ACTIVE,          X
          ALSLIST=M1RPU01,          ADJ LINK STATION          X
          MODETAB=DALLMTAB,          LOGON MODE TABLE          X
          DLOGMOD=NDM622K,          LOGON MODE TABLE ENTRY          X
          RESSCB=5          SESSION CONTROL BLOCKS
*
M1R01LUD CDRSC ISTATUS=ACTIVE,          X
          ALSLIST=M1RPU01,          ADJ LINK STATION          X
          MODETAB=DALLMTAB,          LOGON MODE TABLE          X
          DLOGMOD=NDM621K,          LOGON MODE TABLE ENTRY          X
          RESSCB=5          SESSION CONTROL BLOCKS
*

```

XCA Token Ring: Major Node Definition

The following sample illustrates the major node definitions for an XCA device.

```

*****
*
* XCA MAJOR NODE
*
* CHANGE LOG:
*****
M1XCA516 VBUILD TYPE=XCA          XCA MAJOR NODE
*
M1XP5161 PORT MEDIUM=RING,          TOKEN-RING          X
          SAPADDR=4,          SERVICE ACCESS POINT ADDRESS          X
          ADAPNO=0,          ADAPTER NUMBER          X
          CUADDR=516          CHANNEL UNIT ADDRESS
*
M1XG516D GROUP DIAL=YES,          SWITCHED PERIPHERAL NODE          X
          CALL=IN,          DIAL IN AS PER MCDATA          X
          ISTATUS=ACTIVE          ACTIVATED AT GEN
*
M1XL516D LINE ANSWER=ON          PU CAN DIAL IN
*
M1X516PD PU

```

```
*
***
```

Sample Connect:Direct APPLDEF

The following sample illustrates the application definitions for Connect:Direct for z/OS.

```
ZZAPPGLP VBUILD TYPE=APPL
*****
*           C:D z/OS TEST LU 6.2 ILU APPL DEFINITION           *
*                                                                 *
*****
*
M1CDXY2B APPL ACBNAME=M1CDXY2B,      VTAM APPLID              X
           APPC=YES,                   LU 6.2 CAPABLE          X
           AUTH=(ACQ,VPACE),            VTAM AUTHORITY FOR THIS APP X
           AUTOCES=10,                  # OF AUTO CONT WINNER ACTIVATES X
           DDRAINL=ALLOW,                DRAIN ALLOWED FOR CNOS 0       X
           DLOGMOD=NDMLM1K,              DEFAULT MODE TABLE ENTRY      X
           DMINWNL=10,                   MIN CONT WINNER FOR LOCAL LU   X
           DMINWNR=10,                   MIN CONT WINNER FOR REMOTE LU  X
           DRESPL=ALLOW,                 APPL WILL DO SESSION DEACTIVATES X
           DSESLIM=20,                   MAX # OF ALLOWED SESS FOR MODE X
           EAS=509,                      APPROX # OF CONCURRENT SESSIONS X
           MODETAB=DALLMTAB,             MODE TABLE NAME                X
           VPACING=7                     DEFAULT RECEIVE PACING VALUE
*

```

Sample Connect:Direct MODEENTS (Mode Definitions)

The following sample illustrates the mode definition entries for an independent LU.

```
*****
*                                                                 *
*                               LU 6.2 WITH 4K RU'S               *
*                                                                 *
*****
NDM624K  MODEENT LOGMODE=NDM624K,      *
           TYPE=1,                                     *
           COS=NDMCOS1,                                *
           FMPROF=X'13',                               *
           TSPROF=X'07',                               *
           PRIPROT=X'B0',                              *
           SECPROT=X'B0',                              *
           PSNDPAC=X'04',                              *
           SRCVPAC=X'04',                              *
           SSNDPAC=X'04',                              *
           COMPROT=X'D0B1',                            *
           RUSIZES=X'8989',                            *
           PSERVIC=X'0602000000000000000000000300'   *
*
           0 1 2 3 4 5 6 7 8 9 10 11

```

```

*****
*
*           LU 6.2 WITH 2K RU'S
*
*****
NDM622K  MODEENT LOGMODE=NDM622K,
        TYPE=1,
        COS=NDMCOS1,
        FMPROF=X'13',
        TSPROF=X'07',
        PRIPROT=X'B0',
        PSNDPAC=X'04',
        SRCVPAC=X'04',
        SSNDPAC=X'04',
        SECPROT=X'B0',
        COMPROT=X'D0B1',
        RUSIZES=X'8888',
        PSERVIC=X'0602000000000000000000000300'
*
*           0 1 2 3 4 5 6 7 8 9 1011
*****
*
*           LU 6.2 WITH 1K RU'S
*
*****
NDM621K  MODEENT LOGMODE=NDM621K,
        TYPE=1,
        COS=NDMCOS1,
        FMPROF=X'13',
        TSPROF=X'07',
        PRIPROT=X'B0',
        PSNDPAC=X'04',
        SRCVPAC=X'04',
        SSNDPAC=X'04',
        SECPROT=X'B0',
        COMPROT=X'D0B1',
        RUSIZES=X'87

```

Sample VTAM Start Options (ATCSTRxx)

The following sample represents the VTAM Start Option entries for NETID and SSCPNAME.

```

*****
*
*           z/OS VTAM START DEFINITION
*
*****
HOSTSA=01,
NODETYPE=NN,
CONNTYPE=LEN,
CPCP=YES,
GWSSCP=YES,
NETID=CSDNET,

```

```

SSCPID=15015, X
SSCPNAME=CSDSA01, X
LISTBKUP=DEFAULTS, X
TNSTAT,NOCNSL,TIME=60, X
PPOLOG=YES, X
XNETALS=YES, X
NCPBUFSZ=2048, X
HOTIOTRM=50, X
IOPURGE=5M, X
MSGLEVEL=V4R1, X
MAINTLVL=9311, X
IOBUF=(750,320,50,,30,100,3000), X
CRPLBUF=(500,,0,,25,1), X
LFBUF=(300,,0,,32,1), X
LPBUF=(80,,0,,12,1), X
SFBUF=(40,,0,,34,1), X
SPBUF=(32,,0,,32,1), X
BSBUF=(600,,0,,25,50), X
XDBUF=(55,,0,,5,1)

```

z/OS Network Map Example for VTAM

The following sample illustrates the use of the VTAM parameters (identified by the alphabetic characters inside brackets) in a z/OS network map.

```

LOCALNODE=                                ADJACENT.NODE=(
    (node name[b],                          (node name[a],
    communications name[o],,                  communications name[m],,
    superuser password)                       LU62)
    TCQ=(tcxdsn, tcqdsn))                     PARSESS=(max[d], default)
                                                ENVIRONMENT=NT
                                                LOGMODE=logmode entry name[c])

```

Refer to the platform-specific Connect:Direct installation and administration guides for network map information on other host platforms.

Windows Network Map Example

The following sample illustrates the use of the SNA parameters (identified by alphabetic characters in brackets) in a Windows network map.

```

CREATE_SNA_MODE Name(mode [c])
MAXRUsize (MaxRU [e]) MaxPacingSize(7) MaxNetSessLimit(8)
CREATE_SNA_COMPATH Name(comppathname)
Transport(transport-type) Adapter(0) Address(000000000000)
NetId(netid[f]) PUName() LUName(LUName [m])
ProfileName() LULocAddr(0) Mode(mode[c]) LUSessLimit(8)
CREATE_REMOTENODE Name(remotenodename [b])
LRetry(10) LRetryTime(180) Sretry(10) SretryTime(10) SessPnodeMax(32)
SessSnodeMax(32) DefaultClass(1) RemoteOSEnv(OS/390) NetName(NetName[f])

```

```
PartnerName(PartnerName[o]) TPName(NNV2DTF) Mode(mode[c]) CommPath(commpathname)
```

Access SNA Server Configuration Listing

Use the following Windows SNA Server command to display the configuration and redirect the information to a file:

```
snacfg /print>filename
```

The following sample illustrates the Microsoft SNA server configuration listing for a configured Windows server using the values listed in the VTAM Sample Definitions:

```
MODE #INTER /ADD          \
  /SESSIONLIM: 8          \
  /CONWIN: 4              \
  /CONLOSE: 0            \
  /AUTOACT: 0            \
  /AUTOPARTNER: No       \
  /HIGHPRIORITY: Yes    \
  /PACESEND CNT: 7      \
  /PACERECV CNT: 7      \
  /MAXSEND RU: 1024     \
  /MAXRECV RU: 1024     \
  /MAXSEND RU: 1024     \
  /COMMENT: "Interactive" \
MODE #BATCH /ADD          \
  /SESSIONLIM: 8          \
  /CONWIN: 4              \
  /CONLOSE: 0            \
  /AUTOACT: 0            \
  /AUTOPARTNER: No       \
  /HIGHPRIORITY: No     \
  /PACESEND CNT: 3      \
  /PACERECV CNT: 3      \
  /MAXSEND RU: 1024     \
  /MAXRECV RU: 1024     \
  /MAXSEND RU: 1024     \
  /MAXSEND RU: 1024     \
  /COMMENT: "Batch"      \
MODE #BATCHSC /ADD       \
  /SESSIONLIM: 8          \
  /CONWIN: 4              \
  /CONLOSE: 0            \
  /AUTOACT: 0            \
  /AUTOPARTNER: No       \
  /HIGHPRIORITY: No     \
  /PACESEND CNT: 3      \
  /PACERECV CNT: 3      \
  /MAXSEND RU: 1024     \
  /MAXRECV RU: 1024     \
  /MAXSEND RU: 1024     \
```

```

    /MAXSENDRU:1024
    /COMMENT:"Batch"
MODE BLANK /ADD
    /SESSIONLIM:8
    /CONWIN:4
    /CONLOSE:0
    /AUTOACT:0
    /AUTOPARTNER:No
    /HIGHPRIORITY:No
    /PACESENDCNT:3
    /PACERECVCNT:3
    /MAXSENDRU:1024
    /MAXRECVRU:1024
    /MAXSENDRU:1024
    /MAXSENDRU:1024
    /COMMENT:"8 Blank chars"

```

```

MODE QPCSUPP /ADD
    /SESSIONLIM:64
    /CONWIN:32
    /CONLOSE:0
    /AUTOACT:0
    /AUTOPARTNER:Yes
    /HIGHPRIORITY:Yes
    /PACESENDCNT:7
    /PACERECVCNT:7
    /MAXSENDRU:1024
    /MAXRECVRU:1024
    /MAXSENDRU:1024
    /MAXSENDRU:1024
    /COMMENT:"5250 Mode"

```

```

MODE NDM624K /ADD
    /SESSIONLIM:20
    /CONWIN:10
    /CONLOSE:10
    /AUTOACT:0
    /AUTOPARTNER:No
    /HIGHPRIORITY:No
    /PACESENDCNT:7
    /PACERECVCNT:7
    /MAXSENDRU:4096
    /MAXRECVRU:4096
    /MAXSENDRU:4096
    /MAXSENDRU:4096
    /COMMENT:" "

```

```

SERVER CSD-PUBS /ADD
    /CPNAME:M1RPU01
    /NETNAME:CSDNET
    /COMMENT:" "

```

```

LINK SNADLC1 /ADD
    /SERVER:CSD-PUBS
    /LINKTYPE:Token

```

```

CONNECTION TOKEN1 /ADD
    /SERVER:CSD-PUBS

```

```

/COMMENT:"802.2 Connection" \
/ACTIVATION:OnServerStartup \
/CALLDIRECTION:Both \
/LOCALBLOCKNO:071 \
/LOCALNODENO:6200D \
/CPNAME:CSDSA01 \
/NETNAME:CSDNET \
/REMOTEBLOCKNO: \
/REMOTENODENO: \
/LINKSERVICE:SNADLC1 \
/REMOTEEND:Host \
/CONNTYPE:802.2 \
/XIDTYPE:Format3 \
/REMOTENETADDR:400070006200 \
/REMOTESAPADDR:4 \

/MAXBTTULEN:1929 \
/RECEIVEACKTHRESH:2 \
/NAKSENDLIMIT:8 \
/RETRYLIMIT:10 \
/XIDRETRIES:3 \
/T1TIMEOUT:Default \
/T2TIMEOUT:Default \
/TITIMEOUT:Default \
/ACTIVATEDELAY:Default \
/ACTIVATERETRYLIMIT:None \
APPCLU M1CDXY2B /ADD \
/CONNECTION:TOKEN1 \
/NETNAME:CSDNET \
/LUNAME:M1CDXY2B \
/COMMENT:" " \
/UNINTERPNAME:M1CDXY2B \
/AUTOPARTNER:No \
/PARALLELSESS:Yes \
APPCLU M1R01LUA /ADD \
/SERVER:CSD-NTSNA1 \
/LUNUMBER:0 \
/NETNAME:CSDNET \
/LUNAME:M1R01LUA \
/COMMENT:" " \
/AUTOPARTNER:No \
/DEFAULTPOOL:No \
/TPTIMEOUT:60 \
APPCLU M1R01LUA \
/ADDPARTNER:M1CDXY2B,NDM624K,TOKEN1 \
APPCLU M1R01LUB /ADD \
/SERVER:CSD-NTSNA1 \
/LUNUMBER:0 \
/NETNAME:CSDNET \
/LUNAME:M1R01LUB \
/COMMENT:" " \
/AUTOPARTNER:No \
/DEFAULTPOOL:No \
/TPTIMEOUT:60 \

```

```

APPCLU M1R01LUB \
 /ADDPARTNER:M1CDXX2B,NDM624K,TOKEN1 \
USER USER1 /ADD \
 /DOMAIN:CSD-NTSNA1 \
 /COMMENT:" " \
USER USER1 \
 /INSERT:M1R01LU2 \
USER USER1 \
 /INSERT:M1R01LU3 \
DIAGNOSTIC \
 /AUDITLEVEL:10 \

```

Access Communications Server Configuration Listing

The SNA configuration listing for IBM Communications Server is stored in a file with an extension of acg. The name for this file is defined when you install the Communications Server.

SNA Server/Host Configuration Worksheet

Complete this worksheet before you set up and configure an SNA connection between the host and the SNA server.

For each parameter listed, record the parameter value mapped between SNA and VTAM. Use the alphabetic identifier to understand how the parameters are implemented in the network map in the example.

Identifier	Parameter	Parameter value Mapped Between SNA and VTAM	Host/VTAM
[a]	Local Connect:Direct node name=		LOCAL.NODE
[b]	Remote Connect:Direct node name=		ADJACENT.NODE
[c]	Mode=		LOGMODE
[d]	Session Limits=		VTAM APPLID DSESSLIM
[e]	Max RU=		LOGMODE RU Size
[f]	Server Netname=		VTAMNETID (owner of PU)
[g]	Server CPNAME=		VTAM PU Name
[h]	Connection CPNAME=		VTAM SSCPNNAME
[i]	Connection Netname=		VTAM NETID (owner of PU)
[j]	Connection LOCALBLOCKNO=		VTAM PU DBLK
[k]	Connection LOCALNODENO=		VTAM PU IDNUM
[l]	Connection REMOTENETADDR=		Remote Network Address

[m]	Local LU Name (APPCLU)=	VTAM LU Name (must be independent)
[n]	APPCLU Netname=	VTAM NETID (owner of PU)
[o]	Remote Partner LU (APPCRLU)=	VTAM APPLID
[p]	APPRCLU Netname=	VTAM NETID (owner of APPLID)

Get Support for Sterling Products

Sterling Commerce provides intuitive technical products and superior Help and documentation to enable you to work independently. However, if you have a technical question regarding a Sterling Commerce product, use the Sterling Commerce Customer Support Web site.

The Sterling Commerce Customer Center portal offers you a single location to administer everything associated with Sterling Commerce products and services.

To log in to Customer Center, go to <http://customer.sterlingcommerce.com>. If you do not have a password, click **Join Now** and follow the instructions for new users. If you have a Support on Demand account, define a new password the first time you log on.

Connect:Direct for Windows Documentation

The Connect:Direct for Windows library consists of the following:

- *Getting Started with Connect:Direct Windows* provides instruction to install Connect:Direct Windows, including pre-installation information and installation tasks.
- *Connect:Direct Windows System Guide* provides instruction to set up and use Connect:Direct for Windows.
- *Connect:Direct Windows Release Notes* includes product updates and compatibilities, last-minute changes, instructions for downloading the product from the ESD Portal, known restrictions, enhancements, and installation notes.
- *Connect:Direct Windows Maintenance Updates* contains the latest product maintenance.

The following manuals supplement the Connect:Direct Windows documentation:

- *Connect:Direct Process Language Web site* provides an overview of Connect:Direct, describes the general structure and syntax rules for the Process language, and includes numerous examples. It describes the Process statements for various platforms including Connect:Direct.
- *Connect:Direct Compatibility and Connectivity Chart* provides definitions for the supported Connect:Direct platforms and the mapping of definitions that must match between two communicating platforms.
- *Connect:Direct for Windows Secure+ Option Implementation Guide* provides installation and configuration information for Secure+ Option.
- *Connect:Direct SDK Programmer's Guide* provides system programmers and system developers with the information needed to extend the capabilities of the Connect:Direct environment.

Install Connect:Direct for Windows

Install Connect:Direct for Windows: Overview

After you complete the installation worksheets, you are ready to install Connect:Direct for Windows.

Install all components or selected components. Connect:Direct components include:

- **Connect:Direct for Windows server**—Performs the functions issued from the user interface. If you want a dedicated server, install only this component. It also includes the Command Line Interface (CLI), a tool that allows you to issue commands to the server.
- **Connect:Direct for Windows Requester**—A graphical user interface that makes it easy to configure the Connect:Direct environment, create Processes, and submit commands to the server.
- **Connect:Direct File Agent**—Scans watched directories for files. When a file is detected, Connect:Direct for Windows either submits a default Process to Connect:Direct or performs the actions specified by the rules for the file.
- **Connect:Direct Secure+ Option**—A separately purchased option that allows you to implement security into a Connect:Direct operation. Secure+ must be installed on both nodes in order to activate the security software.

Software Developer's Kit (SDK) is a separately purchased option that allows programmers to customize the functions of Connect:Direct for Windows.

After you install Connect:Direct for Windows, TCP/IP information, database information and notification method is defined in the initialization parameters. To change TCP/IP information, the notification type, or the Connect:Direct database, refer to the *Connect:Direct for Windows System Guide*.

Connect:Direct for Windows Installation Icons

You choose the installation type to meet your needs. For example, if you want to install a standalone server, install only the Connect:Direct for Windows server software. If you want to use a computer as a server and a workstation, install both the server software and Connect:Direct Requester. If you purchase Secure+ Option, use the custom installation to install both Connect:Direct for Windows and Secure+ Option.

Additionally, if you have a large network of computers where you need to install Connect:Direct for Windows, you can set up a silent installation. To configure a silent installation, install Connect:Direct for Windows at one computer. Then use the initialization parameters file that was created during the installation to create a silent installation. Send the modified INI file to each computer on which to perform the silent installation.

Icons are displayed by each component to illustrate the selected installation type. The icons and installation types are described below:



The component is installed to the local drive.



Selected features of the component are installed.



The component is not installed.



Adds an icon to the Connect:Direct program group of the selected computer. The component is only installed when the user clicks the program icon to run the program.



The component is installed on the network.

Connect:Direct is installed in the directory called X:\Program Files\Sterling Commerce\Connect Direct v4.5.00\component.

If you would like to install Connect:Direct for Windows in another location, select the Custom setup during the installation and click **Change**. The remaining procedures use the default installation path.

Apply a Temporary or Permanent License Key

The temporary and permanent license key files must be applied where Connect:Direct for Windows is installed.

To apply a license key:

1. Copy the temporary license key file from the Sterling Commerce e-mail to the C:\Program Files\Sterling Commerce\Connect Direct 4.5.00\server directory.
2. Rename the license key file to license.key.

Note: Do not edit the nnnnn.txt file or the license.key file.

Text editors may insert a carriage return or truncate lines, which will invalidate the key file.

3. To obtain a permanent license key, use the CD System ID Utility to gather needed information. To run the CD System ID Utility:
 - a) Click **Start > Programs > Sterling Commerce Connect:Direct v4.5.00 > CD System ID Utility**. The Utility displays the CPU-ID and number of processors.
 - b) Click **File > Save**.
 - c) Type a name for the file and click **Save**.
 - d) Click **File > Send email**.
 - e) Type requested information in the e-mail template and click **Send**.
You will receive the permanent license key file in approximately 24 to 48 hours.
4. Make a copy of the original permanent license key and keep it in a safe place.
5. To replace the temporary license key with the permanent license key file, repeat steps 1 and 2.

Start the Installation

To start the Connect:Direct for Windows installation:

1. Insert the CD into the CD drive or double-click the setup.exe file extracted from the ESD file download.
2. If Autorun is enabled, the installation automatically starts. If Autorun is disabled, start the setup.exe file from the Windows run option.
3. On the Welcome dialog, click **Next**.
4. On the License Agreement page, read the agreement and click I accept the terms of the license agreement to continue. Click **Next**.
5. To install Connect:Direct Server and Requester, select Typical. Click **Next**.
6. To install Connect:Direct for Windows and Secure+ Option, select **Custom**. Click **Next**. This is the preferred method.

Install Connect:Direct Server and Requester

Start the installation and select Typical before you begin this procedure.

To complete the server and Requester installation:

1. Select Default from the Configure dialog box.
2. Click Browse and locate the license file you received from Sterling Commerce. Click **Next**.
The license file is copied to C:\Program Files\Sterling Commerce\Connect Direct v4.5.00\server.
3. Click **Install**.
4. Click **OK**.
5. When the installation is finished, Connect:Direct Requester is automatically started. If you do not want it to start, uncheck the option.
6. Click **Finish**.

Complete the Connect:Direct for Windows and Secure+ Option Installation

Start the installation and select Custom before you begin this procedure.

To complete a custom installation of Connect:Direct for Windows:

1. After you select Custom and click **Next**, the Custom Setup dialog box is displayed. The Connect:Direct for Windows Server and Requester software will be installed automatically.
2. To install Secure+ Option, click the icon next to it and select the installation method
3. To install SNMP Extension Agent, click the icon next to it and select the installation method.
4. To change the default installation path of Connect:Direct for Windows from C:\Program Files\Sterling Commerce\Connect Direct v4.5.00, highlight Server and click **Change**. Select the installation location and click **OK**.
5. After selecting the components to install, click **Next**.
6. From Configure Connect:Direct for Windows Server dialog box, click **Next**.
7. To change the local node name where Connect:Direct is installed, type the alternate node name and click **Next**.
8. From the License Management dialog box, click Browse and select the license file you received from Sterling Commerce. Click **Next**.
The license file is copied to the C:\Program Files\Sterling Commerce\Connect Direct v4.5.00\server folder.
9. To configure SQL Server to capture statistics, messages, and TCQ information:

- Select the SQL server to use with Connect:Direct.
 - Identify the authentication method: Windows authentication or Microsoft SQL Server using the specified User ID and Password. Click **Next**.
10. To specify an optional user account to run the Connect:Direct service, click Enter an optional service logon account. Type the following information and click **Next**.
- Service Account name
 - Service Password
 - Verify the password

Note: In When setting up the logon account, give the account these privileges:

- Act as part of the operating system
 - Log on as a service
 - Log on locally
 - Replace a process-level token
 - Full permissions over the installation directory, typically "Program Files\Sterling Commerce\Connect Direct v4.5.00"
 - Make the user a member of the local Administrators Group
-
11. To configure TCP/IP as the connection method, provide the following information and click **Next**:
- Node-to-Node IP Address
 - Node-to-Node Port
 - User Interface IP Address
 - User Interface Port
12. If you installed SNA, do the following to configure SNA support:
- a) Select Configure SNA.
 - b) Type the local LU name in the Local LU Name field.
 - c) Type the network name or ID in the Network Name (NET ID) field.
 - d) Type the mode name in the APPC Mode Name field.
 - e) Click **Next**.
13. To use Active Directory, select Register Client Connection Settings and click **Next**.
14. To configure SNMP support:
- a) To enable the SNMP extension agent, select Enable Connect:Direct SNMP Extension Agent.
 - b) To enable event logging, select Enable SNMP Event Logging.
 - c) Click **Next**.
15. To configure notification support:
- a) To enable Windows broadcasting, select NT Network Broadcast.
 - b) To enable SMTP, select SMTP.
 - c) Click **Next**.
16. To use a network map or user authorities that you defined for previous versions of Connect:Direct, click **Browse** and select the network map to import or configuration file to import. Click **Next**.
17. Click **Install**.

18. If you installed Connect:Direct Requester, it starts automatically. To disable the automatic start, deselect this option. Click **Finish**.

Upgrade Connect:Direct for Windows

To upgrade Connect:Direct:

1. Double-click the setup.exe file.
2. On the Welcome dialog, click **Next**.
3. To upgrade Connect:Direct, select Upgrade. Click **Next**.
4. To save the previous version of Connect:Direct, check Keep <version - nodename>." Click **Next**.
5. Click **Install**.
6. If you installed Connect:Direct Requester, it starts automatically. To disable the automatic start, deselect this option. Click **Finish**.

Add Connect:Direct for Windows Components

Before you can add a component, you must have already installed Connect:Direct for Windows.

After you install the product, you can change the installed components including repair a component that is corrupt, remove a component, or install an additional component.

To add, remove, or repair a Connect:Direct component:

1. Start the Connect:Direct for Windows installation.
2. On the Welcome dialog, click **Next**.
3. To install additional components:
 - a) Select Modify and click **Next**.
 - b) Select the component to add and enable This feature will be installed on local hard drive." Click **Next**.
 - c) Click **Install**.
 - d) Click **Finish**.

Repair Connect:Direct for Windows Components

Before performing this procedure, first you must have installed Connect:Direct for Windows.

To repair Connect:Direct for Windows components:

1. Start the Connect:Direct for Windows installation.
2. On the Welcome dialog, click Next.
3. Select Repair and click Next
4. Click Install to repair the installation.
5. Click Finish to complete the modification.

Remove Connect:Direct for Windows Components

Before performing this procedure, first you must have installed Connect:Direct for Windows.

To remove a Connect:Direct for Windows installed component:

1. Start the Connect:Direct for Windows installation.
2. On the Welcome dialog, click Next.
3. Select Modify to remove a Connect:Direct component and click Next.
4. Select the component to remove, choose "This feature will not be available," and click Next.
5. Click Install.
6. Click Finish to complete the modification.

Install Requester Only

For cluster installations, computers other than the one on which Connect:Direct is installed may require that the Requester.

To install Connect:Direct Requester:

1. Insert the Connect:Direct Requester CD into the CD drive or double-click the setup.exe file extracted from the file downloaded from the ESD Portal.
2. If the Autorun option is enabled for the CD drive, the installation automatically starts. If the Autorun option is disabled, start the installation from the Windows Run dialog.do the following:
3. On the Welcome dialog, click **Next**.
4. Read the agreement and indicate acceptance by clicking I accept the terms of the license agreement.
5. Click **Next**.
6. On the Setup Type dialog, select Typical and click **Next**.
7. Click **Install**.

Install Connect:Direct File Agent

When you install Connect:Direct File Agent, Java Runtime Environment (JRE) is automatically installed.

To install File Agent:

1. Insert the Connect:Direct for Windows CD into the CD drive, or locate the files you extracted from the ESD Portal, and double-click the FileAgentInstall.exe file.
2. From the Introduction dialog box, click Next.
3. If you want to install File Agent in a selected location, click Choose and identify the location for the File Agent installation.
4. Click Next, then click Install.
5. When the installation is complete, click Done.

Uninstall Connect:Direct for Windows

Before performing this procedure, first you must have installed Connect:Direct for Windows.

The Connect:Direct for Windows Uninstall program removes the application, its components, Connect:Direct Requester, and Connect:Direct for Windows server, program items, and most server and Registry settings.

To uninstall the Connect:Direct Server program and all of the server utilities, perform the following steps:

1. Click Start > Programs > Settings > Control Panel > Add-Remove Programs.
2. Highlight Connect:Direct for Windows and click Remove.
3. Click Yes to confirm the removal of this program.
4. Click Finish to complete the uninstallation.
5. Click OK to close the Add/Remove Programs Properties dialog box.

Add Initialization Parameters to Support Firewall Navigation

If you communicate with a trading partner using a firewall, set two initialization parameters to support it. You assign a specific TCP/IP source port number or a range of port numbers with a particular TCP/IP address or addresses for outgoing Connect:Direct sessions. Setting these parameters allows controlled access to a Connect:Direct server if it is behind a packet-filtering firewall without compromising security.

To add firewall support initialization parameters:

1. Coordinate IP addresses and associated port assignments with your firewall administrator.
2. Add the following parameter to the Local Node Characteristics section of the initialization parameters file:
tcp.src.ports=(valid IP address/optional subnet mask | valid IP address pattern, associated port number | associated range of port numbers | associated port number, associated range of port numbers)
3. Apply the new initialization parameter.
4. A second parameter called tcp.src.ports.list.iterations is automatically added to the Local Node Characteristics section during installation and has a default value of 1. Refer to the following table for a description and valid values for these parameters:

Parameter Name	Parameter Definition	Valid Values
tcp.src.ports	An IP address or multiple addresses and the ports permitted for the address when going through a packet-filtering firewall.	Valid IP address with an optional mask for the upper boundary of the IP address range and the associated outgoing port number or range of port numbers for the specified IP address, for example: (199.2.4.* , 1024), (fd00:0:0:2015::*, 2000-3000), (199.2.4.0/255.255.255.0, 4000-5000),(fd00:0:0:2015::0/48, 6000, 7000) A wildcard character (*) is supported to define an IP address pattern. If the wildcard character is used, the optional mask is not valid.

Parameter Name	Parameter Definition	Valid Values
tcp.src.ports.list.iterations	The number of times that Connect:Direct scans the list of available ports defined in tcp.src.ports to attempt a connection before going into a retry state. This parameter is automatically added to the initialization parameter and is assigned a value of 1. If desired, change this value.	A numeric value from 1-255. The default value is 1.

5. Coordinate the specified port numbers with the firewall administrators.

Firewall Configuration Example

The following example illustrates a configuration of the firewall navigation initialization parameter. An explanation follows the example. Although the tcp.src.port parameter is shown as a multi-line parameter, Connect:Direct for Windows only supports single-line parameters.

```
tcp.src.ports= (199.2.4.*, 5000-5050),
              (199.2.4.7, 1376),
              (200.200.0.0/255.255.0.0, 2000-2100, 3000-3100),
              (138.16.17.*, 2000-2050, 3000-3050, 4001, 4005)
```

In the example, if Connect:Direct initiates a session with a remote node at the IP address 199.2.4.7, it will use only port 1376. A session 199.2.4.6 (or any other address beginning with 199.2.4) will use any port in the range 5000 to 5050.

A session to 200.200.4.10 uses a port from within the two ranges specified (2000 to 2100 or 3000 to 3100). Additionally, because of the subnet mask specification, a session to any IP address beginning with 200.200 will choose a port from within the two ranges specified.

The port for a session to any address beginning with 138.16.17 is selected from one of the two ranges (2000 to 2050 or 3000 to 3050) or the two individual ports specified (4001 or 4005).

Automate Installation

About Silent Installations

You can automate Connect:Direct for Windows installation and configuration for distribution throughout your enterprise by performing silent installations. Silent installations require no user responses during the installation routine. Configuration information is supplied by the initialization file that you define. Before you perform a silent installation, install Connect:Direct for Windows on a master node and configure a network map and user authorizations.

The Microsoft Installer Properties are the foundation of a silent installation. Properties can be set on the command line or by creating custom transforms. A transform is a collection of changes applied to an installation. Transforms alter the installation database and can be used to customize a base installation package. Applying a transform to a base installation package adds or replaces data in the installation database.

Silent Installation Options

You can perform a default silent installation that installs Connect:Direct server and Connect:Direct Requester, or you can use transforms to modify the settings of an installation package. The transforms included with this product enable, disable, and remove a feature from the Connect Direct for Windows.msi package. To change the silent installation setting, use a transform to enable or disable the desired feature.

Requirements for Silent Installation

Use the following list as a guide to the silent installation requirements for each node:

- To perform the default installation (server and Connect:Direct Requester), the node must have a license key.
- To install only Connect:Direct Requester or SDK, no license key is required.
- If the node uses special services, for example, Active Directory, SNMP, or SNA, a custom INI file is required. If no custom INI file is present, the default installation is performed.

Customize Initialization Information for a Silent Installation

The Connect:Direct server supports an INI file, which can specify the value of installation properties. If you plan to use the INI file to manage a silent installation, change the parameters of the INI file provided with Connect:Direct for Windows to specify site-specific information.

The Connect:Direct for Windows server initialization file (CD_SRVR.INI) is located on the CD in the /advanced folder. The Connect:Direct Requester and SDK installations do not use initialization files. To set the installation directory for an installation, specify the INSTALLDIR property in the command line.

To define site-specific parameter values in an INI file for each node where you install Connect:Direct for Windows using the silent installation, do the following:

1. Open the CD_SRVR.INI file using any text editor, such as Windows Notepad.
2. Define the site-specific initialization parameters for a node and save the file.
3. Repeat steps 1–2 for each server where Connect:Direct will be installed.

CD_SRVR.INI Parameter Values

Parameter Name	Parameter Definition	Values
CD_SETUP_TYPE	Installation type: Default, Custom, or Upgrade.	<u>Default</u> Custom Upgrade
CD_SQL_AUTHENTICATION	SQL authentication.	
CD_SQL_USERID	Service account name to log on with.	
CD_SQL_PWD	Password to log on with.	
CD_NODENAME	Local node name, from 1-16 characters, consisting of numbers, letters, @, #, \$, -, underscore (_), and period (.) with no spaces or apostrophes.	If this field is blank, the parameter defaults to the first eight characters of the computer where the server is installed.
CD_UPGRADE_NODE	The version of software and node to upgrade.	1=enabled.
CD_UPGRADE_KEEPCR_FLAG	Prevents the current version from being deleted before installing the new version.	1=enabled The type must be equal to UPGRADE.
CD_LICENSE_FILE	The location of the license file.	X:\Program Files\Sterling Commerce\Connect Direct \x.x.xx Any valid Windows directory
CD_HOST_IP	The IP address of the host server.	Any valid IP address.
CD_HOST_PORT	The port number that Connect:Direct for Windows, or user-written API programs, will use to establish client sessions with this Connect:Direct server for outgoing communications.	A numeric value in the format nnnn, where nnnn is a positive integer no larger than four digits. The default is 1364.
CD_API_IP	The host IP address. Any valid TCP/IP address may be specified.	Valid TCP/IP address. If blank, the IP address is obtained from the destination computer's IP address in the TCP/IP stack.
CD_API_PORT	The port number that Connect:Direct for Windows or user-written API programs will use to establish client sessions with this Connect:Direct server. You must specify the port when it differs from the default.	A numeric value in the format nnnn, where nnnn is a positive integer no larger than four digits. The default is 1363.

Parameter Name	Parameter Definition	Values
CD_SNA_FLAG	Indicates whether SNA connectivity is supported.	1=enabled
CD_SNA_LUNAME	The local LU name to use during SNA communications, or the name of the computer, if no LU name is specified.	Valid 1-8 character LU name or computer name up to 8 characters.
CD_SNA_NETID	The SNA network ID.	A valid 1-8 character network ID.
CD_SNA_MODE	The SNA mode name.	<u>ndm624K</u> a valid 1-8 character mode name
CD_SNMP_FLAG	Enables SNMP.	1=enabled
CD_EVENTLOG_FLAG	Enables SNMP Event log.	1=enabled
CD_ACTIVEDIR_FLAG	Registers the client IP address to active directory.	1=enabled
CD_NOTIFY_TYPE	Defines the notification type to use.	<u>NT Broadcast</u> SMTP
CD_NOTIFY_SMTP_HOST	If CD_NOTIFY_TYPE = SMTP, this field identifies the IP address of the SMTP host.	Host address in the format xxx.xxx.xxx
CD_NOTIFY_SMTP_PORT	If CD_NOTIFY_TYPE = SMTP, this field identifies the port used by the SMTP host.	Port number up to four characters. The default value is 25.
CD_NOTIFY_SMTP_SENDER	If CD_NOTIFY_TYPE = SMTP, this field identifies the e-mail address to identify the sender of the message	Valid e-mail address
CD_NOTIFY_SMTP_AUTHENTICATE	If CD_NOTIFY_TYPE = SMTP, this field enables authentication. If this value is not set, the user ID and password fields are ignored.	1=enabled
CD_NOTIFY_SMTP_USERID	If CD_NOTIFY_TYPE = SMTP, this field identifies the user ID to use to authenticate the server.	A valid user ID.
CD_NOTIFY_SMTP_PWD	If CD_NOTIFY_TYPE = SMTP, this field identifies the user password to use to authenticate the server.	A valid user password.
CD_USERAUTH_FILE	The path name and file name to the user authority file.	<u>X:\Program Files\Sterling Commerce\Connect Direct</u> <u>\x.x.xx\MyUserAuthSettings.cfg</u> Any valid Windows directory and user authority file name
CD_NETMAP_FILE	The path name and file name of the network map file.	<u>X:\Program Files\Sterling Commerce\Connect Direct</u> <u>\x.x.xx\mynetmap.map</u> Any valid Windows directory and network map file name
CD_SVC_ACCOUNT	Service user account.	
CD_SVC_ACCOUNT_PWD	Service user account password.	
CD_SQL_SERVER	The name of a valid SQL Server.	Valid SQL Server
CD_SQL_AUTHENTICATION	SQL authentication.	

Parameter Name	Parameter Definition	Values
CD_SQL_USERID	SQL Server system administrator's user ID.	Valid SQL Server System Administrator user ID
CD_SQL_PWD	SQL Server system administrator's password.	Valid 1-30 character SQL Server System administrator password

Customize Connect:Direct for Windows Configuration Information

After you install Connect:Direct for Windows on a master node, you can customize configuration information for distribution within your enterprise by using Connect:Direct Requester to configure the network map and user authorizations on the master node. You can then extract those files using the Configuration Utility. For more information about using the Configuration Utility, refer to "Defining and Managing the Connect:Direct Network" in Help or in the *Connect:Direct for Windows System Guide*.

To apply the customized configuration files during a silent installation, set parameter values in the CD_SRVR.INI file as follows:

- To apply a customized network map file, set CD_NETMAP_FILE to the fully qualified path to a customized network map configuration file.
- To apply a customized user authorization file, set CD_USERAUTH_FILE to the fully qualified path to a customized User Authorization configuration file.

Run a Silent Installation

Setup.exe installs the Microsoft Installer, Visual C++ Runtime Libraries and other prerequisites on a system when they do not already exist. To complete the installation, Setup.exe reboots the system if required and resumes the installation after the computer has restarted.

Setup.exe can accept a limited number of command-line parameters. By using these parameters, you can pass parameters through Setup.exe to the included .msi file (MsiExec). To pass arguments to the .msi file, use the /v option. Once you specify this option, you can list any of the supported parameters that can be passed to Msiexec.exe.

If you don't want the Setup.exe to display a progress bar when it launches, use the /s command-line parameter. For example, if you enter Setup.exe /s, Setup.exe launches, but the user interface is not displayed. If you want the .msi setup to run silently as well, you'll need to pass the /qn command-line parameter through Setup.exe using the /v parameter—for example: Setup.exe /s /v/qn

Follow these special formatting rules when passing a parameter in this way. First, place a backslash (\) character before a quotation mark that resides within existing quotes. For example, the command line above contains the following: /v"C:\My Files\SecurePlusEnable.mst". Because the path contains spaces, you must use quotes. However, since quotes are required around the complete argument, if you don't use the backslash before internal quotes, the command-line statement fails.

Do not put a space between the command-line option (/v) and the arguments you are passing. This rule is also illustrated in the above example.

Finally, if you are passing multiple parameters using the /v option, separate them with a space. For example, the following command enables Secure+ Option and specifies the license file:

```
Setup.exe /s /v"C:\My Files\SecurePlusEnable.mst" CD_LICENSE_FILE="C:\My Files\license.key\""
```

To attach to the network and install Connect:Direct for Windows features from the network location in a silent installation:

1. Click Start > Run. The Run dialog box is displayed.
2. In the Open field of the Run dialog box, type a command similar to following example: `Setup.exe /s /v/qn`
This command installs all Connect:Direct for Windows components including Connect:Direct Requester and Secure+ Option.

Note: Setup.exe installs Connect:Direct for Windows in the default directory `c:\Program Files\Sterling Commerce\Connect Direct Windows v[current version]`. If you want to install Connect:Direct for Windows in a different directory, use the `INSTALLDIR` option on the command line. Enclose the pathname in quotes and terminate the path with a backslash, such as `Setup.exe /v"INSTALLDIR=\"D:\Program Files\Sterling Commerce\Connect Direct v4.5.00\""`.

3. Computers in a Windows 2000 or XP Domain that use Active Directory can also automate installations using the software installation extension of the Group Policy Snap-In.

The Windows installer uses an `/M` command line parameter to generate MIF files. In the following example, the `CDNT.mif` file is created to report success or failure: `setup.exe /s /v/qn /M C:\Windows\CDNT.mif`

Perform an Unattended Uninstallation

Connect:Direct for Windows provides for an unattended uninstallation. In the following example, the `/x` command parameter removes the package.

`Setup.exe /x`