



# **IBM® Sterling Connect:Express®**

Adapter for Sterling B2B Integrator

**Version 5.2**

## **Copyright**

This edition applies to the 5.2 Version of IBM® Sterling Connect:Express® Adapter for Sterling B2B Integrator and to all subsequent releases and modifications until otherwise indicated in new editions.

Before using this information and the product it supports, read the information in Notices, on page 125.

Licensed Materials - Property of IBM

IBM® Sterling Connect:Express® Adapter for Sterling B2B Integrator

© Copyright IBM Corp. 2008, 2011. All Rights Reserved.

US Government Users Restricted Rights - Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

# Table of Contents

<b>TABLE OF CONTENTS .....</b>	<b>I</b>
<b>Preface .....</b>	<b>1</b>
<b>Introduction .....</b>	<b>3</b>
<b>CHAPTER 1.....</b>	<b>5</b>
<b>Overview .....</b>	<b>5</b>
<i>Supported Versions .....</i>	5
<i>Installation .....</i>	6
Installing on UNIX .....	6
Installing on Microsoft Windows.....	7
<i>Configuring the Listening Port of Sterling Connect:Express .....</i>	8
Microsoft Windows .....	8
UNIX.....	8
<i>Description of Sterling Connect:Express Services .....</i>	9
<i>Implementing a Sterling Connect:Express Service.....</i>	10
Creating a Service Instance.....	10
Creating a Business Process.....	11
Checking-in the Business Process.....	13
<i>Executing a Sterling Connect:Express Service.....</i>	14
<i>Logging Calls to Services .....</i>	14
<i>Tracing Communications with a Monitor.....</i>	15
<b>CHAPTER 2.....</b>	<b>17</b>
<b>Reference Guide .....</b>	<b>17</b>
<i>Parameters Shared by all Services.....</i>	17
<i>CXActivity .....</i>	19
CXActivity Parameters .....	19
<i>CXConfiguration .....</i>	21
CXConfiguration Parameters .....	21
<i>CXEtb3Presentation.....</i>	23
CXEtb3Presentation Parameters .....	23
<i>CXFile .....</i>	26
CXFile Parameters.....	26
<i>CXJournal.....</i>	33
CXJournal Parameters.....	33
<i>CXPartner .....</i>	37

CXPartner Parameters .....	37
<i>CXPresentation</i> .....	44
CXPresentation Parameters.....	44
<i>CXSession</i> .....	47
CXSession Parameters .....	47
<i>CXStatistics</i> .....	50
CXStatistics Parameters.....	50
<i>CXTransferSubmit</i> .....	52
End Transfer Condition Parameters .....	52
CXTransferSubmit Parameters .....	52
<i>CXTransferControl</i> .....	58
CXTransferControl Parameters.....	58
<i>CXTransferStatus</i> .....	59
CXTransferStatus Parameters.....	59
<i>CXEerpSubmit</i> .....	61
End Transfer Condition Parameters .....	61
CXEerpSubmit Parameters .....	61
<i>CXEerpContextSubmit</i> .....	63
End Transfer Condition Parameters .....	63
CXEerpContextSubmit Parameters.....	63
<i>CXEerpStatus</i> .....	66
CXEerpStatus Parameters.....	66
<b>CHAPTER 3 .....</b>	<b>69</b>
<b>Notifications .....</b>	<b>69</b>
<i>Configuring a SI http Server to Receive Notifications</i> .....	69
Creating the Business Process to Receive the Notification .....	69
Associating the Business Process to an URI of the http Server .....	70
<i>Executing the Business Process to Receive the Notification</i> .....	74
<i>HTTP Notification in Sterling Connect:Express z/OS</i> .....	76
Installing the HTTP Notification .....	76
Configuring the HTTP Notification.....	76
Configuring Transfers for HTTP Notification.....	77
<i>HTTP Notification in Sterling Connect:Express for UNIX</i> .....	79
Installing the HTTP Notification .....	79
Configuring the HTTP Notification.....	80
Configuring Transfers for HTTP Notification.....	81
Executing tom_htpn Process to Send Notifications .....	82
Managing Monitor, SI or Htpn Stop .....	86
Notifications Sequence .....	86
Troubleshooting .....	86
Purging the Notification System .....	87
<i>HTTP Notification in Sterling Connect:Express Microsoft Windows</i> .....	88
Installing the HTTP Notification.....	88

Uninstalling the HTTP Notification .....	88
Configuring the HTTP Notification.....	88
Configuring Transfers for HTTP Notification.....	90
Starting/Stopping the tom_https Process.....	92
Httpn_status.exe Utility Showing Notifications Waiting to be Sent.....	93
Httpn_cmd.exe utility.....	96
Httpn_service.exe Utility for tom_https Installation / Uninstallation as Microsoft Windows Service .....	96
Purging the Notification System .....	97
<i>Notification Fields</i> .....	98
<b>CHAPTER 4.....</b>	<b>101</b>
<b>Sterling Connect:Express User Interface .....</b>	<b>101</b>
<i>Installing the Interface .....</i>	<i>101</i>
Deploying the Interface.....	101
Installing the SI Ressources .....	101
<i>Description of the Interface.....</i>	<i>105</i>
Managing Directories .....	107
File Transfer Request.....	109
Monitoring Requests .....	113
Purging Requests .....	117
<i>Integration with SI.....</i>	<i>119</i>
Parameters of the URI .....	119
Configuration Business Process.....	121
<b>NOTICES .....</b>	<b>125</b>



---

## Preface

This document describes the Sterling Connect:Express Services proposed in Sterling B2B Integrator ( SI). Sterling Connect:Express services enable you to use Sterling Connect:Express functionality from SI.

*Overview* describes the installation procedure and provides an overview of the Sterling Connect:Express services.

*Reference Guide* is the reference guide of Sterling Connect:Express services.

*Notifications* describes the implementation of Sterling Connect:Express notifications with SI.

*Sterling Connect:Express User Interface* describes the implementation of a Sterling Connect:Express browser interface with SI.



---

## Introduction

Sterling Connect:Express Adapter for Sterling B2B Integrator enable a SI business process to use the functionality of a Sterling Connect:Express for UNIX or Microsoft Windows, locally or remotely.

---

For the z/OS platform, only HTTP notifications are available. Availability starts from version 4.2.3.

---

The services provide an interface to the various components of Sterling Connect:Express:

- ❖ Symbolic partners and files: list, create, update, delete.
- ❖ Session and presentation tables: list and update.
- ❖ Sterling Connect:Express configuration file: list
- ❖ File transfers: active, journal and statistics.
- ❖ Submit a file transfer request.
- ❖ Interrupt, restart and purge a file transfer.
- ❖ The services logon to Sterling Connect:Express via a TCP/IP connection.

Sterling Connect:Express services are available for UNIX and Microsoft Windows platforms.

In the following, a Sterling Connect:Express monitor is referred to as a « monitor », the SI Browser interface (dashboard) is referred to as the « SI interface » and the Business process graphical modeler (GPM) is referred to as the « modeler ».

*Reference Guide* provides a detailed description of all services.

The browser interface enables the following operations:

- ❖ Symbolic partners and files: list, create, update, delete.
- ❖ File transfers: active, journal and statistics.
- ❖ Submit a file transfer request.
- ❖ Interrupt, restart, purge a file transfer.



# Chapter 1

This chapter provides an overview of the installation procedure and of the Sterling Connect:Express services.

---

## Overview

Sterling Connect:Express Adapter for Sterling B2B Integrator establish TCP/IP connections with monitors. You must configure an API TCP/IP port for each monitor that you want to administrate. You can configure the connection parameters in an instance of a Sterling Connect:Express service or pass them in the business process.

You can access all Sterling Connect:Express configuration files (Partners, Files, Tables) and manage file transfers.

You are provided a number of services and parameters. You can set default parameters in service instances that you configure and that you select in a business process. You can complement the parameters of the service in the business process itself.

Important note: the file transfer request service does not transfer any file from SI to Sterling Connect:Express. This means that you must place the file in the Sterling Connect:Express environment before sending the transfer request. For this purpose, you can use the SI File System Adapter, if the monitor is on the same system as SI, or FTP for example, if the monitor is remote.

You should take care of access rights to the files.

---

## Supported Versions

The following table shows the correspondence between SI and Sterling Connect:Express versions supported:

Sterling Connect:Express Adapter for Sterling B2B Integrator	SI	Sterling Connect:Express for UNIX	Sterling Connect:Express Microsoft Windows
5.2	5.2	1.4.6-1	3.0.6

---

## Installation

Sterling Connect:Express Adapter for Sterling B2B Integrator are shipped in a zip file for Microsoft Windows CXSI\_WIN\_5.2.zip or a tar file for UNIX CXSI\_UNIX\_5.2.tar. When the installation is complete, Sterling Connect:Express services are shown in the Service Configuration screen of SI interface (Dashboard) and in the modeler (GPM).

### *Installing on UNIX*

Logon to the SI user account and do the following (we suppose that the SI installation directory is <installdir>):

1. Change directory to <installdir>/bin of SI, and stop SI if it is running.

In a test environment:

---

```
# ./hardstop.sh
```

---

In a production environment:

---

```
# ./softstop.sh
```

---

Copy CXSI\_UNIX\_5.2.tar in a temporary directory.

2. Extract the archive:

---

```
# tar xvf CXSI_UNIX_5.2.tar
```

---

3. The following files are extracted:

- ❖ cx\_5.2.jar
- ❖ cxcmd.jar
- ❖ CXJAI.jar
- ❖ cxlogger.txt
- ❖ installer.jar
- ❖ install.sh

If the present version of Sterling B2B Integrator is an upgrade of GIS 4.3/4.2 and if the services of Sterling Connect:Express for GIS were already installed in the previous version, it is necessary to uninstall the previous version before installing this new version of the services (The products name has indeed been changed from Connect\_Express\_GIS\_Adapters to Connect\_Express\_SI\_Adapters). In that case, use the Add or Remove program utility of the Control Panel to uninstall.

---

**IMPORTANT:** VERIFY THAT THE STERLING B2B INTEGRATOR DATABASE SERVER IS STARTED BEFORE BEGINNING TO INSTALL THE SERVICES. (If the database server of SI is installed as a Microsoft Windows service, verify that this Microsoft Windows service is started).

---

4. Install the services:

---

```
# ./install.sh
```

---

5. Restart SI.

---

```
# cd <installdir>/bin  
# ./run.sh
```

---

### *Installing on Microsoft Windows*

1. Logon to the SI user account and do the following (we suppose that the SI installation directory is <installdir>).
2. Open a DOS command Microsoft Windows, change directory to <installdir>\bin of SI, and stop SI if it is running.

In a test environment:

```
# hardstop.cmd
```

In a production environment:

```
# softstop.cmd
```

3. Copy CXSI\_WIN\_5.2.zip in a temporary folder, for example c:\tmpdir.
4. Extract the archive (with WinZip for example).

If the present version of Sterling B2B Integrator is an upgrade of GIS 4.3/4.2 and if the services of Sterling Connect:Express for GIS were already installed in the previous version, it is necessary to uninstall the previous version before installing this new version of the services (The products name has indeed been changed from Connect\_Express\_GIS\_Adapters to Connect\_Express\_SI\_Adapters). In that case, use the Add or Remove program utility of the Control Panel to uninstall.

**IMPORTANT:** VERIFY THAT THE STERLING B2B INTEGRATOR DATABASE SERVER IS STARTED BEFORE BEGINNING TO INSTALL THE SERVICES. (If the database server of SI is installed as a Microsoft Windows service, verify that this Microsoft Windows service is started).

5. Start setup.exe to install the services.
6. Restart SI.

---

```
# run.cmd
```

---

---

## Configuring the Listening Port of Sterling Connect:Express

Activate the listening port of Sterling Connect:Express differently on Microsoft Windows and UNIX.

### *Microsoft Windows*

Sterling Connect:Express for Microsoft Windows monitor can listen to remote API clients. The default port number is 7000. You can display and update the active port number in the Graphical interface of Sterling Connect:Express through the dialog box « Administration \ Parameters \ Monitor \ Network \ TCP/IP ».

### *UNIX*

You can configure the API listening port in the sysin file of Sterling Connect:Express in \$TOM\_DIR/config. Edit the sysin file and add the line:

---

```
APPORt=<port-number>
```

---

Stop/start the monitor to activate the API server, tom\_api process

---

## Description of Sterling Connect:Express Services

The following table shows the list of the services provided:

<b>Service</b>	<b>Description</b>
CXTransferSubmit	Submit a transfer request to Sterling Connect:Express
CXTransferStatus	Inquire the status of a file transfer (Ended or running)
CXTransferControl	Interrupt, restart, purge a file transfer
CXPartner	Manage symbolic partners.
CXFile	Manage symbolic files.
CXSession	Manage PeSIT and Etebac3 session tables.
CXPresentation	Manage PeSIT and Etebac3 presentation tables of Sterling Connect:Express for UNIX Manage PeSIT presentation tables of Sterling Connect:Express Microsoft Windows.
CXEtb3Presentation	Manage Etebac3 presentation tables of Sterling Connect:Express Microsoft Windows.
CXJournal	List of the Journal.
CXActivity	List of active transfers.
CXConfiguration	List the configuration file and the asset protection information.
CXStatistics	List of the statistics.

A service enables you to access a component (Transfer request, Partner, File, Table ...) with different modes. The following table shows the list of the modes available:

<b>Mode</b>	<b>Description</b>
CREATE	Creation. A new element is added, an error is returned if it is a duplicate.
REPLACE	Replace. A new element is added, it is replaced if it is a duplicate.
UPDATE	Update. The element is updated with the parameters provided.
GET	Read one or several elements. Characteristics of the elements selected are recorded in a document.
DELETE	Delete an element.
LIST	Read several elements. The list of elements selected is recorded in a document.
SUBMIT	Submit a file transfer request.
INTERRUPT	Interrupt a file transfer.
RESTART	Restart a file transfer.
PURGE	Purge one or several transfer requests

All modes are not available for each service: for example REPLACE is not available CXJournal service.

## Implementing a Sterling Connect:Express Service

To implement a Sterling Connect:Express service do the following:

- ❖ Create a service instance with SI interface.
- ❖ Create a bpml source file with the modeler, to use this instance.
- ❖ Import the business process source code with the SI interface: check-in the bpml file that you created.


### *Creating a Service Instance*

Use Deployment/Services/Configuration/New Service of SI interface to create a new instance of a service. Sterling Connect:Express services are shown in the list, starting with "CX".

### Services Configuration

**CXFileInst: Name**

Name :	CXFileInst
Description:	Connect:Express symbolic files
Select a group:	
<input checked="" type="radio"/> None	
<input type="radio"/> Create New Group	<input type="text"/>
<input type="radio"/> Select Group:	<input type="button" value="▼"/>

Fill in the parameters of the instance. You are not required to define all parameters: some can be left empty or set to [Undefined]. You will be able to provide them when creating the Business process. If you are creating an instance for one monitor, you can then fill in the IP address, listening port, OS type and Login information.

## Services Configuration

CXFileInst: Connect:Express File Management (1/5)

Connect:Express address:	localhost
Connect:Express api port:	9000
OS type:	Unix
User name:	ADMIN
User password:	*****
Logging:	TRUE
Api Trace:	FALSE
Mode:	[Undefined]
File name:	

Some parameters are OS dependant. For example SNA LU6.2 is available for Sterling Connect:Express for Microsoft Windows only: in this case the name of the OS is indicated in the parameter label . While executing the service, parameters that are not applicable are ignored.


### *Creating a Business Process*

The service instance that you created is available when configuring the service in a business process. The example below shows how the modeler screen displays a Sterling Connect:Express service instance and parameters.


You can change the parameters that you defined in the instance. You can define the parameters that you did not define in the instance, using constants or XPATH expressions.

In order to clear a parameter, use «"» (double quote, between quotes) as shown for the EndReceiveCommand field in the example. If you let the field blank, this means that you don't define the parameter.

In UPDATE mode letting the field blank will not change the field, setting the field to « " » will set the field to spaces or zero according to the type of field.



You can view the result in the bpml source code screen, as shown below:



### Checking-in the Business Process

Use SI interface to check-in the Business Process in SI.

### Process Definition Check In

Process: CXFileUpdateP: Select Definition

Filename:

Description:

Buttons:

## Executing a Sterling Connect:Express Service

While executing the business process, a call to a Sterling Connect:Express service writes the service request parameters in the process data (<CXServiceRequest> element), then the service response (<CXServiceResponse> element) with the return code, possible error message and any information related to the service (number of elements returned, transfer request number ...).

For GET and LIST modes, the execution of the service writes the information returned in a document CX<service>\_<step>. Most are XML documents.

## Logging Calls to Services

If you select option Logging=True for a service, the service parameters are recorded in the cx.log file. Use Operations / System / Logs as shown below. Select ConnectExpress Adapters / cxlog to display the trace of call to Sterling Connect:Express services.

Operations				
System				
▪ Troubleshooter				Logging: Off
▶ Performance				Logging: Off
▶ Support Tools				Logging: Off
▪ Logs				Logging: Off
▪ Licenses				Logging: Off
▪ Reports				Logging: Off
▪ Thread Monitor				Logging: Off
▪ JDBC Monitor				Logging: Off
▪ Archive Manager				Logging: Off
▪ Lock Manager				Logging: Off
▪ Message Monitor				Logging: Off
▪ Perimeter Servers				Logging: Off
▪ Federated Systems				Logging: Off
▶ Accounts				Logging: Off
Business Process Exceptions				
Business Process Execution				
▶ wf.log	03/11/2007 00:00:00	193 KB	Logging: Off	
▶ wf.log	03/10/2007 14:25:46	78 KB	Logging: Off	
Business Process Policy Statistics				
Connect Direct Secure Perimeter Adapter				
Connect:Direct Server Adapter Protocol Layer				
Connect:Direct Server and Requester Adapter and Services				
▶ cdinterop.log	04/02/2007 00:00:00	0 KB	Logging: Off	
▶ cdinterop.log	04/01/2007 00:00:00	1 KB	Logging: Off	
▶ cdinterop.log	03/31/2007 00:00:00	1 KB	Logging: Off	
▶ cdinterop.log	03/30/2007 14:15:26	1 KB	Logging: Off	
Connect:Enterprise Server Adapter and Services				
Connect:Express Adapters				
▶ cx.log	04/02/2007 00:00:00	0 KB	Logging: Off	

[2007-03-30 17:15:22.222] Proces:CXPartnerGetAllP.Id:286085.Service:CXPartnerInst.Request:partner Serverid=localhost:9000:X:ADMIN:****:FALSE:0:30:0,PartnerName=*,Mode=get,	ALL	000000000000	GLOBAL_SCOPE
[2007-03-30 17:39:12.647] Proces:CXTransferSubWaitP.Id:286111.Service:CXTransferSubInst.Request:transfer Serverid=localhost:9000:X:ADMIN:****:FALSE:0:30:0,FileName=FILE01,PhysicalName=\$TOM_DIR/config/sysin.txt,TransferDirection=T,PartnerName=BOUCLE,TypeOfLink=T,FileLabel=lab01,LocalName=BOUCLE,LocalPassword=PSW,TypeOfFile=TV,FileRecordLength=8192,Mode=submit,	ALL	000000000000	GLOBAL_SCOPE

---

## Tracing Communications with a Monitor

If you need to troubleshoot communication problems between a SI service and a monitor, select option ApiTrace=True to trace TCP/IP session. The data flow of the TCP/IP session is written in a file located in the directory « user.home », and called « cxjai.<Monitor-Address>.<api-port >.trc ».

On UNIX, user.home = \$HOME.

On Microsoft Windows, user.home = c:\Document And Settings\username.

You can send this trace file to Sterling Commerce support specialists for analysis.

This chapter provides a detailed description of Sterling Connect:Express services.



# Chapter 2

---

## Reference Guide

The following pages show parameters and examples of process data and documents created for each service. Tables below show parameters, with data types from the following list:

- ❖ S: String, uppercase
- ❖ s: String case sensitive
- ❖ C: Character
- ❖ i: Integer
- ❖ L: Long
- ❖ B: Boolean (true or false)
- ❖ D: Date format AAAA/MM/JJHH:MM:SS or HH:MM

Standard default values for modes CREATE and REPLACE, are spaces for types S and s, spaces for type c, zero for types i and L, false for type Boolean. When the default value is not the standard one, it is specified.

UNIX and Win columns indicate if the parameter is available on this OS, and the maximum length of the parameter if applicable.

The first table shows parameters that are shared by all services, and are required.

---

### Parameters Shared by all Services

Parameters related to connection to monitor and login to monitor as well as trace parameters are listed below. They are required.

Field name	Description	Win	UNIX	Data Type
Sterling Connect:Express Address	IP address or host name of the monitor	128	128	s
Sterling Connect:Express api port	TCP/IP Port of the monitor api server	5	5	i
OSType	Operating system on which the monitor is executing (UNIX, Microsoft Windows)	7	7	S
UserName	User name for loggin to the monitor Use « ADMIN »	8	8	S
UserPassword	User password for loggin to the monitor Use « ADMIN »	8	8	S
Logging	True: service parameters are written in the trace file cx.log of SI	5	5	S
ApiTrace	True: TCP/IP session between SI and the monitor (refer to « Tracing Communications with a monitor »)	5	5	S

---

## CXActivity

CXActivity service enables you to display information about active transfers (GET) or list active transfers (LIST). Information is written in a document.

Active transfers have the following status:

### UNIX:

- ❖ A: Waiting selection
- ❖ C: Running
- ❖ O: Interrupted
- ❖ H: Held
- ❖ D: Delayed
- ❖ J: Waiting delay
- ❖ K: Waiting restart

### Microsoft Windows:

- ❖ W: Waiting selection
- ❖ T: Selected
- ❖ C: Running
- ❖ I: Interrupted
- ❖ S: Selection error
- ❖ R: Automatic restart

Information returned by this service is subject to constant change.

### CXActivity Parameters

Field name	Description	Win	UNIX	Data Type
Mode	get or list	7	7	S
RequestNumber	Transfer request number(wildcard supported)	12	8	S
TransferDirection	Transfer direction (T:Transmission, R:Reception, *:Both)	1	1	c
PartnerName	Symbolic partner name or '*'	8	8	S
FileName	Symbolic file name or '*'	8	8	S
Requestor	Requestor name (User, process, ...) or '*' *	8	8	S
TypeOfUser	Requestor type (E:External, I:Internal, *:Both)	1		c
UserRequestId	Transfer request user identification or '*'	16		s
DocumentFormat	List format: XML, Column, Column with header	-	-	-

---

**Note:** setting a parameter to '\*' is equivalent to omit the parameter.

---

### Example

Executing the CXActivity service with (Mode=list,DocumentFormat=ColumnWithHeader) results in the following:

## *ProcessData*

---

### Process Data

```
Process Name: CXActivityListColP      Instance ID: 289669
Service Name: CXActivityInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXActivityRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <Mode>list</Mode>
  </CXActivityRequest>
  <CXActivityList_1 SCIObjectID="localhost:9ed927:111b192d865:5bba"/>
  <CXActivityResponse>
    <ActivityCount>4</ActivityCount>
    <ReturnCode>ACTIVITY_LIST_SUCCESSFUL</ReturnCode>
  </CXActivityResponse>
</ProcessData>
```

---

## *Document*

---

### CXActivityList\_1

```
Process Name: CXActivityListColP      Instance ID: 289669
Service Name: CXActivityInst
Document in process data:
```

---

Request	Requestor	FileName	PartnerName	Dir	Status
09300006	pga	FILE01	BOUCLE	R	C
09300005	pga	FILE01	BOUCLE	R	C
09300002	pga	FILE01	BOUCLE	T	C
09300001	pga	FILE01	BOUCLE	T	C

---

---

## CXConfiguration

The CXConfiguration service Displays the configuration parameters of a monitor and the content of the asset protection key.

### *CXConfiguration Parameters*

Field name	Description	Win	UNIX	Data Type
Mode	Get	7	7	S

### *Example*

Executing the CXConfiguration service results in the following:

#### *ProcessData*

---

##### Process Data

```
Process Name: CXConfigurationGetP      Instance ID: 286110
Service Name: CXConfigurationInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXConfigurationRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <Mode>get</Mode>
  </CXConfigurationRequest>
  <CXConfigurationGet_1 SCIObjectID="localhost:9ed927:111a2c498f0:-48c2"/>
  <CXConfigurationResponse>
    <ReturnCode>CONFIGURATION_GET_SUCCESSFUL</ReturnCode>
  </CXConfigurationResponse>
</ProcessData>
```

---

#### *Document*

---

##### CXConfigurationGet\_1

```
Process Name: CXConfigurationGetP      Instance ID: 286110
Service Name: CXConfigurationInst
Document Name: CXConfigurationGet_200703301737286110_1      Document Store: Database
Document in process data:

<?xml version="1.0" encoding="UTF-8"?>
<CXConfigurationGet>
  <Configuration>
    <OSType>UNIX</OSType>
    <GMTOffset>7200</GMTOffset>
    <AliasName>UNIX</AliasName>
    <ApiPort>9000</ApiPort>
    <ApiAddress/>
    <BuildDatabaseUsed>true</BuildDatabaseUsed>
    <Dpcsid>FEDORA</Dpcsid>
    <FtpListAllUsed>true</FtpListAllUsed>
```

---

---

```
<FtpDefaultFile>FTPFILE</FtpDefaultFile>
<FtpListenAddress/>
<FtpListenPort>0</FtpListenPort>
<StatisticsUsed>false</StatisticsUsed>
<SyslogUsed>false</SyslogUsed>
<LogSize>10000</LogSize>
<NotificationsUsed>true</NotificationsUsed>
<RunType>C</RunType>
<Dpcpsw>PSW</Dpcpsw>
<SessionTimer>1</SessionTimer>
<TcpipListenAddress/>
<TcpipListenPort>6677</TcpipListenPort>
<TraceUsed>false</TraceUsed>
<MaxTransfer>6</MaxTransfer>
<TransferTimer>1</TransferTimer>
<X25LocalPort/>
<X25LocalAddress/>
<ProductInfo>C:E/UNIX 142-1</ProductInfo>
<SystemInfo>Sysname:Linux.Release:2.6.17-1.2157_FC5.Version:#1
Tue Jul 11 22:55:46
    EDT 2006.Machine:i686.Nodename:localhost.localdomain</SystemInfo>
        <Mode>get</Mode>
    </Configuration>
</CXConfigurationGet>
```

---

---

## CXEtb3Presentation

The CXEtb3Presentation service enables you to manage the Etebac3 presentation tables of a monitor executing on Microsoft Windows. An entry is identified by the field PresentationTableId.

---

**Note:** For managing Etebac3 presentation tables on UNIX use CXPresentation.

---

### *CXEtb3Presentation Parameters*

Parameters for this service depend on the mode.

#### ***Modes create, replace or update***

Field name	Description	Win	UNIX	Data Type
Mode	create, replace or update	7	7	S
PresentationTableId	Name of the Etebac3 presentation table	50		s
TranslationUsed	Transcoding option (true/false)	5		
TranslationToEbcdic	Name or identification number of the transcoding table used from ASCII to EBCDIC	127		
TranslationToAscii	Name or identification number of the transcoding table used from EBCDIC to ASCII	127		

PresentationTableId parameter is required.

#### *Defaults:*

For modes create and replace, the following non standard defaults apply, if the parameter is omitted:  
TypeOfCompression=N, TranslationToEbcdic=TOMNT.ASC, TranslationToAscii=TOMNT.ASC.

#### *Example*

Executing the CXEtb3Presentation service with (Mode=replace) results in the following:

## *ProcessData*

---

### Process Data

```
Process Name: WCXEtb3PresentationReplaceP      Instance ID: 289056
Service Name: CXEtb3Presentation
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXEtb3PresentationRequest>
    <Serverid>10.87.15.92:7000:W:ADMIN:****:FALSE:0:30:0</Serverid>
    <PresentationTableId>Etb3 presentation 1</PresentationTableId>
    <TranslationUsed>TRUE</TranslationUsed>
    <TranslationToEbcdic>XX.ASC</TranslationToEbcdic>
    <TranslationToAscii>YY.EBC</TranslationToAscii>
    <Mode>replace</Mode>
  </CXEtb3PresentationRequest>
  <CXEtb3PresentationResponse>
    <ReturnCode>ETB3PRESENTATION_REPLACE_SUCCESSFUL</ReturnCode>
  </CXEtb3PresentationResponse>
</ProcessData>
```

---

### **Mode delete**

Field name	Description	Win	UNIX	Data Type
Mode	Delete	7	7	S
PresentationTableId	Name of the Etebac3 presentation table	50		s

The PresentationTableId field does not support wildcard.

### **Modes get or list**

Field name	Description	Win	UNIX	Data Type
Mode	get ou list	7	7	S
PresentationTableId	Name of the Etebac3 presentation table or wildcard	50		s

If PresentationTableId is omitted, all tables are displayed.

### *Example*

Executing the CXEtb3Presentation service with (Mode=get) results in the following:

## *ProcessData*

---

### Process Data

```
Process Name: WCXEtb3PresentationGetAllP      Instance ID: 289046
Service Name: CXEtb3Presentation
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
    <CXEtb3PresentationRequest>
        <Serverid>10.87.15.92:7000:W:ADMIN:****:FALSE:0:30:0</Serverid>
        <PresentationTableId/>
        <Mode>get</Mode>
    </CXEtb3PresentationRequest>
    <CXEtb3PresentationGet_1 SCIObjectID="localhost:9ed927:111b192d865:-6d1c"/>
    <CXEtb3PresentationResponse>
        <Etb3PresentationCount>2</Etb3PresentationCount>
        <ReturnCode>ETB3PRESENTATION_GET_SUCCESSFUL</ReturnCode>
    </CXEtb3PresentationResponse>
</ProcessData>
```

---

## *Document*

---

### CXEtb3PresentationGet\_1

```
Process Name: WCXEtb3PresentationGetAllP      Instance ID: 289046
Service Name: CXEtb3Presentation
Document Name: CXEtb3PresentationGet_200704021243289046_1      Document Store: Database
Document in process data:
<CXEtb3PresentationGet>
    <Etb3Presentation>
        <PresentationTableId>ETEBAC3      presentation      with
translation</PresentationTableId>
        <TranslationUsed>true</TranslationUsed>
        <TranslationToEbcdic>TOMNT.ASC</TranslationToEbcdic>
        <TranslationToAscii>TOMNT.EBC</TranslationToAscii>
    </Etb3Presentation>
    <Etb3Presentation>
        <PresentationTableId>ETEBAC3presentation      without
translation</PresentationTableId>
        <TranslationUsed>false</TranslationUsed>
        <TranslationToEbcdic/>
        <TranslationToAscii/>
    </Etb3Presentation>
</CXEtb3PresentationGet>
```

---

The CXFile service enables you to manage the symbolic files of a monitor. An entry is identified by the field FileName.

### CXFile Parameters

Parameters for this service depend on the mode.

#### Modes create, replace or update

Field name	Description	Win	UNI X	Data Type
Mode	create, replace or update	7	7	S
FileName	Symbolic file name Alphanumeric characters: A-Z,0-9,Space	8	8	S
FileComment	User description of the symbolic file	80		s
FileState	Symbolic file status (E: Enabled, H: Disabled)	1	1	C
TypeOfAllocation	Allocation Type (F: Fixed, D:Dynamic)	1	1	C
FileDirection	Transfer direction (T: Transmission, R: Reception, *: Both)	1	1	C
TypeOfFile	Type of file (TF: Text fixed, TV: Text variable, BF: Binary fixed, BU: Binary undefined)	2	2	S
FileOpenOption	File open option (N: New, R: replace, O: Old)	1	1	C
FileSender	Partner or list of partners allowed to transmit the file Characters supported: A-Z,0-9,Space,\$,* (Microsoft Windows) A-Z,0-9, Space,\$,* and # (UNIX)	8	8	S
FileReceiver	Partner or list of partners allowed to receive the file Characters supported: A-Z,0-9,Space,\$,* (Microsoft Windows) A-Z,0-9, Space,\$,* and # (UNIX)	8	8	S
PresentationTableId	Name or identification number of the presentation table	50	1	S
LocalPhysicalName	Local physical name	127	44	s
FileRecordLength	Record length	5	5	i
StartTransmitExit	Beginning of transmission user exit	127	12	s(*)
EndTransmitExit	End of transmission user exit	127	12	s(*)
StartReceiveExit	Beginning of reception user exit	127	12	s(*)
EndReceiveExit	End of reception user exit	127	12	s(*)
StartTransmitCommand	Beginning of transmission user command	127	12	s(*)
EndTransmitCommand	End of transmission user command	127	12	s(*)
StartReceiveCommand	Beginning of reception user command	127	12	s(*)
EndReceiveCommand	End of reception user command	127	12	s(*)
ErrorCommand	Transfer error user command	127		s
NotifyUsed	Notification option (true/false)	5		B

Field name	Description	Win	UNI X	Data Type
ClientToNotify	Name of the client to notify	8		S
Pi99OffsetT	Offset of Pi99ValueT field for pi99 of transmission	3		i
Pi99LengthT	Length of Pi99ValueT field for pi99 of transmission	3		i
Pi99ValueT	Pi99 field for transmission	254		s
Pi99OffsetR	Offset of Pi99ValueR field for pi99 of reception	3		i
Pi99LengthR	Length of Pi99ValueR field for pi99 of reception	3		i
Pi99ValueR	Pi99 field for reception	254		s
FileLabel	User identification of the file	80		s
Priority	Priority (0: High, 1: Normal, 2: Low)		1	C
RemotePhysicalName	Remote physical name		44	S
FtpOptions	FTP Options (Type/Structure/Mode) Type:(E:Ebcdic, A:Ascii, B: Binary, *: unchanged) Structure (F: File, R: Record, *: Unchanged) Mode (B: Block, S: Stream, *: Unchanged)		3	S
ParamFileUsed	Parameter card file option (true/false)		5	B
SpaceAllocationUsed	Space allocation option (true/false)		5	B
FtpStoreUniqueUsed	Ftp « store unique » option (true/false)		5	B
FileAgentUsed	File agent option (true/false)		5	B
TypeOfNotification	Type of Notification: 1 character ('0' to '7'). '0': No notification. '1': Notification at the beginning of the transfer. '2': Notification at the end of the transfer. '4': Notification if transfer error. Other possibilities are combinations with inclusive « OR » of these values. For example: '6' = '2' OR '4' for a notification at the end of transfer or in case of transfer error. Microsoft Windows: This flag is used for HTTP notification only. UNIX: This flag is used for HTTP notification or standard notification depending on the values of the keywords HTTPNF and NOTIFY in the sysin configuration file.	1	1	C

With modes **create** and **replace** the following parameters are required:

#### UNIX:

---

FileName, FileDirection, PresentationTableId, TypeOfFile, FileSender, FileReceiver, LocalPhysicalName.

---

#### Microsoft Windows:

---

```
FileName, FileName, FileDirection, PresentationTableId.
if FileDirection=R ou *: FileSender.
if FileDirection=T ou *: FileReceiver and FileRecordLength.
if NotifyUsed=true: ClientToNotify.
```

---

With mode **update** the following parameters are required:

---

FileName.

---

*Defaults:*

With modes **create** et **replace**, the following non standard defaults apply, if the parameter is omitted:

---

**UNIX, Microsoft Windows:** FileState = E, TypeOfAllocation=D, FileOpenOption=R.

**UNIX:** FtpOptions="\*\*\*\*".

---

(\*) Supported characters for user exit and user commands fields are: A-Z, 0-9, a-z, Space, \$, ., /, & and \_

### *Example*

Executing the CXFile service with (Mode=replace) results in the following:

---

#### Process Data

```
Process Name: CXFileReplaceP      Instance ID: 286098
Service Name: CXFileInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXFileRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <FileName>TEST</FileName>
    <FileState>E</FileState>
    <FileComment/>
    <TypeOfAllocation>D</TypeOfAllocation>
    <FileDirection>*</FileDirection>
    <LocalPhysicalName>$TOM_DIR/in/&REQNUMB.tmp</LocalPhysicalName>
    <Priority>1</Priority>
    <FileOpenOption>R</FileOpenOption>
    <SpaceAllocationUsed>FALSE</SpaceAllocationUsed>
    <FileSender>$$ALL$$</FileSender>
    <FileReceiver>$$ALL$$</FileReceiver>
    <PresentationTableId>1</PresentationTableId>
    <TypeOfFile>TV</TypeOfFile>
    <FileRecordLength>8192</FileRecordLength>
    <StartTransmitCommand/>
    <EndTransmitCommand/>
    <StartReceiveCommand/>
    <EndReceiveCommand>recv.sh</EndReceiveCommand>
    <ErrorCommand/>
    <StartTransmitExit/>
    <EndTransmitExit/>
    <StartReceiveExit/>
    <EndReceiveExit/>
    <FileLabel>lab01</FileLabel>
    <ParamFileUsed>FALSE</ParamFileUsed>
    <Pi990ffsetT/>
    <Pi99LengthT/>
    <Pi99ValueT/>
    <Pi990ffsetR/>
    <Pi99LengthR/>
    <Pi99ValueR/>
    <RemotePhysicalName/>
    <FtpOptions>***</FtpOptions>
    <FtpStoreUniqueUsed>FALSE</FtpStoreUniqueUsed>
    <FileAgentUsed>FALSE</FileAgentUsed>
    <TypeOfNotification>0</TypeOfNotification>
    <NotifyUsed>TRUE</NotifyUsed>
    <ClientToNotify/>
    <Mode>replace</Mode>
  </CXFileRequest>
  <CXfileResponse>
    <ReturnCode>FILE_REPLACE_SUCCESSFUL</ReturnCode>
  </CXfileResponse>
</ProcessData>
```

---

### **Mode delete**

Field name	Description	Win	UNIX	Data Type
Mode	Delete	7	7	S
FileName	Symbolic file name (no wildcard)	8	8	S

FileName field don't support wildcard.

### **Modes get or list**

Field name	Description	Win	UNIX	Data Type
Mode	get ou list	4	4	S
FileName	Symbolic file name or wildcard	8	8	S

If FileName field is omitted, all files are displayed or listed.

### *Example*

Executing the CXFile service with (Mode=get) results in the following:

#### *ProcessData*

---

##### Process Data

```

Process Name: CXFileGetAllP      Instance ID: 286097
Service Name: CXFileInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXFileRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <FileName/>
    <Mode>get</Mode>
  </CXFileRequest>
  <CXFileGet_1 SCIObjectID="localhost:9ed927:111a2c498f0:-4be2"/>
  <CXFileResponse>
    <FileCount>3</FileCount>
    <ReturnCode>FILE_GET_SUCCESSFUL</ReturnCode>
  </CXFileResponse>
</ProcessData>
```

---

## *Document*

---

```
CXFileGet_1
Process Name: CXFileGetAllP      Instance ID: 286097
Service Name: CXFileInst
Document Name: CXFileGet_200703301722286097_1      Document Store: Database
Document in process data:
<CXFileGet>
    <File>
        <FileName>FILE01</FileName>
        <FileState>E</FileState>
        <TypeOfAllocation>D</TypeOfAllocation>
        <FileDirection>*</FileDirection>
        <TypeOfFile>TV</TypeOfFile>
        <FileOpenOption>R</FileOpenOption>
        <FileSender>$$ALL$$</FileSender>
        <FileReceiver>$$ALL$$</FileReceiver>
        <PresentationTableId>1</PresentationTableId>
        <LocalPhysicalName>$TOM_DIR/in/&REQNUMB.txt</LocalPhysicalName>
        <FileRecordLength>2048</FileRecordLength>
        <StartTransmitExit/>
        <EndTransmitExit/>
        <StartReceiveExit/>
        <EndReceiveExit/>
        <StartTransmitCommand/>
        <EndTransmitCommand/>
        <StartReceiveCommand/>
        <EndReceiveCommand/>
        <Priority>1</Priority>
        <RemotePhysicalName/>
        <FtpOptions>***</FtpOptions>
        <ParamFileUsed>false</ParamFileUsed>
        <SpaceAllocationUsed>false</SpaceAllocationUsed>
        <FtpStoreUniqueUsed>false</FtpStoreUniqueUsed>
        <FileAgentUsed>false</FileAgentUsed>
        <TypeOfNotification>2</TypeOfNotification>
    </File>
    <File>
        <FileName>FILE02</FileName>
        ...
    <File>
        ...
</CXFileGet>
```

---

## *Example*

Executing the CXFile service with (Mode=list) results in the following:

### *ProcessData*

---

#### *Process Data*

```
Process Name: CXFileListP      Instance ID: 286099
Service Name: CXFileInst
<?xml version="1.0" encoding="UTF-8"?>
```

---

---

```
<ProcessData>
  <CXFileRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <FileName/>
    <Mode>list</Mode>
  </CXFileRequest>
  <CXFileList_1 SCIObjectID="localhost:9ed927:111a2c498f0:-4b7b"/>
  <CXFileResponse>
    <FileCount>3</FileCount>
    <ReturnCode>FILE_LIST_SUCCESSFUL</ReturnCode>
  </CXFileResponse>
</ProcessData>
```

---

### *Document*

---

#### CXFileList\_1

```
Process Name: CXFileListP      Instance ID: 286099
Service Name: CXFileInst
Document Name: CXFileList_200703301725286099_1      Document Store: Database
Document in process data:
  <CXFileList>
    <FileList>
      <FileName>FILE01</FileName>
      <FileName>FILE02</FileName>
      <FileName>TEST</FileName>
    </FileList>
  </CXFileList>
```

---

The CXJournal service enables you to display the Journal records. The journal record identifier is the RequestNumber field.

---

**Note:** the amount of data that is received when requesting the list of transfers can be very large; you should consider this problem when setting the selection criteria.

---

### CXJournal Parameters

#### **Modes get or list**

Field name	Description	Win	UNIX	Data Type
Mode	get ou list	4	4	S
RequestNumber	Transfer request number	12	8	S
Requestor	Requestor name (User, process, ...)	8		S
FileName	Symbolic file name	8	8	S
PartnerName	Symbolic partner name	8	8	S
TransferDirection	Transfer direction(T: Transmission, R: Reception, *: Both)	1	1	C
MinimumDate	Selection start date or *	18	18	D
MaximumDate	Selection end date or *	18	18	D
Status	Transfer status or * UNIX: A: waiting selection, H: held, K: waiting restart, C:running, E: ended, D: delayed, J: waiting delay, O: interrupted		1	C

#### *Example*

Executing the CXJournal service with (Mode=get) results in the following:

## *ProcessData*

---

### Process Data

```
Process Name: CXJournalGetAllP      Instance ID: 286114
Service Name: CXJournalInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXJournalRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <Interval>600</Interval>
    <Mode>get</Mode>
  </CXJournalRequest>
  <CXJournalGet_1 SCIOBJECTID="localhost:9ed927:111a2c498f0:-4746" />
  <CXJournalResponse>
    <JournalCount>2</JournalCount>
    <ReturnCode>JOURNAL_GET_SUCCESSFUL</ReturnCode>
  </CXJournalResponse>
</ProcessData>
```

---

## *Document*

---

```
CXJournalGet_1
Process Name: CXJournalGetAllP      Instance ID: 286114
Service Name: CXJournalInst
Document Name: CXJournalGet_200703301744286114_1      Document Store: Database
Document in process data:
  <CXJournalGet>
    <Transfer>
      <RequestNumber>08900007</RequestNumber>
      <TransferIdent>5@0007</TransferIdent>
      <ExternalRequestNumber>08900007</ExternalRequestNumber>
      <Requestor>REMAPI</Requestor>
      <Trc>0000</Trc>
      <TrcMessage/>
      <Prc>0000</Prc>
      <Src>0000</Src>
      <Nrc>0000</Nrc>
      <TcpipRc>0000</TcpipRc>
      <X25Rc/>
      <X25Cause/>
      <X25Diagnostic/>
      <Status>E</Status>
      <StatusMessage>Ended</StatusMessage>
      <TypeOfUser>I</TypeOfUser>
      <TypeOfRequest>N</TypeOfRequest>
      <TransferDirection>T</TransferDirection>
      <Priority>1</Priority>
      <TypeOfLink>T</TypeOfLink>
      <FileName>FILE01</FileName>
      <PhysicalName>$TOM_DIR/config/sysin.txt</PhysicalName>
      <LocalPhysicalName>$TOM_DIR/config/sysin.txt</LocalPhysicalName>
```

---

---

```
<RemotePhysicalName/>
<FileLabel>lab01</FileLabel>
<TransferOrigin>BOUCLE</TransferOrigin>
<TransferDestination>BOUCLE</TransferDestination>
<TransferSender/>
<TransferReceiver/>
<FileOrganization>S</FileOrganization>
<TypeOfFile>T</TypeOfFile>
<TypeOfCompression>M</TypeOfCompression>
<TypeOfData>A</TypeOfData>
<FileRecordLength>2048</FileRecordLength>
<NetworkMessageSize>4096</NetworkMessageSize>
<LocalName>BOUCLE</LocalName>
<PartnerName>BOUCLE</PartnerName>
<TypeOfPartner>O</TypeOfPartner>
<Protocol>0</Protocol>
<CrcUsed>false</CrcUsed>
<TcpipPort>6677</TcpipPort>
<TcpipHostName/>
<TcpipAddress>127.0.0.1</TcpipAddress>
<X25RemoteAddress/>
<X25LocalAddress/>
<X25LocalPort/>
<X25UserDataField/>
<X25Facilities/>
<TransferBeginningDate>2007/03/30 17:39:12</TransferBeginningDate>
<TransferEndDate>2007/03/30 17:39:13</TransferEndDate>
<RetryNumber>0</RetryNumber>
<FileOpenOption>R</FileOpenOption>
<NetworkBytes>00000000789</NetworkBytes>
<FileNumberOfRecords>22</FileNumberOfRecords>
<DateOfExecution>2007/03/30 17:39:12</DateOfExecution>
<PartnerPassword>PSW</PartnerPassword>
<UserDataReceived/>
<UserDataSent/>
<OriginPhysicalName/>
<FileApi/>
<ProcessId>21258</ProcessId>
<FileAgentUsed>false</FileAgentUsed>
<MultiArticleUsed>true</MultiArticleUsed>
<TranslationTableNumber>0</TranslationTableNumber>
<TypeOfNotification>2</TypeOfNotification>
<FtpOptions>***</FtpOptions>
<FtpStoreUniqueUsed>false</FtpStoreUniqueUsed>
<SpaceAllocationUsed>false</SpaceAllocationUsed>
<SessionTimer>0</SessionTimer>
<TransferTimer>0</TransferTimer>
<MaxRetries>0</MaxRetries>
<Mode>get</Mode>
</Transfer>
<Transfer>
...
</Transfer>

```

---

```
</CXJournalGet>
```

### *Example*

Executing the CXJournal service with (Mode=list,DocumentFormat=ColumnWithHeader) results in the following:

#### *ProcessData*

---

##### Process Data

```
Process Name: CXJournalListColP      Instance ID: 289007
Service Name: CXJournalInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXJournalRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <Mode>list</Mode>
  </CXJournalRequest>
  <CXJournalList_1 SCIObjectID="localhost:9ed927:111b192d865:-797d"/>
  <CXJournalResponse>
    <JournalCount>156</JournalCount>
    <ReturnCode>JOURNAL_LIST_SUCCESSFUL</ReturnCode>
  </CXJournalResponse>
</ProcessData>
```

---

#### *Document*

---

##### CXJournalList\_1

```
Process Name: CXJournalListColP      Instance ID: 289007
Service Name: CXJournalInst
Document Name: CXJournalList_200704021124289007_1      Document Store: Database
Document in process data:
-----
Request    Requestor   FileName  PartnerName Dir Status Date
-----
08700104    pga        FILE01    BOUCLE      T   E   2007/03/28 15:30:35
08700103    pga        FILE01    BOUCLE      T   E   2007/03/28 15:30:31
08700102    pga        FILE01    BOUCLE      R   E   2007/03/28 15:30:44
08700101    pga        FILE01    BOUCLE      T   E   2007/03/28 15:30:44
...

```

---

The CXPartner service enables you to manage symbolic partners. An entry is identified by the field PartnerName.

### CXPartner Parameters

Parameters for this service depend on the mode.

#### ***Modes create, replace or update***

Field name	Description	Win	UNIX	Data Type
Mode	create, replace or update	7	7	S
PartnerName	Symbolic partner name Supported characters: A-Z,0-9,Space	8	8	S
PartnerPassword	Symbolic partner password Supported characters: A-Z,0-9,Space	8	8	S
LocalNameType	Local identifier type(D:Dynamic, S:Static)	1		C
LocalName	Local alias name of Sterling Connect:Express	8	8	s
LocalPassword	Local alias password of Sterling Connect:Express	8	8	s
PartnerComment	User description of the symbolic partner	80		S
PartnerState	Status of the partner (E: Enabled, H: Disabled)	1	1	C
TypeOfPartner	Type of the partner (O: Non Sterling Connect:Express, T: Sterling Connect:Express)	1	1	C
RestartUsed	Automatic restart option (true, false)	5		B
Protocol	File transfer protocol UNIX: 1: Etebac3, 2: FTP, 3: PeSIT. Note: On UNIX, PeSIT level D or E is set in the session table Microsoft Windows: D: PeSIT-D, E: PeSIT-E, 3: Etebac3.	1	1	C
MaxSession	Maximum simultaneous sessions	3	2	i
MaxSessionIn	Maximum simultaneous Incoming sessions	3	2	i
MaxSessionOut	Maximum simultaneous outgoing sessions	3	2	i
SessionTableId	Name or identification number of the session table Note: Session table number are from « 0 » to « 9 » on UNIX	50	1	S
TypeOfLink	Network link type UNIX: T: TCP/IP, X: X25, P: PAD, M: TCP/IP+X25 Microsoft Windows: T: TCP/IP, S: SNA LU6.2	1	1	C
TcpipAddress	Remote TCP/IP address	15	15	S
TcpipHostName	Remote TCP/IP host name	127	32	s
Field name	Description	Win	UNIX	Data Type
TcpipPort	Remote TCP/IP port	5	5	i

Field name	Description	Win	UNIX	Data Type
SnaLuName	Remote SNA LU6.2 address	8		S
AppcModeName	Remote LU6.2 mode name	8		S
AppcTpName	Remote LU6.2 transaction program name	64		S
X25LocalAddress	Local X25 address Numeric characters: 0-9	15	15	S
X25LocalPort	Local X25 port number	2	1	S
X25RemoteAddress	Remote X25 address Numeric characters: 0-9	15	15	S
X25UserDataField	X25 user data field Hexadecimal characters: 0-9,A-F	8	8	S
X25Facilities	X25 facilities Hexadecimal characters: 0-9,A-F	32	16	S
FtpDefaultFile	Default FTP file name Supported characters: A-Z,0-9,Space		8	S
RetryNumber	Maximum number of retries		8	i
SessionTimer	Session retry Timer		2	i
TransferTimer	Transfer retry Timer		2	i
Ss1ParmId	SSLPARM identifier Supported characters: A-Z,0-9,Space		8	S
RemoteClientSubjectDn	Criteria for remote client subject DN control	256		S
RemoteClientRootDn	Criteria for remote client root DN control	256		S
RemoteServerSubjectDn	Criteria for remote server subject DN control	256		S
RemoteServerRootDn	Criteria for remote server root DN control	256		S

With modes **create** and **replace** the following parameters are required:

---

PartnerName, TypeOfPartner, Protocol, SessionTableId, TypeOfLink.

---

*Microsoft Windows:*

---

For TCP/IP, TcpipAddress or TcpipHostName.

For SNA, SnaLuName and AppcModeName.

For X25, X25LocalPort.

---

With mode **update** the following parameters are required:

---

PartnerName.

---

*Defaults:*

With modes **create** et **replace**, the following non standard defaults apply, if the parameter is omitted:

---

UNIX, Microsoft Windows: PartnerState = E.

Microsoft Windows: RestartUsed=true, MaxSession=2 , MaxSessionIn=1, MacSessionOut=1.

---

(\*) Supported characters for user exit and user commands fields are: A-Z, 0-9, a-z, Blank, \$, ., /, & and \_ .

#### **Mode delete**

Field name	Description	Win	UNIX	Data Type
Mode	Delete	6	6	S
PartnerName	Symbolic partner name (no wildcard)	8	8	S

PartnerName field don't support wildcard.

#### **Modes get or list**

Field name	Description	Win	UNIX	Data Type
Mode	get ou list	4	4	S
PartnerName	Symbolic partner name or wildcard	8	8	S

If the PartnerName field is omitted, all partners are displayed or listed.

#### *Example*

Executing the CXPartner service with (Mode=replace) results in the following:

## *ProcessData*

---

### Process Data

```
Process Name: CXPartnerReplaceP      Instance ID: 286096
Service Name: CXPartnerInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXPartnerRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <PartnerName>TEST</PartnerName>
    <PartnerPassword>PSW</PartnerPassword>
    <LocalNameType/>
    <LocalName>TEST</LocalName>
    <LocalPassword>PSW</LocalPassword>
    <PartnerComment/>
    <PartnerState>E</PartnerState>
    <TypeOfPartner>O</TypeOfPartner>
    <RestartUsed/>
    <Protocol>E</Protocol>
    <MaxSession>20</MaxSession>
    <MaxSessionIn>10</MaxSessionIn>
    <MaxSessionOut>10</MaxSessionOut>
    <SessionTableId>1</SessionTableId>
    <TypeOfLink>T</TypeOfLink>
    <TcpipAddress>127.0.0.1</TcpipAddress>
    <TcpipPort>6677</TcpipPort>
    <TcpipHostName/>
    <SnaLuName/>
    <AppcModeName/>
    <AppcTpName/>
    <X25LocalAddress/>
    <X25RemoteAddress/>
    <X25LocalPort/>
    <X25UserDataField/>
    <X25Facilities/>
    <FtpDefaultFile/>
    <RetryNumber/>
    <SessionTimer/>
    <TransferTimer/>
    <SslparmId/>
    <Mode>replace</Mode>
  </CXPartnerRequest>
  <CXPartnerResponse>
    <ReturnCode>PARTNER_REPLACE_SUCCESSFUL</ReturnCode>
  </CXPartnerResponse>
</ProcessData>
```

---

### *Example*

Executing the CXPartner service with (Mode=get) results in the following:

#### *ProcessData*

---

##### Process Data

```
Process Name: CXPartnerGetAllP      Instance ID: 286085
Service Name: CXPartnerInst

<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXPartnerRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <PartnerName/>
    <Mode>get</Mode>
  </CXPartnerRequest>
  <CXPartnerGet_1 SCIOBJECTID="localhost:9ed927:111a2c498f0:-4f88"/>
  <CXPartnerResponse>
    <PartnerCount>3</PartnerCount>
    <ReturnCode>PARTNER_GET_SUCCESSFUL</ReturnCode>
  </CXPartnerResponse>
</ProcessData>
```

---

### *Document*

---

#### CXPartnerGet\_1

```
Process Name: CXPartnerGetAllP      Instance ID: 286085
Service Name: CXPartnerInst
Document Name: CXPartnerGet_200703301715286085_1      Document Store: Database
Document in process data:
<CXPartnerGet>
  <Partner>
    <PartnerName>BOUCLE</PartnerName>
    <PartnerPassword>PSW</PartnerPassword>
    <LocalName>BOUCLE</LocalName>
    <LocalPassword>PSW</LocalPassword>
    <PartnerState>E</PartnerState>
    <TypeOfPartner>0</TypeOfPartner>
    <Protocol>3</Protocol>
    <MaxSession>20</MaxSession>
    <MaxSessionIn>10</MaxSessionIn>
    <MaxSessionOut>10</MaxSessionOut>
    <SessionTableId>1</SessionTableId>
    <TypeOfLink>T</TypeOfLink>
    <TcpipAddress>127.0.0.1</TcpipAddress>
```

---

---

```
<TcpipPort>6677</TcpipPort>
<TcpipHostName/>
<X25LocalAddress/>
<X25RemoteAddress/>
<X25LocalPort/>
<X25UserDataField/>
<X25Facilities/>
<FtpDefaultFile/>
<RetryNumber>0</RetryNumber>
<SessionTimer>0</SessionTimer>
<TransferTimer>0</TransferTimer>
<SslparmId/>
</Partner>
<Partner>
...
</Partner>
</CXPartnerGet>
```

---

### *Example*

Executing the CXPartner service with (Mode=list) results in the following:

#### *ProcessData*

---

##### Process Data

```
Process Name: CXPartnerListP      Instance ID: 286095
Service Name: CXPartnerInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXPartnerRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <PartnerName/>
    <Mode>list</Mode>
  </CXPartnerRequest>
  <CXPartnerList_1 SCIObjectID="localhost:9ed927:111a2c498f0:-4c4b"/>
  <CXPartnerResponse>
    <PartnerCount>3</PartnerCount>
    <ReturnCode>PARTNER_LIST_SUCCESSFUL</ReturnCode>
  </CXPartnerResponse>
</ProcessData>
```

---

#### *Document*

---

##### CXPartnerList\_1

```
Process Name: CXPartnerListP      Instance ID: 286095
Service Name: CXPartnerInst
Document Name: CXPartnerList_200703301719286095_1      Document Store: Database
Document in process data:
<CXPartnerList>
  <PartnerList>
```

---

---

```
<PartnerName>BOUCLE</PartnerName>
<PartnerName>BOUCLE1</PartnerName>
<PartnerName>BOUCLE2</PartnerName>
</PartnerList>
</CXPartnerList>
```

---

The CXPresentation service enables you to manage the PeSIT and Etebac3 presentation tables of the Sterling Connect:Express for UNIX monitor and PeSIT presentation tables of the Sterling Connect:Express for Microsoft Windows monitor. An entry is identified by the parameter PresentationTableId.

On UNIX the presentation tables are identified by numbers « 0 » to « 9 ». You can neither create nor delete a presentation table. On Microsoft Windows presentation tables are identified by a string. You can create and delete them

---

**Note:** To manage Etebac3 presentation tables of the Sterling Connect:Express for Microsoft Windows monitors, use « CXEtb3Presentation » service.

---

### CXPresentation Parameters

Parameters for this service depend on the mode.

#### **Modes create (Microsoft Windows), replace or update**

Field name	Description	Win	UNIX	Data Type
Mode	create (Microsoft Windows only), replace, update	7	7	S
PresentationTableId	Name or identification number of the presentation table	50	1	s
TypeOfCompression	Type of compression (N: none, H: horizontal, V: vertical, M: horizontal and vertical)	C	C	C
ConcatenationUsed	PeSIT FPDU Concatenation option (true/false)	5		B
MultiArticleUsed	PeSIT fpdu Multi-article option (true/false)	5	5	B
SegmentationUsed	PeSIT fpdu Segmentation option (true/false)	5		B
TranslationUsed	Transcoding option (true/false)	5		B
TranslationToEbcdic	Name or identification number of the transcoding table from ASCII to EBCDIC	127	1	S
TranslationToAscii	Name or identification number of the transcoding table from EBCDIC to ASCII	127		S

With modes **create** and **replace** the following parameters are required:

#### *UNIX replace:*

---

PresentationTableId, TypeOfCompression, TranslationToEbcdic.

---

#### *Microsoft Windows:*

---

PresentationTableId.

---

With mode **update** the following parameters are required:

---

PresentationTableId.

---

*Defaults:*

With modes **create** et **replace**, the following non standard defaults apply, if the parameter is omitted:

TypeOfCompression=N, TranslationToEbcDIC=TOMNT.ASC, TranslationToASCII=TOMNT.ASC (Microsoft Windows).

**Mode delete (Microsoft Windows)**

Field name	Description	Win	UNIX	Data Type
Mode	delete (Microsoft Windows uniquement)	6		S
PresentationTableId	Name or identification number of the presentation table (no wildcard)	50		s

PresentationTableId field does not support wildcard.

**Modes get or list**

Field name	Description	Win	UNIX	Data Type
Mode	get, ou list	4	4	S
PresentationTableId	Name or identification number of the presentation table	50		s

If the PresentationTableId field is omitted, all tables are displayed or listed.

*Example*

Executing the CXPresentation service with (Mode=replace) results in the following:

*ProcessData*

---

```
Process Name: CXPresentationReplaceP      Instance ID: 286109
Service Name: CXPresentationInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXPresentationRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <PresentationTableId>9</PresentationTableId>
    <TypeOfCompression>M</TypeOfCompression>
    <ConcatenationUsed/>
    <MultiArticleUsed>FALSE</MultiArticleUsed>
    <SegmentationUsed/>
    <TranslationUsed/>
    <TranslationToEbcDIC>4</TranslationToEbcDIC>
    <TranslationToASCII/>
    <Mode>replace</Mode>
  </CXPresentationRequest>
  <CXPresentationResponse>
    <ReturnCode>PRESENTATION_REPLACE_SUCCESSFUL</ReturnCode>
  </CXPresentationResponse>
</ProcessData>
```

---

### *Example*

Executing the CXPresentation service with (Mode=get) results in the following:

#### *ProcessData*

---

```
Process Data

Process Name: CXPresentationGetAllP      Instance ID: 286106
Service Name: CXPresentationInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXPresentationRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <PresentationTableId/>
    <Mode>get</Mode>
  </CXPresentationRequest>
  <CXPresentationGet_1 SCIOBJECTID="localhost:9ed927:111a2c498f0:-49df"/>
  <CXPresentationResponse>
    <PresentationCount>9</PresentationCount>
    <ReturnCode>PRESENTATION_GET_SUCCESSFUL</ReturnCode>
  </CXPresentationResponse>
</ProcessData>
```

---

#### *Document*

---

```
CXPresentationGet_1

Process Name: CXPresentationGetAllP      Instance ID: 286106
Service Name: CXPresentationInst
Document Name: CXPresentationGet_200703301734286106_1      Document Store: Database
Document in process data:
  <CXPresentationGet>
    <Presentation>
      <PresentationTableId>1</PresentationTableId>
      <TypeOfCompression>M</TypeOfCompression>
      <MultiArticleUsed>true</MultiArticleUsed>
      <TranslationToEbcdic>0</TranslationToEbcdic>
    </Presentation>
    <Presentation>
      ...
    </Presentation>
  </CXPresentationGet>
```

---

The CXSession service enables you to manage the session tables of the Sterling Connect:Express monitors. An entry is identified by the parameter SessionTableId.

On UNIX the session tables are identified by numbers « 0 » to « 9 ». You can neither create nor delete a session table. On Microsoft Windows session tables are identified by a string. You can create and delete them

### *CXSession Parameters*

Parameters for this service depend on the mode.

#### ***Modes create, replace or update***

Field name	Description	Win	UNIX	Data Type
Mode	create, replace or update	7	7	S
SessionTableId	Name or identification number of the session table	50	1	S
BaseMessageSize	Network message size (negotiated) Microsoft Windows: 256-4096, UNIX: 0-6535	4	5	i
BaseSynchronizationSize	Synchronization buffer size in Kbytes (negotiated) Microsoft Windows: 1-32, UNIX: 0-99	2	2	i
SessionDirection	Direction (T: Transmission only, R: Reception only, *: Both)	1		C
CrcUsed	CRC option (true/false)	5	5	B
ResynchronizationNumber	Number of online retries	2		i
BaseMicrosoftWindowsize	Synchronization window size (negotiated) 0-16		2	i
ProtocolVersion	Protocole version (1: PeSIT-D,2: PeSIT-E)		1	C
RetryNumber	Number of retries		2	i

With modes **create** and **replace** the following parameters are required:

---

**UNIX replace:** SessionTableId, TypeOfCompression, TranslationToEbcdic.

**Microsoft Windows:** SessionTableId.

---

With mode **update** the following parameters are required:

---

SessionTableId.

*Defaults:*

---

With mode **update**, the following non standard defaults apply, if the parameter is omitted:

---

ProtocolVersion=2 (UNIX).

### **Modes delete (Microsoft Windows)**

Field name	Description	Win	UNIX	Data Type
Mode	Delete	6		S
SessionTableId	Name or identification number of the session table (no wildcard)	50		S

SessionTableId field does not support wildcard.

### **Modes get or list**

Field name	Description	Win	UNIX	Data Type
Mode	get ou list	4	4	S
SessionTableId	Name or identification number of the session table	50	1	S

If the SessionTableId field is omitted, all tables are displayed or listed.

### *Example*

Executing the CXSession service with (Mode=replace) results in the following:

#### *ProcessData*

---

##### Process Data

```

Process Name: CXSessionReplaceP      Instance ID: 286105
Service Name: CXSessionInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXSessionRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <SessionTableId>9</SessionTableId>
    <BaseMessageSize>24000</BaseMessageSize>
    <BaseSynchronizationSize>80</BaseSynchronizationSize>
    <SessionDirection/>
    <CrcUsed>TRUE</CrcUsed>
    <ResynchronizationNumber/>
    <BaseMicrosoft Windowsize>8</BaseMicrosoft Windowsize>
    <ProtocolVersion>1</ProtocolVersion>
    <RetryNumber>30</RetryNumber>
    <Mode>replace</Mode>
  </CXSessionRequest>
  <CXSessionResponse>
    <ReturnCode>SESSION_REPLACE_SUCCESSFUL</ReturnCode>
  </CXSessionResponse>
</ProcessData>

```

---

*Example*

Executing the CXSession service with (Mode=get) results in the following:

*ProcessData*

*Document*

---

CXSessionGet\_1

```
Process Name: CXSessionGetAllP      Instance ID: 286104
Service Name: CXSessionInst
Document Name: CXSessionGet_200703301732286104_1      Document Store: Database
Document in process data:
<CXSessionGet>
    <Session>
        <SessionTableId>1</SessionTableId>
        <BaseMessageSize>4096</BaseMessageSize>
        <BaseSynchronizationSize>32</BaseSynchronizationSize>
        <CrcUsed>false</CrcUsed>
        <BaseMicrosoft Windowsize>2</BaseMicrosoft Windowsize>
        <ProtocolVersion>2</ProtocolVersion>
        <RetryNumber>0</RetryNumber>
    </Session>
    <Session>
    ...
    </Session>
</CXSessionGet>
```

---

---

## CXStatistics

If the Statistics function is enabled in the monitor configuration, the CXStatistics service enables you to display selected statistics.

**Note:** the amount of data that is received when requesting the statistics can be very large; you should consider this problem when setting the selection criteria.

---

### CXStatistics Parameters

Field name	Description	Win	UNIX	Data Type
Mode	Get	3	3	S
MinimumDate	Selection start date or *	18	18	D
MaximumDate	Selection end date or *	18	18	D
RequestNumber	Request number or *	12	8	S
Interval	Last events interval in number of seconds	12	12	i

### Example

Executing the CXStatistics service with (Mode=get) results in the following:

### ProcessData

---

#### Process Data

```
Process Name: CXStatisticsGetP      Instance ID: 286125
Service Name: CXStatisticsInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXStatisticsRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <Interval>3600</Interval>
    <Limit>100</Limit>
    <Mode>get</Mode>
  </CXStatisticsRequest>
  <CXStatisticsGet_1 SCIOBJECTID="localhost:9ed927:111a2c498f0:-448b"/>
  <CXStatisticsResponse>
    <StatisticsCount>17</StatisticsCount>
    <ReturnCode>STATISTICS_GET_SUCCESSFUL</ReturnCode>
  </CXStatisticsResponse>
</ProcessData>
```

---

## **Document**

---

CXStatisticsGet\_1

```
Process Name: CXStatisticsGetP      Instance ID: 286125
Service Name: CXStatisticsInst
Document Name: CXStatisticsGet_200703301753286125_1      Document Store: Database
Document in process data:
<CXStatisticsGet>
    <Statistics>
        <DateOfStatisticsRecord>2007/03/3017:39:12</DateOfStatisticsRecord>
        <RecordId>SB</RecordId>
        <MessageId>UXOL134I</MessageId>
        <MonitorId>FEDORA</MonitorId>
        <OperatingSystem>UNIX</OperatingSystem>
        <RequestNumber>08900008</RequestNumber>
        <Status/>
        <Event>ConnectionStarted</Event>
        <MessageText>Communication started - COMMUNICATION OPENED (I) WITH: BOUCLE
REQ: 08900008 PESIT      TCPIP</MessageText>
        <PartnerName>BOUCLE</PartnerName>
        <LocalName>BOUCLE</LocalName>
        <TypeOfPartner>O</TypeOfPartner>
        <Protocol>E</Protocol>
        <TypeOfLink>T</TypeOfLink>
        <TcpipAddress>127.0.0.1</TcpipAddress>
        <TcpipPort>06677</TcpipPort>
        <RetryNumber>0</RetryNumber>
    </Statistics>
    <Statistics>
    ...
    </Statistics>
</CXStatisticsGet>
```

---

---

## CXTransferSubmit

The CXTransferSubmit service enables you to request a file transfer to a monitor.

You can check transfer completion in several ways:

- ❖ Wait for the end of transfer in the CXTransferSubmit service.
- ❖ Check the end of transfer after completion of CXTransferSubmit, using either CXTransferStatus service or CXTransferJournal service.
- ❖ Set up a http server in SI to receive end of transfer notifications sent by the monitor.

Use the following parameters to indicate to the service how to return result:

### *End Transfer Condition Parameters*

Field name	Description	Win	UNIX	Data Type
WaitForTermination	True: The service waits for transfer completion by inquiring the monitor MaxPollCount time, evry PollInterval seconds. False: The service returns immediately after submitting the request.	5	5	S
MaxPollCount	Maximum number of status inquiry before returning (if WaitForTermination=True)	3	3	i
PollInterval	Interval in second between to status inquiries (If WaitForTermination=True)	4	4	i

Use the following parameters to request the transfer to the monitor:

### *CXTransferSubmit Parameters*

Field name	Description	Win	UNIX	Data Type
FileName	Symbolic file name	8	8	S
PhysicalName	Physical file name	127	44	S
TransferDirection	Transfer direction (T: transmission, R: reception)	1	1	C
PartnerName	Symbolic partner name	8	8	S
Priority	Transfer priority (0: high, 1: normal, 2: low)	1	1	C
TypeOfRequest	Type of request (N: normal, I: inquiry, H: hold) If TransferDirection=T the type cannot be « I »	1	1	C
TypeOfLink	Network link type UNIX: T: TCP/IP, X: X25, P: PAD, M: TCP/IP+X25 Microsoft Windows: T: TCP/IP, S: SNA LU6.2	1	1	C
Requestor	Name of the requestor (user, process, ...)	8		S
UserRequestId	User identification of the request	16		S
LocalName	Local alias name of the monitor	8	8	S
Field name	Description	Win	UNIX	Data Type
LocalPassword	Local alias password of the monitor	8	8	S
TypeOfFile	Type of file (TF: text fixed, TV: text variable, BF: binary fixed, BU: binary undefined)		2	S

Field name	Description	Win	UNIX	Data Type
FileRecordLength	Record length If TransferDirection=T, cannot be NULL		5	I
FileApi	User description of the transfer (Etebac3 Card)	80	88	S
FileLabel	User Identification of the file	80	80	S
DateOfExecution	Scheduling date of the request	18	18	D
TypeOfNotification	Type of Notification: 1 character ('0' to '7'). '0': No notification. '1': Notification at the beginning of the transfer. '2': Notification at the end of the transfer. '4': Notification if transfer error. Other possibilities are combinations with inclusive « OR » of these values. For example: '6' = '2' OR '4' for a notification at the end of transfer or in case of transfer error. Microsoft Windows: This flag is used for HTTP notification only. UNIX: This flag is used for HTTP notification or standard notification depending on the values of the keywords HTTPNF and NOTIFY in the sysin configuration file.	1	1	C
NotifyUsed	Notification option (true/false)	5		B
ClientToNotify	Name of the client to notify Required if NotifyUsed=true	255		S
FtpStoreUniqueUsed	FTP « store unique » option (true/false)		5	B
FtpOptions	FTP Options (Type/Structure/Mode) Type:(E:Ebcdic, A:Ascii, B: Binary, *: unchanged) Structure (F: file, R: record, *: unchanged) Mode (B: bock, S: stream, *: unchanged)		3	S
Pi99Offset	Offset in Pi99Value for pi99	3		I
Pi99Length	Length in Pi99Value forPi99	3		I
Pi99Value	pi99 information	254	254	S
AdHocUser	Remote AdHoc user identification	8		S
AdHocPassword	Remote AdHoc user password	8		S
OriginPhysicalName	AdHoc Local physical name sent	44	44	S
RemotePhysicalName	AdHoc remote physical name sent	44	44	S
TransferOrigin	Transfer requestor	8	8	S
TransferDestination	Transfer addressee	8	8	S
TransferSender	File sender (Pi61)	24	24	S
TransferReceiver	File receiver (Pi62)	24	24	S
FileAgentUsed	File agent option (true/false)		5	B

The following parameters are required:


---

FileName, TransferDirection, TypeOfRequest.

---

### Example 1

The business process shown below requests a file transfer. The CXTransferSubmit service waits for the transfer completion; it returns successfully if the transfer is ended or with error code after having checked for completion three times, every 15 seconds.



Executing the CXTransferSubmit service results in the following:

### **ProcessData**

---


#### Process Data

```
Process Name: CXTransferSubWaitP      Instance ID: 286111
Service Name: CXTransferSubInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXTransferSubmitRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <FileName>FILE01</FileName>
    <PhysicalName>$TOM_DIR/config/sysin.txt</PhysicalName>
    <TransferDirection>T</TransferDirection>
    <PartnerName>BOUCLE</PartnerName>
    <TypeOfLink>T</TypeOfLink>
    <FileLabel>lab01</FileLabel>
    <LocalName>BOUCLE</LocalName>
    <LocalPassword>PSW</LocalPassword>
    <TypeOfFile>TV</TypeOfFile>
    <FileRecordLength>8192</FileRecordLength>
    <Mode>submit</Mode>
    <WaitForTermination>TRUE</WaitForTermination>
    <MaxPollCount>3</MaxPollCount>
    <PollInterval>15</PollInterval>
  </CXTransferSubmitRequest>
  <CXTransferSubmitResponse>
    <ReturnCode>TRANSFER_SUBMIT_SUCCESSFUL</ReturnCode>
    <RequestNumber>08900007</RequestNumber>
  </CXTransferSubmitResponse>
  <CXTransferStatus>
    <ReturnCode>TRANSFER_SUCCESSFUL.Request number 08900007</ReturnCode>
  </CXTransferStatus>
</ProcessData>
```


---

## Example 2

The business process shown below requests a file transfer. The CXTransferSubmit service returns successfully with the request number, without checking for transfer completion. The end of transfer must be checked by mean of CXTransferStatus service.



The TransferNotTerminated condition is defined as shown below:



Executing the CXTransferSubmit service results in the following:

### **ProcessData**

---

#### Process Data

```
Process Name: CXTransferSubNoWaitP      Instance ID: 289079
Service Name: DecisionEngineService
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXTransferSubmitRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <FileName>FILE01</FileName>
    <PhysicalName>$TOM_DIR/config/sysin.txt</PhysicalName>
    <TransferDirection>T</TransferDirection>
    <PartnerName>BOUCLE</PartnerName>
    <TypeOfLink>T</TypeOfLink>
    <TypeOfRequest>N</TypeOfRequest>
    <FileLabel>lab01</FileLabel>
    <LocalName>BOUCLE</LocalName>
    <LocalPassword>PSW</LocalPassword>
    <TypeOfFile>TV</TypeOfFile>
    <FileRecordLength>8192</FileRecordLength>
    <Mode>submit</Mode>
    <WaitForTermination/>
    <MaxPollCount/>
    <PollInterval/>
  </CXTransferSubmitRequest>
  <CXTransferSubmitResponse>
    <ReturnCode>TRANSFER_SUBMIT_SUCCESSFUL</ReturnCode>
    <RequestNumber>09200003</RequestNumber>
  </CXTransferSubmitResponse>
  <RequestNumber>09200003</RequestNumber>
  <CXTransferStatusRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <RequestNumber>09200003</RequestNumber>
    <Mode>list</Mode>
  </CXTransferStatusRequest>
  <TransferTerminated>TRANSFER_SUCCESSFUL</TransferTerminated>
</ProcessData>
```

---

---

## CXTransferControl

The CXTransferControl service enables you to interrupt, restart or purge file transfers. For Sterling Connect:Express for Microsoft Windows you can only purge active transfers (CHK file). For Sterling Connect:Express for UNIX you can purge any transfers because they are all recorded in the RENC file.

### *CXTransferControl Parameters*

Parameters for this service depend on the mode.

#### ***Modes interrupt or restart***

Field name	Description	Win	UNIX	Data Type
Mode	Interrupt ou restart	9	9	S
RequestNumber	Request number (no wildcard)	12	8	S

#### ***Mode purge (Microsoft Windows)***

Field name	Description	Win	UNIX	Data Type
Mode	Purge	9	9	S
RequestNumber	Request number (no wildcard)	12	8	S

#### ***Mode purge (UNIX)***

Field name	Description	Win	UNIX	Data Type
Mode	Purge	6	6	S
FileName	Symbolic file name or *	8	8	S
PartnerName	Symbolic partner name or *	8	8	S
TransferDirection	Transfer direction (T: transmission, R: reception, *: Both)	1	1	C
RequestNumber	Request number (only * is supported)	12	8	S
Status	Transfer status or *		1	S
NotAfter	End purge date or *		18	D
DaysToKeep	Number of days to keep Note: Today's date is included		3	S

### **Example**

Executing the CXTransferControl service with (Mode=purge) results in the following:

#### **ProcessData**

---

##### Process Data

```
Process Name: CXTransferPurgeP      Instance ID: 289036
Service Name: CXTransferControlInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXTransferControlRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <DaysToKeep>1</DaysToKeep>
    <Mode>purge</Mode>
  </CXTransferControlRequest>
  <CXTransferControlResponse>
    <ReturnCode>TRANSFERCONTROL_PURGE_SUCCESSFUL</ReturnCode>
  </CXTransferControlResponse>
</ProcessData>
```

---

---

## CXTransferStatus

The CXTransferStatus service enables you to show in the « process data », the status of a transfer (ended, running). You can use it in a business process as a condition.

Depending on the status of the transfer, the following information is shown in the ProcessData:

```
<CheckStatus>TRANSFER_IN_PROGESS</CheckStatus>
<TransferTerminated>TRANSFER_SUCCESSFULL</TransferTerminated>
<TransferTerminated>TRANSFER_FAILED</TransferTerminated>
```

#### **CXTransferStatus Parameters**

Field name	Description	Win	UNIX	Data Type
RequestNumber	Transfer request number	12	8	S

### **Example**

Executing CXTransferStatus service after CXTransferSubmit service results in the following, in case of transfer successful completion:

#### **ProcessData**

---

##### Process Data

```
Process Name: CXTransferSubNoWaitP      Instance ID: 289037
Service Name: DecisionEngineService
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXTransferSubmitRequest>
    ...
    <WaitForTermination/>
    <MaxPollCount/>
    <PollInterval/>
  </CXTransferSubmitRequest>
  <CXTransferSubmitResponse>
    <ReturnCode>TRANSFER_SUBMIT_SUCCESSFUL</ReturnCode>
    <RequestNumber>09200001</RequestNumber>
  </CXTransferSubmitResponse>
  <RequestNumber>09200001</RequestNumber>
  <CXTransferStatusRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <RequestNumber>09200001</RequestNumber>
    <Mode>list</Mode>
  </CXTransferStatusRequest>
  <TransferTerminated>TRANSFER_SUCCESSFUL</TransferTerminated>
</ProcessData>
```

---

---

## CXEerpSubmit

The CXEerpSubmit service enables you to acknowledge a request by sending an eerp.

You can check eerp transfer completion in several ways:

- ❖ Wait for the end of transfer in the CXEerpSubmit service.
- ❖ Check the end of transfer after completion of CXEerpSubmit, using either CXEerpStatus service or CXTransferJournal service.
- ❖ Set up a http server in SI to receive end of transfer notifications sent by the monitor.

Use the following parameters to indicate to the service how to return result:

### *End Transfer Condition Parameters*

Field name	Description	Win	UNIX	Data Type
WaitForTermination	True: The service waits for transfer completion by inquiring the monitor MaxPollCount time, evry PollInterval seconds. False: The service returns immediately after submitting the request.	5	5	S
MaxPollCount	Maximum number of status inquiry before returning (if WaitForTermination=True)	3	3	i
PollInterval	Interval in second between to status inquiries (If WaitForTermination=True)	4	4	i

Use the following parameters to request the transfer to the monitor:

### *CXEerpSubmit Parameters*

Field name	Description	Win	UNIX	Data Type
RequestNumber	Number of the request to acknowledge	127	44	S
PhysicalName	Physical file name	127	44	S
PartnerName	Symbolic partner name	8	8	S
Priority	Transfer priority (0: high, 1: normal, 2: low)	1	1	C
TypeOfLink	Network link type UNIX: T: TCP/IP, X: X25, P: PAD, M: TCP/IP+X25 Microsoft Windows: T: TCP/IP, S: SNA LU6.2	1	1	C
Requestor	Name of the requestor (user, process, ...)	8		S
UserRequestId	User identification of the request	16		S
LocalName	Local alias name of the monitor	8	8	S
LocalPassword	Local alias password of the monitor	8	8	S
MaxMsgSize	Maximum size of the message (<=4096)	4	5	I
DateOfExecution	Scheduling date of the request	18	18	D
TypeOfNotification	Type of Notification: 1 character ('0' to '7'). '0': No	1	1	C

Field name	Description	Win	UNIX	Data Type
	<p>notification. '1': Notification at the beginning of the transfer. '2': Notification at the end of the transfer. '4': Notification if transfer error. Other possibilities are combinations with inclusive « OR » of these values. For example: '6' = '2' OR '4' for a notification at the end of transfer or in case of transfer error.</p> <p>Microsoft Windows: This flag is used for HTTP notification only.</p> <p>UNIX: This flag is used for HTTP notification or standard notification depending on the values of the keywords HTTPNF and NOTIFY in the sysin configuration file.</p>			
NotifyUsed	Notification option (true/false)	5		B
ClientToNotify	Name of the client to notify Required if NotifyUsed=true	255		S
Pi91Offset	Offset in Pi91Value for Pi91	3		I
Pi91Length	Length in Pi91Value for Pi91	3		I
Pi91Value	Pi91 information	254	254	S

The following parameters are required:

---

Windows:	RequestNumber, PartnerName
Unix:	RequestNumber

---

Executing the CXEerpSubmit service results in the following:

### **ProcessData**

---

```

Process Data
Process Name: CXEerpWaitP      Instance ID: 286111
Service Name: CXEerpInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXEerpSubmitRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <RequestNumber>08200003</RequestNumber>
    <PartnerName>08200003</PartnerName>
    <Mode>submit</Mode>
    <WaitForTermination>TRUE</WaitForTermination>
    <MaxPollCount>3</MaxPollCount>
    <PollInterval>15</PollInterval>
  </CXEerpSubmitRequest>
  <CXEerpSubmitResponse>
    <ReturnCode>EERP_SUBMIT_SUCCESSFUL</ReturnCode>
    <RequestNumber>08200006</RequestNumber>
  </CXEerpSubmitResponse>
  <CXEerpStatus>
    <ReturnCode>EERP_SUCCESSFUL.Request number 08900006</ReturnCode>
  </CXEerpStatus>
</ProcessData>

```

---

---

## CXEerpContextSubmit

The CXEerpContextSubmit service enables you submit eerp's from a defined PeSIT transfer context.

You can check eerp transfer completion in several ways:

- ❖ Wait for the end of transfer in the CXEerpContextSubmit service.
- ❖ Check the end of transfer after completion of CXEerpContextSubmit, using either CXEerpStatus service or CXTransferJournal service.
- ❖ Set up a http server in SI to receive end of transfer notifications sent by the monitor.

Use the following parameters to indicate to the service how to return result:

### *End Transfer Condition Parameters*

Field name	Description	Win	UNIX	Data Type
WaitForTermination	True: The service waits for transfer completion by inquiring the monitor MaxPollCount time, evry PollInterval seconds. False: The service returns immediately after submitting the request.	5	5	S
MaxPollCount	Maximum number of status inquiry before returning (if WaitForTermination=True)	3	3	i
PollInterval	Interval in second between to status inquiries (If WaitForTermination=True)	4	4	i

Use the following parameters to request the transfer to the monitor:

### *CXEerpContextSubmit Parameters*

Field name	Description	Win	UNIX	Data Type
FileName	Symbolic file name	8	8	S
PhysicalName	Physical file name	127	44	S
MaxMsgSize	Maximum size of the message (<=4096)	4	5	I
PartnerName	Symbolic partner name	8	8	S
Priority	Transfer priority (0: high, 1: normal, 2: low)	1	1	C
TypeOfLink	Network link type UNIX: T: TCP/IP, X: X25, P: PAD, M: TCP/IP+X25 Microsoft Windows: T: TCP/IP, S: SNA LU6.2	1	1	C
Requestor	Name of the requestor (user, process, ...)	8		S
UserRequestId	User identification of the request	16		S
LocalName	Local alias name of the monitor	8	8	S
LocalPassword	Local alias password of the monitor	8	8	S
DateOfExecution	Scheduling date of the request	18	18	D

Field name	Description	Win	UNIX	Data Type
TypeOfNotification	Type of Notification: 1 character ('0' to '7'). '0': No notification. '1': Notification at the beginning of the transfer. '2': Notification at the end of the transfer. '4': Notification if transfer error. Other possibilities are combinations with inclusive « OR » of these values. For example: '6' = '2' OR '4' for a notification at the end of transfer or in case of transfer error. Microsoft Windows: This flag is used for HTTP notification only. UNIX: This flag is used for HTTP notification or standard notification depending on the values of the keywords HTTPNF and NOTIFY in the sysin configuration file.	1	1	C
NotifyUsed	Notification option (true/false)	5		B
ClientToNotify	Name of the client to notify Required if NotifyUsed=true	255		S
Pi91Offset	Offset in Pi91Value for Pi91	3		I
Pi91Length	Length in Pi91Value for Pi91	3		I
Pi91Value	Pi99 information	254	254	S
TransferOrigin	Transfer requestor	8	8	S
TransferDestination	Transfer addressee	8	8	S
TransferSender	File sender (Pi61)	24	24	S
TransferReceiver	File receiver (Pi62)	24	24	S
Pi11	PeSIT file type (4 hexadecimal digits)	4	4	H
TransferIdent	Transfer identifier (Pi13): Windows 6 hexadecimal digits, unix 8 decimal digits.	6	8	S
Pi51	PeSIT File creation date (Pi51) AAMMJJHHMMSS	12	12	S

The following parameters are required:

---

FileName, PartnerName, Pi11, TransferIdent, TransferOrigin, TransferDestination, Pi51.

---

Executing the CXEerpContextSubmit service results in the following:

### **ProcessData**

---

```
Process Data
Process Name: CXEerpContextSubWaitP      Instance ID: 286111
Service Name: CXEerpContextubInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXEerpContextSubmitRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0:</Serverid>
    <FileName>FILE01</FileName>
    <Pi91Value>File received OK</Pi91Value>
    <PartnerName>BOUCLE</PartnerName>
    <LocalName>BOUCLE</LocalName>
    <LocalPassword>PSW</LocalPassword>
    <TransferOrigin>PI3BIS</TransferOrigin>
    <TransferDestination>PI4BIS</TransferDestination>
    <TransferSender>PI4BIS</TransferSender>
    <TransferReceiver>PI61</TransferReceiver>
    <TransferDestination>PI62</TransferDestination>
    <PI11>0000</PI11>
    <PI51>110104130930</PI51>
    <Mode>submit</Mode>
    <WaitForTermination>TRUE</WaitForTermination>
    <MaxPollCount>3</MaxPollCount>
    <PollInterval>15</PollInterval>
  </CXEerpContextSubmitRequest>
  <CXEerpContextSubmitResponse>
    <ReturnCode>EERP_CONTEXT_SUBMIT_SUCCESSFUL</ReturnCode>
    <RequestNumber>08900007</RequestNumber>
  </CXEerpContextSubmitResponse>
  <CXEerpContextStatus>
    <ReturnCode>EERP_CONTEXT_SUCCESSFUL.Request number 08900007</ReturnCode>
  </CXEerpContextStatus>
</ProcessData>
```

---

---

## CXEerpStatus

The CXEerpStatus service enables you to show in the « process data », the status of an eerp (ended, running). You can use it in a business process as a condition.

Depending on the status of the transfer, the following information is shown in the ProcessData:

```
<CheckStatus>EERPSTATUS_IN_PROGESS</CheckStatus>
<EerpTerminated>EERP_SUCCESSFULL</EerpTerminated>
<EerpTerminated>EERP_FAILED</EerpTerminated>
```

### CXEerpStatus Parameters

Field name	Description	Win	UNIX	Data Type
RequestNumber	Transfer request number	12	8	S

### Exemple

Executing CXEerpStatus service after CXEerpSubmit service results in the following, in case of transfer successful completion:

### ProcessData

---

```
Process Data
Process Name: CXEerpSubNoWaitP      Instance ID: 289037
Service Name: DecisionEngineService
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXEerpSubmitRequest>
    ...
    <WaitForTermination/>
    <MaxPollCount/>
    <PollInterval/>
  </CXEerpSubmitRequest>
  <CXEerpSubmitResponse>
    <ReturnCode>EERP_SUBMIT_SUCCESSFUL</ReturnCode>
    <RequestNumber>09200001</RequestNumber>
  </CXEerpSubmitResponse>
  <RequestNumber>09200001</RequestNumber>
  <CXEerpStatusRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <RequestNumber>09200001</RequestNumber>
    <Mode>list</Mode>
  </CXEerpStatusRequest>
  <EerpTerminated>EERP_SUCCESSFUL</EerpTerminated>
</ProcessData>
```

---

### **Example**

Executing CXTransferStatus service after CXTransferSubmit service results in the following, in case of transfer successful completion:

#### **ProcessData**

---

##### Process Data

```
Process Name: CXTransferSubNoWaitP      Instance ID: 289037
Service Name: DecisionEngineService
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <CXTransferSubmitRequest>
    ...
    <WaitForTermination/>
    <MaxPollCount/>
    <PollInterval/>
  </CXTransferSubmitRequest>
  <CXTransferSubmitResponse>
    <ReturnCode>TRANSFER_SUBMIT_SUCCESSFUL</ReturnCode>
    <RequestNumber>09200001</RequestNumber>
  </CXTransferSubmitResponse>
  <RequestNumber>09200001</RequestNumber>
  <CXTransferStatusRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <RequestNumber>09200001</RequestNumber>
    <Mode>list</Mode>
  </CXTransferStatusRequest>
  <TransferTerminated>TRANSFER_SUCCESSFUL</TransferTerminated>
</ProcessData>
```

---



# Chapter 3

## Notifications

This chapter describes how you can receive Sterling Connect:Express notifications in SI.

You can configure a Sterling Connect:Express monitor to send file transfer notifications, at the beginning or at end of transfer. The monitor sends the notification via HTTP, to a SI server that can be configured to launch a business process.

### Configuring a SI http Server to Receive Notifications

You need to create a business process that will process the notification and to configure the http server to activate the business process.


#### *Creating the Business Process to Receive the Notification*

The business process shown below executes like this:

The « HTTP Respond Service » service writes the Notification (http request body) in the « primary document ». The notification contains the transfer request number.

The « Assign » service copies the notification in <HttpRequest> element of the process data.

The « CXJournalGet » service uses the request number to inquire the corresponding Journal record to the monitor.



### *Associating the Business Process to an URI of the http Server*

Sterling Connect:Express sends the notifications to port **10033** of the SI HTTP server, to URI « **/cxnotif** », as shown before. You can however change these parameters (create a new HTTP server service Instance on a different port, a different URI).

Use SI interface (Deployment/Services/Configuration) to add URI « **/cxnotif** » to the http server instance that is already defined, and associate to this URI the business process « **CXHttpNotif** » shown in the previous paragraph.

---

**Note:** Sterling Connect:Express monitors don't implement **SSL**, and **user authentication** in the http request.

---

Configuration is done as shown in the following:

## **Services Configuration**

### **Http Server Adapter: Name**

Name :	Http Server Adapter
Description:	An HTTPSAdapter instance operating in lo
Select a group:	
<input checked="" type="radio"/> None	
<input type="radio"/> Create New Group	<input type="text"/>
<input type="radio"/> Select Group:	<input type="button" value="▼"/>



[Back](#)

[Next](#)

[Cancel](#)

[Save](#)

## Services Configuration

**Http Server Adapter: HTTP Connection Properties**

HTTP Listen Port:

Perimeter Server Name:  

**Document Storage**

System Default  
 Database  
 File System

**User Authentication Required**

Yes  
 No

**Use SSL ( Note: User Authentication without SSL will result in a weak security configuration )**

Must  
 None

Add the URI /cxnotif. Select « Launch BP ».

## Services Configuration

### Http Server Adapter: URI

URI	
	<a href="#">+ add</a> New URI
	<a href="#">/dashboard</a>
	<a href="#">/DataStore_MsgPrep_Send</a>
	<a href="#">/demosuite</a>
	<a href="#">/DS_Frontend_Import_BP</a>
	<a href="#">/federation</a>
	<a href="#">/hello</a>
	<a href="#">/hello-war</a>
	<a href="#">/myaft</a>
	<a href="#">/onboard</a>
	<a href="#">/portletlets</a>
	<a href="#">/soap/SWIFTNetServerRequest</a>
	<a href="#">/soap/SWIFTNetServerSnFRequest</a>



[Back](#)

[Next](#)

[Cancel](#)

[Save](#)

## Services Configuration

### Http Server Adapter: URI: URI Config

URI:

#### Launch BP Or WAR

- Business Process
- War File



[Back](#)

[Next](#)

[Cancel](#)

[Save](#)

Indicate the name of the business process to launch:

## Services Configuration

### Http Server Adapter: BP Config

Business Process: CXHttpNotifP 

Send Raw Messages:

No  Yes



 Back

 Next

 Cancel

 Save

---

## Executing the Business Proccess to Receive the Notification

---

Executing the Business process described above results in the following:

### **ProcessData**

---

#### Process Data

```
Process Name: CXHttpNotifP      Instance ID: 289080
Service Name: CXJournalInst
<?xml version="1.0" encoding="UTF-8"?>
<ProcessData>
  <PrimaryDocument SCIOBJECTID="localhost:9ed927:111b192d865:-62a9"/>
  <b2b-protocol>http</b2b-protocol>
  <transport-instance-id>HttpServerAdapter_HttpServerAdapter_node1</transport-instance-id>
  <http-request-uri>/cxnotif</http-request-uri>
  <transport-session-id>Mon Apr 02 11:15:31 CEST 2007:8</transport-session-id>
  <output>OK</output>
  <b2b-raw-message>true</b2b-raw-message>
  <HttpRequest>
    <Notification>
      <MonitorIdentification>FEDORA</MonitorIdentification>
      <NotificationType>U02</NotificationType>
      <RequestNumber>09200003</RequestNumber>
      <TransferDirection>T</TransferDirection>
      <PartnerName>BOUCLE</PartnerName>
      <FileName>FILE01</FileName>
      <PhysicalName>/u1/pga/TOM140/tom1/config/sysin.txt</PhysicalName>
      <Status>E</Status>
      <Trc>0000</Trc>
      <Prc>0000</Prc>
      <Src>0000</Src>
      <Nrc>0000</Nrc>
    </Notification>
  </HttpRequest>
  <CXJournalRequest>
    <Serverid>localhost:9000:X:ADMIN:****:FALSE:0:30:0</Serverid>
    <RequestNumber>09200003</RequestNumber>
    <Mode>GET</Mode>
  </CXJournalRequest>
  <CXJournalGet_4 SCIOBJECTID="localhost:9ed927:111b192d865:-624b"/>
  <CXJournalResponse>
    <JournalCount>1</JournalCount>
    <ReturnCode>JOURNAL_GET_SUCCESSFUL</ReturnCode>
  </CXJournalResponse>
</ProcessData>
```

---

## **Primary Document**

---

PrimaryDocument

```
Process Name: CXHttpNotifP      Instance ID: 289080
Service Name: CXJournalInst
Document Name: PsHttpDocument_node1_20070402133638974      Document Store: Database
Document in process data:  text/xml
<Notification>
    <MonitorIdentification>FEDORA</MonitorIdentification>
    <NotificationType>U02</NotificationType>
    <RequestNumber>09200003</RequestNumber>
    <TransferDirection>T</TransferDirection>
    <PartnerName>BOUCLE</PartnerName>
    <FileName>FILE01</FileName>
    <PhysicalName>/u1/pga/TOM140/tom1/config/sysin.txt</PhysicalName>
    <Status>E</Status>
    <Trc>0000</Trc>
    <Prc>0000</Prc>
    <Src>0000</Src>
    <Nrc>0000</Nrc>
</Notification>
```

---

---

## HTTP Notification in Sterling Connect:Express z/OS

### *Installing the HTTP Notification*

HTTP notifications are embedded in Sterling Connect:Express z/OS from version 4.23 and no supplementary installation is necessary.

### *Configuring the HTTP Notification*

HTTP notification configuration takes place in the SYSIN file SYSINFY or profile member located on DDNAME SYSPRF. These DDNAMEs have to be present in TOM monitor PROCedure or JOB stream, APM and EAS PROCedures.

HTTP notifications are managed by the program P1B2PNFY. This program can be internally activated by Sterling Connect:Express or launched using JOB stream.

In both cases, a minimal configuration should be defined to enable HTTP notifications

Minimal parameters are located in SYSINFY DD and/or NFYPRF profile member and/or inline for \$SNFY\$ command. They are the following:

- ❖ FMT=H To specify HTTP notifications
- ❖ HST= HTTP server name or
- ❖ SRV= HTTP server IP address
- ❖ PRT= HTTP port
- ❖ URI= HTTP URI
- ❖ XML= XML fields to include

### *Customization*

The default notification structure is shown below:

```
<MonitorIdentification>
<NotificationType>
<RequestNumber>
<TransferDirection>
<PartnerName>
<FileName>
<PhysicalName>
<Status>
<Trc>
<Prc>
<Src>
<Nrc>
```

This notification fields template can be located in the PARMLIB member XMLNFYx (x is your monitor name TOMx).

To customize the notification fields, add XML= parameters to your SYSINFY DD or NFYPRF member. Refer to the description of CXJournal service for a description of each element.

## *Configuring Transfers for HTTP Notification*

To request a notification sent for a transfer, use the notification option in the file definition or the transfer request.

### ***Symbolic File Definition (ISPF)***

The NOTIFICATION LEVEL (NVL) parameter can take one of the following values: 0 to 7

0: No notification

1: Notification at the beginning of the transfer

2: Notification at the end of the transfer

4: Notification if there is a transfer error

The value x of the parameter is the sum of the values for each kind of notification desired. For example 6 = 2+4 indicates a notification at the end of the transfer or in case of error of transfer.

This is the default value for all transfers of the symbolic file: it can be changed by the transfer request parameter list.

```
TOM4230----- FILES ATTRIBUTES (2/5) -----
OPTION ===>

SYMBOLIC NAME : FILE1      MODE: NORMAL

INIT STATE ..... ==> E      E: IN-SERVICE H: HOLD

NOTIFICATION LEVEL .... ==> 2      0:NO 1:START 2:END 3:START AND END
                                         4,5,6,7: SAME AS 0,1... AND ON ERROR

DIRECTION ..... ==> T      T:TRANSMIT R:RECEIVE *:TRANS./REC.

RECEIVING PARTNER ..... ==> UNIX      'NAME', FLIST, */$ALL$$ OR $$API$$
SENDING PARTNER ..... ==> -      'NAME', FLIST, */$ALL$$ OR $$API$$

PRIORITY ..... ==> 1      0:URGENT 1:FAST 2:NORMAL 3:SLOW
DSN DEFINITION TYPE ... ==> F      D:DYNAMIC F:FIXED
ALLOCATION RULE ..... ==> 1      0:CREATE/REPLACE 1:PREALL. 2:CREATE
                                         3:EXIT A:APPLICATION SERVER
FILE TYPE ..... ==> S      S/H/M/P/PU/V/VU/UU/SU/TU/HU
PRESENTATION ..... ==> 04      COMPRESS.,DATA TYPE (01-24)
UNLOAD/RELOAD MEMBER .. ==> -      OPTIONNAL
SSL CONFIGURATION..... ==> -      OPTIONNAL

OPTION : UPDATE      UPDATE: 10/01/13 04:28 PSR0003
-ENTER- : NEXT SCREEN      -PF3- : CANCEL
```

### ***Transfer Request (ISPF)***

The NOTIFICATION LEVEL parameter of the transfer request is used in the same way as in the file definition. If defined, this parameter overrides parameter declared in the file definition. If not defined, file definition notification level is used as a default.

```

TOM4230      NORMAL TRANSFER
OPTION ===>                               CSGB

SUB-SYSTEM . ===> TOM7
FILE ....... ===> FILE1
NOTIFICATION ===> 4          (0-7/*)
DIRECTION .. ---> T          (T/R)
PARTNER .... ---> GFIPSR7

DSNAME .... ---> PSR$REC.PS.F080.SHORT

TYPE ....... ---> N          (N/H/I/K/U)
MODE ....... ---> I          (I/D)
LINK ....... --->          (/C/I/S/T/X)
CLASS ....... ---> *        (A-Z/*)
PRIORITY ... ---> 1        (0-3)
MEMBER ..... --->          (PRM)
CHECKING ... ---> NO       (YES/NO)
EXTENSION .. ---> NO       (YES/NO) ALIAS/ORG/DST/API-ETB3/SEC/RGR.
NOTE->
      X EXIT, -ENTER- REQUEST, -PF1- HELP TRC, -PF3- END

```

### ***Batch Transfer Request***

When using the batch utilities P1B2PREQ, P1B2PRQ2, P1B2PRQ3, use parameter NLV=x to set the notification level. Refer to SAMPLIB for examples.

### ***Managing Errors***

When notifications can't be sent to server, a recovery process is available. Requests are saved on files and can be processed by a batch notification recovery process.

### ***Batch Notifications recovery***

Refer to Sterling Connect:Express Notification Agent documentation for details on submitting batch notifications for recovery.

### ***Generalized User Exit***

When using the generalized user exit, use NLV parameter to set the notification level when submitting a request. Variable &NLV is available to retrieve the current transfer notification level and can be used in transfer requests using \$REQ\$ command.

For example:

---

```
$REQ$    SSN=&SSN,DIR=T,SPN=&PARTNID,SFN=&FILENAM,DSN=&L1,NLV=&NLV
```

---

---

## HTTP Notification in Sterling Connect:Express for UNIX

### *Installing the HTTP Notification*

**Important Notes:** Using HTTP notification with Sterling Connect:Express for UNIX is not compatible with the TCP notification described in « Sterling Connect:Express for UNIX. Agent\_notification ».

The version of Sterling Connect:Express for UNIX be 143-1 with Patch 143-106 minimum.

---

Perform the following operations under the user account of Sterling Connect:Express (The installation directory of Sterling Connect:Express is defined by the environment variable \$TOM\_DIR):

- Stop Sterling Connect:Express (\$stop\_tom)
- Upgrade the version of Sterling Connect:Express if necessary (See Sterling Connect:Express documentation)
- Go to the httpn directory, where the following files are placed:
  - ❖ check\_httpn.sh
  - ❖ install.sh
  - ❖ notformat.xml (file defining the form of the notifications)
  - ❖ notformat\_template.xml (file defining the form of the notifications)
  - ❖ tom\_httpn (executable)
  - ❖ vardef\_example.txt (environment variables definition example)
- Start the installation script:
  - ❖ The following elements will be necessary:
    - ❖ Installation directory of Sterling Connect:Express (referenced by \$TOM\_DIR).
    - ❖ SI http server IP address or host name (localhost)
    - ❖ SI http server TCP port (10033).

---

```
# ./install.sh
```

- Verify that the notification option has been activated in the file \$TOM\_DIR/config/sysin:

---

```
HTTPNF=1
```

---

**Note:** If a parameter NOTIFY=1 is already defined, change it to 0:

```
NOTIFY=0
```

- Edit the profile file defining the Sterling Connect:Express environment variables and insert the definition of the following new variables (See vardef\_example.txt). These variables enable to start, stop and get the status of the notification process tom\_httpn.

---

```
# Define these variables in the shell profile of user Sterling Connect:Express
export start_httpn=$TOM_DIR/httpn/tom_httpn
export stop_httpn=$TOM_DIR/httpn/"tom_httpn -stop I"
export httpn_status=$TOM_DIR/httpn/"tom_httpn -status"
```

- Execute the profile again and start the monitor (\$start\_tom)
- Start tom\_httpn process (\$start\_httpn)

## *Configuring the HTTP Notification*

### ***Tom\_httpn process initialization file***

The file \$TOM\_DIR/httpn/httpnotcfg.xml defines the following configuration parameters for the tom\_httpn process :

Tag	Description	Défaut
url	url of the http server ( <a href="http://hostname:port/cxnotif">http://hostname:port/cxnotif</a> or <a href="http://ip-address:port/cxnotif">http://ip-address:port/cxnotif</a> )	<a href="http://localhost:port/cxnotif">http://localhost:port/cxnotif</a>
backurl	Optional backup http server url	None
trc	Y/N: Trace of the notifications sent (file tom_httpn.trc)	N
srvtim	Delay in seconds between 2 notification retries	20 (sec)
tim	Time-out in seconds on the tcp/ip network connection with the http server	5 (sec)
env	Y/N: Replace UNIX environment variables in the field PhysicalName of the notification.	Y

### ***Customization***

The default notification structure is shown below:

```
<MonitorIdentification>
<NotificationType>
<RequestNumber>
<TransferDirection>
<PartnerName>
<FileName>
<PhysicalName>
<Status>
<Trc>
<Prc>
<Src>
<Nrc>
```

To customize the notification edit \$TOM\_DIR/httpn/notformat.xml and enable/disable elements from the list. You can also change the order of the elements. Refer to the description of CXJournal service for a description of each element.

### ***Using Environment Variables***

For Sterling Connect:Express for UNIX, some information depend on the environment variables of the Sterling Connect:Express user account. For example PhysicalName can be: \$TOM\_DIR/in/07100017.tmp. \$TOM\_DIR is not easy to manage for the SI business process.

Use the <env> option of the \$TOM\_DIR/httpn/httpnotcfg.xml file to activate/deactivate the substitution of environment variables. The default is Y.

### *Configuring Transfers for HTTP Notification*

To request a notification sent for a transfer, use the notification option in the file definition or the transfer request.

#### **Symbolic File Option (STERM)**

The NOT parameter can take one of the following values: 0 to 7:

0: No notification

1: Notification at the beginning of the transfer

2: Notification at the end of the transfer

4: Notification if there is a transfer error

The value x of the parameter is the sum of the values for each kind of notification desired. For example 6 = 2+4 indicates a notification at the end of the transfer or in case of error of transfer.

This is the default value for all transfers of the symbolic file: it can be changed by the transfer request parameter list.

```
C:X UNIX 147-1 ----- FILES DIRECTORY ----- tom1
OPTION ===>
SYMBOLIC NAME:      FILE03
INITIALIZATION STATUS .: E      E:ENABLE H:DISABLE
DIRECTION .....: R      T:TRANSMIT R:RECEIVE *:EITHER
RECEIVING PARTNER ....: $$ALL$$      'NAME',#LISTE, $$ALL$$
TRANSMITTING PARTNER ...: $$ALL$$      'NAME',#LISTE, $$ALL$$
PRIORITY .....: 0      0:URGENT 1:FAST 2:NORMAL
DEFINITION TYPE .....: D      D:DYNAMIC F:FIXED
PRESENTATION TABLE ....: 1      1 -> 9 PRESENTATION TABLE
PARAMETER CARDS FILE:  N      Y/N
SPACE TO RESERVE .....: N      Y/N
ALLOCATION RULE .....: 0      0:INDIF., 1:PREALL., 2:TO CREATE
PHYSICAL NAME .....: $TOM_DIR/in/&REQNUMB.tmp
RECORD FORMAT .....: BU      TF, TV, BF, BU, T*, B*, **
RECORD LENGTH .....: 04000      1-5 NUMERIC CHARAC.
REMOTE DSN (FTP) .....:
TYPE/STRUCTURE/MODE FTP:      E/A/I/*,F/R/*,B/S/*
STORE UNIQUE (FTP) ....: Y/N      FA: N  Y/N
(0/1/2/3)
OPTION: VIEW          UPD: 05/10/12 14:59 mverz1
-ENTER- NEXT FIELD      -F3- CANCEL      -F8- COMPLETION
                                         NOT:  2
```

### **Transfer Request (STERM)**

The NOT parameter of the transfer request is used in the same way as in the file definition.

```
C:X/UNIX 147-1 ----- TRANSFER REQUEST ----- tom1
OPTION ===>
FILE .....: FILE03          DIRECTION .....: T (T/R)
PARTNER ....: PARTNER.
DPCSID ALIAS ..: MYNAME..   DPCPSW ALIAS .....: MYPASSW.
ORIGIN.....: .....
SENDER.....: .....
RECEIVER....: .....
PHYSICAL NAME ..: $TOM_DIR/out/send.txt.....
REMOTE PHYSICAL NAME ...: .....
LABEL:.....
RECORD FORMAT .....: BU      TF, TV, BF, BU
RECORD LENGTH .....: 04000
TYPE/STRUCTURE/MODE FTP: ***    E/A/I/*,F/R/*,B/S/*
STORE UNIQUE (FTP) ....: N      Y/N FA: Y/N      NOT: 2 (0 - 7)
TYPE .....: N      (N/I/H)
TYPE OF CONNECTION ....: T      (X/P/T)
PRIORITY .....: 0      (0/1/2)
DATE .....: 19980728101604      (YYYYMMDDHHMMSS)
API FIELD (ETEBAC3: 80 CHARACTERS FOR CARD)
1...5....0....5....0....5....0....5....0....5....0....5....0....5....0
DO YOU WANT TO GO ON ?
-ENTER- NEXT FIELD           -F3- CANCEL           -F8- COMPLETION
```

### **Batch Transfer Request (p1b8preq)**

When you use the batch utility p1b8preq, use subparameter /NTF=x (x = 0 to 7) in the first parameter of the command.

For example:

```
$TOM_DIR/itm/p1b8preq      "/SFN=FILE03/DIR=T/SPN=PARTNER/SID=MYNAME/PWD=MYPASSW/NTF=2"
"/DSN=\"$TOM_DIR/out/send.txt"
```

### **Using CXTransferSubmit in SI**

When using CXTransferSubmit service in a Business process use the TypeOfNotification parameter, which can take values from '0' to '7', and works in the way described above.

### **Executing tom\_httpn Process to Send Notifications**

Tom\_httpn process executes in the background and sends notifications on demand. Sterling Connect:Express writes the notifications in files located in \$TOM\_DIR/ntfo directory. Tom\_httpn reads the notifications and sends them from these files.

Tom\_httpn process is started and stopped independently of the monitor.

### **Commands to Tom\_httpn**

You can pass the following commands:

## *Start the Process*

---

```
$start_httpn
```

---

## *Immediat Stop of the Process*

(preferred method)

---

```
$stop_httpn
```

---

## *Differed Stop of the Process*

---

```
$ tom_httpn -stop D
```

---

Tom\_httpn sends all pending notifications before stopping. The process stops on first sending error. If the number of notifications is large and if the monitor continues writing notifications, it may take a long time before the process stops. Unless you stop the monitor first, you should use the immediate stop.

## *Displaying tom\_httpn Process Status and the Number of Pending Notifications*

---

```
$ tom_httpn -status
```

---

If tom\_httpn is running, the following displays:

```
Status      : STARTED
Message queue id: 196610
Process id    : 2545

Next notification record to write on disk
-----
Record number: 324
Current file: N20070421174034

Next notification record to send to http server
-----
Record number = 132
Current file  = N20070421174034

Curent list of notification files
-----
N20070421174034
Current number of notifications waiting to be sent: 292
```

If tom\_htpn is not running, the following displays:

```
Status      : NOT STARTED
Message queue id: -
Process id   : -

Next notification record to write on disk
-----
Record number: 324
Current file: N20070421174034

Next notification record to send to http server
-----
Record number = 132
Current file  = N20070421174034

Current list of notification files
-----
N20070421174034
Current number of notifications waiting to be sent: 292
```

### *Activating/Deactivating the Trace*

---

```
$ tom_htpn -trc Y/N
```

---

The trace is written in a text file: \$TOM\_DIR/httpn/tom\_htpn.trc.

---

### **Miscellaneous commands**

The following commands are valid only if tom\_htpn is stopped:

#### *Send Notification by Batch Processing*

---

```
$ tom_htpn -wait N
```

---

Tom\_htpn starts, sends all pending notifications and stops.

---

#### *Purge Pending Notifications*

---

```
$ tom_htpn -purge all
$ tom_htpn -purge HH:MM
$ tom_htpn -purge AAAA/MM:JJHH:MM:SS
```

---

Example: purge all pending notifications older than today 10:00 AM:

---

```
$ tom_htpn -purge 10:00
```

---

### **Backup http server**

It is possible to redirect automatically the notifications to a backup http server, when the primary http server is stopped.

In this case, define a backup url in the configuration file httnotcfg.xml, as shown in the following example:

---

```
<trc>S</trc>
<tim>5</tim>
<srvtim>20</srvtim>
<env>Y</env>
<url>http://10.87.15.35:10033/cxnotif</url>
<backurl>http://10.87.15.34:10033/cxnotif</backurl>
```

---

The command \$httn\_status displays the active url to which the notifications are currently been sent.

```
Status : STARTED      Message queue id : 19857408
Process id : 15074
url (inactive) : http://10.87.15.35:10033/cxnotif
backup (active) : http://10.87.15.34:10033/cxnotif
retry timer (srvtim) : 20 seconds    connection timer (tim): 5 seconds
trc : Short          env : 1

Next notification record to write on disk
-----
Record number : 31
Current file  : N20081024102139

Next notification record to send to http server
-----
Record number = 29
Current file  = N20081024102139

Current list of notification files
-----
N20081024102139
Current number of notifications waiting to be sent: 2
```

If both servers are stopped, tom\_httn tries alternately to send the notifications to each url until one server has been restarted.

After automatic redirection to the backup url and when the primary http server is restarted, it is necessary to use a manual command to redirect again the notifications back to the primary server:

---

```
tom_httn -activate primary
```

The activation command has the following general form:

---

```
tom_httn -activate primary|backup
```

It is also possible to lock the transmission of the notification to one specific url by using the command:

---

```
tom_httn -lock primary|backup
```

In this case, the automatic backup is deactivated.

## *Managing Monitor, SI or Httpn Stop.*

All three components are running independently: no notification can be lost.

If tom\_httpn stops, the monitor writes the notifications in files placed in the ntfo directory. When tom\_httpn initializes, all pending notifications are sent to SI.

If the monitor is stopped, tom\_httpn sends all pending notifications and returns in wait state.

If SI is stopped, tom\_httpn retries periodically to send the notifications to SI. The retry interval is set in the <srvtim>20</srvtim> parameter of httpnotcfg.xml.

### *Notifications Sequence*

Notifications are sent in a FIFO sequence. No notification is sent before all previous notifications have been sent.

The only way to cancel notifications is to stop tom\_httpn, use the purge command, and start tom\_httpn again. Should any network error occur while sending a notification to SI, tom\_httpn retries periodically to send it every 20 seconds (srvtim parameter), until the notification is successfully sent.

### *Troubleshooting*

Use commands tom\_httpn –status and ps to check the status of the http notification system.

#### **No Notification created by the Monitor**

Check that the HTTPNF parameter is set to 1 in \$TOM\_DIR/config/sysin

Check via STERM that the notification was requested for the transfer request. If it was not requested, check the symbolic file definition and/or the request parameters.

#### **No Notification sent to SI**

Check that tom\_httpn is active, using **tom\_httpn –status** and **ps –ef | grep tom\_httpn**

If tom\_httpn is active, activate the trace with the command **tom\_httpn –trc Y**. The trace is written in \$TOM\_DIR/httpn/tom\_httpn.trc: analyze the trace and search for any network problem.

#### **tom\_httpn Does not Start**

Check that tom\_httpn is not already active using **tom\_httpn –status** and **ps –ef | grep tom\_httpn**

If the status is « active » although **ps** does not show tom\_httpn process, tom\_httpn might have been abnormally stopped (kill -9 or core dump for example). In this case you must purge the IPC queue that has been created during previous execution. Use tom\_httpn –status to retrieve the identifier of the message queue. Use the UNIX command: **ipcrm –q <identifier>**. Then remove all file pid.<process-id> from the \$TOM\_DIR/httpn directory, if any.

---

Another reason for tom\_httpn not initializing is an invalid httpnotcfg.xml file.

---

### *Purging the Notification System*

7. Stop the monitor.
8. Remove the \$TOM\_DIR/ntfo directory and all files.
9. Remove the trace file \$TOM\_DIR/httpn/tom\_httpn.trc if any
10. Start the monitor

---

## HTTP Notification in Sterling Connect:Express Microsoft Windows

HTTP notifications generated by the monitor are sent to the remote SI by a specific executable tom\_httpn.exe. The monitor, tom\_httpn and SI can be stopped or restarted independently, without loss of notifications.

---

**Note:** With Sterling Connect:Express Microsoft Windows, the http notification can be used together with the TCP notification described in « Sterling Connect:Express Microsoft Windows. User Guide ».  
Sterling Connect:Express for Microsoft Windows version must be V3.0.5.001 minimum.

---

### *Installing the HTTP Notification*

The HTTP notification component is shipped with Sterling Connect:Express for Microfsoft Windows. It requires an additional installation on a beforehand installed monitor.

Perform the following operations:

- Stop Sterling Connect:Express
- Upgrade the version of Sterling Connect:Express if necessary (See Sterling Connect:Express documentation)
- Place the CD\_ROM in the drive or download the software and uncompress it in a temporary folder
- Change to the httpn directory
- Execute setup.exe. Indicate during the installation the root directory of the monitor.

### *Uninstalling the HTTP Notification*

Perform the following operations:

- Select « Start / Settings / Control Panel / Add or Remove Programs » from the Microsoft Windows task bar.
- Select « Sterling Connect:Express HTTP Notifications » in the list of installed programs, the click « Remove ».

### *Configuring the HTTP Notification*

You can manage the notification structure.

## **Customization**



The default notification structure is shown below:

```
<MonitorIdentification>
<NotificationType>
<RequestNumber>
<TransferDirection>
<PartnerName>
<FileName>
<PhysicalName>
<Status>
<Trc>
<Prc>
<Src>
<Nrc>
```

To customize the notification edit the file **notformat.xml** located in the Sterling Connect:Express directory and enable/disable elements from the list. You can also change the order of the elements. Refer to the description of CXJournal service for a description of each element.

## ***Httpn\_config.exe Utility used to configure the tom\_httpn Process***

This utility can be started from the menu «Start / Programs»:



At installation, HTTP notifications are configured with the above settings.

The configurable settings are:

**Enabled (Monitor):**

Indicates if the monitor is enabled to create HTTP notifications at the beginning, end or error of transfers. If checked, the monitor creates HTTP notifications that can be sent to the HTTP server by tom\_htpn. A stop-restart of the monitor is necessary for this parameter to be effective.

**Trace:**

Trace level of the process tom\_htpn. The trace file is trace\tom\_htpn.txt.

**HTTP server url:**

Url of the HTTP server, to which the notifications are sent.

**Time-out on server connections:**

Time-out value in seconds for the connections to the server.


*Configuring Transfers for HTTP Notification*

To request a notification to be sent for a transfer, use the notification options in the symbolic file definition or in the transfer request. Setting these options in the symbolic file definition determines the notification conditions for transfers in server mode (For example server/receiver mode).

Setting these options in the parameters of a transfer request determines the notification conditions for transfers in requestor mode. (For example requestor/sender mode).


### **Symbolic File**

The http notification options for a symbolic file are presented by the monitor's graphical interface as below:



### **Transfer request (Graphical interface iu\_tom)**

When requesting a transfer with the graphical interface, the http notification options are indicated by the following dialog of the graphical interface:



### **Batch Transfer Request (Tomreq.exe)**

When you use the batch utility Tomreq.exe, use parameter /L:x (x = 0 to 7).

0: No notification

1: Notification at the beginning of the transfer

2: Notification at the end of the transfer


4: Notification if there is a transfer error

The value x of the parameter is the sum of the values for each kind of notification desired. For example 6 = 2+4 indicates a notification at the end of the transfer or in case of error of transfer.


```
"c:\cexpress\Tomreq.exe" /L:6 /F:FILE01 /P:BOUCLE /S:T /T:N /D:"c:\cexpress\out\out.txt" /C:ADMIN /M:ADMIN /K:I /H:localhost /O:7000 /G:"c:\CExpress\Tomnt.ini" /A:BOUCLE /W:PSW
```

### *Starting/Stopping the tom\_httpn Process*

The process tom\_httpn can be started from the menu « Start / Programs »:




To stop, use the exit menu of the tom\_httpn Microsoft Windows:



## *Httpn\_status.exe Utility Showing Notifications Waiting to be Sent*

This utility can be started from the menu « Start / Programs »:



### **Enabled:**

Indicates if the monitor is enabled to create HTTP notifications at the beginning, end or error of transfers. If checked, the monitor creates HTTP notifications, which can be sent to the HTTP server by tom\_httpn.

### **Service:**

Indicates if the process tom\_httpn is installed as Microsoft Windows service.

### **Trace:**

Indicates if the trace of tom\_httpn is active. The trace file is trace\tom\_httpn.txt

**State:**

State (Started or stopped) of the tom\_htpn process.

**Number of notifications waiting to be sent:**

Indicates the number of notifications created by the monitor and waiting to be sent by tom\_htpn.

**Last notification record written on disk:**

**Record number:** Record number, in the file below, of the last notification written by the monitor.

**File:** Name of the notification file created by the monitor in the ntfo directory. Each notification file contains up to 1000 notifications written sequentially by the monitor.

**Last notification record sent to HTTP server:**

**Record number:** Record number of the last notification sent to the remote HTTP server by tom\_htpn.

**File:** Notification files are read by tom\_htpn and purged after complete emission of all notifications.


**Current list of files containing notifications to send:**

List of files containing notifications waiting to be processed by tom\_htpn.

**Url:**

HTTP server url.

If a backup URL has been configured, httpn\_status displays the following dialog box:



It is possible to manually activate or lock the transmission of the notifications to one of both servers, by clicking on the appropriate radio button and updating with the “Update Backup URL” button.

For example :

If S1 and S2 are the 2 HTTP servers, if S1 is down, the notifications are automatically redirected to S2. Even if S1 restarts, they keep on being sent to S2 while S2 is up. To redirect again towards S1, a manual operation is necessary. Set in this case the “Active” button for Url1. On the other hand, if S2 is stopped, automatic backup towards S1 is done.

The “Active and locked” buttons enable to lock the transmission of the notifications to a specific server. In this case, the backup is deactivated.

### *Httpn\_cmd.exe utility*

This utility is a batch utility enabling to stop the process tom\_httpn, to activate or deactivate the trace and to update the backup flags.



---

```
Usage: httpn_cmd stop
Usage: httpn_cmd trace [medium|full|off]
Usage: httpn_cmd [activate|lock] [1|2]
```

---

### *Httpn\_service.exe Utility for tom\_httpn Installation / Uninstallation as Microsoft Windows Service*

This utility can be started from the menu « Start / Programs »:



This utility is used to install or uninstall the Sterling Connect:Express HTTP notification process as a Microsoft Windows service.

The installation as a Microsoft Windows service ensures that the HTTP notification functionality is permanently available in different ways:

- ❖ Automatically started at system startup
- ❖ Associated with other dependent services that must be started before the C:X Service
- ❖ Locally or remotely stopped/started using the Microsoft Windows Service Manager
- ❖ Locally or Remotely supervised using the Microsoft Windows Events Viewer
- ❖ Executed under system or user account with the associated rights

### *Purging the Notification System*

11. Stop the monitor.
12. Delete all files in the ntfo directory of Sterling Connect:Express.
13. Start the monitor

## Notification Fields

The table below provides the list of notification fields, in alphabetic order, with length. It shows that some fields are not available on all platforms.

The field NotificationType identifies the platform, the type of notification and the version of the notification. The type of notification is common to the three platforms (I = Initialization, E =End, R = Error). The values of the Status field, on the contrary, may be platform dependent (Status=E is common to z/OS, UNIX and Microsoft Windows).

Field	Lg max	Description	u	w	z
AppcModeName	8	Sna Lu6.2 ModeName		x	x
AppcTpName	8	Sna Lu6.2 Tp Name		x	x
ClientName	8	Name of the client ( or administrator) to notify	x	x	x
Erc	4	Ctree return code		x	
ExternalRequestNumber	8	Request number on the remote side (Type Tom only, PeSIT)	x	x	x
FileBytes	12	Number of bytes of the file	x	x	x
FileName	8	Symbolic file name	x	x	x
FileNumberOfRecords	12	Number of records sent/received	x	x	x
FileOpenOption	1	Allocation rule, N = New file, R = Replace, O = Pre-allocated, U = User	x	x	x
FileOrganization	1	File organization, S = Sequential, I = Indexed, R = Relative, P = Pds, V = Vsam	x	x	x
FileRecordLength	5	Local record length	x	x	x
Label	80	File user identification or label (Pi37 PeSIT)	x	x	x
LocalName	8	Alias name of the local Sterling Connect:Express	x	x	x
MonitorIdentification	8	Name of the Sterling Connect:Express server	x	x	x
NetworkBytes	12	Number of bytes transferred	x	x	x
NetworkMessageSize	5	Network message size	x	x	x
NotificationLink	1	Type of link used for sending the notification: T = TcpIp	x	x	x
NotificationType	3	Os,Type,Version: Os = <u>Z/os,UNIX,Microsoft Windows</u> Type = <u>I</u> nitialization, <u>E</u> nd, <u>R</u> eject Version = 2 Example: WE2 = Microsoft Windows, End of Transfer, Version 2	x	x	x
Nrc	12	Network Return code	x	x	x
OriginalPhysicalName	44	File name proposed to remote as their data set name (or Pi99)	x	x	x
PartnerName	8	Symbolic Partner name	x	x	x
PhysicalName	127	Local file physical name	x	x	x
Pi61	24	The entity that is processing the file before sending it (PeSIT)	x	x	x
Pi62	24	The entity that is processing the file after receiving it (PeSIT)	x	x	x
Prc	3	Protocol return code	x	x	x

Field	Lg max	Description	u	w	z
Priority	1	Transfer priority, 0 = Urgent, 1 = Fast , 2 = Normal	x	x	x
Protocol	1	Transfer protocol, D=PeSitD, E=PeSitE, O=Oftp, 3=Etebac3, F=ftp	x	x	x
RealCompression	4	Compression performed (PeSIT, Odette)	x	x	
RegistrationDate	10	Date and time when the notification record is created by Sterling	x	x	x
RegistrationTime	8	Connect:Express	x	x	x
RemotePhysicalName	44	Remote file physical name (Type Tom only, PeSIT)	x	x	x
RequestDate	10	Date when the request is accepted by Sterling Connect:Express	x	x	x
RequestTime	8	Time when the request is accepted by Sterling Connect:Express	x	x	x
RequestNumber	12	Request number given by Sterling Connect:Express	x	x	x
Requestor	8	The name of the entity (user, job ..) that submitted the request	x	x	x
RequestStatus	1	Status of the request after transfer: purged (Y) or not (N)	x	x	x
RetryNumber	2	Number of retries for the request	x	x	x
SendReceiveCount	12	Number of network messages moved	x	x	x
SnaLuName	8	Sna LU name		x	x
SnaRc1	4	Sna return code		x	
SnaRc2	8	Sna return code		x	
Src	8	System Return code	x	x	x
Status	1	Transfer status – this field is platform dependent  z/OS: C = In progress / E = Ended / S = Selection Error / I = Interrupted / W = Connection Error / Q = Inbound request in progress  Microsoft Windows: A or W = Active / C = In progress / E = Ended / S = Selection Error / I = Interrupted  UNIX: C = In progress, O = Selection Error or Interrupted, E = Ended	x	x	x
TcpIpAddress	15	Remote TCP/IP address	x	x	x
TcpIpHost	127	Remote TCP/IP host name	x	x	x
TcpIpPort	5	Remote listening TCP/IP port	x	x	x
TcpipRc	4	TCP/IP return code	x	x	x
TransferBeginningDate	10	Beginning of transfer date and time	x	x	x
TransferBeginningTime	8		x	x	x
TransferDestination	8	The entity that is receiving the transfer request (Pi4bis PeSIT)	x	x	x
TransferDirection	1	Transmission or Reception	x	x	x
TransferEndDate	10	End of transfer date and time	x	x	x
TransferEndTime	8		x	x	x
TransferIdentifier	8	Transfer identifier exchanged with the partner (PeSIT)	x	x	x
TransferOrigin	8	The entity that is initiating the transfer (Pi3bis PeSIT)	x	x	x
Trc	4	Sterling Connect:Express Return code	x	x	x
TypeOfData	1	Type of data, A = Ascii, E = Ebcdic, B = Binary	x	x	x
TypeOfFile	2	Type of file, TF = Text fixed, TV = text variable, UF = UNIX fixed, UV = UNIX Variable, BF = binary fixed, BU = Binary undefined S = Sequential, V = VSAM, P = PDS, PE = PDSE, PU = PDS	x	x	x

Field	Lg max	Description	u	w	z
		unload, VU = VSAM unload, SU = SYSOUT unload, UU = User unload, H = HFS, TU = Sequentiel+Edciconv, HU = HFS+Edciconv			
TypeOfLink	1	Type of link, 0 = LU 6.2, 1 = X25, 2 = TCP/IP, M=mixed	x	x	x
TypeOfPartner	1	Type of Partner, Other or Tom	x	x	x
TypeOfRequest	1	Type of request, N = Normal, I = Inquiry, H = Hold	x	x	x
TypeOfUser	1	Type of user, I = Internal, E = External	x	x	x
UserDataReceived	254	User information received with the file (Pi99 PeSIT)	x	x	x
UserDataSent	254	User information sent with the file (Pi99 PeSIT)	x	x	x
UserRequestID	16	Identification of the request given by the user		x	
X25Cause	2	X25 Cause	x	x	
X25Diag	2	X25 Diagnostic	x	x	
X25Facilities	32	Remote X25 address, facilities	x	x	x
X25LocalAddress	15	Local X25 address	x	x	x
X25Localport	1	Local device	x	x	
X25MchLuName	8	Local Mch name		x	
X25MchName	8	Local Mch Lu name		x	
X25Rc	4	X25 Return code	x	x	
X25RemoteAddress	15	Remote X25 address	x	x	x
X25UserDataField	16	Remote X25 address, user data field	x	x	x

## Chapter 4

---

### Sterling Connect:Express User Interface

This chapter describes how to implement a Sterling Connect:Express Browser Interface under control of the Http server of SI. It describes first the installation procedure and the first tests that you can perform. In a third paragraphe it shows how to integrate this Human interface in SI environment.

A browser interface is provided for integration of Sterling Connect:Express file transfer functionnality with SI. This interface takes advantage of the http server of SI : it can be integrated in an application by the use of an URI configured in the http server adapter.

This interactive facility complements the set of services described above, that you can use for automatizing of the file transfer process managed by Sterling Connect:Express, PeSIT for example. Through screens you can perform the average operations related to file transfer with Sterling Connect:Express : partners and files management, transfer request and monitoring.

---

#### Installing the Interface

First of all extract on your desktop the two files of the CXSI\_IHM\_5.0.05.zip file: CXSession.war and CX\_IHM\_Export.xml.

##### *Deploying the Interface*

Copy the .war file in SI environment: [installdir]/noapp/deploy. SI wil deploy it during next initialization.

##### *Installing the SI Ressources*

The .xml file includes a BP 'CXConfig', a configuration CXConfig of CXConfigurationAdapter, a configuration CXHttpserver of HttpServerAdapter .

Login to the SI server and import the file CX\_IHM\_Export.xml using the menu deployment / resource manager / import. Provide the following parameters:

- ❖ File Name CX\_IHM\_Export.xml
- ❖ Passphrase Sterling Connect:Express
- ❖ Skip Tag Name and Tag Description
- ❖ Update Objects Yes
- ❖ BP Selection select CXConfig
- ❖ Service Configurations select both services

The confirmation screen displays :

## Import Resources

**Confirm**

File Name	C:\Documents and Settings\gcazenave\My Documents\Cazenave\CX\Integrated\CXGIS\CX_JHM_Export.xml
Tag Name	none
Tag Description	none
Business Processes	[CXConfig]
Service Configurations	[CXConfig, CXHttpServer]
Update Objects	Yes

[Back](#)  [Next](#)  [Cancel](#)  [Finish](#)

Configure CXHttpServer using the menu deployment / services / configuration : update Http Listen Port field and the War File Pass field of the URI CXSession.

## Services Configuration

**CXHttpServer: HTTP Connection Properties**

HTTP Listen Port:	<input type="text" value="10000"/>
Perimeter Server Name:	<input type="text" value="node1 &amp; local"/>
Total Business Process queue depth threshold:	<input type="text" value="50"/>

**Document Storage**

System Default  
 Database  
 File System

**User Authentication Required**

Yes  
 No

**Use SSL ( Note: User Authentication without SSL will result in a weak security configuration )**

Must  
 None

[Back](#)  [Next](#)  [Cancel](#)  [Save](#)

## Services Configuration

CXHttpServer: URI

URI	
	<a href="#">+ add</a>
	<a href="#">Edit</a>

New URI  
[/CXSession](#)

[◀ Back](#) [▶ Next](#) [Cancel](#) [Save](#)

## Services Configuration

CXHttpServer: WAR Config

Enter War File Path:

OR

Load a System Generated War File: No Generated War Files

[◀ Back](#) [▶ Next](#) [Cancel](#) [Save](#)

The confirmation screen displays :

## Services Configuration

### CXHttpServer: Confirm

Enable Service for Business Processes

#### Service Settings

Service Name	CXHttpServer
Service Type	HTTP Server Adapter
Description	Http server to accept CX requests
System Name	CXHttpServer
Group	None provided
HTTP Listen Port	10000
Perimeter Server Name	node1 & local
Total Business Process queue depth threshold	5
Document Storage	System Default
User Authentication Required	No
Use SSL ( Note: User Authentication without SSL will result in a weak security configuration )	None
URI	URI: CXSession War File Path: C:\SterlingCommerce\SI\noapp\deploy\ICXSession.war

[Back](#)  [Next](#)  [Cancel](#)  [Finish](#)

## Description of the Interface

Before you make tests with the interface you must restart SI after the intallation procedure and start the monitor.

Connect to the URI as shown below. The parameter cxostype can take two values, MICROSOFT WINDOWS or UNIX according to the platform were the monitor executes.

<http://serveursi:10000/CXSession?cxipaddr=xx.xxx.xxx.xxx&cxipport=nnnn&cxostype=MICROSOFTWINDOWS>


**Remark :** if you connect to URI <http://serveursi:10000/CXSession>, the following default values are taken:

- ❖ cxipaddr=localhost
- ❖ cxipport=7000
- ❖ cxostype=MICROSOFT WINDOWS

In case of a MICROSOFT WINDOWS monitor the defaults user name and password are ADMIN and ADMIN.

This section describes some specificities of the browser interface. Refer to Sterling Connect:Express documentation for any information regarding the implementation of file transfers.

The menu displays.



On the left side some current information is shown about the work and the monitor. The workbench is on the left side.


The name of the monitor, CEXP1, is shown. This is the DPCSID field for C:X UNIX, or the name that you gave to C:X Microsoft Windows during the installation procedure.

The versions of the interface, of the CXCMD and the CXJAI components are displayed respectively on the top left corner of the workbench. This enable you to check the compatibility of all components.

If you place the mouse on the icon representing a computer, you can see the operating system on which the monitor executes.

**Current Date**  
2011/03/09 11:29:25

**Monitor CEXP1**  
C:X Windows V31.001



**TCP/IP Address**  
localhost  
**Port (api / transfers)**  
7000 / 6000

**User**  
ADMIN

You can pass the language as parameter to the URI. The following example shows the menu for a UNIX monitor. The screens are in French.

<http://si:10000/CXSession/?cxipaddr=199.1.4.53&cxipport=5050&cxostype=UNIX&lang=FR>

The screenshot displays the IBM Sterling Connect:Express web interface. At the top, it shows the IBM logo and the title "IBM® Sterling Connect:Express®". Below the title, it indicates the interface version: "Version de l'interface IHM 5.2.00 Cmd-1.4.1 Jai-1.4.1".

The main content area is titled "Gestion des transferts de fichiers". On the left, there's a sidebar with the following information:

- Date courante:** 09/03/2011 11:30:53
- Moniteur LIN1**  
C:X/UNIX 150-0
- Sysname:** Linux.Release :2.6.31
- Adresse TCP/IP:** 10.87.14.33  
**Port (api / transferts):** 5025 / 5055
- Utilisateur:** ADMIN

The main panel has several sections:

- Répertoires:** Buttons for "Partenaires" and "Fichiers".
- Requête de transfert:** Buttons for "Envoyer un fichier", "Recevoir un fichier", and "Envoyer un message".
- Suivi des requêtes:** Buttons for "Activité", "Purger", and "Journal".

At the bottom of the interface, a footer note reads: "IBM(R) Sterling Connect:Express(R) - Licensed Material - Property of IBM Corp. (c) Copyright IBM corp. 2008, 2011, All Rights Reserved. IBM and the IBM Logo are Trademarks of International Business Machines Corp."

In such configuration, all functions are based on the Sterling Connect:Express API, with no SI Business Process involved.

## Managing Directories


You can create, update and delete Partners and Files. The interface provides a filter : you can either use the filter or fill in the name directly. The field is required, letters are set to uppercase automatically.  
In filter mode, The field supports wild characters '\*' and '?'.

### Examples :

- ❖ '\*' = all names
- ❖ 'RAC\*' or 'RAC' = all names starting with RAC
- ❖ 'RAC ?0' = all names starting with 5 characters : 'RAC', any character, then character '0'.



Click filter.



### Partners Management

Enter the partner name

Filter : TEST\*

Screens are structured as the following : buttons on the right part enable you to go forward, buttons on the left side enable you to go backward :

Filter	=	define a new filter
Previous	=	previous screen
Return	=	return to the first screen of the current process
Cancel	=	cancel the current process

**Sterling Connect:Express**

**Update**      Partner **DEVUNIX**

**Description :** [ ]

**Current Date** : 2010/11/12 16:08:41

**Monitor CEXP1** C:X Windows V31.001

**TCP/IP Address** localhost  
Port (api / transfers)  
7000 / 6000

**User** ADMIN

<b>State</b>	: Enabled	<b>Password</b>	: PSW		
<b>Local Identification</b>	: Static	<b>Local Name / Password</b>	: GFIPSR / PSR		
<b>Protocol</b>	: PeSIT E	<b>C:X Profile</b>	: No	<b>Link Type</b>	: TCP/IP
<b>Session Table</b> : PeSIT session (TCP/IP)					
<b>Max. Session Number</b>	: 4	<b>Inbound</b>	: 2	<b>Outbound</b>	: 2
<b>Automatic Restart</b>	: Yes	<b>SSL</b>	: No	<b>SSL Client Profile</b>	: [ ]

**Network Parameters**

**Cancel**

Session and Presentation tables are not supported by this interface : use the Standard operator interface of the product.

### File Transfer Request

You can send or receive a file : you are first asked for the name of the file. If the file definition matches the direction, you can provide the name of the partner. However, if the name of the partner is defined in the definition of the file, the interface skips this step and goes directly to next screen.

**Sterling Connect:Express**

**Transfer Request**

**Current Date** : 2010/11/12 16:12:09

**Monitor CEXP1** C:X Windows V31.001

**TCP/IP Address** localhost  
Port (api / transfers)  
7000 / 6000

**User** ADMIN

**Send**

Enter the file name

[ ]

**Filter**

Filters : BEG\*, M?D\*D?E, \*END, ...

**Next**

**Menu**



Once you have provided the file and partner names, you can provide more parameters, first from the file definition, then from the partner definition, and finally parameters specific to the request.

**File parameters**

**IBM**

### Sterling Connect:Express

**Transfer Request**

**Send FILE01 to DEVUNIX**

**DEVUNIX :**

State : Enabled	Protocol : PeSIT E	C:X Profile : No	Link Type : TCP/IP
SSL : No	Session Table : PeSIT session (TCP/IP)		
Local Name / Password : GFIPSR / PSR ( Static )			
Label (P37) : C:\CExpress\in\Report_&REQNUMB_&PI99			
Origin :	Destination :		
Sender :	Receiver :		
Pi99	Offset	Value	
0		&REQDAT&REQTIM	

**Previous** **Next**

**Cancel**

Partner parameters – depending on the protocol

**IBM**

### Sterling Connect:Express

**Transfer Request**

**Send FILE01 to DEVUNIX**


**Local Physical name**  
C:\CExpress\in\Report\_&REQNUMB\_&PI99

User Request ID :	<input type="text"/>	User Name :	ADMIN
Request Type :	<input type="button" value="Normal"/>		

**Previous** **Send the Request** **Cancel**

Request parameters

When the request is accepted, you request number is shown and you can access to Activity and Journal functions.



## *Monitoring Requests*

You can monitor requests in two ways : Activity or Journal. Activity consists of requests that are being processed or eligible to processing, Journal consists of requests ended successfully or not.  
The list of status considered as active depends on the platform.


### **On Microsoft Windows :**


- ❖ . W : Waiting selection
- ❖ . T : Selected
- ❖ . C : Running
- ❖ . I : Interrupted
- ❖ . S : Selection error
- ❖ . R : Restarting

### **On UNIX :**


- ❖ . A : Waiting selection
- ❖ . C : Running
- ❖ . O : Interrupted
- ❖ . D : Deferred
- ❖ . J : Restarting
- ❖ . K : Waiting restart

Activity function provide a filter as shown in the figure below. You can either provide one request number or one or several criteria.





The list screen displays the active filter in the upper part. If you want to display information of a request, select it and click on Detail. You can also interrupt a started request, restart an interrupted request or purge a request. You can refresh the list and update the status.



Request information is displayed in one screen.

You can display journal records using a filter as shown in the following figure. You can either provide one request number or one or several criteria.

The default time interval, in the format 'AAAAMMMJJ HHMMSS', is the current day, for the interface environment. The screen shows the GMT offsets in the monitor environment (C:X GmtOffset) and the GMT offsets in the interface environment (local GmtOffset) because the time interval must be considered in the monitor environment : if the two offsets are equal, just consider your time

The screenshot shows the 'Journal' screen of the Sterling Connect:Express application. At the top left is the IBM logo, and at the top right is the title 'Sterling Connect:Express'. On the left side, there's a sidebar with the following information:

- Current Date:** 2010/11/12 16:26:02
- Monitor CEXP1:** C:X Windows V31.001
- TCP/IP Address:** localhost  
Port (api / transfers)  
7000 / 6000
- User:** ADMIN

At the bottom of the sidebar is a 'Menu' button. The main area is titled 'Display Requests' and contains a form for entering search criteria:

Enter a request number or selection criteria

Request Number	:	<input type="text" value="*"/>
User Name	:	<input type="text" value="*"/>
File	:	<input type="text" value="*"/>
Partner	:	<input type="text" value="*"/>
Direction	:	<input type="button" value="Not Defined"/>
Beginning Date-Time	:	<input type="text" value="2010"/> / <input type="text" value="11"/> / <input type="text" value="12"/> <input type="text" value="00"/> : <input type="text" value="00"/> : <input type="text" value="00"/>
End Date-Time	:	<input type="text" value="2010"/> / <input type="text" value="11"/> / <input type="text" value="12"/> <input type="text" value="23"/> : <input type="text" value="59"/> : <input type="text" value="59"/>

C:X GmtOffset = 1H , Local GmtOffset = 2H

The list screen displays the active filter in the upper part. It shows that the list is limited to 100 requests. If the time interval corresponds to more than 100 requests, you might have to modify the beginning and end date to obtain the 100 requests you want.

If you want to display information of a request, select it and click on Detail. You can Refresh the list and update the status.

Request information is displayed in two screens: the first screen displays the results of the transfer, the second screen displays information that depend on the protocol

**Sterling Connect:Express**

**Journal**

Display Requests

Request: \* User Name: \* File: \* Partner: \* Dir.: \*

Beginning Date-Time: 2010/11/12 00:00:00 End Date-Time: 2010/11/12 23:59:59 Limit: 100

**Current Date**  
2010/11/12 16:26:39

**Monitor CEXP1**  
C:X Windows V31.001

Request	User Name	File	Partner	Dir.	Status	End
201031600001	ADMIN	FILE01	DEVUNIX	T	S	2010/11/12 16:18:30
201031600003	ADMIN	FILE01	DEVUNIX	T	S	2010/11/12 16:22:31
201031600004	ADMIN	FILE01	LOOP	T	E	2010/11/12 16:23:04
201031600005		FILE01	LOOP	R	E	2010/11/12 16:23:04

**TCP/IP Address**  
localhost  
Port (api / transfers)  
7000 / 6000

**User**  
ADMIN

**Detail**

**Filter**

**Refresh**

**Sterling Connect:Express**

**Journal**

Request N° 201031600005 /

**File:** FILE01 **Dir.:** Receive **Partner:** LOOP **User Name ( External )** **Priority:** 0

Request Type: Normal Protocol: PeSIT E C:X Profile No SSL: No

Type of Notification:

**Status** Ended Trc: 0000 Prc: 0000 Src: 00000000 CTree: Nrc: 0000

**Local Physical name** Open Option: Create

C:\CEXpress\in\Report REQ00005 &REQDAT&REOTIM

Type of Data: Binary Type of File: Binary Variable Record Length: 1024

**Statistics** File Bytes: 76800 Records: 75

Scheduling: 2010/11/12 16:23:04 Beginning: 2010/11/12 16:23:04 End: 2010/11/12 16:23:04

Network Bytes: 000000076738 Network Messages: 23 Retry Number: 0

**Back to the List** **Protocol-Network**

**Filter**

**Sterling Connect:Express**

**Request N° 201031600005 /**

<b>Current Date</b> 2010/11/12 16:29:14	<b>Protocol</b> PeSIT E <b>C:X Profile</b> No <b>Local Name</b> LOOP <b>Transfer ID</b> 020DF9
<b>Monitor</b> CEXP1 C:X Windows V31.001	<b>Origin</b> LOOP <b>Destination</b> LOOP <b>Sender</b> LOOP <b>Receiver</b> LOOP
<b>TCP/IP Address</b> localhost <b>Port (api / transfers)</b> 7000 / 6000	<b>Label (P37)</b> C:\CEXpress\in\report_REQ00004 <b>Pi99 Received</b> &REQDAT&REQTIM <b>Pi99 Sent</b>
<b>User</b> ADMIN	<b>Network TCP/IP</b> <b>Address</b> : 127.0.0.1 <b>Port</b> : 0 <b>TcpIpRc</b> : 0000 <b>Message</b> : 4096 <b>Host</b> :

[Back to the List](#)    [Previous](#)


**Filter**

### Purging Requests


The purge request functionality depends on the platform where the monitor executes.

For Sterling Connect:Express for Microsoft Windows and UNIX, the purge function is available in the Activity screen, along with interrupt and restart functions.


For Sterling Connect:Express for UNIX, the purge function is also available in the Journal screen : it works the same way as in the Activity screen. On the other hand, you are provided a purge function on the Menu screen: this function enables you to purge one request or several requests from criteria. Among the criteria, you can provide either the date after which requests must be kept or the number of days to keep. These two parameters exclude each other.



Purge function from the menu for UNIX



Criteria for purge on UNIX



Purge function from the journal screen for UNIX

## Integration with SI

The description above is available whatever the implementation is, with or without integrating it in an application. You can integrate the interface in a SI application passing parameters to a business process through the URI : the BP is launched during the login phase.

The default configuration of the interface works without SI control : you can use parameters to implement controls.

### *Parameters of the URI*

The parameters of the URI enable you to determine the way the interface will initialize and to provide all or part of the parameters to access the monitor.

There are three ways to initialize :

Interfacing directly with Sterling Connect:Express : this is the default as described above. You can provide parameters to access the monitor. No login phase is activated, no business process is launched.

Login to Sterling Connect:Express : only available with Sterling Connect:Express Microsoft Windows, this mode of initialization requires the user to login to the monitor. A Sterling Connect:Express login is activated. No business process is activated.

Login to SI : in this mode, the user is required to login to SI. The standard SI login screen is activated and the Sterling Connect:Express configuration business process is launched.

The syntax to use is discussed below :

---

```
CXSession? [cxconfigbp=xxxxx/NO] [&cxlogin=YES/NO]
[&cxuser=xxxxx/ADMIN] [&cxpassword=xxxxx/ADMIN ]
[&cxipaddr= xxx.xxx.xxx.xxx/localhost] [&cxipport=ppppp/7000]
[&cxostype=MICROSOFT WINDOWS/UNIX] [&lang=FR/EN]
```

---

Parameter	Description
cxconfigbp	NO (default): direct call to Sterling Connect:Express, no SI session, input Sterling Connect:Express parameters provided. xxxxx: name of a business process to launch. An example is provided: CXConfig. The BP receives the Sterling Connect:Express parameters input, completes or modifies them, returns to the calling jsp page. This parameter is overrided by cxlogin=YES.
cxlogin	YES: direct call to Sterling Connect:Express, no SI session, after login to Sterling Connect:Express for Microsoft Windows (user/password) NO (default): Sterling Connect:Express identification is provided in the parameters or equals to default (C:X Microsoft Windows) cxlogin=YES iverrides cxconfig parameter.
Cxuser Cxpassword	Identification parameters to Sterling Connect:Express Microsoft Windows. Default is ADMIN for both parameters.
Cxipaddr Cxipport Cxostype	Parameters to access Sterling Connect:Express. Default address is localhost, default port is 7000, default OS is the OS where the interface executes (Microsoft Windows more generally)
lang	FR (default): screens are in French. US, EN ... screens are in English

**Example 1 :**

<http://si:10000/CXSession/?cxconfigbp=CXConfig&cxipaddr=199.1.4.53&cxipport=5050&cxostype=MICROSOFTWINDOWS>

Calling the URI CXSession this way results in the following:

- ❖ The user logs in to SI
- ❖ The Business process CXConfig is launched: it receives input the characteristics of Sterling Connect:Express and the name of the SI user. The Business process role is to define the identification parameters to Sterling Connect:Express for Microsoft Windows for this SI user.
- ❖ If this step is executed successfully, communications with Sterling Connect:Express can start. The menu is displayed and all consecutive operations are executed without launching any Business process.

**Example 2 :**

<http://si:10000/CXSession/?cxlogin=YES>

Calling the URI CXSession this way results in the following:

- ❖ The user logs in to Sterling Connect:Express Microsoft Windows
- ❖ The interface initializes the process by acquiring the monitor configuration. Because no Sterling Connect:Express parameters are provided with the URI, the monitor is called at address = localhost, port = 7000, OS = the OS where the interface is executing (probably MICROSOFT WINDOWS).
- ❖ If the login is accepted by the monitor, the menu is displayed and all consecutive operations are executed without launching any Business process.

**Configuration Business Process**


The Business process role is to provide all or part of the parameters to access the monitor. The example of BP provided defines all parameters : this means that only one monitor can be accessed through this Business Process, and the Sterling Connect:Express user is unique.

The monitor is defined by CXConfig configuration of CXConfigurationAdapter service : CXConfig 'defines' the monitor localhost:7000, user ADMIN, password ADMIN.

The user logged in to SI as admin.

The business process inquires the monitor configuration and returns the information to the calling jsp page. This information is shown on the left part of the screen.





## Services Configuration

### CXConfig: Connect:Express configuration display (1/1)

Connect:Express Address:	<input type="text" value="localhost"/>
Connect:Express Api Port:	<input type="text" value="7000"/>
OS Type:	<input type="button" value=" [Undefined]"/>
User Name:	<input type="text" value="ADMIN"/>
User Password:	<input type="text" value="*****"/>
Logging:	<input type="button" value=" FALSE"/>
Api Trace:	<input type="button" value=" FALSE"/>
Mode:	<input type="button" value=" Get"/>

[◀ Back](#) [▶ Next](#) [Cancel](#) [Save](#)

Communication structures with the Business process are shown below.  
The business process receives input the parameters provided by a jsp page.

---

```
Parm = CXUser=CXUser&CXPASSWORD=CXPASSWORD&CXIPADDR=CXIPADDR&CXIPPORT=CXIPPORT&CXOSTYPE=CXOSTYPE  
runBP user="username" nvp=parm pridoc="" bpname="CXConfig" >
```

---

The input structure is :

```
<ProcessData>  
  <PrimaryDocument SCIObjectID="Gis:fa7e74:11c795e7d84:-6aa0" />  
  <CXIPPORT>7000</CXIPPORT>  
  <system-account-user-id>admin</system-account-user-id>  
  <CXOSTYPE>MICROSOFT WINDOWS</CXOSTYPE>  
  <CXIPADDR>localhost</CXIPADDR>  
  <CXUSER>ADMIN</CXUSER>  
  <CXPASSWORD>ADMIN</CXPASSWORD>  
  <username>admin</username>  
</ProcessData>
```

The expected output structure is :

```
<CXResult>  
  <CXServerId>localhost:7000:W:ADMIN:****:FALSE:0:30:0</CXServerId>  
  <Dpcsid>CEXP1</Dpcsid>  
  <CXUser>ADMIN</CXUser>  
  <TcpipListenAddress>localhost</TcpipListenAddress>  
  <CXOSType>MICROSOFT WINDOWS</CXOSType>  
  <TcpipListenPort>6000</TcpipListenPort>  
  <ApiPort>7000</ApiPort>  
  <ProductInfo>C:X Microsoft Windows V3.0.5.001</ProductInfo>  
  <SystemInfo>Microsoft Windows XP</SystemInfo>  
  <BPRResponse>Connected</BPRResponse>  
</CXResult>
```


---

<BPRResponse> field stands for the return code : the character string "Connected" is for success. Any other string means that the connection failed.

```
<CXResult>  
  <CXServerId>localhost:7000:W:ADMIN:****:FALSE:0:30:0</CXServerId>  
  <CXUser>ADMIN</CXUser>  
  <TcpipListenAddress>localhost</TcpipListenAddress>  
  <CXResponse>ERROR.CONFIGURATION_GET_FAILED.Unable to connect to  
    server: localhost:7000:W:ADMIN:ADMIN:FALSE:0:30:0</CXResponse>  
  <BPRResponse>Connection rejected</BPRResponse>  
</CXResult>
```

---

CXResponse fields contains the error message from Sterling Connect:Express interface : The browser interface shows this message in the bottom.



Using a Business Process enables you to limit the number of parameters you provide to the URI. For example you can define one BP for one monitor and pass no parameter in the URI. You can define one BP for one user and pass the monitor parameters through the URI.

---

## Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing

IBM Corporation

North Castle Drive

Armonk, NY 10504-1785

U.S.A.

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing

Legal and Intellectual Property Law

IBM Japan Ltd.

1623-14, Shimotsuruma, Yamato-shi

Kanagawa 242-8502 Japan

**The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:** INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation

J46A/G4

555 Bailey Avenue

San Jose, CA 95141-1003

U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information is for planning purposes only. The information herein is subject to change before the products described become available. This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

#### COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are

written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work, must include a copyright notice as follows:

© IBM 2010. Portions of this code are derived from IBM Corp. Sample Programs.

© Copyright IBM Corp. 2010.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

## Trademarks

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "[Copyright and trademark information](#)" at [www.ibm.com/legal/copytrade.shtml](http://www.ibm.com/legal/copytrade.shtml).

Adobe, the Adobe logo, PostScript, and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

IT Infrastructure Library is a registered trademark of the Central Computer and Telecommunications Agency which is now part of the Office of Government Commerce.

Intel, Intel logo, Intel Inside, Intel Inside logo, Intel Centrino, Intel Centrino logo, Celeron, Intel Xeon, Intel SpeedStep, Itanium, and Pentium are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

ITIL is a registered trademark, and a registered community trademark of the Office of Government Commerce, and is registered in the U.S. Patent and Trademark Office.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Cell Broadband Engine is a trademark of Sony Computer Entertainment, Inc. in the United States, other countries, or both and is used under license therefrom.

Linear Tape-Open, LTO, the LTO Logo, Ultrium and the Ultrium Logo are trademarks of HP, IBM Corp. and Quantum in the U.S. and other countries.

Connect:Express®, Connect Control Center®, Connect:Direct®, Connect:Enterprise, Gentran®, Gentran:Basic®, Gentran:Control®, Gentran:Director®, Gentran:Plus®, Gentran:Realtime®, Gentran:Server®, Gentran:Viewpoint®, Sterling Commerce™, Sterling Information Broker®, and Sterling Integrator® are trademarks or registered trademarks of Sterling Commerce, Inc., an IBM Company.

Other company, product, and service names may be trademarks or service marks of others.

