

Connect:Enterprise® for z/OS

Remote User's Guide

Version 1.4

Connect:Enterprise for z/OS Remote User's Guide

Version 1.4

First Edition

(c) Copyright 2000-2008 Sterling Commerce, Inc. All rights reserved. Additional copyright information is located at the end of the release notes.

STERLING COMMERCE SOFTWARE

*****TRADE SECRET NOTICE*****

THE CONNECT:ENTERPRISE SOFTWARE ("STERLING COMMERCE SOFTWARE") IS THE CONFIDENTIAL AND TRADE SECRET PROPERTY OF STERLING COMMERCE, INC., ITS AFFILIATED COMPANIES OR ITS OR THEIR LICENSORS, AND IS PROVIDED UNDER THE TERMS OF A LICENSE AGREEMENT. NO DUPLICATION OR DISCLOSURE WITHOUT PRIOR WRITTEN PERMISSION, RESTRICTED RIGHTS.

This documentation, the Sterling Commerce Software it describes, and the information and know-how they contain constitute the proprietary, confidential and valuable trade secret information of Sterling Commerce, Inc., its affiliated companies or its or their licensors, and may not be used for any unauthorized purpose, or disclosed to others without the prior written permission of the applicable Sterling Commerce entity. This documentation and the Sterling Commerce Software that it describes have been provided pursuant to a license agreement that contains prohibitions against and/or restrictions on their copying, modification and use. Duplication, in whole or in part, if and when permitted, shall bear this notice and the Sterling Commerce, Inc. copyright notice. As and when provided to any governmental entity, government contractor or subcontractor subject to the FARs, this documentation is provided with RESTRICTED RIGHTS under Title 48 52.227-19. Further, as and when provided to any governmental entity, government contractor or subcontractor subject to DFARS, this documentation and the Sterling Commerce Software it describes are provided pursuant to the customary Sterling Commerce license, as described in Title 48 CFR 227-7202 with respect to commercial software and commercial software documentation.

These terms of use shall be governed by the laws of the State of Ohio, USA, without regard to its conflict of laws provisions. If you are accessing the Sterling Commerce Software under an executed agreement, then nothing in these terms and conditions supersedes or modifies the executed agreement.

Where any of the Sterling Commerce Software or Third Party Software is used, duplicated or disclosed by or to the United States government or a government contractor or subcontractor, it is provided with RESTRICTED RIGHTS as defined in Title 48 CFR 52.227-19 and is subject to the following: Title 48 CFR 2.101, 52.227-19, 227.7201 through 227.7202-4, FAR 52.227-14, and FAR 52.227-19(c)(1-2) and (6/87), and where applicable, the customary Sterling Commerce license, as described in Title 48 CFR 227-7202 with respect to commercial software and commercial software documentation including DFAR 252.227-7013, DFAR 252.227-7014, DFAR 252.227-7015 and DFAR 252.227-7018, all as applicable.

The Sterling Commerce Software and the related documentation are licensed either "AS IS" or with a limited warranty, as described in the Sterling Commerce license agreement. Other than any limited warranties provided, NO OTHER WARRANTY IS EXPRESSED AND NONE SHALL BE IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR USE OR FOR A PARTICULAR PURPOSE. The applicable Sterling Commerce entity reserves the right to revise this publication from time to time and to make changes in the content hereof without the obligation to notify any person or entity of such revisions or changes.

Connect:Direct is a registered trademark of Sterling Commerce. Connect:Enterprise is a registered trademark of Sterling Commerce, U.S. Patent Number 5,734,820. All Third Party Software names are trademarks or registered trademarks of their respective companies. All other brand or product names are trademarks or registered trademarks of their respective companies.

Sterling Commerce, Inc.

4600 Lakehurst Court Dublin, OH 43016-2000 *
614/793-7000

Contents

Chapter 1 Connect:Enterprise FTP Implementation 7

Data Representation and Storage	7
Data Type	8
ASCII	8
EBCDIC	8
Format Control for Character Data	8
Image	9
Data Structure	10
File	10
Record	10
Page	10
Transfer Mode	11
Stream	11
Block	11
Compressed	12
Controlling FTP Connections	13
Implementing Firewall Navigation	13
Implementing the Clear Control Channel (CCC) Feature	13
Connecting to a Connect:Enterprise FTP Server	14
Prerequisites	14
Log On	14
Connect:Enterprise FTP Server and Equivalent Client Commands	15
SITE Command Parameters	19
Sample Output of STATUS Command	27
VSAM Batch Status Flags	29
Different DIRFORM Layouts Returned by LIST	30
Connect:Enterprise Variations from Standard FTP Commands	34
User Batch ID Syntax and Formats	34
delete or mdelete Command	35
Connect:Enterprise FTP del, delete, and mdelete Command Syntax	36
Batch Selection with Connect:Enterprise FTP del Command	36
dir Command	37
Connect:Enterprise FTP dir Command Syntax	38
Batch Selection with Connect:Enterprise FTP dir Command	38
get or mget Command	38
Connect:Enterprise FTP get Syntax	39
Batch Selection	39
Batch Transmission	40
Batch Status Flags	40

put or mput Command (STOR)	41
Connect:Enterprise FTP put Syntax	41
put or mput Command (STOU)	42
Connect:Enterprise FTP put Syntax	42
pwd Command	43
pwd Command Syntax	43
cd Command	43
NLST Command	43
Connect:Enterprise NLST Command Syntax	44
Batch Selection	44
Preparing Batches for the Connect:Enterprise FTP Server	45
Using \$\$Commands and /*Cards	46
\$\$Commands and /*SIGNON with /*BINASC	47
\$\$Commands and /*SIGNON without /*BINASC	47
Syntax	48
\$\$ADD Command Parameters	48

Chapter 2 Communicating with SNA Sites **51**

Start and End a Session	51
Using Connect:Enterprise	52
Wildcard Characters in Connect:Enterprise Names	52
Terminal-Dependent Options	53
SNA Sites	54
MLU (Multiple Logical Unit) Support	54
Device Media Support	54
Console Display Use	55
Data Compression	55
Batch Separation Using FMHs	56
SNA Transparency	56
Disconnect Interval	56
EBCDIC Support	57
Sample Data Streams	57
SNA Site Parameters	58

Chapter 3 Communicating with BSC Sites **63**

Start and End a Session	63
Connect:Enterprise Support for Signon (BSC Sites)	63
Host-Initiated Communications (Auto Connect)	64
Using Connect:Enterprise	64
Wildcard Characters in Connect:Enterprise Names	65
Terminal-Dependent Options	65
BSC Options	66
Free-Form BSC SIGNON	66
Blank Compression	66
Blank Truncation	66
Blocked Data Records	67

BSC Transparency	67
Record Separator Override	67
Use of \$TURNLINE\$	67
Temporary Text Delay (TTD)	68
WAIT Acknowledgement (WACK)	68
Sample Data Streams	68
BSC Site Parameters	69
Chapter 4 Remote User Commands	71
Submit Commands	71
\$\$ADD Command	74
\$\$ADD Defaults	74
Multiple Batches	75
Syntax	75
Description	75
\$\$DELETE Command	76
Syntax	76
Description	76
\$\$DIRECTORY Command	76
Syntax	76
Description	77
Output	77
SNA Logon System Function	79
Syntax	79
Description	79
SNA LOGOFF and \$\$LOGOFF System Functions	80
Syntax	80
Description	80
\$\$REQUEST Command	80
Syntax	81
Description	81
Parameter Interrelationships	81
\$\$REQUEST Sample Outputs	81
Chapter 5 Error Messages	83
Remote User Error Messages (** ERROR **)	83
Glossary	89
Index	101

Connect:Enterprise FTP Implementation

The Connect:Enterprise FTP feature provides the standard FTP interface to an FTP client. It operates as an FTP server for connections from remote FTP clients. Connect:Enterprise places restrictions on the use and meaning of some FTP commands, which are discussed in this chapter. In addition, remote users can embed \$\$ADD commands in an FTP data stream to add data to the host data repository on the Connect:Enterprise FTP server. The last section in this chapter deals with using the \$\$ADD command and how data files must be formatted in order for the Connect:Enterprise FTP server to properly scan and interpret the \$\$ADD command including the data.

Data Representation and Storage

Transferring files between different computer systems introduces a myriad of issues emanating from the differences between computer systems. The IBM System z/OS architecture uses an 8-bit EBCDIC byte to represent character data. The IBM PS/2 system uses an 8-bit ASCII byte to represent character data. Some computers use a 7-bit ASCII code. The IBM PS/2 system organizes files as a continuous stream of data. The IBM System z/OS organizes files into records. With all these differences, Connect:Enterprise must provide a method of transferring these files and making them available for use on the receiving system.

The Connect:Enterprise FTP feature deals with these issues. FTP provides for FTP client and FTP server implementations to negotiate the data representation and storage types through the use of the data type, data structure, and transmission mode standard specifications.

Note: You are responsible for specifying the Connect:Enterprise FTP server options and the remote FTP client options so that the data transferred is usable by the receiving host.

Data storage attributes are determined by the host system. The Connect:Enterprise FTP feature stores character data in EBCDIC and image (binary) data as received. Data received as NVT-ASCII is converted to EBCDIC before being added to the current working data repository.

Connect:Enterprise performs the role of FTP server and the types are set by the remote FTP client.

The Connect:Enterprise FTP feature transfers data as 8-bit bytes. If your remote FTP client uses a different byte length, it is up to you to implement the appropriate conversion between local byte size and the Connect:Enterprise FTP feature 8-bit byte transfer length.

Data Type

Data type specifies how the receiver interprets the data bits being transferred. The receiver is either the Connect:Enterprise FTP server or the remote FTP client.

Connect:Enterprise FTP server assumes that the remote FTP client uses the ASCII character set. If the remote site does not use the ASCII character set, the remote FTP client must send the TYPE command to change the data type to EBCDIC or BINARY.

The FTP standard includes four data types: ASCII, EBCDIC, image, and local. Connect:Enterprise FTP server provides the ability to specify *three* data types: ASCII, EBCDIC, and image. The local byte size is 8 bits (L 8) for Connect:Enterprise, and cannot be changed.

ASCII

ASCII is character data. The sender converts the data from its internal representation into standard 8-bit NVT-ASCII before sending the data. Each line of data ends with a carriage-return-line-feed (<CRLF>). An ASCII <CRLF> is hexadecimal '0D0A'.

If Connect:Enterprise is receiving, the data is translated from NVT-ASCII to EBCDIC and the <CRLF> sequences are replaced with a new line (<NL>) character before the data is added to the current data repository. An EBCDIC <NL> is hexadecimal '15'.

If Connect:Enterprise is sending, the data is translated from EBCDIC into NVT-ASCII and the <NL> characters are replaced with the <CRLF> characters before transmitting the data to the remote FTP server.

ASCII (TYPE A) is the default data type for Connect:Enterprise FTP feature.

EBCDIC

EBCDIC is character data. The EBCDIC data type is the most efficient way to transfer data between EBCDIC hosts.

If Connect:Enterprise is receiving, the data is not translated before being added to the current data repository.

If Connect:Enterprise is sending, the data is not translated before being transmitted.

Not all remote ASCII hosts accept data type EBCDIC. Some remote FTP servers reject data type EBCDIC. Some hosts accept data type EBCDIC and store it as binary. Other hosts accept data type EBCDIC as binary, and then translate the data into data type ASCII.

Format Control for Character Data

Data types ASCII and EBCDIC have a second, optional parameter called format control. The format control parameter specifies the presence and type of vertical formatting control in the data being transferred. The Connect:Enterprise FTP implementation ignores ASCII and EBCDIC format

controls. The following table shows the data types accepted by Connect:Enterprise FTP and the TELNET codes associated with the data types.

Type	Description
A See Note 1.	ASCII nonprint
A C See Note 1.	ASCII nonprint
A N See Note 1.	ASCII nonprint
A T See Note 1.	ASCII telnet
E See Note 2.	EBCDIC nonprint
E C See Note 2.	EBCDIC nonprint
E N See Note 2.	EBCDIC nonprint
E T See Note 2.	EBCDIC telnet
I	Image (binary)

1 Data types A, A C, A N, and A T are identical in the Connect:Enterprise FTP implementation.

2 Data types E, EC, E N, and E T are identical in the Connect:Enterprise FTP implementation.

Image

Image is noncharacter data. Data is sent and received as contiguous bits packed into 8-bit bytes. No translation takes place by Connect:Enterprise. Connect:Enterprise also assumes that no translation takes place at the remote FTP server. Character data can be transmitted as image, but no translation occurs.

Term	Definition
CC	Indicates that data contains ASA control characters in the first position of every line. The first character determines the vertical movement of the paper before the data is printed. The ASA control character is not printed. The first character after the ASA control character is printed on the first position of the output line on the paper.

Term	Definition
NONPRINT	Indicates the data does not include format control characters. Nonprint format control is generally accepted by all FTP implementations. This format can be used for data destined for storage or processing. A print processor can assume that nonprint data contains standard values for spacing and margins.
TELNET	The file contains ASCII or EBCDIC vertical format controls that a printer Process can interpret. Some examples of TELNET vertical form control are carriage return (<CR>), line feed (<LF>), new line (<NL>), and vertical tab (<VT>). The <CRLF> sequence denotes end-of-line, not vertical control.

The four standard ASA control characters are:

Character	Vertical Spacing
blank	Move paper up one line.
0	Move paper up two lines.
1	Move paper to top of next page (form).
+	No movement. Overtyping the previous line.

Data Structure

The FTP client specifies the structure of files being transferred to and from Connect:Enterprise. Data structure is significant when transferring files between systems that have different methods of storing files. Some systems store files as file-oriented, whereas others store them as record-oriented.

The FTP standard includes three data structures: file, record, and page. Connect:Enterprise FTP provides the ability to specify *two* FTP data structures: file and record. Connect:Enterprise FTP does not support the page structure.

File

File has no internal structure and is considered a continuous sequence of bytes. File structure can be used with all transfer modes and data types. End-of-file (<EOF>) is indicated when the sender closes the data connection. File is the default data structure for Connect:Enterprise.

Record

The data is sent as a set of sequential records. The record structure is only valid with transfers of text files (data type ASCII or data type EBCDIC). End-of-record (<EOR>) indicators for all records, including the final record, must be explicit.

Page

The page structure is not implemented in the Connect:Enterprise FTP feature.

Transfer Mode

Transfer mode indicates which transmission services Connect:Enterprise must provide for z/OS FTP server.

There are three transfer modes defined in the FTP standard and implemented in Connect:Enterprise: stream, block, and compressed.

Stream

Data is transferred as a stream of bytes. Use any of the data types or data structures implemented in the Connect:Enterprise FTP feature. Stream mode is the default transfer mode for the Connect:Enterprise server.

For the file structure, end-of-file is indicated when the sending host closes the data connection. All bytes transferred are data bytes.

For the record structure, the end-of-record (<EOR>) and end-of-file (<EOF>) is identified by 2-byte control sequences. The <EOR> control sequence must be explicit, including the last record. The <EOR> and <EOF> control sequences are not stored as a part of the batch's data.

The first byte of a control sequence is the escape code—hexadecimal 'FF'. An <EOR> sequence is hexadecimal 'FF01'. An <EOF> sequence is hexadecimal 'FF02'. <EOR> and <EOF> can be indicated together on the last byte of the data as hexadecimal 'FF03'. An implicit <EOF> is indicated when the sender closes the data connection without receiving the <EOF> sequence.

If a data byte contains hexadecimal 'FF', two bytes of hexadecimal 'FFFF' are transmitted and received to prevent the loss of data. The single byte of hexadecimal 'FF' is stored with the batch, not the two bytes of hexadecimal 'FFFF'.

Block

Data is transferred as a series of blocks. Any of the data types are valid for a block mode transfer. Any of the file structures are valid for block mode transfer.

A header precedes each data block. The header is three (3) bytes long and contains a descriptor code and byte count field. The descriptor code is a binary code and is not data type sensitive. The byte count field is an unsigned half-word integer, and is not data type sensitive.

The descriptor code is the high-order byte (8 bits) of the header, and defines the block's attributes. The following table contains the valid descriptor codes:

Dec Code	Value	Meaning
128	X'80	'End of byte count is EOR
64	X'40	'End of byte count is EOF
32	X'20	'Suspected errors in data block (informational only)
16	X'10	'Data block is a restart marker
0	X'00	'Data continues to next block

The count field is the low order two bytes (16 bits) of the header, and contains of the number of bytes in the block excluding the header.

Compressed

Data is transferred as a series of blocks in a compressed format. ASCII and EBCDIC are the only valid data types for a compressed mode transfer. The only valid data structure for a compressed mode transfer is file. Compressed format transfers contain three kinds of information: uncompressed data, compressed data, and control information.

Uncompressed data is transferred as a byte string, and is preceded by a 1-byte count field. The maximum length of an uncompressed string is 127 bytes. If the byte contains a value from 1 through 127 (hexadecimal '01' through '7F'), it is a count field that describes the number of uncompressed bytes that follow.

There are two types of compressed data: replication and filler.

- ◆ Replication compressed data is represented by a 1-byte count field in front of the replicated character. The count field is the number of times the single character occurs in the data. If the byte contains a value from 128 to 191 (hexadecimal '80' through 'BF'), it is a count of the number of times the next byte is replicated. The first two bits of the byte are ignored. The last six bits contain the number of times the character is replicated. The maximum length of a compressed replicated field is 63 bytes. The replicated character is included in the count field.
- ◆ Filler compressed data is represented by a 1-byte count field. The count field is the number of filler characters that occur in the data. The filler byte is a blank character. If the byte contains a value from 192 to 255 (hexadecimal 'C0' through 'FF'), it is a count of the number of filler bytes to expand into the data. The first two bits of the byte are ignored. The last six bits contain the number of filler bytes. For ASCII and EBCDIC, the filler byte is a blank character. A blank is ASCII code 32 (hexadecimal '20') or EBCDIC code 64 (hexadecimal '40'). The maximum length of a compressed filler field is 63 bytes.

Control information is sent as a 2-byte control sequence. The first byte is an escape (<ESC>) character. The second byte contains a descriptor code. Control information is optional. The count and control sequence fields are not part of the data. The count and control field lengths are not included in the length of the information fields.

Data that is read from the TCP/IP stack is decompressed before any translation is done. Each byte read from the TCP/IP stack is examined for the count or control sequence field.

If the value of the byte is zero (hexadecimal '00'), it is the first byte of a 2-byte control sequence. The first byte of zero is the escape character. The second byte contains a descriptor code. The descriptor codes have the same meaning as in block mode and apply to the succeeding string of bytes. The succeeding string can be an uncompressed data string, a compressed replicated character, or a compressed filler character.

The compression count information fields are eliminated when the file is decompressed. The compression <EOR> control sequence field (hexadecimal 0080') is replaced with the <EOR> control sequence field, hexadecimal 'FF01'. The compression <EOB> control sequence field (hexadecimal '0040') is replaced with the <EOB> control sequence field, hexadecimal 'FF02'.

The following table shows which transfer modes you can specify for a given data type and data structure when using the Connect:Enterprise FTP server. Transfer mode *stream*, data type *ASCII*, and data structure *file* are the defaults for Connect:Enterprise FTP server.

Transfer Mode	Data Type			Data Structure	
	ASCII	EBCDIC	Image	File	Record
Stream	X	X	X	X	X
Block	X†	X	X†	X	X†
Compressed	X†	X	X†	X	X†

Note: The combinations marked by a dagger are not currently supported by the IBM z/OS FTP server.

When selecting among the options listed, consider the purpose of the file transfer. If programs on the receiving host use the transferred file, select options that make the file usable on the receiving host. If the receiving host is being used as an intermediate storage location for the transferred file, and the file will be retrieved again by the original host, you can select data type image, data structure file, and transfer mode stream.

Controlling FTP Connections

This section describes considerations for navigating firewalls and using the Clear Control Channel feature.

Implementing Firewall Navigation

Certain parameters defined in the Option Definition File (ODF) in Connect:Enterprise for z/OS enable you to apply restrictions to FTP operations in active and passive FTP mode, enabling you to control FTP connections through your firewall. These parameters enable you to define port ranges, the number of retries if socket acquisition fails, and how long to wait between retries.

Although you can specify all available ports on a system in each range, you can control firewall navigation more effectively by assigning a limited number of ports for FTP operations.

Implementing the Clear Control Channel (CCC) Feature

Using the CCC feature provides a way to negotiate the control connection from an encrypted content to a clear text content. After the user ID and password have been transmitted in encrypted format, the remainder of the control transmission is in clear text until the connection ends. All data and objects transferred between the client and server remain encrypted.

Note: The CCC command is valid for Secure FTP only, and each endpoint of the connection must support the use of this command.

Connecting to a Connect:Enterprise FTP Server

The following procedure describes how to connect to a Connect:Enterprise FTP server. This is a generic procedure and assumes that you have access to an FTP client software package. Your FTP client software can require different procedures.

Note: Point and Click FTP systems do not have a command line. The prerequisite information is included during installation.

Prerequisites

Obtain the following information from your Connect:Enterprise administrator:

- ◆ Connect:Enterprise FTP server IP address or host name and port number or range of ports
- ◆ User name or remote name and password
- ◆ Mailbox ID

Log On

1. At the command line prompt, issue the following command:

```
> ftp host_name port_number
```

If your FTP client does not allow parameters on the initial ftp command, use the following two commands to establish the connection:

```
> ftp
> open host_name port_number [port_range(s)]
```

where “host_name” and “port_number” are the server IP address or host name and port number obtained from the Connect:Enterprise administrator, and “port_range(s)” limits the port or range of ports available for FTP transmissions through firewalls.

The Connect:Enterprise FTP server sends the following messages when the connection is complete, where:

```
220-Connect:Enterprise vv.rr.mm on opsys_name opsys_rel.
220-Connection will close if idle for more than discintv.
220 Ready (at local host date and time) yyyy/mm/dd at hh:mm:ss
```

- ◆ *vv.rr.mm* is the version, release, and modification level of Connect:Enterprise at the host site.
- ◆ *opsys_name* is the standard name for the operating system executing Connect:Enterprise.
- ◆ *opsys_rel* is the release information of the operating system.

- ◆ *discintv* is the idle disconnect interval.

The idle disconnect interval is the number of seconds that the FTP client and FTP server connection remains open with no activity. The Connect:Enterprise FTP server forces the session to end by closing the control connection. Get the required disconnect interval from the Connect:Enterprise administrator at the host site

- ◆ *hh:mm:ss* and *yyyy/mm/dd* are the time and date of the connection.

The time and date of the connection is the Connect:Enterprise local time and date. Batches added by the FTP client are posted using the Connect:Enterprise local time and date.

2. The FTP client prompts you for your user name. The user name is assigned by the Connect:Enterprise administrator and is referred to as the remote name. If the FTP client does not prompt you for your user name, type the following command:

```
> user username
```

3. The FTP client prompts you for your password. The initial password is assigned by the Connect:Enterprise administrator. When you are connected, the current working mailbox ID is the same as your user name.

Connect:Enterprise FTP Server and Equivalent Client Commands

This section describes the standard FTP commands that the Connect:Enterprise FTP server accepts along with the typical FTP client commands that invoke them. They are labeled typical FTP commands because some FTP client interface panels contain non-standard commands, like *get*, instead of the standard FTP commands, like *retr*. The client software translates a non-standard FTP client command into a standard FTP command before sending it to the FTP server.

The following table describes terminology specific to Connect:Enterprise FTP. The Connect:Enterprise terms have synonyms that may be more familiar to experienced FTP users.

Connect:Enterprise Term	Synonym
Mailbox ID	Directory
Batch ID or user batch ID	File name
Batch Number	Batch Number

Note: In Connect:Enterprise, it is possible for a mailbox ID to contain identical batch IDs or file names. The unique identifier for individual files in Connect:Enterprise thus becomes the batch number.

The exact format in which you issue a command depends on your operating system and follows any conventions required. For example, the Help command can provide help from your own operating system but not from Connect:Enterprise.

Caution: If you are issuing FTP commands from a client that does not use a Point and Click system, inconsistent results may occur if you do not follow the conventions of your operating system.

The dialog feature of Connect:Enterprise provides a way to track and troubleshoot inconsistencies that result from failure to adhere to your operating system conventions for commands. All transmissions between Connect:Enterprise FTP client and server are monitored and written to a dialog log file at the client site. This file lists each transmission, the command you thought you were issuing, and the command that Connect:Enterprise actually received. In addition, any error or confirmation messages returned by Connect:Enterprise are recorded in this file. Coordinate with your host site administrator to turn dialog on as the default for your site. If you do not want dialog on as a default, you can issue the \$\$DIALOG command from the command line to turn it on temporarily and troubleshoot for a particular session.

Connect:Enterprise FTP supports only the FTP commands in the following table, which lists FTP client commands available for a remote FTP client and the equivalent FTP command invoked by the Connect:Enterprise FTP server. When necessary, the Connect:Enterprise FTP description states how the Connect:Enterprise FTP implementation differs from the standard. Variations from the standard FTP commands are detailed in *Connect:Enterprise Variations from Standard FTP Commands* on page 34.

Command Invoked by Connect:Enterprise FTP Server	FTP Client Command	Standard Description	Connect:Enterprise FTP Implementation
ABOR	abort	Terminates the current data transfer. If a data transfer is not occurring, ABOR does not affect the session. Invalid if issued prior to logon completion.	Same as standard
AUTH	AUTH	Identifies the security mechanism used. Required to initiate a secure FTP session. SSL and TLS are the only security mechanism supported. Must be received prior to the USER and PASS commands.	Same as standard

Note: By default, anonymous remote sites can execute all commands except CWD and DELE. The security exit or security interface can further limit the abilities of anonymous remote sites.

Command Invoked by Connect:Enterprise FTP Server	FTP Client Command	Standard Description	Connect:Enterprise FTP Implementation
CCC	CCC	Secure FTP only. Negotiates the control connection from an encrypted content to a clear-text content after the user ID and password have been transmitted in encrypted format. All data and objects transferred between client and server remain encrypted. Both ends of the connection must support this command.	Negotiate a clear-text control channel.
CWD	cd See table Note.	Change working directory Invalid if issued prior to logon completion.	Change current working mailbox ID
DELE	delete and mdelete See table Note.	Delete a file Invalid if issued prior to logon completion.	<i>Logically</i> delete batches from the current working mailbox ID This command does NOT delete the batch permanently. The information is recoverable until a purge is performed.
HELP	HELP	Display help information Invalid if issued prior to logon completion.	Same as standard
LIST	dir	List file information Invalid if issued prior to logon completion.	List batches in the current working mailbox ID
NLST	ls, mdelete, mget	Names only list Invalid if issued prior to logon completion.	List user batch IDs in the current working mailbox ID
MODE	mode	Transfer mode	Same as standard
NOOP	NOOP	No operation Invalid if issued prior to logon completion.	Same as standard
PASV	PASV	Listen on alternate port Invalid if issued prior to logon completion.	Same as standard
PASS	PASS	Password	Same as standard

Note: By default, anonymous remote sites can execute all commands except CWD and DELE. The security exit or security interface can further limit the abilities of anonymous remote sites.

Command Invoked by Connect:Enterprise FTP Server	FTP Client Command	Standard Description	Connect:Enterprise FTP Implementation
PBSZ	PBSZ	Specifies maximum buffer size in bytes of encrypted data sent or received during file transfer. Must occur prior to PROT command. Valid if issued prior to logon completion.	Same as standard
PORT	port	Host data port number	Same as standard
PROT	PROT	Indicates the type of data channel protection used by client and server during transfer. P is the only value currently supported. Indicates all data on channel is encrypted.	Same as standard
PWD	pwd	Print current directory name	Print current working mailbox ID
QUIT	QUIT	Disconnect	Same as standard
RETR	RETR, get, mget	Transfer (get) a file Invalid if issued prior to logon completion.	Retrieve batches from the current working mailbox ID
SITE	SITE	Site-specific information Invalid if issued prior to logon completion.	Same as standard
STAT	STAT	Send status Invalid if issued prior to logon completion.	Same as standard
STOR	STOR, put, mput	Transfer a file Invalid if issued prior to logon completion.	Add a batch to the current working mailbox ID
STOU	STOU	Store a file with a unique name Invalid if issued prior to logon completion.	Add a batch to the current working mailbox ID
STRU	STRU	Set file transfer structure	Same as standard
SYST	SYST	Type of operating system	Same as standard
TYPE	TYPE	Data representation type Valid if issued prior to logon completion.	Same as standard
USER	USER	User name	Same as standard

Note: By default, anonymous remote sites can execute all commands except CWD and DELE. The security exit or security interface can further limit the abilities of anonymous remote sites.

Connect:Enterprise commands are not case-sensitive. Connect:Enterprise FTP server translates all commands to upper case. For example, "Help" is the same as "help," "HELP," and "help"

All commands end with a carriage-return-line-feed (<CRLF> is hexadecimal '0D0A') for ASCII and new line (<NL> is hexadecimal '15') for EBCDIC.

The <SP> symbol denotes a single space (blank). A blank is ASCII code 32 (hexadecimal '30') and EBCDIC code 64 (hexadecimal '40').

SITE Command Parameters

The SITE command sets parameters specific to Connect:Enterprise that affect adding batches (STOR), retrieving batches (RETR), listing batches (LIST), and listing user batch IDs (NLST). You can view the current values of the SITE command parameters using the STAT command. Refer to *Sample Output of STATUS Command* on page 27.

Multiple parameters can be specified on the SITE command. Specifying the SITE command with the RESET parameter sets all of the SITE parameter's values to the session default value. IDENT parameters are not affected by RESET.

The values set for a SITE command parameter remain in effect for the remainder of the session, except for the DIR_FILTER and LS_FILTER parameters. The DIR_FILTER and LS_FILTER parameter value changes are only effective for the next execution of the LIST or NLST command, respectively. To make the DIR_FILTER and LS_FILTER parameter values effective for the remainder of the session, specify the KEEP option.

No security checks are made for the SITE command.

The following table lists the parameters valid for the SITE command. The column labeled "FTP server Command" lists the Connect:Enterprise FTP server command that is affected by the

parameter listed. The column labeled “Remote FTP Client Command” lists the typical FTP client command that invokes the FTP server command affected by the parameter.

SITE Parameter	Description	FTP Server Command	Remote FTP Client Command
BCHSEP=NONE OPT3 OPT4 See Note 1.	Batch separation options. Note: BCHSEP=OPT4 affects the format of the responses from an NLST command, which can affect the typical FTP client mdelete and mget commands. See <i>Batch Status Flags</i> on page 40 for an explanation of the BCHSEP options.	NLIST, RETR	get, ls, mdelete, mget
BLKSIZE=0-32760 or blank	Block size of allocated file being sent.	STOR, STOU	put, mput
BLOCKS	Primary allocation amount of file being sent is in BLOCKS.	STOR, STOU	put, mput
BLOCKSIZE=0-32760 or blank	Block size of file being sent.	STOR, STOU	put, mput
CYLINDERS	Primary allocation amount of file being sent is in CYLINDERS.	STOR, STOU	put, mput
DIR_FILTER [QUERY]	Display batch exclusion filter.	N/A	N/A
DIR_FILTER DEFAULT NONE OFF [KEEP]	Reset batch exclusion filter.	LIST	dir
DIR_FILTER=<flags> [KEEP] See Note 1.	Specify batch exclusion filter.	LIST	dir
DIRECTORY=1-16777215 or blank	Number of directory blocks allocated for file being sent.	STOR, STOU	put, mput

- 1 The default values for these parameters are specified in the *REMOTES sections of the ODF by the Connect:Enterprise administrator.
- 2 FTIME, ORIGIN, and TTIME affect the contents of the response from an NLST command. The response from the NLST command affects the typical client mdelete and mget commands.

SITE Parameter	Description	FTP Server Command	Remote FTP Client Command
DIRFORM= BROWSER BROWSER64 MBOX_CLIENT MBOX_CLIENT64 MBOX_ZOS MBOX_ZOS64 \$MIBNSDFXY UNIX UNIX64 See Note 1.	<p>Reply format options. The values following the \$ can be specified in any order to achieve the desired directory display format. Any number of options can be specified. See <i>Different DIRFORM Layouts Returned by LIST</i> on page 30 for examples.</p> <p>\$ User-defined format</p> <p>M 8-character mailbox ID</p> <p>I 24-character batch ID.</p> <p>B 24-character user batch ID.</p> <p>N 7-digit batch number (#nnnnnn)</p> <p>S 12-digit file size in number of bytes (CT=nnnnnnnnnnnn)</p> <p>D time/date of batch creation (hhmm-yyddd)</p> <p>F Batch status flags.</p> <p>X 64-character Batch ID (BID=xxxx....xxxx)</p> <p>Y 64-character Batch ID (xxxx....xxxx)</p>	LIST	dir
EDI= <u>NO</u> YES	<p>Specifies whether single byte x'15' segment terminators are used.</p> <p>EDI=YES indicates that X'15' segment terminators are being used and allows the translation table to translate the X '15' to a single byte.</p> <p>EDI=NO (the default) indicates that X'15' segment terminators are not being used so standard EBCDIC to ASCII translation is used to translate the X '15' to the 2-byte X '0D0A'.</p>	RETR	mget, get

- The default values for these parameters are specified in the *REMOTES sections of the ODF by the Connect:Enterprise administrator.
- FTIME, ORIGIN, and TTIME affect the contents of the response from an NLST command. The response from the NLST command affects the typical client mdelete and mget commands.

SITE Parameter	Description	FTP Server Command	Remote FTP Client Command
EO=NO YES See Note 1.	Extract once. EO=YES specifies that the batch is extracted and stored one time from a remote client and cannot be transmitted. The default value EO=NO does not prevent transmission or multiple extractions.	STOR, STOU	mput, put
FIXRECFM	Sent by IBM—ignore.	STOR, STOU	put, mput
FTIME=<from_time> See Note 2.	Limit batch selection by specifying the starting date for all data selected for processing. This value is used to calculate dates relative to the current date (for example, FROMDATE=3 is resolved to the date three days ago). The default is 1980001. Valid formats: nnn hhmm yyddd ccyyddd nn:hhmm yyddd:hhmm ccyyddd:hhmm	DELE, LIST, NLST, RETR	delete, dir, get, ls, mdelete, mget
IDENT PROD_ID=n PROD_REL=x.x.xx	Identification of Connect:Enterprise product.	N/A	N/A
KALIVEOFF	Turns off the KALIVEON parameter. Note: KALIVEOFF is equivalent to setting KALIVEON=0.	N/A	N/A
KALIVEON=nnnnnnn	Keeps remote control ports open for the specified number of seconds (0–2147460) for non-Connect:Enterprise applications that experience timeouts on their control ports even though they have data port activity.	N/A	N/A

- 1 The default values for these parameters are specified in the *REMOTES sections of the ODF by the Connect:Enterprise administrator.
- 2 FTIME, ORIGIN, and TTIME affect the contents of the response from an NLST command. The response from the NLST command affects the typical client mdelete and mget commands.

SITE Parameter	Description	FTP Server Command	Remote FTP Client Command
KIRN=YES NO	<p>(KIRN stands for <u>K</u>eep <u>I</u>nput <u>R</u>ecsep <u>N</u>L)</p> <p>Connect:Enterprise removes the record separator string so that the batch is stored as a file structure instead of being record-oriented or keeps the record separator string, NL (New Line feed), for incoming SFA and SFE batches or allows. If the batch is not recordized, this parameter is ignored.</p> <p>The default comes from the KIRN setting in the *REMOTES record.</p> <p>NO = Connect:Enterprise removes the record separator string after recordizing the batch.</p> <p>YES = The Record separator strings are kept in the batch. The corresponding FTP_DEFAULT_RIFS parameter must be set to YES.</p> <p>For more information on recordizing, see the chapter on configuring ODF records for FTP connections in the <i>Connect:Enterprise for z/OS Administration Guide</i>.</p>	STOR, STOU	put, mput
LRECL=0-32760 or blank or "x"	LRECL of file being sent.	STOR, STOU	put, mput
LS_FILTER [QUERY]	Display batch exclusion filter.	NLST	ls, mdelete, mget
LS_FILTER DEFAULT OFF NONE [KEEP]	Reset batch exclusion filter.	NLST	ls, mdelete, mget
LS_FILTER=<flags> [KEEP] See Note 1.	Specify batch exclusion filter.	NLST	ls,mdelete, mget
MULTXMIT=NO YES See Note 1.	Multiple transmission flag.	STOR, STOU	put
nnnnnn	Sent by IBM–ignore.	STOR, STOR	put, mput
ONEBATCH=NO YES See Note 1.	Duplicate user batch ID	RETR	get, mget

- 1 The default values for these parameters are specified in the *REMOTES sections of the ODF by the Connect:Enterprise administrator.
- 2 FTIME, ORIGIN, and TTIME affect the contents of the response from an NLST command. The response from the NLST command affects the typical client mdelete and mget commands.

SITE Parameter	Description	FTP Server Command	Remote FTP Client Command
ORIGIN=<originator> See Note 2.	Limit batch selection.	DELE, LIST, NLST, RETR	Delete, dir, get, ls, mdelete, mget
PRIMARY=1-16777215 or blank	Primary allocation amount of file being sent.	STOR, STOU	put, mput
RECFM=<recfm_list>	RECFM value for file being sent.	STOR, STOU	put, mput
REMOTE_FILENAME_LENGTH= SHORT LONG LONG64 See Note 1.	Length of remote file name.	NLST	ls, mdelete, mget
RESET	Set all values to default.	DELE, LIST, NLST, RETR, STOR, STOU	delete, dir, get, ls, mdelete, mget
RIFS=YES NO	<p>(RIFS stands for <u>R</u>ecordize <u>I</u>nput <u>F</u>ile <u>S</u>tructure)</p> <p>Changes the batch to record structure or retains the batch as file structure.</p> <p>YES = Recordizes the batch after recognizing a record separator string and uses CRLF for SFA batches and NL for SFE batches.</p> <p>NO = Retains file structure of batch and does not recognize record separator strings in SFA or SFE batches.</p> <p>The default comes from the RIFS setting in the *REMOTES record.</p> <p>For more information on recordizing, see the chapter on configuring ODF records for FTP connections in the <i>Connect:Enterprise for z/OS Administration Guide</i>.</p> <p>Note: Processing results cannot be predicted or supported when RIFS=NO and SCAN is set to YES or ALL.</p>	STOR, STOU	put, mput

- 1 The default values for these parameters are specified in the *REMOTES sections of the ODF by the Connect:Enterprise administrator.
- 2 FTIME, ORIGIN, and TTIME affect the contents of the response from an NLST command. The response from the NLST command affects the typical client mdelete and mget commands.

SITE Parameter	Description	FTP Server Command	Remote FTP Client Command
SCAN= <u>NO</u> YES ALL	<p>Specifies whether the Connect:Enterprise FTP server scans STOR or STOU received batches for \$\$ commands and /* cards. For more information, see <i>Preparing Batches for the Connect:Enterprise FTP Server</i> on page 45.</p> <p>NO= Scanning for Connect:Enterprise \$\$ commands is not enabled. Connect:Enterprise \$\$ commands, /*SIGNON, and /*BINASC cards embedded in a received batch are treated as data.</p> <p>YES= Scanning for Connect:Enterprise \$\$ commands is enabled initially, but scanning for a subsequent \$\$ADD card is not automatic. Each \$\$ADD card must include the parameter SCAN=YES to continue scanning for \$\$ commands. Use this value to make FTP command scanning behave like it does in SNA.</p> <p>ALL= Scanning for Connect:Enterprise \$\$ commands is enabled for the entire batch unless the batch contains a \$\$ADD card with the parameter SCAN=NO. Use this value to make FTP command scanning behave like it does in BSC.</p>	STOR, STOU	put, mput
SECONDARY=1-16777215 or blank	Secondary allocation amount of file being sent.	STOR, STOU	put, mput
TO=NO YES See Note 1.	<p>Transmit once.</p> <p>TO=YES specifies that the batch being received can only be transmitted once and is not extractable. TO=YES can be thought of as "transmit once, transmit only".</p> <p>TO=NO specifies that the batch is not marked non-transmittable.</p>	STOR, STOU	put
TRACKS	Primary allocation amount of file being sent is in TRACKS.	STOR, STOU	put, mput

- 1 The default values for these parameters are specified in the *REMOTES sections of the ODF by the Connect:Enterprise administrator.
- 2 FTIME, ORIGIN, and TTIME affect the contents of the response from an NLST command. The response from the NLST command affects the typical client mdelete and mget commands.

SITE Parameter	Description	FTP Server Command	Remote FTP Client Command
TTIME=<to_time> See Note 2.	Limit batch selection by specifying the ending date for all data selected for processing. This value calculates dates relative to the current date. The default is 1980001. Valid formats: nnn hhmm yyddd ccyyddd nnn:hhmm yyddd:hhmm ccyyddd:hhmm	DELE, LIST, NLST, RETR	delete, dir, get, ls, mdelete, mget
VARRECFM	Sent by IBM—ignore	STOR, STOU	put, mput
VBQ#=nn Note: You cannot display or update this parameter in the ISPF and CICS screens related to the Options Definition File. Only a SITE or LOCSITE command can direct FTP batches to a VBQ other than the Current Collection VBQ.	Specifies the number of the VBQ file on which batches collected in FTP sessions are to be stored. To set this value for multiple collections, the command is: LOCSITE VBQ#=nn KEEP KEEP must be the next parameter after VBQ#=nn to retain the value for more than one batch collection unless it part of an MGET command. If nn is 00, the assignment resets to the Current Collect VBQ. If nn is 01 through 20 that particular VBQ is allocated.	STOR, STOU	dir, get, list, nlist, mget, scget
XMIT=NO YES See Note 1.	Transmission control	STOR, STOU	put

- 1 The default values for these parameters are specified in the *REMOTES sections of the ODF by the Connect:Enterprise administrator.
- 2 FTIME, ORIGIN, and TTIME affect the contents of the response from an NLST command. The response from the NLST command affects the typical client mdelete and mget commands.

Sample Output of STATUS Command

The type of information returned depends on the remote server. If the remote FTP server is a Connect:Enterprise system, the status and setting information is displayed in the following messages:

```

211-Connect:Enterprise at 10:09:49 on 2003.275 host time.
211-Session started at 10:09:33 on 2003/275 host time.
211-User: FTPRMT      Current working Mailbox ID: FTPRMT
211-TYPE: A          MODE: S              STRUcture: F
211-Local SITE option values:
211- Allocation type=NONE      BCHSEP=NONE  BLKSIZE=0
211- DIR_FILTER=18Fe          DIRECTORY=0      DIRFORM=MBOX_ZOS

211- EO=NO      FTIME=1980001:0000  LRECL=0      LS_FILTER=BDI!RST

211- MULTXMIT=NO  ONEBATCH=NO  ORIGIN=      PRIMARY=0
211- RECFM=      REMOTE_FILENAME_LENGTH=LONG  SECONDARY=0
211- TO=NO      TTIME=      XMIT=NO      VBQ=01      SCAN=NO
211-           0 Kbytes received for      0 batches during this session
211           0 Kbytes sent from          0 batches during this session

```

In addition to the following SITE parameter setting information, the time the session started is shown (in hh:mm:ss and yyyy.ddd format) along with the number of bytes and batches received and sent during the session. The following table lists the information for each data label in alphabetical order:

Data Label	Description
Allocation type	The type of allocation used – BLOCKS, CYLINDER, TRACKS or NONE.
AUTH	The security mechanism used (SSL or TLS).
BCHSEP	The batch separation option used – NONE, OPT3, or OPT4 option. See <i>BCHSEP=NONE OPT3 OPT4</i> on page 20.
BLKSIZE	The file block size.
Current working Mailbox ID	The name of the current working mailbox.
DIR_FILTER	The filter used by the LIST command to exclude batches from the list returned to the remote FTP client. Refer to <i>DIR_FILTER=<flags> [KEEP]</i> on page 20.
DIRECTORY	The file directory size.
DIRFORM	The DIRFORM reply format. Refer to <i>DIRFORM=BROWSER BROWSER64 MBOX_CLIENT MBOX_CLIENT64 MBOX_ZOS MBOX_ZOS64 \$MIBNSDFXY UNIX UNIX64</i> on page 21.
EO	Indicates if the file can be extracted once (EO) and transmitted (Yes or No).

Data Label	Description
FTIME	The date in year, month, day format followed by a semicolon and time in hours and minutes representing the from time parameter. Specifies the starting date for all data selected for processing. The nnn (1–3 digit number) value calculates dates relative to the current date. If nnn is specified, the FROMDATE value is calculated as today- <i>nnn</i> (for example, FROMDATE=3 is resolved to the date three days ago). The default is 1980001.
LRECL	The file logical record length.
LS_FILTER	A filter used by the NLST command to exclude batches from the list returned to the remote FTP client.
MODE	The mode – blocked (B), compressed (C), or stream (S).
MULTXMIT	Indicates if the batch being received can be transmitted multiple times (Yes or No).
ONEBATCH	Indicates if only the first eligible batch can be selected for transfer to the remote FTP client (Yes or No).
ORIGIN	The name of the remote or user ID of the batch job that added the batch.
PBSZ	The size of the protection buffer.
PRIMARY	The file primary allocation amount.
PROT	The type of data channel protection used by client and server during transfer. (P indicates all data on the channel is encrypted.)
RECFM	The file record format.
REMOTE_FILENAME_LENGTH	The length of the Batch ID returned by NLST (short or long).
SCAN	The last known value of the remote (server-side) SCAN setting, which indicates whether the Connect:Enterprise FTP server is scanning RETR received batches for \$\$ commands and /* cards. For more information, see the description for the SCAN parameter on page 25.
SECONDARY	The file secondary allocation amount.
STRUcture	The file structure – file (F) or record (R).
TO	Indicates if the file can only be transmitted once (TO) and cannot be extracted (Yes or No).
TTIME	The date in year, month, day followed by a semicolon and time in hours and minutes representing the to time (TTIME) parameter.

Data Label	Description
TYPE	The file type – ASCII (A), EBCDIC (B), or BINARY (I).
User	The name of the user ID currently logged into the remote FTP Server.
XMIT	Indicates if the batch is available to be transmitted to other sites (Yes or No).
VBQ	The number of the VBQ file on which batches collected in FTP sessions are to be stored.

VSAM Batch Status Flags

The DIR_FILTER parameter uses the values in the following batch status flags. Some combinations of these flags are always processed together or are not accepted.

For example:

- ◆ A batch with flag 8 or 9 also has an F flag.
(DIR_FILTER=89 is stored in the Remote definition as DIR_FILTER=F)
(DIR_FILTER=!8!9 is stored in the Remote definition as DIR_FILTER=!F)
- ◆ A batch with any combination of 1, 2, or 3 is not accepted.

Code	Description
A	The batch was added by the offline ADD utility.
B	The batch originated at a BSC remote site.
C	The batch was collected from a remote site through online Connect:Enterprise.
D	The batch is flagged for deletion due to an online \$\$DELETE request or an offline DELETE utility.
e	The batch was encrypted when added by the offline ADD utility.
E	The batch was extracted by the offline EXTRACT utility. This flag does not inhibit another EXTRACT from running and does not prevent online access to the batch.
F	The batch originated at an FTP remote site.
I	The batch is incomplete. Either no records were in the batch, or an online data collection was interrupted due to an error condition. This batch is ignored by Connect:Enterprise and only the EXTRACT utility can extract it.
M	The batch is available for multiple transmission, can be transmitted to any remote site, and is not marked T when transmitted unless mailboxID = AC Listname.

Code	Description
N	Nontransmittable. The batch is locked for transmissions. The status is set immediately after the batch is successfully collected, when the EO=Y option of a \$\$ADD command is specified. It is also set following successful transmission of a batch added with the TO=Y parameter.
R	Requestable. A remote site can request the batch or a host-initiated Auto Connect can transmit the batch.
S	The batch originated at an SNA remote site.
T	The batch was transmitted online to a remote site.
U	Unextractable. When displayed, this status replaces the E status. The batch is locked for extractions. This status is set immediately after the batch is added, when the TO=Y option added the batch. It is also set following successful extraction of the batch when the EO=Y option was used to add the batch.
X	The batch contains transparent data.
Z	EBCDIC data added through the APPC user API.
0	The batch is sorted on the VBQ as FILE_STRUCTURE (non record oriented). The batch was added offline or collected online as a contiguous byte string with no logical record delineation.
1	FTP mode is blocked.
2	FTP mode is compressed.
3	FTP mode is stream.
4	FTP collected SSL.
8	FTP structure is file.
9	FTP structure is record.

Different DIRFORM Layouts Returned by LIST

The layout of the information returned by the LIST command depends on the value of the DIRFORM parameter of the SITE command. The format returned when DIRFORM=MBOX_ZOS64 is shown in the following example, which illustrates the default directory list format.

(1)	(2)	(3)	(4)	(5)	(6)	(7)	(8)
COMPANYB	#0000047	CT=00000320	BID=LIST TEST	1508-01199	A R	F 038	VBQ01 OFFLINE
COMPANYB	#0000067	CT=00000420	BID=LIST	1046-01205	C T	F 038	VBQ20
COMPANYB	#0000068	CT=00000210	BID=LIST	1046-01205	C	F 038	VBQ03

Column	Description
(1)	Mailbox where the batch resides.
(2)	Batch number—zero filled.
(3)	Size of batch in bytes.

Column	Description
(4)	Batch ID
(5)	Date batch added (HHMM-YYDDDD)
(6)	Batch flags in 20 character field in the following order: I = Incomplete A C = Offline Added, Online Collected D = Delete N = Not Transmittable U = Unextractable R = Requestable T = Transmitted E = Extracted M = Multi-transmittable X = Transparent B F S Z = BSC, FTP, SNA or API Space = Reserved for future use. Space = Reserved for future use. 0 = File oriented data. 1 2 3 =FTP mode – blocked, compressed, stream 8 9 = FTP structure – file, record e = Offline added with encryption (ENCR=) Space = Reserved for future use. Space = Reserved for future use. Space = Reserved for future use.
(7)	The number of the VSAM Batch Queue where the batch is stored.
(8)	VBQ status–OFFLINE if VBQ is not available or blank if available.

The format returned when DIRFORM=BROWSER is shown below with an explanation of the columns:

(1)	(2)	(3)	(4)	(5)	(6)	(7)
A R	1	COMPANYB	0000047	00000320	JUL 18 15:08	LIST TEST
C T	1	COMPANYB	0000067	00000420	JUL 24 10:46	LIST
IC	1	COMPANYB	0000074	00000320	JUL 24 11:31	July Invoice

Column	Description
(1)	Batch flags in 10-character field in the following format: I = Incomplete A C = Offline added, Online Collected D = Delete R = Requestable T = Transmitted E = Extracted M = Multi-transmittable U = Unextractable N = Not transmittable X = Transparent
(2)	Constant 1.
(3)	Mailbox where batch resides.
(4)	Batch number—zero filled.
(5)	Size of batch in bytes.
(6)	Date batch added (MMM DD HH-MM)
(7)	Batch ID

The format returned when DIRFORM=MBOX_CLIENT is shown below with an explanation of the columns.

(1)	(2)	(3)	(4)	(5)	(6)	(7)
COMPANYB	#0000047	CT=00000320	BID=LIST TEST	1508-01199	A R	COMPANYB
COMPANYB	#0000067	CT=00000420	BID=LIST	1046-01205	C T	COMPANYB
COMPANYB	#0000068	CT=00000210	BID=LIST	1046-01205	C	COMPANYB

Column	Description
(1)	Mailbox where batch resides.
(2)	Batch number—zero filled.
(3)	Size of batch in bytes.
(4)	Batch ID
(5)	Date batch added (HHMM-YYDDD)

Column	Description
(6)	Batch flags in 10-character field in the following order: I = Incomplete A C = Offline Added, Online Collected D = Delete R = Requestable T = Transmitted E = Extracted M = Multi-transmittable U = Unextractable N = Not transmittable X = Transparent
(7)	Batch job name or remote name that added the batch.

The format returned when DIRFORM=UNIX is shown below with an explanation of the columns.

(1)	(2)	(3)	(4)	(5)	(6)	(7)
-A-R-----	1	CRONLY	2845	05 AUG 11 20:14	'CRONLY TEST	'.#0002845
-A-R-----	1	CRONLY	2846	05 AUG 11 20:14	'CRONLY TEST	'.#0002846
-A-R-----	1	CRONLY	2847	05 AUG 11 20:14	'CRONLY TEST	'.#0002847

Column	Description
(1)	Batch flags in 10-character field in the following order: I = Incomplete A C = Offline Added, Online Collected D = Delete R = Requestable T = Transmitted E = Extracted M = Multi-transmittable U = Unextractable N = Not transmittable X = Transparent Note: A hyphen (-) is returned as a placeholder for each batch status which is not present.
(2)	Constant 1.
(3)	Mailbox ID where batch resides.
(4)	Size of batch in bytes
(5)	Date batch added (YY month DD HH:MM), where month = Jan, Feb,, Nov, Dec.

Column	Description
(6)	Batch ID, enclosed in single quotes with .#nnnnnnn appended, where nnnnnnn = batch number, for example, '24 character batchid '#0001234

Connect:Enterprise Variations from Standard FTP Commands

The Connect:Enterprise FTP server uses a construct called a mailbox ID as the equivalent of the directory in other FTP implementations. Connect:Enterprise supports a single level of the directory, which is referred to as the current working mailbox ID.

The following table summarizes the typical FTP commands that are implemented by the Connect:Enterprise FTP server in a manner that differs from other FTP server implementations. The way that Connect:Enterprise implements each command is detailed. The syntax and format for specifying user batch ID are also detailed.

FTP Command	Connect:Enterprise FTP Server Command	Connect:Enterprise Implementation
del, delete, mdelete	DELE	Logically delete batches from the current working mailbox ID
dir	LIST, NLST	List batches in the current working mailbox ID
get, mget	RETR	Retrieve batches from the current working mailbox ID
ls, mdelete, mget	NLST	List the user batch IDs in the current working mailbox ID
put, mput, STOU	STOR, STOU	Add a batch to the current working mailbox ID
cd	CWD	Change current working mailbox ID
pwd	PWD	Print current working mailbox ID

User Batch ID Syntax and Formats

The value of the user batch ID is case-sensitive and you cannot use the following characters in the user batch ID. The results of attempts to retrieve batches using FTP commands that contain wildcards in the user batch ID are unpredictable.

-	.	*	?	[]	\	/
---	---	---	---	---	---	---	---

Additionally, do not use the number symbol (#) as the first character in the user batch ID.

Caution: Some systems support ID numbers using the # character, but Connect:Enterprise can return inconsistent, redundant, or incorrect responses to queries that use # as the first character of the user batch ID.

Pathnames, or '<pathname>', consist of an optional Mailbox ID and a User Batch ID in the form: '[/<mailbox_ID>/]<batch_ID>'. Specifying the Mailbox ID in the <pathname> overrides the setting of the current working mailbox for the current command and the current working Mailbox ID is not changed. If <mailbox_ID> is not specified as part of the path name, then the current working Mailbox ID is used.

The user batch ID can be specified in one of the following ways:

Format	Description
nnnnnnn	The 1–7 digit batch number from 1–9999999. Leading zeros are optional.
"generic-name"	1–64 characters used to identify batches in the current working mailbox ID. (The quotation marks are required for this form of batch ID. Do not use wildcard characters in the "generic-Name" value.
'specific'	1–64 character user batch ID left justified, padded with trailing blanks. The single quotes are required to delimit the ID. If the ID contains an apostrophe, two apostrophes must be encoded for each single apostrophe in the ID. Example: UID1235'BNK1 would need to be encoded 'UID1235"BNK1' If blanks are embedded within the ID, the single quotes must be left off. Example: UID1235 BNK1
'SPEC*?[]'	Indicates any batch that matches the specified pattern. 1–64 characters including any wildcard card characters. The pattern is compared to all batches in the current working mailbox ID and any matching batches are selected.
'batch_ID.#nnnnn nn'	1–64 character ID with trailing blanks truncated, followed by .# and the 7-digit batch number from 0000001–9999999 (including leading zeros) and enclosed in single quotes. Without the single quotes, you cannot use embedded blanks in this ID. This format is normally seen as part of a RETR or DELE command.
'#nnnnnnn.dat'	# and the 7-digit batch number from 0000001–9999999 with leading zeros followed by .dat and optionally enclosed in single quotes. This format is typically used as part of a RETR or DELE command.

delete or mdelete Command

In Connect:Enterprise, the **DELE** command *logically* deletes batches from the current working mailbox ID specified by the <pathname> parameter. You can set the current working mailbox ID using the FTP client cd command. Display the current working mailbox ID using either the STAT

command or the PWD command. A mailbox ID specified in <pathname> temporarily overrides the permanent setting of the current working mailbox ID, for the duration of the current command.

The FTIME, ORIGIN, and TTIME parameters of the SITE command affect DELE processing. Set the FTIME, ORIGIN, and TTIME parameters using the SITE command and display them using either the STAT command or the PWD command.

The following two security checks are made before the DELE command deletes a batch:

- ◆ Session security exit call
- ◆ Security interface security checks

Note: Remote sites with the name anonymous are not permitted to use DELE.

Connect:Enterprise FTP del, delete, and mdelete Command Syntax

The typical FTP client **delete** and **mdelete** commands invoke the FTP server DELE command as shown in the following table. Required parameters are displayed in bold font. No optional parameters are available.

FTP Command	Connect:Enterprise FTP Server Command	Syntax	Parameter Description
del, delete, mdelete	DELE	DELE<SP><pathname>	Required. <pathname> specifies the batch or batches to delete.

Batch Selection with Connect:Enterprise FTP del Command

If the user batch ID specified in <pathname> is in the form '#nnnnnnn', 'nnnnnnn', 'batch_ID.#nnnnnnn', or '#nnnnnnn.dat' and the batch is in the current working mailbox ID, the single batch with batch number 'nnnnnnn' is deleted.

Note: Your operating platform may not support using the number (#) character as the first character of a batch_ID. See *Transfer Mode* on page 11.

If the user batch ID specified in <pathname> is in form “generic-name”, 'specific', or 'spec*?[]', all batches in the current working mailbox ID that match the value specified are eligible for deletion.

An eligible batch is selected for deletion if the following conditions are met:

1. The batch's creation date and time is on or after the value specified in the FTIME parameter.
2. The batch's creation date and time is on or before the value specified in the TTIME parameter.
3. The batch's origination matches the value of the ORIGIN parameter or the ORIGIN parameter is blank.

If the user batch ID specified in <pathname> is in '#nnnnnnn', 'nnnnnnn', 'batch_ID.#nnnnnnn', or '#nnnnnnn.dat' format, the SITE parameters FTIME, ORIGIN, and TTIME are ignored.

The SITE parameters FTIME and TTIME limit the selection of batches based on the batch's earliest and latest creation date and time, respectively.

The ORIGIN parameter limits the selection of batches based on the name of the user or remote that created the batch.

dir Command

In Connect:Enterprise the **LIST** command lists batches in the current working data repository or the mailbox ID specified in the <pathname> parameter. You set the current working mailbox ID using the FTP client cd command. Display the current working mailbox ID using either the STAT command or the PWD command. For the dir command, the mailbox ID specified in <pathname> overrides the setting of the current working mailbox ID, but does not change its value.

Note: The current data representation must be either ASCII or EBCDIC. Image type is unsupported and is not recognized.

The DIR_FILTER, FTIME, ORIGIN, and TTIME parameters of the SITE command affect LIST processing. The DIR_FILTER, FTIME, ORIGIN, and TTIME parameters are set using the SITE command and displayed using either the STAT command or the PWD command.

The sequence of the list returned by the LIST command is in ascending order by mailbox ID. The batches listed for each mailbox ID are sequenced based on the values of the batch transmission status and batch age. The batches in the data repository that did not transmit are listed first in ascending sequence by creation date and time. The batches that transmitted are listed last in ascending sequence by creation date and time. The format of the list returned by the LIST command depends on the value of the DIRFORM parameter of the FTP server SITE command. The DIRFORM parameter is set using the FTP server SITE command and displayed using the FTP server STAT command.

The following two security checks are made before the LIST command accesses the data repository:

- ◆ Session security exit call
- ◆ Security interface security checks

If you did not specify a data connection port (using either the PORT or PASV command) before issuing the dir command, Connect:Enterprise assumes that the data uses the client's control connection port and the server's port adjacent to the control port (for example, L-1). Always specify the data connection port explicitly (through PORT or PASV commands) instead of assuming the default.

Connect:Enterprise FTP dir Command Syntax

The typical FTP client **dir** command invokes the FTP server LIST command as shown in the following table. Required parameters are displayed in bold font.

FTP Command	Connect:Enterprise FTP Server Command	Syntax	Parameter Description
dir, LIST, NLST	LIST	LIST[<SP><pathname>]	Optional. <pathname> specifies the batch or batches to list

Batch Selection with Connect:Enterprise FTP dir Command

If the user batch ID specified in <pathname> is formatted as '#nnnnnnn', 'nnnnnnn', 'batch_ID.#nnnnnnn', or '#nnnnnnn.dat' and the batch is in the current working mailbox ID, the single batch with batch number 'nnnnnnn' is eligible for the list.

If the user batch ID specified in <pathname> is in the form “generic-name”, 'specific', or 'spec*?[]', all of the batches in the current working data repository that match the specified value are eligible for the list.

If <pathname> is not specified, all of the batches in the current working data repository are eligible for the list. Eligible batches are selected for listing depending on the current settings of the SITE parameters DIR_FILTER, FTIME, ORIGIN, and TTIME.

An eligible batch is listed if the following conditions are met:

- ◆ The batch's status flags do not match any of the values specified in the DIR_FILTER parameter.
- ◆ The batch's creation date and time is on or after the value specified in the FTIME parameter.
- ◆ The batch's creation date and time is on or before the value specified in the TTIME parameter.
- ◆ The batch's origination matches the value of the ORIGIN parameter or the ORIGIN parameter is blank.

If the user batch ID specified in <pathname> is in '#nnnnnnn', 'nnnnnnn', 'batch_ID.#nnnnnnn', or '#nnnnnnn.dat' format, the DIR_FILTER, FTIME, ORIGIN, and TTIME parameters are ignored.

- ◆ The DIR_FILTER parameter limits the selection of batches based on a batch's status flags.
- ◆ The FTIME and TTIME parameters limit the selection of batches based on the batch's earliest and latest creation date and time, respectively.
- ◆ The ORIGIN parameter limits the selection of batches based on the name of the user or remote that created the batch.

get or mget Command

In Connect:Enterprise, the RETR command retrieves batches from the current working data repository or the mailbox ID specified in the <pathname> parameter. For this command, the mailbox ID specified in <pathname> overrides the setting of the current working mailbox ID, but does not change its value. Set the current working mailbox ID using the FTP client cd command.

Display the current working data repository using either the STAT command or the PWD command.

The FTP client creates the file names at the remote site using the typical FTP client get and mget commands, and using the replies returned from the NLST command.

Several parameters of the SITE command affect RETR processing. You can set these parameters using the SITE command and display them using either the STAT command or the PWD command.

Several other parameters of the SITE command cause file characteristics to be stored with the batch.

Note: BCHSEP does not affect the selection of batches. It only determines when a batch is marked transmitted.

The following two security checks are made before the RETR command retrieves a batch:

- ◆ Session security exit call
- ◆ Security interface security checks

Before issuing this command, specify the data collection port using either the PORT command or the PASV command. Connect:Enterprise assumes that the data connection uses the client's control connection port and the server's port adjacent to the control port (for example, L-1). For optimum performance, always specify the data connection port explicitly (through the PORT or PASV commands) instead of assuming the default.

When the control connection is established and secure, SSL negotiation of the data connection is expected.

Connect:Enterprise FTP get Syntax

The typical FTP client **get** and **mget** commands invoke the FTP server RETR command as shown in the following table. Required parameters are displayed in bold font. No optional parameters are available.

FTP Command	Connect:Enterprise FTP Server Command	Syntax	Parameter Description
get, mget	RETR	RETR<SP>< pathname >	Required. <pathname> specifies the batch or batches to be listed.

Batch Selection

If the user batch ID specified in <pathname> is in the form '#nnnnnnn', 'nnnnnnn', 'batch_ID.#nnnnnnn', or '#nnnnnnn.dat' and the batch is in the current working data repository, the single batch with batch number 'nnnnnnn' is eligible for retrieval.

If the user batch ID specified in <pathname> is in the form "generic-name", 'specific', or 'spec*?[]', all of the batches in the current working data repository that match the user batch ID are eligible for retrieval.

Eligible batches are selected for listing depending on the current settings of the SITE parameters TIME, ORIGIN, and TTIME, and of the data representation type.

A batch is selected for retrieval when the following conditions are met:

- ◆ The batch is contained in an online VBQ.
- ◆ The data representation type of the batch matches that of the TYPE parameter.
- ◆ The batch's creation date and time is on or after the value specified in the FTIME parameter.
- ◆ The batch's creation date and time is on or before the value specified in the TTIME parameter.
- ◆ The batch's origination matches the value of the ORIGIN parameter or the ORIGIN parameter is blank.
- ◆ The batch is requestable.

If the user batch ID specified in <pathname> is in '#nnnnnnn', 'nnnnnnn', 'batch_ID.#nnnnnnn', or '#nnnnnnn.dat' format, the SITE parameters FTIME, ORIGIN, and TTIME are ignored.

- ◆ The FTIME and TTIME parameters limit the selection of batches based on the batch's earliest and latest creation date and time, respectively.
- ◆ The data representation type of the batch limits the selection of batches based on current setting of the TYPE parameter.
- ◆ The ORIGIN parameter limits the selection of batches based on the name of the user or remote that created the batch.

Batch Transmission

If batches are selected for retrieval, the batches are transferred through the data connection.

If the user batch ID specified in <pathname> is in the form '#nnnnnnn', 'nnnnnnn', 'batch_ID.#nnnnnnn', or '#nnnnnnn.dat' and the batch is in the current working data repository, the single batch with batch number 'nnnnnnn' is eligible for retrieval unless the data representation type does not match.

If ONEBATCH=NO is specified, the RETR command concatenates all the batches selected and sends them as one file. If ONEBATCH=YES is specified, the RETR command only sends the first batch selected.

Batch Status Flags

The batch status flags have the following meaning.

- ◆ If BCHSEP=NONE or BCHSEP=OPT4, each batch is flagged as transmitted (“T”) when it is sent successfully. If a failure occurs during transmission, BCHSEP=NONE or BCHSEP=OPT4 prevents batches previously sent from being retransmitted. If the transmission is restarted to the same remote client file, the data from the previous batches is replaced with the data from the unsent batches, and the data from the previously sent batches are lost. If the transmission is restarted to a different remote client file, data sent in previous batches are not lost.
- ◆ If BCHSEP=OPT3, all batches are flagged as transmitted (“T”) when all of the batches are sent successfully. If a failure occurs during transmission, BCHSEP=OPT3 permits all batches to be transmitted again. If the transmission is restarted to the same remote client file, the data

from the previous batches are retransmitted with no loss of data. If the transmission is restarted to a different remote client file, duplicate records are sent to the remote site.

put or mput Command (STOR)

In Connect:Enterprise, the STOR command adds a batch to the current working data repository or the mailbox ID specified in the <pathname> parameter. Set the current working mailbox ID using the FTP client cd command. Display the current working data repository using either the STAT command or the PWD command. For this command, the mailbox ID specified in <pathname> overrides the setting of the current working mailbox ID, but does not change its value.

Several parameters of the SITE command affect STOR processing. You can set these parameters using the SITE command and display them using either the STAT command or the PWD command.

Several other parameters of the SITE command cause file characteristics to be stored with the batch.

The following two security checks are made before the STOR command adds a batch:

- ◆ Session security exit call
- ◆ Security interface security checks

A unique batch number is assigned to every batch that is added allowing Connect:Enterprise to support duplicate user batch IDs.

Before issuing this command, specify a data connection port using either the PORT command or the PASV command. Connect:Enterprise assumes that the data connection uses the client's control connection port and the server's port adjacent to the control port (for example, L-1). Always specify the data connection port explicitly (through the PORT or PASV commands) instead of assuming the default.

Connect:Enterprise FTP put Syntax

The typical FTP client **put** and **mput** commands invoke the FTP server STOR command as shown in the following table. Required parameters are displayed in bold font. No optional parameters are available.

FTP Command	Connect:Enterprise FTP Server Command	Syntax	Parameter Description
put, mput	STOR	STOR<SP>< pathname >	Required. <pathname> specifies the 1–64 character user batch ID of the batch to be added. User batch IDs can contain no wildcard characters, ('.', '*', '?', '[', ']', '/', and '\'). Additionally, you cannot specify '#' as the first character. If more than 64 characters are specified, a command syntax error occurs.

put or mput Command (STOU)

In Connect:Enterprise, the STOU command adds a batch to the current working data repository or the mailbox ID specified in the <pathname> parameter. Set the current working mailbox ID using the FTP client cd command. Display the current working data repository using either the STAT command or the PWD command. For this command, the mailbox ID specified in <pathname> overrides the setting of the current working mailbox ID, but does not change its value.

Several parameters of the SITE command affect STOU processing. You can set these parameters using the SITE command and display them using either the STAT command or the PWD command.

Several other parameters of the SITE command cause file characteristics to be stored with the batch.

The following two security checks are made before the STOU command adds a batch:

- ◆ Session security exit call
- ◆ Security interface security checks

The user batch ID returned by the STOU command is defined in the BID sub-parameter of the RECEIVE_OPTIONS of the remote's definition in the *REMOTES section of the ODF. If the BID sub-parameter is not specified, the user batch ID assigned is 'NONE'.

The format of the user batch ID returned by the STOU command is:

```
batch_ID.#nnnnnnn
```

where *batch_ID* is the 1–64 character user batch ID, # is a constant, and #nnnnnnn is the 7-digit batch number with leading zeroes.

A unique batch number is assigned to every batch that is added allowing Connect:Enterprise to support duplicate user batch IDs.

Note: Before issuing this command, specify a data connection port using either the PORT command or the PASV command. Connect:Enterprise assumes that the data connection uses the client's control connection port and the server's port adjacent to the control port (for example, L-1). For optimum performance, always specify the data connection port explicitly (through the PORT or PASV commands) instead of assuming the default

Connect:Enterprise FTP put Syntax

The typical FTP client **put** and **mput** commands invoke the FTP server STOU command. Required parameters are displayed in bold font. No optional parameters are available.

FTP Command	Connect:Enterprise FTP Server Command	Syntax	Parameter Description
put, mput	STOU	STOU<SP><pathname>	No parameters are required.

pwd Command

For Connect:Enterprise FTP the PWD prints the current working mailbox ID. It prints to your standard output. No security checks are made for the PWD command.

pwd Command Syntax

The typical FTP client **pwd** command invokes the FTP server PWD command as shown in the following table. Required parameters are displayed in bold font. No optional parameters are available.

FTP Command	Connect:Enterprise FTP Server Command	Syntax	Parameter Description
pwd	PWD	PWD	None

cd Command

The typical FTP client **cd** command invokes the FTP server CWD command.

For Connect:Enterprise FTP the CWD command changes the current working mailbox ID to the specified value. The slash character (/) must precede the mailbox ID. Subsequent commands use the specified mailbox ID as the current working mailbox ID. The mailbox ID specified may or may not exist. Display the current working data repository using either the Stat command or the PWD command.

Note: The values of 2 periods in a row (..) or a single period between two blank characters (.) are not supported and are treated as syntax errors.

No security checks are made by this command. Authorization to use the specified mailbox ID is determined when an FTP server command attempts to access Connect:Enterprise.

Note: Remote sites with the name “anonymous” are not permitted to use CWD. They are restricted to the “PUBLIC” mailbox ID.

NLST Command

For Connect:Enterprise FTP the NLST command lists user batch IDs in the current working data repository or the mailbox ID specified in the pathname parameter. For this command, the mailbox ID specified in pathname overrides the setting of the current working mailbox ID, but does not change its value. Set the current working mailbox ID using the FTP client cd command. Display the current working data repository using the STAT command or the PWD command.

Note: The current data representation must be either ASCII or EBCDIC. Image type is unsupported and is not recognized.

The SITE parameters BCHSEP, FTIME, LS_FILTER, ORIGIN, REMOTE_FILENAME_LENGTH, and TTIME affect NLST processing. You display these parameters using either the STAT command or the PWD command.

The current data representation type value does not affect NLST processing. Unless LS_FILTER is used, output from NLST lists batches of any data type. Set the appropriate data type (ASCII or EBCDIC) before retrieving batches.

The format of the list returned by the NLST command depends on the value of the BCHSEP parameter of the SITE command. See *Batch Status Flags* on page 40 for a description of these values.

The following two security checks are made before the NLST command lists a batch:

- ◆ Session security exit call
- ◆ Security interface security checks

Note: Before issuing this command, specify a data connection port (using either the PORT or PASV command). Connect:Enterprise assumes the data connection uses the client's control connection port and the server's port adjacent to the control port (for example, L-1). Always specify the data connection port explicitly (through the PORT or PASV commands) instead of assuming the default.

Connect:Enterprise NLST Command Syntax

The typical FTP client **ls**, **mdelete**, and **mget** commands invoke the FTP server NLST command as shown in the following table.

FTP Command	Connect:Enterprise FTP Server Command	Syntax	Parameter Description
pwd	PWD	NLST[<SP><pathname>]	Optional. <pathname> specifies the 1–64 character user batch ID of the batch to be listed.

Batch Selection

If the user batch ID specified in <pathname> is in '#nnnnnnn', 'nnnnnnn', 'batch_ID.#nnnnnnn', or '#nnnnnnn.dat' format, and the batch is in the current working data repository, the single batch with batch number 'nnnnnnn' is eligible for the list.

If the user batch ID specified in <pathname> is in “generic-name”, 'specific', or 'spec*?[]' format, all of the batches in the current working data repository that match the user batch ID are eligible for the list.

If the user batch ID is not specified, all of the batches in the current working data repository are eligible for the list.

Eligible batches are selected for listing depending on the current settings of the SITE parameters FTIME, LS_FILTER, ORIGIN, and TTIME.

An eligible batch is selected for listing if the following conditions are met:

- ◆ The batch is contained in an online VBQ.
- ◆ The batch's status is not excluded by the values specified in the LS_FILTER parameter.
- ◆ The batch's creation date and time is on or after the value specified in the FTIME parameter.
- ◆ The batch's creation date and time is on or before the value specified in the TTIME parameter.
- ◆ The batch's origination matches the value of the ORIGIN parameter or the ORIGIN parameter is blank.

If eligible batches are available and selected, the list is returned through the data connection.

If the user batch ID specified in <pathname> is formatted as '#nnnnnnn', 'nnnnnnn', 'batch_ID.#nnnnnnn', or '#nnnnnnn.dat', the FTIME, LS_FILTER, ORIGIN, and TTIME parameters are ignored.

The LS_FILTER parameter limits the selection of batches based on a batch's status flags.

The FTIME and TTIME parameters limit the selection of batches based on the batch's earliest and latest creation date and time, respectively.

The ORIGIN parameter limits the selection of batches based on the name of the user or remote that created the batch.

Preparing Batches for the Connect:Enterprise FTP Server

The typical FTP client **put** and **mput** commands invoke the FTP server STOR or STOU command to add batches of data to the host data repository on the Connect:Enterprise FTP server. Scanning must be in effect on the Connect:Enterprise FTP server side for \$\$ADD commands to function as instructions to add batches of data to the VSAM batch files for transmission instead of being treated as data. If scanning is not in effect, all \$\$ADD and other embedded \$\$ commands as well as /* cards (/*SIGNON and /*BINASC, which contain session startup information) are treated as data.

No \$\$ADD batches transferred by one FTP command are considered complete until the final \$\$ADD is complete.

To continue scanning for additional \$\$ADD commands after each \$\$ADD command, you can use one of the following methods:

- ◆ At the FTP client site, include the parameter, SCAN=YES in each \$\$ADD command, or set the initial SCAN setting to ALL using the SITE command.
- ◆ At the FTP server site, set the initial SCAN setting to ALL in the ODF or by using the LOCSITE script command.

When you embed \$\$commands in data, use the following table to determine how to delimit records, depending on the data structure, transfer mode, and data type.

Data Structure	Transfer Mode/Data Type	End of Record Delimiter
Record	Stream	Explicit End of Record (control code x'FF02')
File	Block or Compressed	EOR descriptor in block header (B) or Esc sequence (C)
File	Stream/ASCII	Carriage Return-Line Feed (CRLF or x'0D0A')
File	Stream/EBCDIC	New Line (NL or 'x15')
File	Stream/Images	Records not supported—only one \$\$ADD allowed and must be delimited by either: <ul style="list-style-type: none"> ◆ \$\$END with the rest of file being considered data ◆ 4096 bytes with data starting at the 4097th byte after the first \$ in ADD.

For more information about how \$\$ADD commands are processed and how Connect:Enterprise recordizes batches, see the chapter on configuring ODF records for FTP connections in the *Connect:Enterprise for z/OS Administration Guide*.

Using \$\$Commands and /*Cards

Files using embedded \$\$commands and /* cards must meet certain requirements. The first table summarizes these requirements for a file with a /*BINASC card; the second table is for a file without a /*BINASC card. In both tables, the file components are listed in the order of appearance in the file.

The third column in both tables lists the character set for ASCII, Image, and EBCDIC data types. The character set can be ASCII (A), Scanning (S), and E (EBCDIC). When a record is scanned, its first byte determines the character set for that record:

- ◆ /*SIGNON, /*BINASC, \$\$ADD, \$\$DEL, \$\$DIR, \$\$LOG, \$\$REQ.
- ◆ Only look for /*SIGNON on first record.
- ◆ Only look for /*BINASC immediately after the first \$\$ADD.
- ◆ First check for EBCDIC then ASCII. The translate table used is specified in the TRANSLATE parameter in the *REMOTES record for FTP Client and server connections in the Options Definition File. This parameter specifies the name of the translation table to use when converting ASCII data to EBCDIC data or EBCDIC data to ASCII data.
- ◆ If no match for either type, data is assumed and is always binary.
- ◆ The last column, Ends with, lists the delimiter used to mark the end of the file:
 - ◆ EOR stands for End of Record meaning the last byte of the record or \$\$END
 - ◆ EOB stands for End of batch meaning the last byte of the batch
 - ◆ EOF stands for End of File meaning the last byte of the file

\$\$Commands and /*SIGNON with /*BINASC

File Component	Specification	Char Set for TYPE = A / I / E	Begins at	Ends with
/*SIGNON	Optional	A / S / E	First byte of file	EOR
First non-\$\$ADD \$\$command	Optional	A / S / E	First byte of file or after /*SIGNON	EOR
Subsequent non-\$\$ADD \$\$commands	Any number	A / S / E	After the previous non- \$\$ADD \$\$cmd	EOR
First \$\$ADD command	Optional	A / S / E	First byte of file or after the last present one of the preceding	EOR
/*BINASC	Present in file	A / S / E	First byte of file or after the last present one of the preceding	bytes
First data	Required	Binary	After /*BINASC	EOF
Subsequent \$\$ADD and data	Not allowed			

\$\$Commands and /*SIGNON without /*BINASC

File Component	Specification	Char Set for TYPE = A / I / E	Begins at	Ends with
/*SIGNON	Optional	A / S / E	First byte of file	EOR
First non-\$\$ADD \$\$command	Optional	A / S / E	First byte of file or after /*SIGNON	EOR
Subsequent non-\$\$ADD \$\$commands	Any number	A / S / E	After the previous non- \$\$ADD \$\$cmd	EOR
First \$\$ADD	Optional	A / S / E	First byte of file or after the last present one of the preceding	EOR
/*BINASC	Not present			
First data	Required	A / Binary / E	First byte of file or after the last present one of the preceding	EOF or EOB
Subsequent \$\$ADD	Any number	A / S / E	After last record of first data	EOR
Subsequent data	Any number	A / S / E	After a subsequent \$\$ADD	EOF or EOB

Syntax

The syntax for the \$\$ADD command at FTP sites is:

```

$$ADD ID=xxxxxxxx BATCHID='xxx...xxx' EO=N|NO|Y|YES MULTXMIT=N|NO|Y|YES
SCAN=N|NO|Y|YES TO=N|NO|Y|YES VBQ#=n|nn XMIT=N|NO|Y|YES [ $$END]

```

Be sure to follow these rules:

- ◆ The first \$ of the command must be the first character of a record.
- ◆ Use one or more blanks to separate each parameter.
- ◆ You must specify a BATCHID within a pair of single quotes. Otherwise, the parameter is not recognized. Once the string, BATCHID=' is found, a corresponding close quote must be found within 24 bytes or the rest of the \$\$ADD card is ignored.
- ◆ Only ID and BATCHID values can have mixed case. All else must be upper case.

Both unrecognized and duplicate parameters are ignored without generating any messages. Only the first parameter for each keyword is processed.

\$\$ADD Command Parameters

The following table describes the parameter that can be used with the \$\$ADD command at FTP client sites:

Parameter	Description
ID=xxxxxxxx	Optional. 1–8 bytes.
BATCHID='xx...xxx'	Optional. 1–64 bytes. Default for STOR or RETR is the BID. For STOU, it is taken from RECEIVE_OPTIONS BID parameter. If no BID parameter is specified, the STOU \$\$ADD BID defaults to 'BATCH WITHOUT \$\$ADD', not 'NONE'. A null BATCHID takes the default value, AC BATCH WITHOUT \$\$ADD.
EO=N NO Y YES	Optional. Extract once. EO=YES specifies that the batch is extracted and stored one time from a remote client and cannot be transmitted. The default value EO=NO does not prevent transmission or multiple extractions.
MULTXMIT=N NO Y YES	Optional. Multi-Transmittable. The default is NO.
SCAN=N NO Y YES	Optional. Overrides current SCAN setting. The default is NO. Specifies whether Connect:Enterprise scans received batches for \$\$ commands. NO = Scanning for Connect:Enterprise \$\$ commands ends and the rest of the file is treated as data. YES = Scanning for Connect:Enterprise \$\$ commands continues. To keep scanning in effect when a \$\$ADD card is encountered, each \$\$ADD card must include the parameter SCAN=YES. Use this value to make FTP command scanning behave like it does in SNA.

Parameter	Description
TO=N NO Y YES	Optional. Transmit once. TO=YES specifies that the batch being received can only be transmitted once and is not extractable. TO=YES can be thought of as "transmit once, transmit only". The default TO=NO specifies that the batch is not marked non-transmittable.
VBQ#=n nn	Optional. The default is the current collection VBQ. Specifies the number of the VBQ file on which batches collected in FTP sessions are to be stored. To set this value for multiple collections, the command is: LOCSITE VBQ#=nn KEEP KEEP must be the next parameter after VBQ#=nn to retain the value for more than one batch collection unless it part of an MGET command. If nn is 00, the assignment resets to the Current Collect VBQ. If nn is 01 through 20 that particular VBQ is allocated.
XMIT=N NO Y YES	Optional. Transmittable.
\$\$END	Optional for all files except for files with a File data structure transferred in stream mode containing images.

Communicating with SNA Sites

This chapter contains procedures and information specific to operating Connect:Enterprise with SNA sites.

Start and End a Session

The procedures for starting and ending a session are:

1. Establish a connection.

Your remote site may exist on a switched (dialup) or nonswitched (dedicated or leased) line. You may have different procedures to follow when you first establish a connection with Connect:Enterprise. Get the specific procedures to establish a connection from your Connect:Enterprise system administrator.

2. Log on SNA.

This procedure is done either manually or automatically and is remote-site dependent.

3. Type the commands described in this chapter.

4. Log off SNA.

See Chapter 4, *Remote User Commands* for more information about logon and logoff functions for SNA.

Host-Initiated Communications (Auto Connect)

Connect:Enterprise has a function called Auto Connect that enables the host site computer to contact an unattended remote site. Using Auto Connect, Connect:Enterprise can both transmit to and collect data batches from remote sites.

For Auto Connect to work, the remote site must appropriately respond to the host computer. Host site personnel provide the actions you take to prepare your site for responding to an Auto Connect from the host site.

Connect:Enterprise is very flexible in the way it uses the Auto Connect function. For example, Connect:Enterprise can be configured to transmit batches to your remote site at different times throughout the night. Your remote site terminal or computer is then required to receive the batches whenever the host makes contact.

Batches can be sent to the host site during Auto Connect. Since Auto Connect is often used with remote sites that can operate unattended, program or set up these terminals to send batches when the terminal is called by the host site.

Alternatively, you may receive a call from the host site at certain times of the day. You can then manually send batches to the host, if instructed to do so.

Host-initiated sessions do not support any \$\$ commands from the remote other than \$\$ADD.

Using Connect:Enterprise

Connect:Enterprise is a command-driven application. For example, a remote site can precede the transmittable data with a \$\$ADD header record.

The following command tells Connect:Enterprise to add the data that follows to the host data repository and identify that batch as report summary from ACME:

```
$$ADD ID=ACME BID='report summary'
```

The following command tells Connect:Enterprise to transmit all batches with an ID of ACME and a batch identifier of 'report summary' to the requesting remote site:

```
$$REQUEST ID=ACME BID='report summary'
```

The following command tells Connect:Enterprise to flag as deleted all batches with an ID of ACME and a batch identifier of 'report summary':

```
$$DELETE ID=ACME BID='report summary'
```

Wildcard Characters in Connect:Enterprise Names

Connect:Enterprise, SPC Option 3.1, and Connect:Enterprise for UNIX 3.1 use the following special characters as wildcard characters when making decisions for various types of data repository

processing. Use the following wildcard characters in selection checks, most notably with BID values.

Wildcard Character	Function
asterisk (*)	Indicates any number of characters
question mark (?)	Indicates a single character
square brackets ([]) with any number of characters inside the brackets including an exclamation mark (!)	Indicates a specific character, or characters within a string of characters.

You may create batches with a BID value that include wildcard characters. However you may get unexpected results if you use wildcard characters in requests. For example:

- ◆ You create three batches with a BID value of ‘Test **’, ‘Test 123’, and ‘Test **456’ respectively. Because offline ADD processing and online collection processing do not restrict putting wildcard characters in the BID parameter, the batches are added to Connect:Enterprise without errors.
- ◆ To collect the batch with the BID of ‘TEST **’ you create the following \$\$REQUEST card:

```
$$REQ ID=yourid BID='TEST **'
```

- ◆ After submitting the request, you discover that you have collected data from all three batches.

To prevent the previous error, take one of the following steps:

- ◆ Refrain from using the wildcard characters when defining any name in data repository. The Connect:Enterprise System Administrator can enforce this rule by creating a Security Exit 1 and Offline ADD Exit to restrict the use of these characters in name values when adding data.
- ◆ Continue to use wildcard characters in data repository name values, but do not use any parameters that support wildcard characters. For example, use the #nnnnnnn parameter to request a specific batch by number. Do not use BID='xxx-xxx', as this parameter supports wildcards. Using this method limits selection, but eliminates confusion.

Terminal-Dependent Options

A variety of terminals and devices can communicate with Connect:Enterprise, but they do not all have the same capabilities. For this reason, Connect:Enterprise supports some terminal-dependent options for SNA. Some of these options are used only if they are installed by host site personnel. Other options do not require host site installation; they are used if your terminal type supports them.

SNA Sites

SNA terminal-dependent options are enabled only if your remote terminal supports the capability. These options include:

- ◆ Multiple Logical Unit (MLU) support
- ◆ Device media support
- ◆ Console display use
- ◆ Data compression
- ◆ Batch separation using Function Management Headers (FMHs)
- ◆ SNA transparency
- ◆ Disconnect interval
- ◆ Extended Binary Coded Decimal Information Code (EBCDIC) support

Detailed information about these options is provided in the sections that follow:

MLU (Multiple Logical Unit) Support

MLU Support permits a single remote terminal to be considered up to six terminals or sessions. Each session can have a different transaction in progress with Connect:Enterprise for a mixture of simultaneous data collections or transmissions on each of the separate terminals.

Type a logon command to Connect:Enterprise for each MLU session you wish to activate. These sessions are used as pipelines to activate multiple inbound and outbound data streams that all come from the same remote site. Alternatively, think of these sessions as logical remotes, with each remote site appearing as a separate remote to Connect:Enterprise. It is possible to let your remote terminal have one or more active sessions with Connect:Enterprise, along with active sessions to other applications in the host, such as JES2. All these options depend on the implementation of MLU capabilities in your remote terminal. Connect:Enterprise automatically handles the MLU capability if it receives more than one logon for the same remote site.

To implement MLU support:

1. Find out if and how your remote terminal supports MLU.
2. Logon multiple times to Connect:Enterprise.
3. Use any active MLU session to send or receive data.

Device Media Support

Some terminals have the capability to send or receive data on a certain medium.

You can send data to Connect:Enterprise from the following media:

- ◆ Console keyboard
- ◆ Card reader
- ◆ Exchange disk (transmission format or basic exchange)
- ◆ Printer output

You can receive data from Connect:Enterprise to the following media:

- ◆ Console display
- ◆ Card punch
- ◆ Exchange disk (transmission format or basic exchange)
- ◆ Printer

You always control the medium for inbound data sent to Connect:Enterprise. The medium used for outbound data sent to your terminal is controlled by you or by defaults set by host site personnel when Connect:Enterprise is installed.

When you request a batch from Connect:Enterprise, specify the medium that receives data from Connect:Enterprise. If you do not specify the medium, the batch is sent to the default medium for your remote site, as selected by host site personnel.

To implement device media support:

1. Determine if your remote terminal supports the receipt of data to a variety of media.
2. Ask your host site personnel to set a certain default medium for your remote site.
3. Specify the medium used when you request data from Connect:Enterprise, if different from the default. (optional)

Console Display Use

Connect:Enterprise can direct specific short information messages or error messages to a console display screen if your remote site is set up to handle the messages. Some types of messages are:

- ◆ A message following a successful logon to Connect:Enterprise
- ◆ A message indicating that Connect:Enterprise is ready to receive data from your terminal
- ◆ A message following a security violation

These messages are very helpful, so use them whenever possible.

In order for Connect:Enterprise to send the messages, your host site personnel must set an option for your remote site before Connect:Enterprise is brought online.

To implement console display:

1. Find out if your remote terminal can display control messages or other data on a console.
2. Ask host site personnel to define your remote site as a console device. This is the default value.

Data Compression

If your device cannot receive data from Connect:Enterprise in a compressed format, personnel at the host site need to know so they can specify COMPRESS=NO in the ODF. In addition, ensure the host VTAM Logon Mode Table reflects that compression is not supported. If these two areas are in conflict, message CMB184I is issued on the host system console.

Batch Separation Using FMHs

Remote sites can sometimes insert Functional Management Headers (FMHs) at the beginning and end of a batch sent to Connect:Enterprise. Your terminal probably controls the use of FMHs, and you need not worry about them. Some terminals enable you to influence the insertion of these FMHs, thereby indicating what is considered a batch to Connect:Enterprise. If your terminal has this capability, Connect:Enterprise automatically supports it.

You have the option to control when the FMHs are used, or you may configure this Process to run in the background.

If your terminal or the software package used on your terminal mentions FMHs, ensure your use of FMHs is compatible with Connect:Enterprise. Connect:Enterprise assumes that an FMH for Begin Data Set (BDS) marks the beginning of a batch, and an FMH for End Data Set (EDS) marks the end of a batch. If you are sending a single batch to Connect:Enterprise, this is probably handled automatically. If you are sending multiple batches or using nested send functions, your terminal may or may not separate the batches with FMHs. If you want Connect:Enterprise to consider the multiple batches as separate, you must ensure FMHs are inserted.

To implement batch separation using FMHs:

1. Determine if you have any control over the insertion of FMHs. This control influences what constitutes a batch to Connect:Enterprise.
2. No host site installation option is needed. Connect:Enterprise automatically handles FMHs if present.

SNA Transparency

SNA transparency enables Connect:Enterprise to send and receive data that contains special embedded control characters, such as object modules. This function is often needed when sending data from a remote personal computer to the host site, but the data is not converted from ASCII to EBCDIC.

Connect:Enterprise automatically supports the use of SNA transparency with two restrictions:

- ◆ Outbound data from Connect:Enterprise to your terminal does not use transparency for data sent to the printer media or to the basic exchange media.
- ◆ Connect:Enterprise cannot recognize control commands that are sent as transparent data and not converted to EBCDIC transmission code.

To implement SNA transparency:

1. Choose the appropriate method for your terminal type to send transparent data to Connect:Enterprise.
2. No host site installation option is needed. Connect:Enterprise automatically handles transparent data.

Disconnect Interval

The disconnect interval forces your session with Connect:Enterprise to terminate when your session is inactive for a certain time interval.

The function of the Connect:Enterprise disconnect interval is to:

- ◆ Reduce phone costs in a dial-up network
- ◆ Provide added security

Host site personnel implement remote Connect:Enterprise disconnect intervals and define time intervals, which are from 1-9 seconds, 999 seconds, or set to 0 to prevent any forced disconnect.

If your remote site has a similar function, set a different disconnect interval than that used by Connect:Enterprise. For information about setting a different disconnect interval, contact your host site system administrator.

Note: If you lose your connection to Connect:Enterprise while transmitting data, the cause is probably a network issue rather than the expiration of the disconnect interval.

EBCDIC Support

Connect:Enterprise can receive any data format, but can only interpret data that uses EBCDIC character code.

Sample Data Streams

The following are samples of valid data streams sent from a remote site to Connect:Enterprise:

1. At SNA sites, request a directory listing of all batches associated with mailbox ID BRANCH01 and send in two files containing data for a payroll job run at the host.

```

$$DIRECTORY      ID=BRANCH01
$$ADD            ID=BRANCH01 BATCHID='4/23 PAYROLL DATA' SCAN=Y
data record 1
data record 2
.
.
last data record
$$ADD            ID=BRANCH01 BATCHID='4/24 PAYROLL DATA' SCAN=N
data record 1
data record 2
.
.
last data record

```

Note: Because the \$\$ADD commands are processed first, the newly added batches are included in the \$\$DIRECTORY output.

- Request three data transmissions from the host: one for all batches waiting for transmission to mailbox ID BRANCH01, and two for specific batches for mailbox ID MARY. Data requested for mailbox ID MARY is sent directly to a printer.

```

$$REQUEST      ID=BRANCH01
$$$REQUEST     ID=MARY BATCHID='LETTER FROM JOE'  MEDIA=PR
$$REQUEST      ID=MARY BATCHID=#14 MEDIA=PR

```

- For SNA sites the MEDIA operand is added so that the directory list is displayed on the console display.

```

$$DELETE      ID=MARY BATCHID=#67
$$DIRECTORY   PASSWORD=SECRET MEDIA=CN

```

SNA Site Parameters

The following table describes the SNA site parameters:

Operand	Command	Description
APPLID(xxxxxxxx)	LOGON LOGOFF \$\$LOGOFF	The 1–8 character APPLID given to Connect:Enterprise at the host site, as chosen by your host site personnel.
BCHSEP=OPT3	\$\$REQUEST	Separates batches sent to remote sites when sending multiple batches in a single connection. OPT3 BCHSEP must remain consistent throughout a single connection and all \$\$ commands.
DATA(XXX,,XXX)	LOGON	Supplies your remote name to Connect:Enterprise. Host site personnel supply you with your own unique, confidential remote name. If required, you may supply a password (separated from the remote name by two commas) and use the new password option. This information resides in the logon, because it determines some options to use during communications.
EO=N Y	\$\$ADD	Specifies that the batch is extracted only once and cannot be transmitted. After extraction, the batch is permanently locked.

Operand	Command	Description
FORMAT=BID24 <u>BID64</u>	\$\$DIRECTORY	Specifies the format to use when listing batches. BID24 displays the directory using the first 24 characters of the User Batch ID. BID64 displays the directory display using the full 64 characters of the User Batch ID.
LOGMODE(xxxxxxxx)	LOGON	Supplies a value to determine the rules for communications between Connect:Enterprise and your remote site. It is a 1-8 character name, as chosen by your host site personnel.
MEDIA=CN PR PU EX BX	\$\$DIRECTORY \$\$REQUEST	(SNA sites only.) This parameter asks the host site to send the output data to the specified media on the remote device. Your remote device must support the requested media, ensure the media is ready and available for use. CN sends output data to the console display. This option causes Connect:Enterprise to use an X'15' (new line) as a record separator. PR sends output data to the printer. This option causes Connect:Enterprise to use an X'15' (new line) as a record separator. PU sends output data to the card punch. This option causes to use an X'1E' (standard IRS) as a record separator. EX sends output data to the exchange disk, and uses transmission exchange format. BX sends output data to the exchange disk, and uses basic exchange format. Many remote devices have the capability to assign media. For example, output data sent to the card punch is often assigned to a disk file on a personal computer. Connect:Enterprise is not aware of how you assign your remote site's media.
MULTXMIT= <u>NO</u> YES	\$\$ADD	(MX=) NO indicates that the batch is not available for multiple transmission. If a batch marked NO transmits to a remote site, that batch is marked with a T and is not available for transmission unless requested by batch number. YES indicates that the batch is available to all remote sites and is not marked with a T when requested by and transmitted to a remote site. Note: When MULTXMIT=YES, XMIT is forced to YES.

Operand	Command	Description
ONEBATCH=NO YES	\$\$REQUEST	(OB=) NO indicates all matching batches are returned. YES indicates that when BATCHID= is specified, only the first matching batch is returned.
PASSWORD=xxxxxxx	\$\$DIRECTORY	(PSWD=) The PASSWORD, if used, must match that supplied by host personnel for the Connect:Enterprise system. This parameter is required if the ID parameter is omitted.
RMT=xxxxxxx	LOGOFF \$\$LOGOFF	Replace the xxxxxx with the 1-8 byte remote name assigned to your remote terminal. It must match the remote name supplied in the logon. This operand is required.
SCAN=NO YES	\$\$ADD	NO indicates that all \$\$ commands must begin at the start of a data block. The default is NO. YES indicates that each record of each data block is decompressed and deblocked to SCAN for embedded \$\$ commands. This removes the requirement for starting \$\$ commands at the beginning of a data block. Use of this operand could result in system degradation due to the increased overhead. Note: Specifying SCAN=YES causes Connect:Enterprise to scan for only the next \$\$ command in subsequent data blocks. Once the next \$\$ command is found, further scanning is controlled by repeated specification of the SCAN= parameter. Note: The SCAN=YES facility for the \$\$ADD control card is ignored on remote sites that have SC=YES defined in the *REMOTES record in the ODF.
TO=N Y	\$\$ADD	Specifies that the batch is not extracted. It permits only one successful transmission, then the batch is permanently locked.
TRUNC=NO YES	\$\$REQUEST	This parameter specifies whether Connect:Enterprise truncates all trailing blanks from records before data transmission. NO means no blanks are truncated. YES means all blanks are truncated prior to data compression and data transmission.

Operand	Command	Description
VBQ#=xx	\$\$ADD	<p>Specifies the VBQxx (where xx is any number from 1-20) file where you want to add the batch. If this option is not specified, the batch is placed in the current collection VBQ file. If the specified VBQ is not allocated, the batch is added to the current collection VBQ.</p>
WAIT=hh:mm:ss, C	\$\$REQUEST	<p>Specifies the maximum Connect:Enterprise wait time and retry cycle used for the \$\$REQUEST. Permits the remote site to wait for transmittable batches for a specified time if no batches are initially found.</p> <p>The wait time is specified in hours, minutes, and seconds. The following describes valid values for the first subparameter:</p> <ul style="list-style-type: none"> • ss— Specifies the amount of time to wait, in seconds. The maximum allowable value in this form is 59. • mm:ss—Specifies the amount of time to wait, in minutes and seconds. The maximum allowable value in this form is 59:59. • hh:mm:ss—Specifies the amount of time to wait, in hours, minutes, and seconds. The maximum allowable in this form is 23:59:59. <p>The second parameter is optional. It specifies the number of wait and retry cycles to attempt before failing the request if no batches are available. The maximum allowable value is 999. The default value is 1.</p> <p>For example, use the following to request all batches for an ID and to specify the wait period, if no batches are found:</p> <pre>\$\$REQUEST ID=DALLAS WAIT=59,10</pre> <p>This request waits 59 seconds for a transmittable batch and retries the search for a transmittable batch 10 times. This effectively waits for a batch for a total of 9 minutes and 50 seconds.</p> <p>Once a request is satisfied by sending one or more batches, the request is removed from the wait loop. If all retries are done and no batches are available for transmission, then the standard message of no batches for transmission is sent to the remote site.</p> <p>Note: If your SNA session is through SPC, verify that the disconnect interval defined in SPC is adequate to support appropriate processing.</p>

Operand	Command	Description
XMIT=NO YES	\$\$ADD	NO indicates that the batch is available only to the host site. YES indicates that the batch being sent to the host is available for transmission to any remote site that requests it with the appropriate mailbox ID.

Communicating with BSC Sites

This chapter contains procedures and information specific to operating Connect:Enterprise with BSC sites.

Start and End a Session

The specific procedures for starting and ending a session are:

1. Establish a connection.

Your remote site may exist on a switched (dialup) or nonswitched (dedicated or leased) line. You may have different procedures to follow when you first establish a connection with Connect:Enterprise. Get the appropriate procedures to establish a connection from your Connect:Enterprise system administrator.

2. SIGNON (optional).

This procedure is done either manually or automatically and is remote-site dependent.

3. Type the commands described in this chapter.

Connect:Enterprise Support for Signon (BSC Sites)

Remote terminals that communicate with Connect:Enterprise are often designed to communicate with special RJE (Remote Job Entry) systems on the host computer, such as JES. Some RJE systems require a SIGNON record sent from the remote site when the transmission connection is established. Connect:Enterprise does not require this SIGNON record, but can accept it if your remote terminal sends it to the host site.

Connect:Enterprise is configurable to permit a free-form SIGNON record, which is received by the host from your remote but is not validated. The host site personnel who install Connect:Enterprise define one or more valid SIGNON records, and inform the remote sites of the appropriate data to use.

Connect:Enterprise does not require the fixed-form SIGNON record. Begin your input data with any of the Connect:Enterprise \$\$ commands other than the SIGNON.

Host site personnel can also define optional free-form SIGNON records that create an environment for security checking. Coordinate the use of this or other SIGNON support with the host site.

Host-Initiated Communications (Auto Connect)

Connect:Enterprise has a function called Auto Connect that enables the host site computer to contact an unattended remote site. Using Auto Connect, Connect:Enterprise can both transmit to and collect data batches from remote sites.

For Auto Connect to work, the remote site must appropriately respond to the host computer. Host site personnel provide the actions you take to prepare your site for responding to an Auto Connect from the host site.

Connect:Enterprise is very flexible in the way it uses the Auto Connect function. For example, Connect:Enterprise is configurable to transmit batches to your remote site at different times throughout the night. Your remote site terminal or computer is then required to receive the batches whenever the host makes contact.

Batches can be sent to the host site during Auto Connect. Since Auto Connect is often used with remotes that can operate unattended, program or set up these terminals to send batches when the terminal is called by the host site.

Alternatively, you may receive a call from the host site at certain times of the day. You can then manually send batches to the host, if instructed to do so.

Host-initiated sessions do not support any \$\$ commands from the remote other than \$\$ADD.

Using Connect:Enterprise

Connect:Enterprise is a command-driven application. For example, a remote site can precede the transmittable data with a \$\$ADD header record.

The following command tells Connect:Enterprise to add the data that follows to the host data repository and identify that batch as report summary from ACME:

```
$$ADD ID=ACME BID='report summary'
```

The following command tells Connect:Enterprise to transmit all batches with an ID of ACME and a batch identifier of 'report summary' to the requesting remote site:

```
$$REQUEST ID=ACME BID='report summary'
```

The following command tells Connect:Enterprise to flag as deleted all batches with an ID of ACME and a batch identifier of 'report summary':

```
$$DELETE ID=ACME BID='report summary'
```

Wildcard Characters in Connect:Enterprise Names

Connect:Enterprise, SPC Option 3.1, and Connect:Enterprise for UNIX 3.1 use the following special characters as wildcard characters when making decisions for various types of data repository processing. Use the following wildcard characters in selection checks, most notably with BID values.

Wildcard Character	Function
asterisk (*)	Indicates any number of characters
question mark (?)	Indicates a single character
square brackets ([]) with any number of characters inside the brackets including an exclamation mark (!)	Indicates a specific character, or characters within a string of characters.

You may create batches with a BID value that include wildcard characters. However you may get unexpected results if you use wildcard characters in requests. For example:

- ◆ You create three batches with a BID value of 'Test **', 'Test 123', and 'Test **456' respectively. Because offline ADD processing and online collection processing do not restrict putting wildcard characters in the BID parameter, the batches are added to Connect:Enterprise without errors.
- ◆ To collect the batch with the BID of 'TEST **' you create the following \$\$REQUEST card:

```
$$REQ ID=yourid BID='TEST **'
```

- ◆ After submitting the request, you discover that you have collected data from all three batches. To prevent the previous error, take one of the following steps:
 - ◆ Refrain from using the wildcard characters when defining any name in data repository. The Connect:Enterprise System Administrator can enforce this rule by creating a Security Exit 1 and Offline ADD Exit to restrict the use of these characters in name values when adding data.
 - ◆ Continue to use wildcard characters in data repository name values, but do not use any parameters that support wildcard characters. For example, use the #nnnnnnn parameter to request a specific batch by number. Do not use BID='xxx-xxx', as this parameter supports wildcards. Using this method limits selection, but eliminates confusion.

Terminal-Dependent Options

A variety of terminals and devices can communicate with Connect:Enterprise, but they do not all have the same capabilities. For this reason, Connect:Enterprise supports some terminal-dependent options for BSC remote sites. Some of these options are used only if they are installed by host site personnel. Other options do not require host site installation; they are used if your terminal type supports them.

BSC Options

BSC terminal-dependent options are used only if your remote terminal supports them. These options include:

- ◆ Free-form BSC SIGNON
- ◆ Blank compression
- ◆ Blank truncation
- ◆ Blocked data records
- ◆ BSC transparency
- ◆ Record separator override
- ◆ Use of \$TURNLINES\$
- ◆ Temporary Text Delay (TTD)
- ◆ Wait acknowledgement (WACK)

Detailed information about these options is provided in the sections that follow:

Free-Form BSC SIGNON

This SIGNON requires a remote name and an optional password. It is optional and must be coordinated with the Connect:Enterprise host site system administrator.

BSC SIGNON permits users to identify themselves as a specific remote. Without this SIGNON, users are identified only by the line on which they connected. This line is typically shared by other users and does not provide a unique identification.

For more information on the free-form BSC SIGNON, refer to the *Defining the ODF* chapter in the *Connect:Enterprise for z/OS Installation Guide*.

Blank Compression

Data sent over telecommunications systems may contain many blanks (spaces). By using the blank compression method defined for the IBM 3780 data communication terminal, Connect:Enterprise can remove four or more contiguous blank spaces and replace them with a control character that indicates the number of compressed blanks. In order to specify blank compression to Connect:Enterprise in a transmission request, the remote terminal must also use the IBM 3780 method. In addition, both the host and the remote sites must use blank compression/decompression for a given transmission or the data is invalid. A batch collected using blank compression is stored in the VSAM batch files in compressed form and is automatically decompressed by the EXTRACT utility when extracted from the data repository.

Blank Truncation

Text data sent over telecommunications systems may have a large number of blanks at the end of each record. Connect:Enterprise can remove trailing blanks from records sent to remote sites. If the trailing blanks are necessary, the remote site must have the capability to replace them. Also, Connect:Enterprise can accept data with the trailing blanks stripped.

Blank truncation is restricted to 80-byte fixed-length records. Connect:Enterprise assumes blank truncated records are 80-byte fixed-length and a control character indicating the number of blanks removed is not required.

Blocked Data Records

It is more efficient to transmit blocks of data containing multiple records than it is to transmit individual records. Connect:Enterprise sends and receives blocked data records. However, the block size must not exceed 4096 bytes. If a record does not fit into a block, it is sent in the next block. An Inter-Record Separator (IRS) X'1E' or Inter-Unit-Separator (IUS) X'1F' must separate the records. X'1E' is the most commonly used and is the system default for an IRS. The record separator used by Connect:Enterprise when transmitting is set by the host site personnel for each BTAM transmission line at system installation. All terminals using the same line must handle the record separator sent by the host. If the terminals cannot handle the record separator sent by the host, the remote site must use the Record Separator Override option.

Note: All data, including record separators and BSC control characters (for example, STX (X'02'), ETX (X'03'), and so forth), must fit in the block size. This is the BUFSIZ= value in the M\$LINE user assembly defined at the host site.

Blocked data collected by Connect:Enterprise is stored in the VSAM batch files in blocked form. The EXTRACT utility automatically deblocks the blocked data while extracting it from the data repository.

BSC Transparency

Connect:Enterprise is capable of sending and receiving transparent data. Transparent data can contain embedded line control characters. BSC transparency is often a hardware function on terminals and is invoked by setting a switch. When Connect:Enterprise receives a \$\$REQ from a remote site in transparency form, it transmits all return data in transparency form. Refer to your terminal or computer operation manual to determine the action required to use BSC Transparent Data Transmission.

Record Separator Override

A Record Separator (control character) separates multiple records sent in a single nontransparent block. A default IRS is set by the host site personnel for each line used by Connect:Enterprise. If a remote site cannot process the default record separator, the site may request a record separator override when it asks for data from Connect:Enterprise. The record separator is typically either X'1E' or X'1F.'

Use of \$TURNLINE\$

The \$TURNLINE\$ capability provides a special method of limited conversational transmissions between your remote site and Connect:Enterprise at the host site. Instead of the standard send all-receive all mode of communications, your remote site can send-receive-send-receive-send-receive, and so on, as done for conversational transmissions.

To use this option, coordinate the send-receive sequence exactly with the data batch being sent from the host site. You send your terminal a signon record, receive data from your terminal, then send data to your terminal. In this case, set up your terminal to receive the signon record, send data to the host site, then receive data from the host site. Changing from receive to send, and vice versa, is called a line turnaround.

The host site data batch being sent controls when the line turnaround occurs. The data batch must contain a \$TURNLINES\$ record. When the host site detects a \$TURNLINES\$ record, it stops sending and does a line turnaround to receive. The \$TURNLINES\$ record is not sent to the remote site. After the receive is complete, the host site can again do a line turnaround to send.

Carefully coordinate the use of this option with the host site. If the \$TURNLINES\$ feature is used, get any special requirements for its implementation from the host site personnel.

Temporary Text Delay (TTD)

Connect:Enterprise sends a BSC 3780 TTD to remotes when file I/O requires more than a set period of time to complete (usually 3 seconds). TTD processing is invoked when Connect:Enterprise is searching for a transmittable batch or when flagging batches matching the Auto Connect listname as transmitted. The format of the TTD is STX ENQ or X'022D'. The remote must reply with a BSC NAK X'3D'.

WAIT Acknowledgement (WACK)

Connect:Enterprise is capable of handling a variable number of WACKs (X'106B') from a remote site while waiting for the transmission to continue. Connect:Enterprise responds with the appropriate ENQ (X'2D') until the limit, which is controlled by the WACKMAX ODF parameter, is reached. If you find that Connect:Enterprise disconnects before your remote continues transmission, contact host site personnel about increasing the WACKMAX value.

Sample Data Streams

The following are samples of valid data streams sent from a remote site to Connect:Enterprise:

1. At BSC sites, request three data transmissions from the host: one for all batches waiting for transmission to mailbox ID BRANCH02, and two for specific batches for mailbox ID MARY. Data requested for mailbox ID MARY is sent compressed, and all data is sent in blocks of six records each.

```

$$$REQUEST      ID=BRANCH02 BLOCK=6
$$$REQUEST      ID=MARY BATCHID='LETTER FROM JOE' BLOCK=6 CMP=Y
$$$REQUEST      ID=MARY BATCHID=#0014 BLOCK=6 CMP=Y

```

2. Request Connect:Enterprise to delete a batch for mailbox ID MARY and send a directory listing of all batches for all mailbox IDs on the VSAM batch files.

```

$$DELETE        ID=MARY BATCHID=#0067
$$DIRECTORY     PASSWORD=SECRET

```

BSC Site Parameters

The following table describes the BSC site parameters.

Operand	Command	Description
BCHSEP=NO OPT1 OPT2 OPT3	\$\$DELETE \$\$DIRECTORY \$\$REQUEST	<p>Specifies the method Connect:Enterprise uses to separate the data for multiple \$\$ commands.</p> <p>NO indicates batches are not separated. If multiple batches are sent in a single connection, they are concatenated and sent as a single batch. Ensure remote sites using this line can process concatenated data batches if this option is chosen.</p> <p>OPT1 causes Connect:Enterprise to use a common RJE method of separating batches. At the end of each batch, Connect:Enterprise sends an EOT (x'37') to the remote, reads a response from the remote, and then sends ENQ (x'02') to request use of the line. Do not use OPT1 if the remote site using this line cannot appropriately respond to this protocol.</p> <p>OPT2 Connect:Enterprise separates batches using an ETX (X'03'). Do not use OPT2 unless the remote can appropriately respond to this protocol.</p> <p>BCHSEP must remain consistent throughout a single connection and all \$\$ commands.</p>
BLOCK=xx	\$\$DIRECTORY \$\$REQUEST	<p>The BLOCK operand prompts Connect:Enterprise to send multiple records in a single data block, separated by control characters.</p> <p>xx--specifies the number of records sent per block, up to a maximum of 99. If BLOCK is omitted, the records are transmitted to the remote site unblocked. To use this operand, a remote site terminal must be capable of deblocking the records for use at the remote site. If the BLOCK factor specified causes Connect:Enterprise to build a block that is larger than the maximum buffer size (4096), a smaller blocking factor forces the specific transmission size.</p>
\$\$END	\$\$ADD	The \$\$END parameter signifies the end of a \$\$ADD card. It is valid only for blocked BSC transparent transmissions. The \$\$END characters are the last five bytes of the \$\$ADD record.
EO=N Y	\$\$ADD	Specifies that the batch is extracted only once and cannot be transmitted. After extraction, the batch is permanently locked.
FORMAT=BID24 <u>BID64</u>	\$\$DIRECTORY	<p>Specifies the format to use when listing batches.</p> <p>BID24 displays the directory using the first 24 characters of the User Batch ID.</p> <p>BID64 displays the directory display using the full 64 characters of the User Batch ID.</p>

Operand	Command	Description
MULTXMIT=NO YES	\$\$ADD	(MX=) NO indicates that the batch is not available for multiple transmission. If a batch marked NO transmits to a remote site, that batch is marked with a T and is not available for transmission unless requested by batch number. YES indicates that the batch is available to all remote sites and is not marked with a T when requested by and transmitted to a remote site. Note: When MULTXMIT=YES, XMIT is forced to YES.
ONEBATCH=NO YES	\$\$REQUEST	(OB=) NO indicates all matching batches are returned. YES indicates that when BATCHID= is specified, only the first matching batch is returned.
PASSWORD= xxxxxxx	\$\$DIRECTORY	(PSWD=) The PASSWORD, if used, must match that supplied by host personnel for the Connect:Enterprise system. This parameter is required if the ID parameter is omitted.
RECSEP=1E 1F	\$\$DIRECTORY \$\$REQUEST	Temporarily overrides the assigned line Record Separator that sends blocked records from the host site. Either 1E or 1F is specified as the record separator.
TO=N Y	\$\$ADD	Specifies that the batch is not extracted. It permits only one successful transmission, then the batch is permanently locked.
TRUNC=NO YES	\$\$REQUEST	This parameter specifies whether Connect:Enterprise truncates all trailing blanks from records before data transmission. NO means no blanks are truncated. YES means all blanks are truncated prior to data compression and data transmission.
VBQ#=xx	\$\$ADD	Specifies the VBQxx (where xx is any number from 1-20) file where you want to add the batch. If this option is not specified, the batch is placed in the current collection VBQ file. If the specified VBQ is not allocated, the batch is added to the current collection VBQ.
XMIT=NO YES	\$\$ADD	NO indicates that the batch is available only to the host site. YES indicates that the batch being sent to the host is available for transmission to any remote site that requests it with the appropriate mailbox ID.

Remote User Commands

This chapter describes the following commands available to Connect:Enterprise remote users.:

- ◆ \$\$ADD sends a batch of data to the host site
- ◆ \$\$DELETE flags a batch of data, as deleted, at the host site
- ◆ \$\$DIRECTORY requests a formatted listing of batches from the host site
- ◆ \$\$LOGOFF logs off from Connect:Enterprise at the host site
- ◆ \$\$REQUEST requests a batch of data from the host site

In addition, this chapter gives session information and user instructions to assist you during a Connect:Enterprise session.

Submit Commands

When a remote connection is established, the remote site communicates with Connect:Enterprise by means of the command utilities, referred to as the \$\$ commands. These commands are described in the following sections.

The \$\$ADD command is the only command available for a remote site when the connection is initiated by the host using an Auto Connect.

\$\$REQUEST, \$\$DIRECTORY, \$\$DELETE, and \$\$LOGOFF (SNA only) are typed in these three ways:

- ◆ Individual commands from your remote computer console keyboard or from a data file
- ◆ Commands before a \$\$ADD record at the start of a data batch
- ◆ Commands after a \$\$ADD record with SCAN=Y (SNA sites)

When the host receives \$\$ commands that precede \$\$ADD, they are saved and processed in the order received after all inbound data for the \$\$ADD is received. When the host receives \$\$ commands as single commands that do not precede \$\$ADD, they are processed immediately and the output data is sent to your remote site.

For BSC only, if multiple \$\$ output commands are received, the output data is sent as batches separated by EOTs (X'37') (see BCHSEP=OPT1 on page 3-11). If a remote site is unable to use

this method of batch separation, the remote must specify BCHSEP=OPT2 on each \$\$ output command line. This separates batches with an ETX (X'03').

The following rules apply to \$\$ commands:

- ◆ Place the \$\$ command in column 1.
- ◆ Code any number of blanks between operands.
- ◆ Do not use commas between operands.
- ◆ Type commands and operands in upper case.
- ◆ Code must be EBCDIC.
- ◆ Code each parameter value as documented in *Chapter 3, Communicating with BSC Sites*. Short forms are not allowed.
- ◆ Do not exceed the maximum record length. The maximum \$\$ remote command record length is 100 for BSC and 256 for SNA.

The following worksheets can assist you in typing information pertinent to the \$\$ commands. The worksheets can be duplicated and used routinely.

\$\$ Command Worksheet

Command \$\$ADD | \$\$DELETE | \$\$DIRECTORY | LOGON | \$\$LOGOFF | \$\$REQUEST

Remote site IDs Contact your host site administrator for the following remote site IDs.

Mailbox ID: ID=_____

User Batch ID: BATCHID=_____

Circle the appropriate option or contact you host site administrator for the values required for the following operands.

SNA Options		BSC Options	
Operand	Value	Operand	Value
BCHSEP	= OPT3	BCHSEP	= NO OPT1 OPT2 OPT3
EO	= <u>N</u> Y	EO	= <u>N</u> Y
FORMAT	= BID24 <u>BID64</u>	FORMAT	= BID24 <u>BID64</u>
MEDIA	= <u>CN</u> PR PU EX BX	CMP	= <u>NO</u> YES
MULTXMIT	= <u>NO</u> YES	MULTXMIT	= <u>NO</u> YES
ONEBATCH	= <u>NO</u> YES	RECSEP	= <u>NO</u> YES
SCAN	= <u>NO</u> YES	TO	= <u>N</u> Y
TO	= <u>N</u> Y	TRUNC	= <u>NO</u> YES
TRUNC	= <u>NO</u> YES	XMIT	= <u>NO</u> YES
WAIT	= hh:mm:ss, C _____	BLOCK	= _____
XMIT	= <u>NO</u> YES	PASSWORD	= _____
APPLID	= _____	VBQ#	= _____
DATA	= _____		
LOGMODE	= _____		
PASSWORD	= _____		
RMT	= _____		

\$\$ADD Command

\$\$ADD places batches of data into the data repository, and precedes the batch data that is sent. You may send any number of \$\$ADD records and associated data files to the host site.

The data collection function is initiated by the remote site. Connect:Enterprise permits two methods of initiating data collection:

- ◆ The preferred method uses a \$\$ADD record that precedes the data
- ◆ Another method is to send only data once communications are established. The drawback of the second method is that the batch is identified by the remote name (BSC and SNA), BSC line name, or BSC Auto Connect remote name (if BSC SIGNON is not used), rather than your specific mailbox ID.

\$\$ADD Defaults

If a data batch is sent to the host site without a \$\$ADD record, the following defaults are used:

Default Name	Description
BATCHID	BATCH WITHOUT \$\$ADD
ID	LINEID for BSC remotes not using the free-form BSC SIGNON
MULTXMIT	No
SCAN	No
VBQ#	Current collection VBQ
XMIT	No

If a data batch is sent to the host site without a \$\$ADD record during a host-initiated Auto Connect to the remote site, the following defaults are used:

Default Name	Description
BATCHID	AC BATCH WITHOUT \$\$ADD
ID	The remote name from the Auto Connect list
MULTXMIT	No
SCAN	No
VBQ#	Current collection VBQ
XMIT	No

Multiple Batches

If multiple batches are sent per transmission, precede each batch with a \$\$ADD record. If multiple batches are sent to the host computer in a single transmission, and the batches are separated by \$\$ADD records, use caution if the records are blocked by your remote terminal before they are sent to the host site. Connect:Enterprise cannot detect a \$\$ADD record unless it is the first record in a block of data. Ensure that your remote terminal begins a new block for each \$\$ADD record.

Connect:Enterprise can also create multiple batches on the VSAM batch files as follows:

- ◆ At SNA sites, use standard Function Management Headers (FMHs) to separate files sent to the host site. If Connect:Enterprise receives an End Data Set FMH from the remote site during a data collection, the current batch is marked complete and a new batch is started when the next Begin Data Set FMH is received.
- ◆ For BSC sites, if Connect:Enterprise receives a block ending with ETX (X'03'), the current batch is marked complete and a new batch is started with the next data input from the remote site.

A new \$\$ADD record at the beginning of a BSC block causes batch separation as if an ETX had terminated the previous block.

Syntax

The syntax for the \$\$ADD command at SNA sites is:

```

$$ADD BATCHID='xxx...xxx' EO=N|Y ID=xxxxxxxxx MULTXMIT=NO|YES
SCAN=NO|YES TO=N|Y VBQ#=nn XMIT=NO|YES
    
```

The syntax for the \$\$ADD command at BSC sites is:

```

$$ADD BATCHID='xxx...xxx' EO=N|Y ID=xxxxxxxxx MULTXMIT=NO|YES TO=N|Y
VBQ#=nn XMIT=NO|YES [ $$END]
    
```

Description

Use any number of blanks to separate operands. Do not use commas to separate operands. \$\$ADD must begin in the first record position.

Note: The parameter setting, SCAN=YES, is ignored on SNA remote sites that have SC=YES defined in the *REMOTES record in the Options Definition File. See the *Connect:Enterprise for z/OS Administration Guide* for more information on the SC parameter.

\$\$DELETE Command

Any batch on the VSAM batch files can be flagged as deleted by a remote site. To delete a batch, you must know the batch identifiers. Run a directory list to confirm you know the correct batch identification data before deletion.

After the host receives the input requests, Connect:Enterprise processes the delete requests and then turns the line around and sends a message to the remote site concerning the outcome of the \$\$DELETE request. Ensure that your terminal is ready to first send the \$\$DELETE request to the host site, then receive the output from the host in the same transmission session.

Syntax

To flag a batch as deleted from an SNA site, send the host a \$\$DELETE record in the following format:

```
$$DELETE BATCHID=#nnnnnnn ID=xxxxxxxx
```

To flag a batch as deleted from a BSC site, send the host a \$\$DELETE record in the following format:

```
$$DELETE BATCHID=#nnnnnnn BCHSEP=OPT1|OPT2 ID=xxxxxxxx
```

Description

Use any number of blanks to separate operands. \$\$DELETE must begin in the first record position. Abbreviate this command as \$\$DEL.

\$\$DIRECTORY Command

Remote sites can send inquiries about the contents of the VSAM batch files to the host by submitting a directory request and their mailbox ID. The directory listing is received in mailbox ID order. Connect:Enterprise searches the VSAM batch files for all batches that match the submitted mailbox ID. A listing of the batch control information for each batch is sent back to the remote site. It is only possible to obtain a listing of all batches for all mailbox IDs if two conditions exist: 1) a password was defined when Connect:Enterprise was installed, and 2) the password was appropriately submitted in the \$\$DIRECTORY command from the remote site.

Syntax

To request a directory listing from an SNA site, send the host a record in the following format:

```
$$DIRECTORY ID=xxxxxxxxx FORMAT=BID24|BID64 MEDIA=CN|PR|PU|EX|BX PASSWORD=xxxxxxxxx
```

To request a directory listing from a BSC site, send the host a record in the following format:

```
$$DIRECTORY BCHSEP=OPT1|OPT2 BLOCK=xx ID=xxxxxxxxx FORMAT=BID24|BID64  
PASSWORD=xxxxxxxxx RECSEP=1E|1F
```

Description

Use any number of blanks to separate operands. \$\$DIRECTORY must begin in the first record position. Abbreviate this command as \$\$DIR.

After the host receives your \$\$DIRECTORY request, Connect:Enterprise turns the line around and sends the requested data to the remote site. Ensure that your remote site is ready to send the \$\$DIRECTORY request to the host site, and receive the output from the host in the same transmission session.

Output

One record is returned to the remote site for each batch in the VSAM batch files that matches the requested mailbox ID. The directory listings use the following format:

```
xxxxxxxxx #nnnnnnn CT=nnnnnnnnn BID=x...x HHMM-YYDDD ICADNURTEMXBSZ  
VBQnn|OFFLINE
```

The contents of the fields are:

Field	Description
xxxxxxxxx	The 8-byte mailbox ID with which the batch is associated
#nnnnnnn	The 7-digit batch number assigned by Connect:Enterprise
CT=nnnnnnnnn	The record/block count in the batch. Depending on the installation parameters, this value is either the total number of records in the batch or the total number of blocks in the batch. Contact your Connect:Enterprise administrator to determine which value is being used. If the count = 0, then either the batch data collection is in progress or is interrupted before completion.

Field	Description
BATCHID=xx....xx	The 64-byte user batch ID assigned to the batch when added to the VSAM batch files. If the batch is created due to an online data collection without a \$\$ADD record, this field contains: BID=BATCH WITHOUT \$\$ADD (For Remote Connects) BID=AC BATCH WITHOUT \$\$ADD (For Auto Connects) If the batch is created in an online data collection with a \$\$ADD record, but no BATCHID is specified, this field contains BID=NONE.
HHMM	The time the batch is created
YYDDD	The Julian date the batch is created
I C A D N U R T E M X B S Z	One or more of the letters ICADNURTEMXBSZ occurs in the directory listing. These letters indicate the batch status.
I	The batch is incomplete; collection is in progress or the transmission is interrupted
C	The batch is collected from a remote site while Connect:Enterprise is online.
A	The batch is added by the offline utilities
D	The batch is flagged as deleted from the VSAM batch files
N	The batch is nontransmittable (locked for transmissions). When displayed, this status replaces the D status. This status is set immediately after the batch is successfully collected when the EO=Y option of the \$\$ADD command is specified. It is also set after a successful transmission of the batch added with the TO=Y option
U	The batch is unextractable (locked for extractions). When displayed, this status replaces the D or N status. This status is set immediately after the batch is added, when the TO=Y option adds the batch. It is also set after the batch's successful extraction when the EO=Y option added the batch.
R	The batch is requestable through a \$\$REQUEST from a remote site.
T	The batch is transmitted to a remote site. It is not transmitted on a <i>transmit all for the mailbox ID</i> , but can be transmitted again by specific batch number.
E	The batch is extracted by host site personnel
M	The batch is available for multiple transmission and any remote site can request it by its ID.
X	The batch contains transparent data.
B	The batch originated at an online BSC remote site
S	The batch originated at an online SNA remote site.
Z	EBCDIC data added through the APPC User API

Field	Description
VBQnn OFFLINE	The name of the VSAM batch queue where the data resides. If the batch resides on a VSAM batch queue, which is not currently allocated to Connect:Enterprise, OFFLINE is displayed instead of the VBQ name.

SNA Logon System Function

Logon is a system function, rather than a Connect:Enterprise command. Your remote terminal must log on through VTAM to gain access to Connect:Enterprise at the host site.

The logon function may be totally automated by your remote site, or you may have to type a logon or other command on your terminal's keyboard. The procedures you must use are determined by host site personnel, not by Connect:Enterprise. Therefore, this section cannot tell you exactly how to type a logon, or if a logon is automatic for your terminal. It can give you a general idea of the information Connect:Enterprise requires, but the exact format of the logon may vary.

The following is a sample common logon. This example may not necessarily work for your particular installation, and the names in parentheses probably differ for your installation.

```
LOGON APPLID(MAILBOX) LOGMODE(RJE3770) DATA(RMT001)
```

If something is wrong with your logon, you receive the message SESSION NOT BOUND. This means that your logon attempt is rejected, either by the system or by Connect:Enterprise. Correct the logon format and retype the logon.

For MLU support, you must log on for each session you activate. The sessions can use the same format for all the logons, or you may be instructed to use a different remote name for each logon. This decision is made by your host site personnel. MLU supports a maximum of six sessions.

Syntax

Use the following format to log on from an SNA site. This format may not necessarily work for your particular installation.

```
LOGON APPLID(xxxxxxxx)
DATA (xxxxxxxx, , yyyyyyyy, zzzzzzzz)
LOGMODE (xxxxxxxx)
```

Description

Connect:Enterprise gains control when you type a logon. Three key logon items are required.

Note: The keywords APPLID, LOGMODE, and DATA are standards for typing a logon, but they are determined by host site personnel. Different keywords may be used, or the information can be typed as positional parameters instead.

SNA LOGOFF and \$\$LOGOFF System Functions

Type LOGOFF as a system function or as a Connect:Enterprise \$\$ command. In either case, the purpose of the logoff is to end the session with the host site. When the logoff function is processed from a dial-up line, the telephone connection is also dropped.

Type the LOGOFF system function as a command on your terminal's keyboard or press a specified function key. The exact procedure depends upon your terminal type and on the implementation by host site personnel.

The \$\$LOGOFF Connect:Enterprise function is essentially a data string that Connect:Enterprise interprets as a request to end the session. For security, correctly type your remote name and the APPLID defined to Connect:Enterprise.

Syntax

The Connect:Enterprise logoff function is initiated by sending the host a record with the following format:

```
$$LOGOFF APPLID=xxxxxxxx RMT=xxxxxxxx
```

Description

Use any number of blanks to separate operands. \$\$LOGOFF must begin in the first record position.

\$\$REQUEST Command

Data transmission to your remote site is initiated by sending a \$\$REQUEST. A request for a transmission can identify a single batch on the VSAM batch files or can request transmission of all batches associated with a mailbox ID. When requesting all batches for a mailbox ID, remember that only batches not already flagged transmitted are sent. A transmission request for a single batch by its batch number can access a batch flagged as already transmitted.

If multiple batches are transmitted to a remote site in response to a \$\$REQUEST for an ID (without a BATCHID), Connect:Enterprise separates the batches using standard SNA FMHs, unless BCHSEP=OPT3 is used, which concatenates the separate batches into one.

Syntax

At SNA sites, the \$\$REQUEST record uses the following syntax:

```
$$REQUEST BATCHID='xx.xx'|"yyy.yyy"|#nnnnnnn BCHSEP=OPT3
ID=xxxxxxxxx MEDIA=xx ONEBATCH=NO|YES TRUNC=NO|YES WAIT=hh:mm:ss,C
```

At BSC sites, the \$\$REQUEST record uses the following syntax:

```
$$REQUEST BATCHID='xx.xx'|"yyy.yyy"|#nnnnnnn
BCHSEP=NO|OPT1|OPT2|OPT3 BLOCK=xx CMP=NO|YES ID=xxxxxxxxx
ONEBATCH=NO|YES RECSEP=xx TRUNC=NO|YES
```

Abbreviate this command as \$\$REQ.

Description

Use any number of blanks to separate operands. \$\$REQUEST must begin in the first record position.

Parameter Interrelationships

The following is a list of parameter interrelationships:

- ◆ If TRUNC=Y and CMP=Y are both selected, the data is first truncated and then compressed.
- ◆ Do not attempt to use BSC transparency in conjunction with blocked data, with TRUNC=Y, or with CMP=Y.
- ◆ If a batch is requested using BLOCK for blocked data, and if the requested batch is already blocked on the VSAM batch files, double blocking can occur. This is appropriately handled by Connect:Enterprise, but the remote terminal must be able to deblock such records.

\$\$REQUEST Sample Outputs

Connect:Enterprise uses certain criteria to determine which batches are sent to your remote site for a \$\$REQUEST. The batch status indicators (such as those displayed for a \$\$DIRECTORY) are checked and the following rules are applied:

Requesting all batches for an ID:

```
$REQUEST ID=xxxxxxxxx
```

The batch must be marked R (requestable). The batch must not be marked T (already transmitted), D (deleted), I (incomplete), or N (nontransmittable).

Requesting all batches by ID and batch ID:

```
$$REQUEST ID=xxxxxxxxx BATCHID='xxx.yyy'
```

The rules are the same as for requesting all batches for an ID.

Requesting a single batch by ID and batch number:

```
$$REQUEST ID=xxxxxxxx BATCHID=#nnnnnnn
```

The batch must be marked R (requestable). The batch must not be marked D (deleted) or N (nontransmittable).

If you are unable to request a batch that is on the VSAM batch files, try a \$\$DIRECTORY and examine the batch status indicators to determine the reason.

Error Messages

Usually the data collection and data transmission processing proceeds with no problems. However, some error messages may occasionally transmit to the remote site.

Sometimes when the remote site is expecting to receive a batch data transmission, it may instead receive a message that the requested batch does not exist. Use caution in processing received data to ensure you are not processing an error message from Connect:Enterprise instead of actual batch data.

If your SNA remote site is defined as a console device, you may display these messages on the console screen.

All of the remote site messages are identified and explained in this chapter. They are also included in the *Connect:Enterprise for z/OS Error Messages and Codes Guide*.

Remote User Error Messages (***) ERROR (***)

The following is a list of all of the remote site messages. An identifier, description, and action for these messages is included.

Message	Description	Action
*** ERROR ***	An unidentifiable error occurred at the host.	Verify that your input data is correct, and retry the data transmission at a later time.
*** ERROR *** BATCH DATA BLOCKS EXCEED BUFFER SIZE.	You requested a batch with record sizes that are larger than allowed on the telecommunications line. Connect:Enterprise cannot send the batch to you using this line.	Try another line which may allow larger records. If it still does not work, you cannot access the batch.
*** ERROR ***BSC SIGNON SECURITY VIOLATION.	Your BSC SIGNON attempt has failed.	Contact host site personnel for further information.

Message	Description	Action
*** ERROR *** COLLECTION FAILED. ID VALIDATION FAILED FOR ID=XXXXXXXX.	The Connect:Enterprise system at the host site uses the batch security option. The ID for your input data batch is incorrect, and your batch is rejected.	Correct the ID used if it is spelled incorrectly, or contact host site personnel to obtain a valid ID.
*** ERROR *** COLLECTION FAILED. SECURITY VIOLATION.	You attempted to send batches without following security procedures. These procedures are unique for your installation and are activated by a user security exit.	Contact host site personnel if you cannot correct the problem.
*** ERROR *** COLLECTION FAILED. INVALID DATA COULD NOT BE DEBLOCKED.	You attempted to send batches to the host, but Connect:Enterprise cannot deblock your data to analyze its contents. This is generally due to a data format error or to a very large data block.	Attempt to correct your input data and retry the collection. If the problem persists, contact host personnel.
*** ERROR *** COLLECTION FAILED. INVALID FMH SENT.	Your remote site sent a Function Management Header (FMH) that is not supported by Connect:Enterprise. Connect:Enterprise supports only a 6-character FMH Type 1.	If you cannot correct the problem, contact host personnel.
*** ERROR *** COLLECTION FAILED. HOST SITE FILE PROBLEM.	The host site experienced a problem with its files while attempting to process your data collection. This is usually due to a file full condition or to a very large input data block.	If you cannot correct the problem, contact host personnel.
*** ERROR *** DATA COLLECTION REJECTED. TRY AGAIN LATER.	A temporary busy condition is encountered at the host site.	Retry the data collection at a later time.
*** ERROR *** DATA COLLECTION ABORTED. TRY AGAIN LATER.	An error condition at the host or on the line caused a data collection in progress to fail. The partial data batch is ignored and must be retransmitted at a later time. If this message occurs repeatedly, check the data you are sending the host.	Verify the data being transmitted if you receive this error.
*** ERROR *** ID VALIDATION FAILED FOR ID=xxxxxxxx.	The Connect:Enterprise system at the host site uses the batch security option. The ID in your input data is incorrect, and your communications attempt is rejected.	Correct the ID used if it is spelled incorrectly or contact host site personnel to obtain a valid ID.

Message	Description	Action
*** ERROR *** INVALID PASSWORD FOR FULL DIRECTORY REQUEST.	You attempted a \$\$DIRECTORY request without supplying a mailbox ID, and you did not supply the correct password.	Retype the request with the correct password, or only attempt a \$\$DIRECTORY for a single mailbox ID.
*** ERROR *** INVALID DELETE. BATCH NOT FOUND.	You attempted a \$\$DELETE for a batch that does not exist.	Correct the \$\$DELETE to specify the specific batch for deletion and retry the transmission.
*** ERROR *** INVALID DELETE. ENTER ID AND BATCHID=#nnnnnnn.	You attempted a \$\$DELETE but typed the batch identifiers incorrectly.	Correct the \$\$DELETE request and retry the transmission.
*** ERROR *** NO BATCHES FOR TRANSMISSION.	You have requested a data transmission with a \$\$REQUEST record, but the batch requested either does not exist or is not available for a data transmission to a remote site.	Use a \$\$DIRECTORY input to verify the identification of the batch. Note: Batches flagged T (transmitted) do not transmit again if you are requesting all batches for a mailbox ID.
*** NOTE *** NO BATCHES FOR TRANSMISSION.	The host site has initiated a data transmission to your site through the Auto Connect feature. At the time of the Auto Connect, no batches are available for transmission to your remote site. This is normally not an error.	None.
*** ERROR *** SECURITY VIOLATION.	You attempted to access batches without following security procedures. These procedures are unique for your installation and are activated by a user security exit.	Contact host site personnel if you cannot correct the problem by changing your batch identifiers.
*** ERROR ***SELECTED BATCH ON DEALLOCATED FILE.	The selected batch is not accessible because it is located on an offline VSAM batch queue.	Contact host site personnel to have the VSAM batch queue allocated and retry your request.
*** ERROR *** SNA BATCH CANNOT BE CONVERTED TO BSC.	You attempted to request transmission of a batch which originated at an SNA remote site. The batch contains SNA control characters and cannot be converted and sent to your BSC remote site. The batch is accessible only to host site personnel or to SNA remote sites.	Verify batch selection. If correct, contact host site personnel.
*** ERROR ***SYSTEM I/O LIMIT REACHED TRY AGAIN LATER.	Host system activity is too high to satisfy this request.	Try your request later.

Message	Description	Action
*** ERROR *** TRANSMIT FAILED. INCORRECT \$\$LOGOFF OPERAND.	You typed a \$\$LOGOFF command, but failed to supply the appropriate RMT or APPLID parameters. The \$\$LOGOFF is ignored.	Supply the appropriate \$\$LOGOFF format and retype the request.
*** ERROR *** TRANSMIT FAILED. ID VALIDATION FAILED FOR ID=XXXXXXXX.	The Connect:Enterprise system is installed at the host site with the batch security option. The ID you used is incorrect, and your request is rejected.	Correct the ID used if it is spelled incorrectly, or contact host site personnel to obtain a valid ID.
*** ERROR *** TRANSMIT FAILED. NO BATCHES FOR TRANSMISSION.	You have requested a data transmission with the \$\$REQUEST function, but the batch requested either does not exist or is not available for a data transmission to a remote site.	Use a \$\$DIRECTORY to verify the identification of the batch and to determine if it is transmittable.
*** NOTE *** TRANSMIT FAILED. NO BATCHES FOR TRANSMISSION DURING Connect:Enterprise AUTO CONNECT.	The host site initiated a connection to your remote site through the Connect:Enterprise Auto Connect feature. At this time, no batches are ready for transmission to your remote site. This may not be an error. No batches are sent to you, but you may now have the opportunity to send data to the host site.	None.
*** ERROR *** TRANSMIT FAILED. INVALID PASSWORD FOR FULL DIRECTORY REQUEST.	You attempted a \$\$DIRECTORY request without supplying an ID, and did not supply the appropriate system password.	Retype the \$\$DIRECTORY with the appropriate password, or attempt a \$\$DIRECTORY for a single mailbox ID only.
*** ERROR *** TRANSMIT FAILED. SECURITY VIOLATION.	You attempted to access host data without following security procedures. These procedures are unique for your installation and are activated by a user security exit.	Contact host site personnel if you cannot correct the problem.

Message	Description	Action
*** ERROR *** TRANSMIT FAILED. YOUR REMOTE SENT NEGATIVE RESPONSE TO TRANSMIT.	Connect:Enterprise attempted a data transmission to your remote site, but your remote site rejected it by sending a negative response. This can occur for many reasons. For example, your remote site may want to send data to the host at this time and not receive it. Or, Connect:Enterprise has directed the batch to a certain media that is currently not ready and available for use. Connect:Enterprise handles the negative response, and you can retry the failed transmission later if appropriate. Ensure the appropriate output media device is assigned and ready for use.	If you cannot determine why your remote site is rejecting a transmission with a negative response, contact host site personnel. Connect:Enterprise records the transaction that failed and the reason for failure. It may be possible to recreate the problem and have host site personnel explain the negative response.
*** ERROR *** TRANSMIT FAILED. DATA CANNOT BE FORMATTED FOR YOUR REMOTE.	The batch you have requested cannot be sent to your remote site due to a data formatting problem. This can occur when attempting to transmit BSC originated data to an SNA remote site, or vice versa.	If you are unable to correct the problem, contact host site personnel.
*** ERROR *** TRANSMIT FAILED. RECORDS ARE TOO LARGE FOR YOUR BUFFER SIZE.	The batch you have requested cannot be sent to your remote site. One or more of the batch data records exceeds the buffer size for your remote.	Contact remote site personnel if the problem persists and you require access to the batch. They may need to assign a larger buffer to your remote site.
*** ERROR *** TRANSMIT FAILED. SELECTED BATCH REQUIRES A STERLING CONNECT REMOTE DEFINITION.	The batch you have requested requires a Sterling Connect remote definition to transmit correctly. Your current remote definition is not defined as such.	Make the appropriate changes to support Sterling Connect remotes and retry the \$\$REQUEST or refrain from selecting this batch.

A

ACQUEUE

Specifies the disposition of an Auto Connect session that is unable to be initiated because there is no BSC line, SNA session, or FTP thread available or the Auto Connect session is currently active. When the parameter ACQUEUE=YES is specified, the Auto Connect session is queued and initiation is attempted at a later time. Otherwise, the Auto Connect session is terminated with an error condition.

ADD Utility

A set of instructions used to submit the Connect:Enterprise ADD utility. The ADD utility is used to add batches to the VSAM batch files for access by the remote sites.

APPL (Application)

See *VTAM Application Program*.

Application Agent

A Connect:Enterprise interface that allows the customization of Connect:Enterprise execution. Each application agent is driven by a user-defined set of rules. The rules can display system console messages, issue system console commands, execute programs, and submit jobs. Connect:Enterprise supports the following application agents: Console, End Of Batch, Logging, Scheduler, and Wake Up Terminate.

Auto Connect

A Connect:Enterprise feature that allows host-initiated data communications to one or more remote sites. The host and remote sites may be connected using SNA, FTP, bisync manual dial, auto dial, or nonswitched lines. The Auto Connect session may be fully automated by time of day, or controlled with the \$\$CONNECT console command. Full reporting of Auto Connect activity is available.

Auto Dial

Refers to the capability of the host computer to automatically dial the remote site to establish a connection on a switched line. The Auto Dial feature is usually generated for the Transmission Control Unit or front-end processor of the host site on a line-by-line basis.

B

Batch

A set of related data collected by or added to Connect:Enterprise and maintained on the VSAM Batch Files at the host.

Batch Number

A unique 7-digit number assigned internally by Connect:Enterprise to each individual batch on the VSAM Batch Files. The number may be obtained by the \$\$DIRECTORY function or the offline utilities LIST function.

Batch Queue

See *VBQ (VSAM Batch Queue)*.

Batch Security

Optional Connect:Enterprise method of providing security for remote site access to the system. Mailbox IDs are assigned to remote sites and defined as valid at the host site. If Batch Security is used, remote sites must supply a valid ID as part of the \$\$ commands that access the Connect:Enterprise data files. (Formerly called ID Validation.)

Batch Status

A set of flags maintained for each batch on the VSAM Batch Files. The Batch Status flags are displayed in the LIST offline utility report or the \$\$DIRECTORY output data. Some of the Batch Status indicators are incomplete batch, deleted batch, batch transmitted to remote site, and batch extracted at the host site.

Batch Type

Used to indicate which batches to recall from Connect:Enterprise. Types include batches containing data received from remote sites and batches containing data to be transmitted.

Blank Compression

A method of replacing strings of contiguous blanks with control characters indicating the number of blanks removed. Commonly used to shorten the amount of data sent over telecommunications lines. Connect:Enterprise uses standard 3780 blank compression techniques on BSC lines and standard SNA blank and character compression on SNA sessions.

Blank Truncation

A method of dropping trailing blanks from the end of fixed length data records before sending the data over telecommunications lines. Used by Connect:Enterprise as an option to shorten the amount of data sent over telecommunications lines.

BSC (Binary Synchronous)

A standard telecommunications line protocol used to transmit blocks of data over telecommunications lines between host computers and remote sites. Binary Synchronous (also known as bisync) allows a faster transmission rate than a start/stop protocol, because its ratio of data bits to checking bits is higher. This line protocol is used by Connect:Enterprise.

BTAM (Basic Telecommunications Access Method)

A standard IBM access method used by Connect:Enterprise to read and write data over telecommunications lines to a variety of terminals and devices.

BTAM ID Verification

An optional BTAM feature that enables the exchange and verification of host site and remote site IDs. Available on switched lines only, the feature provides added security in a Connect:Enterprise system. Both the host site and the remote site must be capable of implementing the option. Connect:Enterprise allows the host site ID to be sent, the remote site ID to be received, or both IDs to be exchanged.

C**Clear Control Channel (CCC)**

A command that enables Connect:Enterprise to negotiate a clear-text control channel after the user ID and password have been transmitted in encrypted format. The control channel remains in clear-text until the connection ends. All data and objects transferred between the client and server remain encrypted. Both ends of the connection must support the use of this command.

Compression

See *Blank Compression*.

Connection ID

The CICS definition that describes the remote system in terms of Netname (APPLID). The connection ID is a local name (within the local CICS only) that is used to define the remote partner system (Connect:Enterprise).

Cross System Client Utility (CSCU)

A Connect:Enterprise utility that enables you to use a subset of the offline utilities to access the VSAM batch and log files from a remote logical partitioning (LPAR), unlike offline utilities which must run from the same LPAR as the Connect:Enterprise VSAM File Server. CSCU control and output is similar to the offline utilities.

D**Data Collection**

The process in which Connect:Enterprise collects data from remote sites and stores it in the VSAM Batch Files. Data Collection means data is input from a remote site to Connect:Enterprise at the host computer.

Data Repository

The component that transmits and collects data from BSC, FTP, and SNA sites. The repository handles all session activity and accepts service requests from the console, the user API, the ISPF interface, the CICS interface, and the Connect:Enterprise FTP server.

Data Transmission

The process in which Connect:Enterprise transmits data from the VSAM Batch Files to remote sites. Data transmission means data is output from Connect:Enterprise at the host computer to the remote site.

Directory

A formatted listing of control information for batches on the Connect:Enterprise VSAM Batch Files. It is obtained from the `$$DIRECTORY` command.

Disconnect Interval

The number of seconds a session may be inactive before forcing session termination. This may differ for each remote site defined to Connect:Enterprise. This safety feature, which is implemented using the `DISCINTV` parameter, is used to reduce the use of resources by remote sites that have no current activity and to prevent an Auto Connect session from suspending if a remote site does not respond.

EXTRACT Utility Model

A set of JCL statements and parameter (specification) data submitted by Connect:Enterprise CICS or ISPF interface to initiate execution of the Connect:Enterprise EXTRACT utility. The EXTRACT utility is used to retrieve batches from VSAM batch files to a sequential output file.

F

FMH (Function Management Header)

A standard SNA feature that allows a data stream to be sent to a specific destination and controls the way the data is presented at the destination. Connect:Enterprise supports FMH Type 1, a 6-character field sent at the start and the end of a data stream. This FMH selects the media used for the data, marks the beginning and end of a Connect:Enterprise batch, and further describes the format of the data.

FTP (File Transfer Protocol)

An international standard for reading and writing files across a TCP/IP network.

FTP Server

The capability of Connect:Enterprise to function as an FTP server. This enables remote FTP client sites to access, retrieve, and send data to the Connect:Enterprise batch queues through standard FTP commands.

G

GSKKYMAN

An IBM utility that is used to create and maintain the SSL key database.

H

Host

The main processing computer where Connect:Enterprise is running and where you send your data batches. Also referred to as the host site or host computer.

I

IRS (Inter-Record Separator)

A special character used to separate multiple records in a block of data being transmitted over a telecommunications line. Connect:Enterprise allows either X'1E' or X'1F' as the inter-record separator on BSC lines, and allows only X'1E' for SNA sessions. Also referred to as an IRS.

J

Job Entry Subsystem (JES)

A system facility for spooling, job queuing, and managing job-related data.

L

Leased Line

Refers to telecommunications lines on which connection is not established through a switched network. Connect:Enterprise Leased Line support is point-to-point and therefore allows data to be exchanged only between the host site and a single remote site. Leased Multipoint lines are not supported by BSC connections in Connect:Enterprise.

Line ID

Uniquely identifies a BSC line that is accessed during Auto and Remote Connects. This is a BSC-only entry generated by a nonswitched M\$LINE or M\$LINEX macro in the User Assembly.

List Name

The Auto Connect List Name defined in the Connect:Enterprise ODF.

Log Facility

A Connect:Enterprise feature that provides file logging and full reporting for remote-initiated transactions. An additional option provides host system console log messages both for host-initiated and for remote-initiated connections and disconnections.

LOGOFF

The process of ending a remote site session with a host site program such as Connect:Enterprise. A LOGOFF may be a text command or a control function from a remote device.

LOGON

The process of establishing a session between a remote site and a host site program such as Connect:Enterprise. A LOGON may be automatic after a connection is established, or may be entered as a text command or a control function. In Connect:Enterprise, either the remote site or the host site may attempt to initiate the LOGON process.

Logon Mode Table

A table defined to VTAM containing a set of entries that provide session parameters, or the rules for controlling SNA communications. The LOGON that attempts to establish a session causes access to this table to obtain the session rules.

LOGON Security

An optional Connect:Enterprise/SNA method of providing security during a remote site's attempt to LOGON to Connect:Enterprise. The LUNAME (assigned to the remote site as part of the VTAM definition process) is provided to and validated by Connect:Enterprise when a LOGON is attempted.

LU (Logical Unit)

A logical unit provides the port for user access to an SNA network. Each remote device that can establish a session with Connect:Enterprise is a logical unit.

LU1RJE (LU Type 1 RJE)

A device emulating 3770, or a similar device or software package that uses Logical Unit Type 1 protocols and is used primarily for data transfer or RJE (Remote Job Entry) purposes. The devices typically have multiple I/O devices, such as printers, card readers, and storage devices. An operator console for messages or interactive use is often present.

M

Mailbox ID

The 1–8 character ID which defines batches in the VSAM Batch Files.

Mailbox Name

The 8-character symbolic name used to identify individual Connect:Enterprise systems to the user interface.

Mailbox Password

A security password used to control access to Connect:Enterprise systems.

Mailbox User ID

An 8-character field used to identify each user to Connect:Enterprise. In order for a user to access a Connect:Enterprise system, the User ID must be defined and assigned. The CICS and ISPF Interface panel displays the current user in the upper right corner.

Manual Dial

Refers to the method the host site uses to dial remote sites to establish a connection on a switched line. With Manual Dial, an operator at the host site must manually dial the telephone number of the remote site if the connection is initiated by the host site.

If the connection is initiated by the remote site, the manual dialing at the host is not used.

Media

An input/output device on a terminal, such as a printer, card reader, card punch, keyboard, display, or diskette. Commonly available on LU Type 1 RJE terminals, and supported by Connect:Enterprise/SNA.

MLU (Multiple Logical Unit)

A terminal designed to allow the operation of more than one session between a remote terminal and a host site such as Connect:Enterprise. A single terminal may actually appear as multiple devices, and may have concurrent inbound and outbound data streams active for each. Some 3770-type devices have this capability. Connect:Enterprise supports up to six MLU sessions per remote site.

N

NCP (Network Control Program)

The Network Control Program, generated by host site personnel, that controls the operations of a communications controller such as a 37x5.

Non-Switched Line

A telecommunications line on which connection is not established through a switched network. Sometimes referred to as a Leased Line.

NPSI (Network Control Program Packet Switching Interface)

An IBM licensed program that allows SNA users to communicate over packet switching data networks that have interfaces complying with CCITT Recommendation X.25. It allows SNA programs to communicate with SNA or non-SNA equipment over such networks.

O

(ODF) Options Definition File

A file containing Connect:Enterprise control records and keyword parameters that specify options in effect for the current execution of online Connect:Enterprise. The file contains options that control security, password, Auto Dial telephone numbers, SIGNON records, Auto Connect, SNA sites, and other system options.

Offline Utilities

The Connect:Enterprise utilities used to access and maintain the data batches on the VSAM Batch Files. The offline utilities allow you to LIST control information for batches, ADD batches, EXTRACT batches, DELETE batches, ERASE batches, alter batch status flags (STATFLG), MOVE batches from one VBQ to another, and REPORT on session activity.

P

Password

See *Mailbox Password*.

PLU (Primary Logical Unit)

In a particular session between two LUs, one LU adheres to a set of SNA-defined primary protocols and is known as the primary logical unit (PLU) for that session. The other LU adheres to a set of secondary protocols and is known as the secondary logical unit (SLU) for that session. More than one session can exist between two LUs. Multiple concurrent sessions between the same two LUs are referred to as parallel sessions. Not all LUs have parallel session capability.

Point-to-Point Line

A telecommunications line connection that allows data exchange between two points on the connection, usually the host site and a remote site. When a dialed connection is established on a switched network, the connection is considered point-to-point. Leased lines where the remote site is a single station are also considered point-to-point.

R

RDW (Record Descriptor Word)

A 4-byte field used to define the length of variable length records within a data file. For batch data coming into Connect:Enterprise (ADD), the RDW may be removed or retained. For batch data sent from Connect:Enterprise (REQUEST) the RDW may be created or not created.

Remote Name

A 1–8 character name assigned to identify a remote site that may be contacted by the host site during an Auto Connect session. Also used to identify every remote site that can establish a session with Connect:Enterprise.

Remote Site

Any terminal, computer, or software that can connect with Connect:Enterprise in the host computer.

REXX (Restructured Extended Executor) Language

A general-purpose, procedural language for scripting end-user programs designed for IBM systems.

RFC (Request for Comments)

One of a series, begun in 1969, of numbered Internet informational documents and standards widely followed by commercial software and freeware in the Internet and UNIX communities.

S

Session

A logical connection between Connect:Enterprise at the host site and another logical unit, such as a 3770 device. When a LOGON is completed between Connect:Enterprise and a remote site, they are said to be in session.

SIGNON

A special format data record sent by some remote BSC terminals designed to communicate with RJE software (such as JES or VSE POWER) in the host computer. The SIGNON record may be required by Connect:Enterprise provided Connect:Enterprise has been configured to do so when installed. The SIGNON format(s) used must also be specified at installation. A SIGNON is not required and not supported for SNA remote sites.

SLU (Secondary Logical Unit)

See *PLU (Primary Logical Unit)*.

SNA (Systems Network Architecture)

A set of rules, procedures, and structures for a communications network.

Socket Number

A two way connection identified by the unique combination of IP addresses and port numbers in a given connection. For example, the following combination illustrates the unique ID representing a complete socket: Client IPAddress/Port Number - Server IPAddress/Port Number.

SPLITCOUNT

Specifies a 1–4 digit numeric count of records to be contained in an added batch, allowing you to split a large sequential input file into several smaller batches with the same batch identifiers. Sequential input records are read and added to the output batch until the SPLITCOUNT limit is reached. Connect:Enterprise then closes out the batch and begins a new batch with the same identifiers.

SSL (Secure Sockets Layer)

A protocol for transmitting private documents over the Internet. SSL uses a private key to encrypt data that is transferred over the SSL connection.

Status Codes

The status flag indicators for a batch. Codes include the following: D, deleted; T, transmitted; R, Requestable; E, Extracted; M, Multxmit (for a list of these codes, see information on VSAM Batch Status Flags in the *Connect:Enterprise for z/OS User's Guide*).

Switched Line

A telecommunications line on which connection is established over a switched (dialup) telephone line.

T

TLS (Transport Layer Security)

A protocol based on SSL 3.0 protocol specification and designed to provide privacy and data integrity between two communicating applications.

TRACE

In Connect:Enterprise, the capability to create a snapshot dump of internal Connect:Enterprise control information for communications activity, User Exit calls, or VSAM Batch Files access.

Transparency

A method of transmitting data over a telecommunications line wherein special line control characters embedded in the data are transparent and do not function in their normal capacity as line control characters. Transparency is used when non-text data (such as object modules or other binary data) must be sent over telecommunications lines. Connect:Enterprise supports both BSC transparency and SNA transparency.

Truncation

See *Blank Truncation*.

\$TURNLINE\$

An optional feature in Connect:Enterprise that provides for a limited conversational mode transmission. When a \$TURNLINE\$ record is encountered in data being sent to a remote site, the sender temporarily

stops sending and issues the proper BSC protocol to turn around the line and begin receiving. After all data is received, sending resumes with the record following \$TURNLINE\$.

U

User

See *Mailbox User ID*.

User Assembly

A series of macros used to define a network of BSC lines to be used by Connect:Enterprise. The macros are generated by each user to define their requirements and input to the Assembler to create a module for use by Connect:Enterprise BSC connections. A User Assembly is not required by SNA connections.

User Batch ID

A 1–64 character free-form batch identifier used to describe the contents of a batch of data on the Connect:Enterprise VSAM Batch Files.

User Exits

A user-written program called by online Connect:Enterprise, offline utilities, and the CICS interface at appropriate times during the processing of a transaction. The user-supplied program can thereby alter the standard processing done by Connect:Enterprise. User Exits may be supplied to examine all input data from a remote site, to examine output data to a remote site, to provide unique security processing, or to examine and alter data in Connect:Enterprise \$\$ commands. No alteration of data is possible by a user exit in the offline utilities and the CICS interface processing.

USS Table

A table defined to VTAM that provides conversion of character-coded LOGON or LOGOFF to field-formatted LOGON or LOGOFF. You may need to provide this table to VTAM to allow a remote site to establish and terminate SNA sessions with Connect:Enterprise.

V

VBQ (VSAM Batch Queue)

The Connect:Enterprise data set used for storing batches of data collected from remote sites during online Connect:Enterprise. These batches may be available for transmission to remote sites, and are always available for extraction at the host site. The VSAM Batch Queue may be defined as a single VSAM cluster or up to 20 VSAM clusters that are processed as a single repository for batch data. The VSAM Batch Queue contains multiple individual batches of data which can be accessed by their Mailbox ID.

VBQ Blocking

A Connect:Enterprise feature that blocks multiple records or collection buffers into a single VBQ record for transmission. This improves transmission performance by reducing the disk I/O overhead.

VCF (VSAM Control File)

The Connect:Enterprise data set that contains control information for batches stored on the VSAM Batch Queue.

VLF (VSAM Log File)

The Connect:Enterprise data set that contains logged information on the progress of a Connect:Enterprise execution.

VPF (VSAM Pointer File)

The Connect:Enterprise data set that contains control information for every file defined in the Connect:Enterprise system and locator information for every existing batch.

VSAM (Virtual Storage Access Method)

A standard IBM access method for creating and maintaining data sets at the host. Used by Connect:Enterprise for the VSAM Batch Files.

VSAM Batch Files

A term used for the group of up to 24 files used by the Connect:Enterprise system for storing and maintaining data. The VSAM Batch Files consist of the VSAM Control File, the VSAM Pointer File, the VSAM Batch Queue Files (up to 20), and the VSAM Log Files (up to 2).

VTAM (Virtual Telecommunications Access Method)

An SNA access method used by Connect:Enterprise to receive and send data to a variety of SNA devices or application programs.

VTAM Application Program

A program, such as Connect:Enterprise, that is defined to VTAM and can establish sessions with SNA devices or other VTAM application programs.

X

Xmit once

Specifies that the batch cannot be extracted and that it can be transmitted only one time. After a successful transmit, the batch is permanently locked.

Symbols

\$\$ADD
example 64
header record 64

\$\$ADD command
defaults 74
example 52
header record 52
initiating 74
multiple batches 75
operands 75
syntax
 BSC 75
 FTP 48
 SNA 75

\$\$DELETE, example 64

\$\$DELETE command
definition 71
example 52
operands 76
syntax
 BSC 76
 SNA 76

\$\$DIRECTORY command
definition 71
operands 77
output 77
syntax
 BSC 77
 SNA 77

\$\$LOGOFF command
definition 71
SNA 80

\$\$REQUEST, example 64

\$\$REQUEST command
definition 71
example 52
operands 81

\$\$REQUEST command (continued)
syntax
 BSC 81
 SNA 81
using 81

\$TURNLINES 67

A

ADD
utility, VSAM status flags 29

auto connect
configuration 51, 64
definition 51, 64

B

blocked data records 67

BSC
\$TURNLINES\$ 67
blank compression 66
blank truncation 66
blocked data records 67
options 66
record separator override 67
RJE, communication 63
SIGNON, implementation 66
temporary text delay 68
transparency 67
WAIT Acknowledgement (WACK) 68

C

CCC, see Clear Control Channel

Clear Control Channel 13

command conventions, FTP 16

Commands
 \$\$ADD
 defaults 74
 initiating 74
 multiple batches 75

Commands (continued)

\$\$ADD
 operands 75
 syntax
 BSC 75
 FTP 48
 SNA 75
\$\$DELETE
 operands 76
 syntax
 BSC 76
 SNA 76
\$\$DIRECTORY
 operands 77
 output 77
 syntax
 BSC 77
 SNA 77
\$\$LOGOFF, SNA 80
\$\$REQUEST
 operands 81
 SNA 80
 syntax
 BSC 81
 SNA 81
 using 81
 logoff 80
 remote site 71
 standard FTP syntax
 del 36
 dir 37
 get 38
 mput 41, 42
 pwd 43
 recv 38
 submitting 71
 configuration 51, 64
 console display
 implementing 55
 messages 55
 procedures 55

D

data compression 55
 Data streams 57, 68
 Definition
 \$\$DELETE 71
 \$\$DIRECTORY 71
 \$\$LOGOFF 71

Definition (continued)

\$\$REQUEST 71
BSC
 \$TURNLINES 67
 record separator override 67
 temporary text delay 68
 WAIT Acknowledgement (WACK) 68

del
 standard FTP syntax, instructions 36
 device media, procedures 55
dir
 standard FTP syntax, instructions 37
 disconnect interval, definition 56

E

EBCDIC 57
EXTRACT
 utility, VSAM status flags 29

F

firewall navigation 13
FMH
 batch separation 56
 insertion 56
 procedures 56
 terminal control 56
 free-form BSC SIGNON 66
FTP
 data structure 10
 data type 8
 delimiting records with \$\$ commands 46
 processing \$\$ADD commands 45
 scanning for \$\$ADD commands 45
 transfer mode 11
 user batch ID syntax and formats 11
FTP Commands 15
 standard FTP syntax
 del 36
 dir 37
 get 38
 mput 41, 42
 pwd 43
 recv 38
FTP SITE command, parameters 19

G

get
 standard FTP syntax
 examples 39
 format 39
 instructions 38

H

host
 initiated communication, definition 51
 site 51
 host initiated communication, definition 64
 host site 64

I

IRS (inter-record separator) 67

L

log on, FTP 14
 Logoff
 command 80
 SNA 80
 syntax 80
 Logon
 requirements 79
 SNA 79

M

media, device support 54
 MLU, see Multiple Logical Unit
 mput, instructions 41, 42
 Multiple Logical Unit (MLU) 54

P

pwd, instructions 43

R

Record separator override, BSC 67
 record separator override, blocked data records 67

recv
 standard FTP syntax
 examples 39
 instructions 38
 Remote site, commands 71
 Requirements
 BSC, \$TURNLINES\$ 67
 logon 79
 RJE communication 63
 RJE SIGNON 64

S

SNA
 logoff 80
 logon
 example of 79
 syntax 79
 procedures 56
 terminal options 54
 transparency 56
 starting and stopping sessions, procedures 51, 63

T

Terminal options, SNA 54
 transparency, SNA 56
 TTD (temporary text delay) 68

V

VSAM batch
 status flags, list of 29
 VTAM Log Mode Table 55

W

WAIT acknowledgement (WACK) 68

