

Trading Partner Management

Version 5.1



Trading Partner Management

Version 5.1

ore using this information	and the product it supp	ports, read the inform	ation in "Notices" of	n page 131.	

Copyright

This edition applies to Version 5 Release 1 of Sterling Integrator and to all subsequent releases and modifications until otherwise indicated in new editions.

© Copyright IBM Corporation 2000, 2012. US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Chapter 1. Introduction to Trading	Chapter 14. Check in a BPSS	
Partners 1	Use an XML Version for BPSS	
Chapter 2. Before You Create Trading		
Partner Profiles 3	Chapter 15. Import and Export a BPSS	31
Chapter 3. Basic Trading Partner Profile 5	Chapter 16. Check in a CPA	
	Use an XML Version of the CPA	
Chapter 4. Advanced Trading Partner	Ose the lext Editor	. 33
Profile	Chapter 17. Create a BPSS Extension	35
Identity Record	onaptor irr oreate a 21 co Extension	
Transport Record	Chapter 18. About ebXML	37
Document Exchange Record 8	Edit ebXMLMessaging.	
Delivery Channel Record 8	Edit ebXMLInbound	. 37
Packaging Record	Earl Contribution	. 0,
Tiome Record	Chapter 19. ebXML CPA Lookup	39
Chapter 5. Import and Export Trading		
Partner Data 9	Chapter 20. Create a Basic Trading	
Resource Manager	Partner Profile using AFT	43
Basic Import Utility		
ı	Chapter 21. Create a Basic Trading	
Chapter 6. Contracts	Partner Profile using FTP	45
Before You Create a Contract		
	Chapter 22. Create a Basic Trading	
Chapter 7. Code Lists 15	Partner Profile using HTTP	47
Chapter 8. Introduction to B2B		
Services	Chapter 23. Create a Basic Trading	
B2B Service Example	Partner Profile using SMTP	49
bzb Service Example		
Chapter 9. B2B Lookup Service 19	Chapter 24. Create an Advanced	
How the B2B Lookup Service Works	Trading Partner Profile	51
Tion the BZB Edokap Service Works		
Chapter 10. B2B Send Service 21	Chapter 25. Create an Identity Record	53
How the B2B Send Service Works		
Use the B2B Send Service	Chapter 26. Create a Document	
	Exchange Record	55
Chapter 11. B2B Respond Service 23		
How the B2B Respond Service Works	Chapter 27. Create a Transport Record	
Use the B2B Respond Service	Specify FTP Settings	
	Specify HTTP Settings	
Chapter 12. B2B Request-Response	Specify SMTP Settings	. 65
Service	Chantar 29 Create a Dalivary Channel	
How the B2B Request-Response Service Works 25	Chapter 28. Create a Delivery Channel	60
Use the B2B Request-Response Service 25	Record	оэ
Chapter 13. Implementing Business	Chanter 20 Create a Backgaing Bacard	72
Process Specification Schemas (BPSS) 27	Chapter 29. Create a Packaging Record	13
Implement a BPSS and a CPA	Chapter 30. Create a Trading Partner	
impiement a Di 35 and a CiA	Profile Record	75
	FIUIIIC NECUIU	13

Advanced Trading Partner Record 77	Chapter 45. Delete Versions of a Code List
Chapter 32. Disable a Trading Partner Record	Chapter 46. Configure the Basic Customer Import File System Adapter . 111
Chapter 33. Delete a Trading Partner Record	Chapter 47. Import Trading Partner Data as a File Containing Envelopes and/or Control Numbers
Chapter 34. Create a Trading Partner Contract	Chapter 48. Import Trading Partner
Chapter 35. Update a Trading Partner	Data Through the Basic Import Utility . 115
Contract	Chapter 49. Import Trading Partner Data as a CSV File
Chapter 36. Delete a Trading Partner Contract	Chapter 50. Export Trading Partner
Chapter 37. Create a Code List 93	Data Using the Command Line 119
•	Chapter 51. Import Service GPM or
Chapter 38. Update a Code List 95	the Workflow Context
Chapter 39. Change the Default Version of a Code List 97	Chapter 52. Import Trading Partner using Basic Import Utility Process 123
Chapter 40. Search for a Code List 99	Chapter 53. CSV File Layout 125
Chapter 41. Enable a Code List 101	Chapter 54. Exit Codes 127
Chapter 42. Copy a Code List 103	Chapter 55. Test an HTTP Profile 129
Chapter 43. Create a Version of a Code List	Notices
Chapter 44. Delete a Code List 107	

Chapter 1. Introduction to Trading Partners

A *trading partner* is an organization that conducts e-business with other organizations. Sterling Integrator must have certain information about trading partners to automate the secure exchange of business documents with them. Sterling Integrator stores this information in a trading partner profile, which is known as a *trading profile*.

A trading profile:

- Links a trading partner with the business processes created to exchange business documents and transactions.
- Describes the role of a trading partner in those business processes as a producer of messages, consumer of messages, or both.
- Determines which documents are allowed into and out of Sterling Integrator.

Sterling Integrator offers three ways to create trading partner profiles:

- Basic Provides shorter input method that requires less information to get started
- Advanced Provides separate records for profile, identity, document exchange, transport method, delivery method, and packaging
- AS2 Provides records specific to AS2 trading partners

Using Trading Partners

To successfully conduct e-business using Sterling Integrator, you must:

- Enter your organizations trading partner information.
- Set up or import trading partner profiles.
- Decide what security methods (for example, digital certificates) you and your trading partners will employ.
- Define contracts for your trading partners.

Chapter 2. Before You Create Trading Partner Profiles

Gather this required information and complete these actions prior to creating your trading partner profiles.

Note: If you are exchanging EDI documents using a value-added network (VAN), you may not need to set up trading profiles. When using a VAN, you may need only to create document envelopes, which sufficiently completes the information requirements that Sterling Integrator needs to exchange the EDI documents.

- Determine if you and your trading partner are going to use digital certificates for secure data transport. If so, create and check in those certificates.
- Decide if you are going to enter the trading partner using a basic profile or an advanced profile.
- Collect this information about yourself and your trading partner:
 - Name
 - Identifier Unique string that identifies this trading partner
 - Address Conventional street address, city, and zip or postal code
 - Sending and receiving protocols and settings FTP, SMTP, HTTP, or File Transfer
 - IP addresses and port numbers
 - Enveloping properties
 - Passwords
- Ensure that necessary servers and adapters are installed and configured.

Chapter 3. Basic Trading Partner Profile

Some businesses require a simplified method for entering trading partner data quickly.

The basic trading partner profile option enables you to:

- Provide contact information about your trading partner
- Set up communication properties to exchange documents with your trading partners

When a basic profile is created, these records are created automatically and assigned default record names:

Record Type	Record Function
Transport	Describes the document delivery protocol
Document Exchange	Describes properties of documents and messages between trading partners
Delivery Channel	Links a document exchange record and a transport record
Packaging	Describes the organization of a document and its contents
Profile	Links a delivery channel record and a packaging record to a business process

Chapter 4. Advanced Trading Partner Profile

Sterling Integrator offers an advanced trading profile set up option, which includes separate records for each of the following:

- Identity
- Transport
- Document exchange
- · Delivery channel
- Packaging
- Profile

"Identity Record"

"Transport Record" on page 8

"Document Exchange Record" on page 8

"Delivery Channel Record" on page 8

"Packaging Record" on page 8

"Profile Record" on page 8

Identity Record

Every trading partner is represented by at least one record, called an identity. An *identity record* describes the trading partner and contains information referenced when a business process involving the trading partner is run. A trading partner can have more than one identity to represent the different ways it does business. For example, a company's central office procurement organization might be radically different from its manufacturing supplies procurement organization. In such cases, you need a separate identity record for each organization.

A base identity is a regular identity that you can use as a starting point to create a new identity. The base identity maintains a link to the identity that inherited its properties. If you modify the base identity, all related identities (that is, ones that inherited the base identity properties) change, as well. When you create an identity record using a base identity, everything in the new identity is the same as in the base identity, except the identity name, description, and other unique parameters, such as unique identification numbers.

Note: If you plan to create many identities using the base identity, do not use the base identity in production. You should record the identities that are related to the base identity.

You must create an identity before you can create a transport, document exchange, delivery channel, packaging, profile, and (when required) a contract. Each of these components references an identity.

Transport Record

The *transport record* describes the document delivery protocol. It identifies the protocol, such as HTTP, FTP, or SMTP. In addition, the transport record provides details about the use of the protocol, such as HTTP configured with SSL for secure data exchange. Each identity can have more than one transport record. When an identity has more than one transport record, you must create corresponding profile records.

Parent topic: Chapter 4, "Advanced Trading Partner Profile," on page 7

Document Exchange Record

A *document exchange record* describes the properties of the documents and messages passed between trading partners. These properties include the messaging services and message envelopes selected by a trading partner. For example, digital enveloping properties include the trading partner digital signature and encryption required when using the SMIME protocol. To describe properties of the documents and messages passed between trading partners, you must create a document exchange record.

Parent topic: Chapter 4, "Advanced Trading Partner Profile," on page 7

Delivery Channel Record

A *delivery channel record* links a document exchange record and a transport record. The combination of these two records provides a complete description of how a trading partner expects to receive documents. A delivery channel record eliminates re-entry of document exchange information for every transport protocol. **Parent topic:** Chapter 4, "Advanced Trading Partner Profile," on page 7

Packaging Record

A *packaging rec*ord describes the organization of a document and its contents, including a message:

- Header or envelope that contains identifying metadata
- Body or payload that contains the business content

A packaging record can be shared among trading partners. In addition, a packaging record provides details about protocol-specific security, as well as envelope fields like a MIME content type or an XML namespace.

Parent topic: Chapter 4, "Advanced Trading Partner Profile," on page 7

Profile Record

A *profile rec*ord is a type of document exchange record that links a delivery channel record and a packaging record to a business process. A profile links a delivery channel and packaging records of a trading partner to a business process. **Parent topic:** Chapter 4, "Advanced Trading Partner Profile," on page 7

Chapter 5. Import and Export Trading Partner Data

Sterling Integrator provides several utilities to help you:

- · Convert and import trading partner data.
- Import a file containing document envelopes or control numbers (or both) from the command line.
- Import document envelopes without control numbers so you can keep your test
 and production systems synchronized. The document envelopes are imported
 but the sequential control numbers from the production system (the system to
 which the envelope is being imported) are used.
- Export trading partner data

Sterling Integrator uses two types of control numbers: *local*, in which the control number is contained in the partner envelope, and *global*, which references a control number outside of the envelope (a control number that many envelopes can reference).

You can import trading partner data into Sterling Integrator by using any of the following:

- Resource Manager (Administration Menu > Deployment > Resource Manager)
- Basic Import Utility (Command Line)

You can export trading partner data using a command line script. This is the preferred method when exporting large amounts of data, as it exports the data directly to the file system instead of saving the output file in memory.

"Resource Manager"

"Basic Import Utility" on page 10

Resource Manager

The Import/Export feature supports many different resource types, including trading partner data. When you use the Resource Manager to export an envelope that uses a **global control number**, the export file uses the global control number and you need to have configured a global control number on the import system.

When you import a file that contains envelopes or control numbers (or both), the Import option converts an XML file or installable bundle to Sterling Integrator resources format.

Depending on the type of export you used (standard or advanced, default or all versions), the Import option performs the following functions:

- Creates and checks in new versioned envelopes (assigns time/date of the import)
- Updates or preserves existing non-versioned envelopes
- Preserves or appends existing checked-in envelopes

Note: To prevent the loss or corruption of existing records, preserve and download the backup file of all imports that you conduct.

The standard import:

- · Appends to existing versioned resources
- Sets the default according to imported records

Some important general information about importing resources:

- You must manually update imported resources that contain hard-coded, computer-specific information. For example, system paths in scripts must be manually changed to use the new path after importing resources to their new location.
- During import, Sterling Integrator creates a backup file containing records as they existed prior to import. After you import the resources, you can download and preserve the backup file, which is named backup.xml by default. You can change the name of the backup file so that you do not overwrite an existing backup file.

The import process creates a new record where none exists. If you are importing envelopes to an environment that already contains the same envelopes, you have the option to update the existing envelope or to preserve the existing envelope. **Parent topic:** Chapter 5, "Import and Export Trading Partner Data," on page 9

Basic Import Utility

You can use the Basic Import Utility to quickly and easily create new trading partner identities, by importing the trading partner data into Sterling Integrator.

This tool enables you to import a CSV file containing trading partner identity information from the command line. The utility converts the CSV file to XML and imports the file, and then provides the status when it has completed or when a time-out has occurred (whichever comes first).

You will need to configure the Basic Customer Import File System adapter (BasicCustomerImport_FSA) to create the appropriate adapter configuration for use with the Basic Import utility. You must specify field settings in Sterling Integrator to set up how often and when the adapter checks the file collection folder for CSV files to translate to XML and import to Sterling Integrator. Before you import the CSV file, you should you should compare trading partner names between the CSV file and Sterling Integrator, to be sure you are not overwritten information you need.

Note: Using a text editor, you can view the BasicImport.rpt file, a report of the conversion from CSV to XML and status of importing the CSV file into Sterling Integrator located in the <code>install_dir/tp_import</code> directory.

As part of this functionality, Sterling Integrator also provides you with the following:

- The basicimport.sh utility (used for UNIX), located in the install_dir/tp_import directory
- The basicimport.cmd utility (used for Windows), located in the install_dir/tp_import directory
- A map (BasicCustomerImport.map)

Note: It is possible for you to change the BasicCustomerImport.map, but you are strongly cautioned not to change the right hand side of the map (the output side) that was generated from the schema. If you were to change a mandatory

- element to conditional, and then did not have the data present when you attempted to import the data, the import will fail.
- A translation object (BasicCustomerImport.txo) that is automatically checked in to Sterling Integrator
- An instance of the File System Adapter (BasicCustomerImport_FSA)
- A predefined business process (BasicCustomerImport.bp. This business process is used by Sterling Integrator to implement the Basic Import utility:

 BasicCustomerImport.bp. This predefined business process is initiated by the Basic Customer Import File System adapter during basic import utility processing and does not require you to modify it.
- A report of the conversion from CSV to XML and status of importing the CSV file into Sterling Integrator (BasicImportReport.rpt, in XML format), located in the install_dir/tp_import directory after the Basic Import utility is run
- The XML file containing the converted CSV file (basicimport.XML), located in the <code>install_dir/tp import</code> directory after the Basic Import utility is run
- A folder (*install_dir*/tp_import), where the files needed to use the Basic Import utility are located
- A subfolder (install_dir/tp_import/basic_customer_import_collect), where you
 can drop CSV files to be automatically picked up by the Basic Customer Import
 File System adapter

This table describes how Sterling Integrator supports the Basic Import Utility:


Functionality	Enhancements	Action You Need to Take to Implement the Basic Import Utility
Service	New Basic Customer Import Service File System Adapter added (BasicCustomerImport_FSA).	Configure BasicCustomerImport_FSA.
Predefined business processes	Predefined Basic Customer Import business process (BasicCustomerImport.bp) added.	None.
Map Editor	New map (BasicCustomerImport.map) and translation object (Basic CustomerImport.txo).	Modify the Basic Customer Import map to correspond to your CSV file layout or ensure that your CSV file layout corresponds to the necessary file layout.
Basic Import Utility	New utility to enable you to import CSV files (basicimport.sh for UNIX or basicimport.cmd for Windows).	Use the Basic Import Utility (basicimport.sh or basicimport.cmd) to import your CSV files into Sterling Integrator.
	 New report in XML format of the conversion from CSV to XML and status of importing the CSV file into Sterling Integrator (BasicImport.rpt). 	View the BasicImport.rpt file (in the install_dir/tp_import directory) using a text editor.

Parent topic: Chapter 5, "Import and Export Trading Partner Data," on page 9

Chapter 6. Contracts

A contract is an agreement between trading partners. It details how they will conduct business transactions. Contracts are useful when you want a customized process for a specific customer that does not apply to any of your other customers. Or perhaps you have a specific arrangement with a customer that is not the same as the arrangement you have with a second customer. A single trading partner can be associated with more than one contract.

The following figure shows a typical contract negotiation process between two trading partners:



If you use the Advanced Trading Partner options on the Admin Console to create a trading partner profile, you need to add a contract manually.

"Before You Create a Contract"

Before You Create a Contract

Before creating a contract, here are some items to consider:

- Create a trading profile for each trading partner or identity that will be participating.
- Determine business requirements and, if necessary, create a business process based on the requirements to associate with the contract.
- Determine if you are going to have a code list associated with the contract.
- If this trading partner uses RosettaNet, then the contracts require specific configurations. For information on creating a RosettaNet contract, see the Documentation Library.
- If this trading partner uses ST or UNH inbound envelopes, you cannot create a standard rule to perform a process data lookup during translation. To perform a process data lookup in a standard rule, specify the contract on the ST or UNH inbound envelopes, and then run a separate translation following the deenveloping process.

Parent topic: Chapter 6, "Contracts"

Chapter 7. Code Lists

Sterling Integrator uses code pairs in code lists to identify items in transactions between two or more trading partners. A trading partner *code list* consists of one or many pairs of code values containing a sender code and a receiver code. Each code pair has one description and up to four additional codes relating to the pair. Code lists are dynamic and are stored in a database.

From the Trading Partner menu, you can create, edit, copy, create versions, and enable and disable code lists. In the Map Editor when you use Select standard rule, you can change the content of a field using a code list. Sterling Integrator uses the code list name, sender identity, receiver identity, and either the sender code or the receiver code to determine the correct code list for a map to use, according to what the map is processing.

Note: Attempting to view a very large code list (over 100,000 entries) may fail with an Out of Memory error displayed. See *Performance and Tuning* for information on how to increase the memory allocated to Sterling Integrator.

If you have a code list for the same sender and receiver that has several different sets of code pairs, you can create a new version of the code list for each code pairs set. In addition, you can also create different versions of individual code pairs contained within a code list.

Chapter 8. Introduction to B2B Services

The B2B services simplify sophisticated decisions, run business subprocesses, and send documents to trading partners through the appropriate transport protocol. B2B services are preconfigured and installed as part of Sterling Integrator. Therefore, you do not need to configure these services to use them.

B2B services are dynamic services, independent of transport protocols or adapters, trading profiles, and contracts, that determine how to exchange data between trading partners. By using these services in a business process, you can eliminate the need to configure many of the details necessary to define this data exchange.

To communicate with trading partners, you must define a trading partner record and use at least one of the following B2B services in every business process (unless you are using the EDIINT Message service):

- B2B Lookup Service
- B2B Send Service
- B2B Respond Service
- B2B Request-Response Service "B2B Service Example"

B2B Service Example

You are a reseller for several suppliers who update their inventory levels periodically and a single customer who purchases items from you. When an inventory level is updated, you receive a notification from a supplier. When you receive the notification, you must request the new inventory listing from the supplier, merge it with your existing inventory report, and send it to your customer.

Assuming your supplier is the producer and you are the consumer in a contract, the steps in the business process for the example are:

- 1. Translate the notification of an inventory change to a request for an inventory change report.
- Use the B2B Request-Response service to request the inventory level report from the trading partner that sent the notification.
- Create a complete report for the customer using various services.
- 1. Send the report to the customer using the B2B Respond service.

For the sample business process, the following roles would perform the indicated tasks:

Role	Task
Business analyst	Define a business process that requests an inventory listing from a trading partner, format it properly and merge it with existing inventory reports, and send the resulting inventory to the customer.

Role	Task
System administrator	Configure the communications protocol adapters to start the business process correctly.
Trading partner administrator	Type all the trading profile information for the producers and consumers of the data. This information includes contracts between the producers and Sterling Integrator.

Parent topic: Chapter 8, "Introduction to B2B Services," on page 17

Chapter 9. B2B Lookup Service

The B2B Lookup service is a system service that is used by other services and business processes to retrieve trading partner contract records and profile information. The B2B Lookup service runs automatically when the B2B Send, B2B Respond or B2B Request-Response service, or the B2B_LOOKUP system business process is used. Therefore, for many of your business processes, you do not need to include the B2B Lookup Service.

Note: You must configure the trading profile and contract before the B2B Lookup service runs.

"How the B2B Lookup Service Works"

How the B2B Lookup Service Works

The B2B Lookup service uses two parameters defined within a business process:

- B2B Contract ID
- B2B Message Mode

The B2B Lookup service:

- 1. Retrieves the profile associated with the contract and message mode.

 Depending on the B2B Message Mode, the B2B Lookup service performs one of the following actions:
 - If the B2B Message Mode is Respond, the service uses the production (sending) profile of the contract.
 - If the B2B Message Mode is Send, the service uses the consumption (receiving) profile of the contract.
 - If the B2B Message Mode is Request-response, the service uses the production (sending) profile of the contract.
- 2. Retrieves the business process referenced in the transport record associated with the contract.

Parent topic: Chapter 9, "B2B Lookup Service"

Chapter 10. B2B Send Service

The B2B Send service sends messages to a consumption (receiving) trading partner using trading profile information in the contract.

Note: You must configure the trading profile and contract before using B2B Send service.

"How the B2B Send Service Works"

"Use the B2B Send Service"

How the B2B Send Service Works

When a business process includes the B2B Send service:

- 1. The service runs as part of the business process.
- 2. This service starts the B2B Lookup service.
- 3. The B2B Lookup service locates:
 - The consumption profile of the contract
 - The transport protocol of the consumption profile
 - The appropriate transport business process for the transport protocol of the profile, or the business process associated with the Send message mode in the consumption profile, if specified.
- 4. The B2B Lookup service either runs the default business process if none was specified in the profile, or runs the business process specified in the consumption profile for Send message mode.
- 5. The B2B Lookup service starts the appropriate communications adapter.
- 6. The communications adapter sends a message to the consumption profile transport server.

Parent topic: Chapter 10, "B2B Send Service"

Use the B2B Send Service

About this task

To use the B2B Send service:

Procedure

- 1. In your business process, precede the B2B Send service with the Assign service and configure it to assign the contract ID to b2b-contract-id or the contract name to b2b-contract-name.
- 2. Include the B2B Send service in the business process.

Results

After a business process is created that uses the B2B Send service, the same business process can be associated with any number of contracts to send messages to the consumption profile of the contract.

The B2B Lookup service looks up the trading partner transport information and uses the specified transport protocol, such as HTTP, SMTP, or FTP, to send the message.

Parent topic: Chapter 10, "B2B Send Service," on page 21

Chapter 11. B2B Respond Service

The B2B Respond service responds to messages from a production (sending) trading partner using trading profile information in the contract. Thus, after creating and executing a business process that includes the B2B Respond service, the business process responds to a message received from the trading partner by sending a message.

Note: You must configure the trading profile and contract before using this service.

"How the B2B Respond Service Works"

"Use the B2B Respond Service"

How the B2B Respond Service Works

The following is a description of how the B2B Respond service works:

- 1. The service runs as part of the business process.
- 2. The B2B Respond service starts the B2B Lookup service.
- 3. The B2B Lookup service locates:
 - The production profile of the contract
 - The transport protocol of the production profile
 - The appropriate transport business process for the transport protocol of the profile, or the business process associated with the Respond message mode in the production profile, if specified
- 4. The B2B Lookup service either runs the default business process if none was specified in the profile, or runs the business process specified in the production profile for Respond message mode.
- 5. The B2B Lookup service starts the appropriate communications adapter.
- 6. The communications adapter sends a message to the production transport server of the trading partner.

Parent topic: Chapter 11, "B2B Respond Service"

Use the B2B Respond Service

About this task

To use the B2B Respond service:

Procedure

- 1. In your business process, precede the B2B Respond service with the Assign service and configure it to assign the contract ID to b2b-contract-id or the contract name to b2b-contract-name.
- 2. Include the B2B Respond service in the business process.

Parent topic: Chapter 11, "B2B Respond Service"

Chapter 12. B2B Request-Response Service

The B2B Request-Response service uses the production (sending) profile of a contract to send a request to, and to retrieve a response from, the production trading partner.

"How the B2B Request-Response Service Works"

"Use the B2B Request-Response Service"

How the B2B Request-Response Service Works

When a business process includes the B2B Request-Response service:

- 1. The service runs as part of the business process.
- 2. The B2B Request-Response service starts the B2B Lookup service.
- 3. The B2B Lookup service locates:
 - The production profile of the contract
 - The transport protocol of the production profile
 - The appropriate transport business process for the profile's transport protocol, or the business process associated with the Request-Response message mode in the production profile, if specified
- 4. The B2B Lookup service either runs the default business process if none was specified in the profile, or runs the business process specified in the production profile for Request-Response message mode.
- 5. The B2B Lookup service starts the appropriate communications adapter.
- 6. The communications adapter sends a message to the transport server of the production profile.

Parent topic: Chapter 12, "B2B Request-Response Service"

Use the B2B Request-Response Service

About this task

To use the B2B Request-Response service:

Procedure

- 1. In your business process, precede the B2B Respond service with the Assign service and configure it to assign the contract ID to b2b-contract-id or the contract name to b2b-contract-name.
- 2. Include the B2B Request-Response service in the business process.

Parent topic: Chapter 12, "B2B Request-Response Service"

Chapter 13. Implementing Business Process Specification Schemas (BPSS)

Sterling Integrator enables you to implement an ebXML *Business Process Specification Schema* (BPSS), which provides a standard structure for defining a business process. The BPSS contains the specification of business activities within a business process, which enables Sterling Integrator to assemble the activities according to business agreements among trading partners.

The BPSS uses trading partner information and ebXML *Collaboration Protocol Agreement (CPA)* specifications to show the relationship among trading partners, a business process, and Sterling Integrator. Trading partner information and a CPA reference the BPSS and serve as configuration files for running business processes to exchange data with trading partners.

"Implement a BPSS and a CPA"

Implement a BPSS and a CPA

About this task

To implement a BPSS, you must complete the following steps in order:

Procedure

- 1. Create an XML version of the BPSS using the text editor in Sterling Integrator or any text editor.
- 2. Check the BPSS (.xml file) in.
- 3. Create an XML version of the CPA using the text editor in Sterling Integrator or any text editor.
- 4. Check in the CPA (.xml file) in.

Parent topic: Chapter 13, "Implementing Business Process Specification Schemas (BPSS)"

Chapter 14. Check in a BPSS

There are two ways to check in a BPSS:

- You can check in an XML version (.xml file) of a BPSS that you have previously created.
- You can use the text editor in Sterling Integrator to either type or copy XML to create an XML version of the BPSS and then check in the .xml file.

"Use an XML Version for BPSS"

"Use the Text Editor for BPSS"

Use an XML Version for BPSS

About this task

To check in an XML version (.xml file) of a BPSS that you have previously created:

Procedure

- 1. From the **Deployment** menu, select **EBXML > BPSS**.
- 2. Next to Check in new BPSS schema, click Go!
- 3. In the **Name** field, type the name located in the BPSS Process Specification element.
- 4. Under Select an input mode for defining the new BPSS schema, select Check-in BPSS Schema and click Next.
- 5. In the **BPSS** schema filename (.xml) field, type or click **Browse** to select the file name of the BPSS.
- 6. In the Check-in Comments field, type a comment that helps identify the BPSS.
- In the Encoding Type field, select the character encoding type for the BPSS and click Next.
- 8. Verify that **Enable for Business Processes** is selected and click **Finish** to check the BPSS in.

Parent topic: Chapter 14, "Check in a BPSS"

Use the Text Editor for BPSS

About this task

To use the text editor in Sterling Integrator to create and check in an XML version of a BPSS:

Procedure

- 1. From the **Deployment** menu, select **EBXML > BPSS**.
- 2. Next to Check in new BPSS schema, click Go!
- 3. In the **Name** field, type the name located in the BPSS Process Specification element.
- 4. Under Select an input mode for defining the new BPSS schema, select BPSS Schema Text Editor and click Next.
- 5. In the **Description** field, type a description that helps identify the BPSS.

- 6. In the BPSS Schema field, either type or copy and paste the XML code that makes up the BPSS, and click Next.
- 7. Verify that Enable for Business Processes is selected and click Finish to check the BPSS in.

Parent topic: Chapter 14, "Check in a BPSS," on page 29

Chapter 15. Import and Export a BPSS

About this task

To import or export a BPSS:

- 1. From the **Deployment** menu, select **Resource Manager** > **Import/Export**.
- 2. Depending on whether you want to import or export a BPSS, next to the appropriate heading, click **Go!**
- 3. Type a file name or click **Browse** to locate the file you want to import or export, then click **Next**.
- 4. The import/export process completes.

Chapter 16. Check in a CPA

After checking in a BPSS, you can check in a CPA. The process to check in a CPA is similar to the process to check in a BPSS.

There are two ways to check in the CPA:

- You can use an XML version (.xml file) of the CPA that you have previously created and check it in.
- You can use the text editor in Sterling Integrator to either type or copy XML to create an XML version of the CPA and check in the .xml file.

"Use an XML Version of the CPA"

"Use the Text Editor"

Use an XML Version of the CPA

About this task

To check in an XML version (.xml file) of the CPA that you have previously created:

Procedure

- 1. From the **Deployment** menu, select **EBXML > CPA**.
- 2. Next to Check in new CPA specification, click Go!
- 3. In the **Name** field, type a value defined as the cpaid attribute, under the CollaborationProtocolAgreement element of the CPA.
- 4. Under Select an input mode for defining the new CPA specification, select Check-in CPA Specification and click Next.
- 5. In the **CPA Specification filename (.xml)** field, type or click **Browse** to select the file name of the CPA.
- 6. In the **Check-in Comments** field, type a comment that helps identify the CPA.
- From the Encoding Type list, select the character encoding type for the CPA and click Next.
- **8**. Verify that **Enable for Business Processes** is selected and click **Finish** to check the CPA in.

Parent topic: Chapter 16, "Check in a CPA"

Use the Text Editor

About this task

To use the text editor in Sterling Integrator to either type or copy XML to create an XML version of the CPA and check in the .xml file:

- 1. From the **Deployment** menu, select **EBXML > CPA**.
- 2. Next to Check in new CPA specification, click Go!
- 3. In the **Name** field, type a value defined as the cpaid attribute, under the CollaborationProtocolAgreement element of the CPA.

- 4. Under Select an input mode for defining the new CPA specification, select CPA Specification Text Editor and click Next.
- 5. In the **Description** field, type a description that helps identify the CPA.
- 6. In the CPA Specification field, either type or copy and paste the XML code that makes up the CPA, and click Next.
- 7. Verify that Enable for Business Processes is selected and click Finish to check the CPA in.

Parent topic: Chapter 16, "Check in a CPA," on page 33

Chapter 17. Create a BPSS Extension

Before you begin

Create a BPSS extension to assign one or more business processes to the requesting or responding activities in the schemas.

About this task

To create a BPSS extension:

Procedure

- 1. From the Admin menu, select EBXML > BPSS Extension.
- 2. Next to Create new BPSS Extension, click Go!
- 3. Assign a BPSS Extension Name. Use the pull-down to select available values for the following fields:

Field	Description
CPA Id	Collaboration Protocol Agreement ID that has been checked in to Sterling Integrator. Required.
BPSS Name	BPSS specified (as ProcessSpecification) in the selected CPA. Required.
BPSS Version	Available version for the selected BPSS. Required.
BPSS Extension Name	Name for the new extension. Required.

- 4. Select a Binary Collaboration and an internal process for all requesting or responding activities. Click **Next**.
- 5. Verify your changes and click **Finish** to create the extension.

Results

You are now ready to check in a CPA for the BPSS.

Chapter 18. About ebXML

When implementing ebXML, consider that ebXML fails to retrieve dsig key cert from CPA because the XPath in the BPML is wrong and fails to test Ping/Pong.

To correct this, you must edit the following two business processes:

- · ebXMLMessaging
- ebXMLInbound

"Edit ebXMLMessaging"

"Edit ebXMLInbound"

Edit ebXMLMessaging

About this task

To edit ebXMLMessaging:

Procedure

- 1. Search for the text "signCertificateIdentifier." This text is the *to* attribute of the assign tag within the ebXMLDSig service.
- Edit the xpath of the 'from' attribute to "cpa/ tp:CollaborationProtocolAgreement/tp:PartyInfo[1]/tp:Certificate[@tp:certId/ text() = //ProcessData/cpa/tp:CollaborationProtocolAgreement/ tp:PartyInfo[1]/tp:DocExchange/tp:ebXMLSenderBinding/ tp:SenderNonRepudiation/tp:SigningCertificateRef/@tp:certId/text()]/ ds:KeyInfo/ds:KeyName/text()"

Parent topic: Chapter 18, "About ebXML"

Edit ebXMLInbound

About this task

To edit ebXMLInbound:

- 1. Search for the text "signCertificateIdentifier". This text is the 'to' attribute of the assign tag within the ebXMLDSig service.
- Edit the xpath of the 'from' attribute to "request/
 tp:CollaborationProtocolAgreement/tp:PartyInfo[1]/tp:Certificate[@tp:certId/
 text() = //ProcessData/request/tp:CollaborationProtocolAgreement/
 tp:PartyInfo[1]/tp:DocExchange/tp:ebXMLSenderBinding/
 tp:SenderNonRepudiation/tp:SigningCertificateRef/@tp:certId/text()]/
 ds:KeyInfo/ds:KeyName/text()"
- 3. To enable ebXML to test Ping/Pong, search for the text "isAcknowledgement"
- 4. Add two conditions into this rule:
 - a. "or IboundMIME/mime:message/mime:body/mime:message[1]/mime:body/SOAP-ENV:Envelope/SOAP-ENV:Header/eb:MessageHeader/eb:Action/text() = 'Ping'"

b. "or InboundMIME/mime:message/mime:body/mime:message[1]/mime:body/SOAP-ENV:Envelope/SOAP-ENV:Header/eb:MessageHeader/eb:Action/text() = 'StatusRequest'"

Parent topic: Chapter 18, "About ebXML," on page 37

Chapter 19. ebXML CPA Lookup

Before you begin

Because ebXML CPA Lookup does not output a unique service name, you must edit the ebCPALookup.xslt business process.

About this task

To edit ebCPALookup.xslt business process:

Procedure

```
1. Search for the text "tp:Service."
```

```
2. Replace the following paragraph: <xs1:choose>
   <xsl:when test="$action!=''">
   <tp:ServiceBinding>
   <xsl:copy-of elect="tp:CollaborationRole/tp:ServiceBinding/tp:Service"/>
   <xsl:if test="($flag='outgoing' and tp:PartyId/text() = $partyId) or</pre>
   ($flag='incoming' and tp:PartyId/text() != $partyId)">
   <xsl:copy-of select="tp:CollaborationRole/tp:ServiceBinding/</pre>
   tp:CanSend[tp:ThisPartyActionBinding/@tp:action=$action] |
   tp:CollaborationRole/tp:ServiceBinding/tp:CanReceive/
   tp:CanSend[tp:ThisPartyActionBinding/@tp:action=$action]"/>
   </xsl:if>
   <xsl:if test="($flag='outgoing' and tp:PartyId/text() != $partyId) or</pre>
   ($flag='incoming' and tp:PartyId/text() = $partyId)">
   <xsl:copy-of select="tp:CollaborationRole/tp:ServiceBinding/</pre>
   tp:CanReceive[tp:ThisPartyActionBinding/@tp:action=$action] |
   tp:CollaborationRole/tp:ServiceBinding/tp:CanSend/
   tp:CanReceive[tp:ThisPartyActionBinding/@tp:action=$action]"/>
   </tp:ServiceBinding>
   </xsl:when>
   <xsl:otherwise>
   <tp:ServiceBinding>
   <xsl:copy-of select="tp:CollaborationRole/tp:ServiceBinding/</pre>
   tp:Service"/>
   <xsl:if test="($flag='outgoing' and tp:PartyId/text() = $partyId) or</pre>
   ($flag='incoming' and tp:PartyId/text() != $partyId)">
   <xsl:copy-of select="tp:CollaborationRole/tp:ServiceBinding/</pre>
   tp:CanSend[tp:ThisPartyActionBinding/tp:ActionContext/
   @tp:binaryCollaboration=$binaryCollaboration and
   tp:ThisPartyActionBinding/tp:ActionContext/
   @tp:businessTransactionActivity=$businessTransactionActivity and
   tp:ThisPartyActionBinding/tp:ActionContext/
   @tp:requestOrResponseAction=$requestOrResponseAction] |
   tp:CollaborationRole/tp:ServiceBinding/tp:CanReceive/
```

tp:CanSend[tp:ThisPartyActionBinding/tp:ActionContext/

```
@tp:binaryCollaboration=$binaryCollaboration and
tp:ThisPartyActionBinding/tp:ActionContext/
@tp:businessTransactionActivity=$businessTransactionActivity and
tp:ThisPartyActionBinding/tp:ActionContext/
@tp:requestOrResponseAction=$requestOrResponseAction]"/>
</xsl:if>
<xsl:if test="($flag='outgoing' and tp:PartyId/text() != $partyId) or</pre>
($flag='incoming' and tp:PartyId/text() = $partyId)">
<xsl:copy-of select="tp:CollaborationRole/tp:ServiceBinding/</pre>
tp:CanReceive[tp:ThisPartyActionBinding/tp:ActionContext/
@tp:binaryCollaboration=$binaryCollaboration and
tp:ThisPartyActionBinding/tp:ActionContext/
@tp:businessTransactionActivity=$businessTransactionActivity and
tp:ThisPartyActionBinding/tp:ActionContext/
@tp:requestOrResponseAction=$requestOrResponseAction] |
tp:CollaborationRole/tp:ServiceBinding/tp:CanSend/
tp:CanReceive[tp:ThisPartyActionBinding/tp:ActionContext/
@tp:binaryCollaboration=$binaryCollaboration and
tp:ThisPartyActionBinding/tp:ActionContext/
@tp:businessTransactionActivity=$businessTransactionActivity and
tp:ThisPartyActionBinding/tp:ActionContext/
@tp:requestOrResponseAction=$requestOrResponseAction]"/>
</xsl:if>
</tp:ServiceBinding>
</xsl:otherwise>
</xsl:choose>
with this paragraph:
<xsl:choose>
<xsl:when test="$action!=''">
<tp:ServiceBinding>
<tp:Service><xsl:value-of select="$service"/></tp:Service>
<xsl:if test="($flag='outgoing' and tp:PartyId/text() = $partyId) or</pre>
($flag='incoming' and tp:PartyId/text() != $partyId)">
<xsl:copy-of select="tp:CollaborationRole/tp:ServiceBinding/</pre>
tp:CanSend[tp:ThisPartyActionBinding/@tp:action=$action] |
tp:CollaborationRole/tp:ServiceBinding/tp:CanReceive/
tp:CanSend[tp:ThisPartyActionBinding/@tp:action=$action]"/>
</xsl:if>
<xsl:if test="($flag='outgoing' and tp:PartyId/text() != $partyId) or</pre>
($flag='incoming' and tp:PartyId/text() = $partyId)">
<xsl:copy-of select="tp:CollaborationRole/tp:ServiceBinding/</pre>
tp:CanReceive[tp:ThisPartyActionBinding/@tp:action=$action] |
tp:CollaborationRole/tp:ServiceBinding/tp:CanSend/
tp:CanReceive[tp:ThisPartyActionBinding/@tp:action=$action]"/>
</xsl:if>
</tp:ServiceBinding>
</xsl:when>
<xsl:otherwise>
<tp:ServiceBinding>
```

```
<xsl:if test="($flag='outgoing' and tp:PartyId/text() = $partyId) or
($flag='incoming' and tp:PartyId/text() != $partyId)">
<tp:Service><xsl:value-of
select="tp:CollaborationRole/tp:ServiceBinding[tp:CanSend/
tp:ThisPartyActionBinding/tp:ActionContext/
@tp:binaryCollaboration=$binaryCollaboration and tp:CanSend/
tp:ThisPartyActionBinding/tp:ActionContext/
@tp:businessTransactionActivity=$businessTransactionActivity and
tp:CanSend/tp:ThisPartyActionBinding/tp:ActionContext/
@tp:requestOrResponseAction=$requestOrResponseAction]/tp:Service/text()
|
tp:CollaborationRole/tp:ServiceBinding[tp:CanReceive/tp:CanSend/
tp:ThisPartyActionBinding/tp:ActionContext/
@tp:binaryCollaboration=$binaryCollaboration and tp:CanReceive/
tp:CanSend/tp:ThisPartyActionBinding/tp:ActionContext/
@tp:businessTransactionActivity=$businessTransactionActivity and</pre>
```

Chapter 20. Create a Basic Trading Partner Profile using AFT

Before you begin

Advanced File Transfer (AFT) functionality is licensed separately.

About this task

To create a Basic Trading Partner Profile using AFT:

- 1. From the Administration menu, select Trading Partner > Basic.
- 2. Under Create Trading Partner, select Type of Exchange, select File Transfer and click Next.
- **3**. You are transferred to the Advanced File Transfer menu. See *Advanced File Transfer*.

Chapter 21. Create a Basic Trading Partner Profile using FTP

About this task

To create a basic trading partner profile using FTP:

- 1. From the Administration menu, select Trading Partner > Basic.
- 2. Under Create Trading Partner, Select Type of Exchange, select General Document and click Next.
- **3**. Specify the Trading Partner Information. On the Identity page, enter the following trading partner information and click **Next**:.

Trading Partner Information Field	Description
Name	Name of the trading partner for which you are creating the identity record. Required.
Identifier	Primary ID that identifies this trading partner. This can be a Data Universal Numbering System (DUNS) number, EDI interchange ID, e-mail address, or another unique string. Required.
Address Line 1	Conventional mailing address of this trading partner organization. Required.
Address Line 2	Conventional mailing address of this trading partner organization. Optional.
City	City where this trading partner is located. Required.
State or Province	State or province where the organization of the trading partner represented by the identity is located. Optional.
Zip or Postal Code	ZIP code [®] or postal code where this trading partner is located. Required.
E-mail Address	E-mail address of the trading partner. Optional.
Telephone Number	Telephone number of the trading partner. Optional.
Time Zone	Select a time zone from the list. Optional.
Country	Select a country from the list. Optional.

- 4. On the Protocol page, select **FTP** and click **Next**:.
- 5. Specify the Communication settings. On the Communications page, enter the following information and click **Next**:.

Communications Field	Description
	IP address that the server monitors for incoming sessions. Valid value is a valid IP address. Optional.

Communications Field	Description
End Point Port	IP port that the server monitors for incoming sessions. Valid value is a valid port number. Optional.
Directory	Name of a directory on the trading partner's server where outbound data is stored for pickup. Used for outbound sessions. Optional.
Protocol Mode	Mode or method that will be used by the protocol (FTP). Required. Valid values are:
	PUT – Send data to the remote party when making an FTP connection
	GET – Receive data from the remote party
Document	Document to be retrieved for selected protocol mode. Optional, if PUT is selected. Note: If you selected GET as the protocol mode, the document you specify must exist on the remote trading partner's FTP server. Note: Each document (file name) that you GET from the remote trading partner FTP server requires a separate profile.
User ID	Unique ID associated with a transport record, from the FTP server you are communicating with. Required for FTP.
Password	Password from the server that you are communicating with. It authenticates the user ID. Required for FTP.

- 6. On the Confirm page, review the trading partner information and click Finish.
- 7. Review the default information that is created Click any of the default record names to edit, or click **Return** to continue.

Record Type	Default Record Name
Transport	transport_identityname_timestamp
Document Exchange	docexchange_identityname_timestamp
Delivery Channel	delivchan_identityname_timestamp
Packaging	packaging_identityname_timestamp
Profile	profile_identityname_timestamp

Chapter 22. Create a Basic Trading Partner Profile using HTTP

About this task

To Create a Basic Trading Partner Profile using HTTP:

- 1. From the Administration menu, select Trading Partner > Basic.
- 2. Under Create Trading Partner, select Type of Exchange, select General Document and click Next.
- 3. Specify the Trading Partner Information settings. On the Identity page, enter the following trading partner information and click **Next**:.

Trading Partner Information Field	Description
Name	Name of the trading partner for which you are creating the identity record. Required.
Identifier	Primary ID that identifies this trading partner. This can be a Data Universal Numbering System (DUNS) number, EDI interchange ID, e-mail address, or another unique string. Required.
Address Line 1	Conventional mailing address of this trading partner organization. Required.
Address Line 2	Conventional mailing address of this trading partner organization. Optional.
City	City where this trading partner is located. Required.
State or Province	State or province where the organization of the trading partner represented by the identity is located. Optional.
Zip or Postal Code	ZIP code or postal code where this trading partner is located. Required.
E-mail Address	E-mail address of the trading partner. Optional.
Telephone Number	Telephone number of the trading partner. Optional.
Time Zone	Select a time zone from the list. Optional.
Country	Select a country from the list. Optional.

- 4. On the Protocol page, select HTTP and click Next:.
- 5. Specify the Communication settings. On the Communications page, enter the following information and click **Next**:.

Communications Field	Description
	Address where you can contact the server. Valid value is a URL in the following format:http:// <server address="" ip="">:<port number="">Required.</port></server>

- 6. On the Confirm page, review the trading partner information and click Finish.
- 7. Review the default information that is created: Click any of the default record names to edit or click Return to continue.

Record Type	Default Record Name
Transport	transport_identityname_timestamp
Document Exchange	docexchange_identityname_timestamp
Delivery Channel	delivchan_identityname_timestamp
Packaging	packaging_identityname_timestamp
Profile	profile_identityname_timestamp

Chapter 23. Create a Basic Trading Partner Profile using SMTP

About this task

To create a basic trading partner profile using SMTP:

- 1. From the **Administration** menu, select **Trading Partner** > **Basic**.
- 2. Under Create Trading Partner, Select Type of Exchange, select General Document and click Next.
- 3. Specify the Trading Partner Information settings. On the Identity page, enter the following trading partner information and click **Next**:.

Trading Partner Information Field	Description
Name	Name of the trading partner for which you are creating the identity record. Required.
Identifier	Primary ID that identifies this trading partner. This can be a Data Universal Numbering System (DUNS) number, EDI interchange ID, e-mail address, or another unique string. Required.
Address Line 1	Conventional mailing address of this trading partner organization. Required.
Address Line 2	Conventional mailing address of this trading partner organization. Optional.
City	City where this trading partner is located. Required.
State or Province	State or province where the organization of the trading partner represented by the identity is located. Optional.
Zip or Postal Code	ZIP code [®] or postal code where this trading partner is located. Required.
E-mail Address	E-mail address of the trading partner. Optional.
Telephone Number	Telephone number of the trading partner. Optional.
Time Zone	Select a time zone from the list. Optional.
Country	Select a county from the list. Optional.

- 4. On the Protocol page, select **SMTP** and click **Next**:.
- 5. Specify the Communication settings. On the Communications page, enter the following information and click **Next**:.

Communications Field	Description
	Mailbox name, alias, or ID number for a mail server. Must be unique for each e-mail address. Required.

Communications Field	Description
From	E-mail address of the sender. Required.
	E-mail address of the receiver. Same as Mail To. Required

- 6. On the Confirm page, review the trading partner information and click Finish.
- 7. Review the default information that is created Click any of the default record names to edit or click **Return** to continue.

Record Type	Default Record Name
Transport	transport_identityname_timestamp
Document Exchange	docexchange_identityname_timestamp
Delivery Channel	delivchan_identityname_timestamp
Packaging	packaging_identityname_timestamp
Profile	profile_identityname_timestamp

Chapter 24. Create an Advanced Trading Partner Profile

About this task

To set up an advanced profile for a trading partner, perform this sequence of tasks:

- 1. Create an Identity record
- 2. Create a Transport record
- 3. Create a Document Exchange record
- 4. Create a Delivery Channel record
- 5. Create a Packaging record
- 6. Create a Profile record

Chapter 25. Create an Identity Record

About this task

To create an identity record:

- 1. From the Administration menu, select Trading Partner > Advanced > Identities.
- 2. Under Create, next to New Identity, click Go!
- 3. On the Identities page, do one of the following:
 - To create an identity record that inherits all the components of an existing trading profile, select an identity record from Select Base Identity, and click Next.
 - To specify properties, leave **Select Base Identity** blank, and click **Next**.
- 4. Specify the Information settings. On the Information page, complete the following fields and click **Next**:

Information Fields	Description
Name	Name for the identity record to create for this trading profile. Required.
Reference URL	Uniform Resource Locator (URL) is the Internet address of the trading partner. Optional.
DUNS	Data Universal Numbering System (DUNS) is a unique nine-character company identification number issued by Dun & Bradstreet Corporation. Optional.
Identifier	Primary ID of this identity record. It could be a DUNS number, EDI interchange ID, e-mail address, or another unique string. Required.
Address Line 1	Conventional mailing address of the trading partner organization. Required.
Address Line 2	Additional mailing address information of the trading partner organization. Optional.
City	City where the trading partner is located. Required.
State or Province	State or province where the organization of the trading partner represented by the identity is located. Optional.
Zip or Postal Code	ZIP Code or postal code where the trading partner is located. Required.
E-mail Address	E-mail address of the trading partner. Optional.
Telephone Number	Telephone number of the trading partner. Optional.
Time Zone	Time zone where the trading partner is located. Optional.

Information Fields	Description
Country	Country where the trading partner is located. Optional.
Federation Peers	Discovery point URL for the trading partner you want to associate this identity with. Optional.

- 5. Click Finish to add the identity.
- 6. Click **Return** to continue.

Chapter 26. Create a Document Exchange Record

About this task

To create a document exchange record:

Procedure

- 1. From the **Administration** menu, select **Trading Partner > Advanced > Document Exchange**.
- 2. Under Create, next to New Document Exchange, click Go!
- 3. Specify the Information settings. On the Information page, complete the following fields and click **Next**:

Information Fields	Description
Name	Name for the document exchange record to create for this trading profile. Required.
Identity	Unique ID associated with the identity that links this document exchange record to the identity record. The ID must match the Name field of the identity record. Required.

4. Specify the Retry settings. On the Retry Settings page, complete the following fields and click **Next**:

Retry Setting Fields	Description
Number of Retries	Number of times that Sterling Integrator tries to contact the trading partner before timing out. Zero (0) is invalid. Required.
Retry Interval (sec)	Number of seconds that Sterling Integrator waits before trying again to contact the trading partner after the previous attempt timed out. Zero (0) is invalid. Required. Note: To avoid overwriting this Document Exchange portion of trading profile, manually set the Retry Interval field in an inherited document exchange every time you modify the same field in the base document exchange.
Persist Duration (sec)	Number of seconds that a message received is kept before being passed to the integration engine. Zero (0) is invalid. Required.

5. Specify the Enveloping Properties settings. On the Enveloping Properties page, complete the following field and click **Next.** If you select None, go to step 7:

Enveloping Properties Fields	Description
	Used only by the EDIINT Message service. The security protocol to be used. Valid values are SMIME and NONE (default). Required.

6. Specify the Security settings. On the Security page, complete the following fields and click **Next**:

Security Fields	Description
Encryption Algorithm	Used only by the EDIINT Message service if a payload type requiring encryption is selected. Identifies the encryption algorithm to be used. Required if Protocol value is anything other than None. Required.Supported algorithms are: • Triple DES 168 CBC with PKCS5 padding • 56-bit DES CBC with PKCS5 padding • 128-bit RC2 CBC with PKCS5 padding
	• 40-bit RC2 CBC with PKCS5 padding
Signing Algorithm	Used only by the EDIINT Message service to transfer data to the trading partner. Identifies the fixed-length of compressed representation of signed messages.Required. Valid values are:
	• MD5 – Message digest algorithm that verifies the integrity of data through a 128-bit message digest.
	 SHA1 – Secure hash algorithm that verifies the integrity of data through a 160-bit (20 byte) message digest. Transmission is a bit slower that MD5; however, the larger message digest size offers a more secure data transference.
Signing Key Certificate	Used only by the EDIINT Message service. The key certificate for the encryption key of the identity, if available, that is used to encrypt the message when using SMIME. Required if Message Symmetric Algorithm Strength is selected. Note: This is also the private key the EDIINT Message Service uses to sign messages it builds. A signing key certificate is not required if encryption is selected. Note: To guarantee that messages are signed, you must also select non-repudiation of origin when creating a delivery channel record.

Security Fields	Description
Config Multi Certs	Allows you to configure multiple digital certificates against a certificate in Sterling Integrator so you can automate which certificate is used based on a time window, status, and certificate order.
	Select multiple certificates by name – Click the right or left arrow to move selected certificates to or from the used column.
	• Specify a Certificate Order – Specifies the order the system should follow to find a certificate to use. The first certificate found in this order that has a status of "Ok" and fits within the specified time window will be used.
	Specify Status – Read-only field that documents the current status of the certificate.
	 Edit Go Live Date – Default is: "Not Before Date" in the certificate. You can choose to keep the date in the certificate or change it to a date that exceeds the default. This field does not overwrite the date in the certificate, instead it specifies to the system when you would like to use the certificate. You cannot specify a date that predates the "Not Before Date" in the certificate. You also cannot specify a date for this field that exceeds the "Not After Date" in this window. Type in mm/dd/yy format. Edit Not After Date – This field will default to the "Not After Date" in the certificate. You can chose to keep the date or change it to a value that predates the default. This field does not overwrite the date in the certificate, instead, it specifies to the system when you would like to use the certificate. You cannot specify a date that predates the "Not Before Date" in the window. You also cannot specify a date for this field that exceeds the "Not After Date" in this window. Type in mm/dd/yy format.
	Note: The Config Multi Certs link appears only when multiple certificates are available.
Signing User Certificate	Used only by the EDIINT Message service. The trusted certificate for the signing certificate of the trading partner. Required if Signing Algorithm is selected. Note: This is also a trusted certificate that the EDIINT Message service uses to verify signatures on messages it receives.

- 7. Click Finish to add the document exchange record.
- 8. Click **Return** to continue.

Chapter 27. Create a Transport Record

About this task

To create a transport record:

Procedure

- 1. From the **Administration** menu, select **Trading Partner > Advanced > Transport**.
- 2. Under Create, next to New Transport, click Go!
- **3**. Specify the Transport settings. On the Transports page, complete the following fields and click **Next**:

Information Fields	Description
Name	Name for the transport record to create for this trading profile. Required.
	In order to link the transport record to the identity record, select the identity record name from the list. Required.

4. Specify the Communication settings. On the Communications page, complete the following fields and click **Next**:

Communication Fields	Description
Receiving Protocol	Communications protocol supported by this transport when receiving data. Valid values are FTP, HTTP, and SMTP. Required.
Sending Protocol	Communications protocol supported by this transport when sending data. Valid values are FTP, HTTP, SMTP, and blank. Optional.
End Point IP	IP address to contact the server. Valid value is a valid IP address. Optional.
End Point Port	Port that the server monitors for incoming sessions. Valid value is a valid port number. Optional.

- 5. In step 4, if you selected:
 - FTP as the receiving protocol, go to *Specifying FTP Settings*.
 - HTTP as the receiving protocol, go to *Specifying HTTP Settings*.
 - SMTP as the receiving protocol, go to *Specifying SMTP Settings*.

Specify FTP Settings

About this task

To specify FTP settings as part of a transport record:

[&]quot;Specify FTP Settings"

[&]quot;Specify HTTP Settings" on page 63

[&]quot;Specify SMTP Settings" on page 65

Procedure

1. Specify the Transfer settings. On the Transfer Settings page, complete the following fields and click **Next**:

Transfer Settings Fields	Description
Transfer Mode	Which party initiates an FTP session through a network firewall. The default transfer mode, ACTIVE, indicates that Sterling Integrator makes the connection to clients. PASSIVE transfer mode indicates that clients make the connection. Required.
Directory	Name of a directory on the server of the trading partner where outbound data is stored and awaits pickup by the trading partner. Used for outbound sessions. Optional.
Local Data Port Range	Local control port numbers to be used on the server of the trading partner to establish an FTP connection for data transfers. Valid value is any positive number that is optimal for your system. Zero (0) enables the operating system to select a port number. Optional.
Local Control Data Port Range	Local control port number to use for control/command connections for the control channel. Used for outbound sessions. Select a port that is not used by another application on the system. Zero (0) enables the operating system to select a port number. Optional.

2. Specify the Protocol settings. On the Protocol Settings page, complete the following fields and click **Next**:

Protocol Settings Fields	Description
Response Timeout (sec)	Number of seconds to wait for remote response to an outbound queue. Used for outbound sessions. Valid value is number of seconds. Zero (0) indicates wait indefinitely. Optional.
Firewall Proxy	IP address, port number, login ID, and password of the remote firewall. Used for outbound sessions. Separate values with a comma. If used, you must specify both login ID and password. Optional.
Firewall Connect Count	Number of seconds that Sterling Integrator attempts to contact the transport port address before timing out. Optional.
Socket Timeout (sec)	Number of seconds to wait for remote response to a command. Valid value is any positive number that is optimal for your system. Zero (0) indicates wait indefinitely. Optional.

3. Specify the Security Settings. On the Security page, complete the following fields and click **Next**:

Security Fields	Description
SMIME Encryption User Certificate	Encryption certificate of the trading partner. The EDIINT Message service uses the certificate to encrypt messages. Optional.
SMIME Decryption Certificate (System Store)	Optional. Valid values are:
	• B2BHttp
	• UIKey
	OpsDrv
	OpsKey
Config Multi Certs	Allows you to configure multiple digital certificates against a certificate in Sterling Integrator so you can automate which certificate is used based on a time window, status, and certificate order.
	Select multiple certificates by name – Click the right or left arrow to move selected certificates to or from the used column.
	Specify a Certificate Order – Specifies the order the system should follow to find a certificate to use. The first certificate found in this order that has a status of "Ok" and fits within the specified time window will be used.
	Specify Status – Read-only field that documents the current status of the certificate.
	• Edit Go Live Date – Default is: "Not Before Date" in the certificate. You can choose to keep the date in the certificate or change it to a date that exceeds the default. This field does not overwrite the date in the certificate, instead it specifies to the system when you would like to use the certificate. You cannot specify a date that predates the "Not Before Date" in the certificate. You also cannot specify a date for this field that exceeds the "Not After Date" in this window. Type in mm/dd/yy format.
	• Edit Not After Date – This field will default to the "Not After Date" in the certificate. You can chose to keep the date or change it to a value that predates the default. This field does not overwrite the date in the certificate, instead, it specifies to the system when you would like to use the certificate. You cannot specify a date that predates the "Not Before Date" in the window. You also cannot specify a date for this field that exceeds the "Not After Date" in this window. Type in mm/dd/yy format.
	Note: The Config Multi Certs link appears only when multiple certificates are available.

Security Fields	Description
SSL	Whether Secure Sockets Layer (SSL) must be active. Required. Valid values are:
	• NONE – SSL is not used by the transport.
	• OPTIONAL – FTP handles SSL encryption appropriately if present.
	MUST – Transport uses this protocol configured for SSL encryption (default).
	Note: If OPTIONAL or MUST is specified, the asset protection key must allow SSL for the appropriate protocol.
Key Certificate Passphrase	Passphrase that protects the server key certificate. Required, if SSL value is anything other than NONE.
Cipher Strength	Strength of the algorithms used to encrypt data. Optional. Valid values are:
	• ALL
	 WEAK – Required for international e-business if government regulations prohibit STRONG encryption from being exported.
	• STRONG – Required if SSL value is anything other than NONE (default).
Key Certificate (System Store)	Private key and certificate for the component. Used to encrypt and decrypt messages. Also used by the EDIINT Message service as the key for decrypting encrypted messages. Required, if SSL value is anything other than NONE.
CA Certificates	Certificate used to validate the certificate of the trading partner. This is the public key. Required if the Server SSL value is Must or Optional.

4. Specify the Protocol Mode settings. On the Protocol Mode page, complete the following fields and click **Next**:

Protocol Mode Fields	Description
Protocol Mode	Mode or method that will be used by the protocol (FTP). Required. Valid values are:
	PUT – Send data to the remote party when making an FTP connection.
	GET – Receive data from the remote party.
Document	Document to be retrieved for selected protocol mode. If mode is GET, can leave the field blank. Optional if PUT is selected. Note: If you selected GET as the protocol mode, the document you specified must exist on the remote trading partner FTP server.

5. Specify the Transport Account settings. On the Transport Account page, complete the following fields and click **Next**:

Transport Account Fields	Description
User ID	Unique ID associated with a transport record. Optional.
Password	Password that authenticates the user ID. Optional.
Confirm Password	Password typed in the Password field. Optional.

- 6. Click **Finish** to add the transport record.
- 7. Click **Return** to continue.

Parent topic: Chapter 27, "Create a Transport Record," on page 59

Specify HTTP Settings

About this task

To specify HTTP settings as part of a transport record:

Procedure

1. Specify the End Point settings. On the End Point Settings page, complete the following fields and click **Next**:

End Point Fields	Description
End Point	HTTP address of the transport. It can be a URL. Required.
End Point Type	Purpose of this end point. Required. Valid values are:
	Login – Address where the initial HTTP session is established.
	• Request – Address to which HTTP request messages are sent.
	Response – Address to which response messages are sent.
	Error – Address to which HTTP error messages are sent.
	All Purpose – End port can be used for login, request, response, or error messages.

2. Specify the Protocol settings. On the Protocol Settings page, complete the following fields and click **Next**:

Protocol Settings Fields	Description
Response Timeout (seconds)	Number of seconds to wait for remote response to an outbound queue. Used for outbound sessions. Valid value is number of seconds. Zero (0) indicates wait indefinitely. Optional.
Firewall Proxy	IP address, port number, login ID, and password of the remote firewall. Separate values with a comma. If used, you must specify both login ID and password. Used for outbound sessions. Optional.

Protocol Settings Fields	Description
Firewall Connect Count (seconds)	Number of seconds that Sterling Integrator attempts to contact port address of the transport before timing out. Optional.
Socket Timeout (seconds)	Number of seconds to wait for remote response to a command. Valid value is any positive number that is optimal for your system. Zero (0) indicates wait indefinitely. Optional.

3. Specify the Security settings. On the Security page, complete the following fields and click **Next**:

Security Fields	Description
SMIME Encryption User Certificate	Encryption certificate of the trading partner. The EDIINT Message service uses the certificate to encrypt messages. Optional. Note: After receiving a trusted certificate from the trading partner and checking it in, you can select the certificate from this field.
SMIME Decryption Certificate (System Store)	Optional. Valid values are: • B2BHttp • UIKey • OpsDrv • OpsKey
SSL	 Whether Secure Sockets Layer (SSL) must be active. Optional. Valid values are: None – SSL is not used by the transport. Optional – FTP handles SSL encryption appropriately if present. Must – Transport uses this protocol configured for SSL encryption (default). Note: If Optional or Must is specified, the asset protection key must allow SSL for the appropriate protocol.
Key Certificate Passphrase	Passphrase that protects the server key certificate. Required if SSL value is anything other than None.
Cipher Strength	Strength of the algorithms used to encrypt data. Optional. Valid values are: • ALL • WEAK – Required for international e-business if government regulations prohibit STRONG encryption from being exported. • STRONG – Required if SSL value is anything other than None (default).

Security Fields	Description
Key Certificate (System Store)	Private key and certificate for the component. Used to encrypt and decrypt messages. Also used by the EDIINT Message service as the key for decrypting encrypted messages. Required, if SSL value is anything other than NONE. Note: After receiving a public key certificate from the trading partner and checking it in, you can select the certificate from this field.
CA Certificates	Certificate used to validate the certificate of the trading partner. This is the public key. Required, if the SSL value is Must or Optional.

4. Specify the Protocol Mode settings. On the Protocol Mode page, complete the following fields and click **Next**:

Protocol Mode Fields	Description
Protocol Mode	Mode or method that will be used by the protocol (FTP). Required. Valid values are:
	PUT – Send data to the remote party when making an FTP connection.
	• GET – Receive data from the remote party.
Document	Document to be retrieved for selected protocol mode. If mode is GET, can leave the field blank. Optional if PUT is selected. Note: If you selected GET as the protocol mode, the document you specified must exist on the remote trading partner FTP server.

5. Specify the Transport Account settings. On the Transport Account page, complete the following fields and click **Next**:

Transport Account Fields	Description
User ID	Unique ID associated with a transport record. Optional.
Password	Password that authenticates the user ID to the system. Optional.
Confirm Password	Password typed in the Password field. Optional.

- 6. Click **Finish** to update the transport record.
- 7. Click **Return** to continue.

Parent topic: Chapter 27, "Create a Transport Record," on page 59

Specify SMTP Settings

About this task

To specify SMTP settings as part of a transport record:

Procedure

1. Specify the secuity settings. On the Security page, complete the following fields and click **Next**:

Security Fields	Description
SMIME Encryption User Certificate	Encryption certificate of the trading partner. The EDIINT Message service uses the certificate to encrypt messages. Optional.
SMIME Decryption Certificate (System Store)	Optional. Valid values are:
	• B2BHttp
	• UIKey
	OpsDrv
	OpsKey
SSL	Whether Secure Sockets Layer (SSL) must be active. Required. Valid values are:
	NONE – SSL is not used by the transport.
	OPTIONAL – FTP handles SSL encryption appropriately if present.
	MUST – Transport uses this protocol configured for SSL encryption (default).
	Note: If OPTIONAL or MUST is specified, the asset protection key must allow SSL for the appropriate protocol.
Key Certificate Passphrase	Passphrase that protects the server key certificate. Required if SSL value is anything other than NONE.
Cipher Strength	Strength of the algorithms used to encrypt data. Optional. Valid values are:
	• ALL
	WEAK – Required for international e-business if government regulations prohibit STRONG encryption from being exported.
	STRONG – Required if SSL value is anything other than NONE (default).
Key Certificate (System Store)	Private key and certificate for the component. Used to encrypt and decrypt messages. Required if SSL value is anything other than NONE. Also used by the EDIINT Message service as the key for decrypting encrypted messages.
CA Certificates	Certificate used to validate the certificate of the trading partner. This is the public key. Required if the Server SSL value is Must or Optional.

2. Specify the SMTP settings. On the SMTP Settings page, complete the following fields and click **Next**:

SMTP Settings Fields	Description
	Mailbox name, alias, or ID number for a mail server. Required.

SMTP Settings Fields	Description
From	E-mail address of the sender. Required.
То	E-mail address of the receiver. Same as Mail To. Required.
CC	Carbon copy e-mail address. Optional.
BCC	Blind carbon copy e-mail address. Optional.

3. Specify the Transport Account settings. On the Transport Account page, complete the following fields and click **Next**:

Transport Account Fields	Description
User ID	Unique ID associated with a transport record. Optional.
Password	Password that authenticates the user ID. Optional.
Confirm Password	Password typed in the Password field. Optional.

- 4. Click **Finish** to update the transport record.
- 5. Click **Return** to continue.

Parent topic: Chapter 27, "Create a Transport Record," on page 59

Chapter 28. Create a Delivery Channel Record

About this task

To create a delivery channel record:

Procedure

- 1. From the Administration menu, select Trading Partner > Advanced > Delivery Channels.
- 2. Under Create, next to New Delivery Channel, click Go!
- **3**. Specify the Information settings. On the Information page, complete the following fields and click **Next**:

Information Fields	Description
Name	Name for the delivery channel record to create for this trading profile. Required.
Identity	Unique ID that links the delivery channel record to the identity record. It must match the Name field of the identity record. Required.

4. Specify the Channel Definition settings. On the Channel Definition page, complete the following fields and click **Next**:

Channel Definition Fields	Description
Transport	Name of the transport that links this delivery channel record to the transport records. It must match the Transport Name field of the transport record. Required.
Document Exchange	Name of the document exchange associated with this delivery channel record. It must match the Document Exchange Name field of the document exchange record. Required.

5. Specify the Security settings. On the Security page, complete the following fields and click **Next**:

Security Fields	Description
Sync Reply Mode	What the receiving application expects in a response when bound to a synchronous communications protocol, such as HTTP. Required. Valid values are:
	• Response Only – Only the business response message is returned.
	Signals and Response – Application returns the business response message in addition to one or more business signals.
	Signals Only – Response includes one or more business signals as defined in the ebXML Business Process Specifications Schema (ebBPSS), but not a business response message.
	msh Signals Only – Response includes errors or acknowledgments only. Business response messages or business signals must be returned asynchronously.
	NONE – No business response messages, business signals, or msh signals are returned (default).
Non Repudiation of Origin	Whether the message sender must sign the message with a digital certificate. Valid values are Yes and No. Required.
Non Repudiation of Receipt	Whether the message receiver must sign the message with a digital certificate. Valid values are Yes and No. Required.
Secure Transport	Whether the delivery channel record uses a secure transport protocol such as SSL or IPSEC. Valid values are Yes and No. Required.
Confidentiality	Whether the message must be encrypted. Valid values are Yes and No. Required.
Authenticated	Whether the digital signature of the message must be checked to verify that it came from the expected sender and it has not been modified in transit or storage. Valid values are Yes and No. Required.
Authorized	Whether the message sender must be authorized (granted access to a network resource) before the message can be delivered to the application. Valid values are Yes and No. Required.

6. Specify the Delivery settings. On the Delivery Settings page, complete the following fields and click **Next**:

Delivery Settings Field	Description
Receipt Type	Used only by the EDIINT Message service. The type of receipt to request. Valid values are Message Disposition Notification (MDN) and NONE (default). Required.

Delivery Settings Field	Description
Receipt Signature Type	Used only by the EDIINT Message service to transfer data to the trading partner. Identifies the fixed-length of compressed representation of messages requested on receipts. Required.Valid values are:
	• None
	MD5 – Message digest algorithm that verifies the integrity of data through a 128-bit message digest.
	SHA1 – Secure hash algorithm that verifies the integrity of data through a 160-bit (20 byte) message digest. Transmission is a bit slower that MD5; however, the larger message digest size offers a more secure data transference.
	Note: Selection of a value other than None prompts the EDIINT Message service to request a signed Message Disposition Notification (MDN) when building messages to the trading partner.
Receipt Timeout	Timeout value for receipt of expected MDNs, in seconds. Optional.
Delivery Mode	Used only by the EDIINT Message service to deliver receipts for messages received. Required. Valid values are:
	Asynchronous HTTP – Used for AS2 and RosettaNet if you want an asynchronous receipt.
	Asynchronous HTTPS – Used for AS2 if you want an asynchronous receipt.
	• Asynchronous SMTP – Used for AS1 and AS2 if you want an asynchronous receipt.
	• Synchronous – Used for AS2 if you want a synchronous receipt.
Receipt to Address	Used only by the EDIINT Message service. Indicates where a receipt must be sent if it is not going to the e-mail address in the associated identity. Required if you are using EDIINT AS2 requesting asynchronous MDNs. You must type the complete URL where you want the message to be sent. Required.

- 7. Click Finish to add the delivery channel record.
- 8. Click **Return** to continue.

Chapter 29. Create a Packaging Record

About this task

To create a packaging record:

Procedure

- 1. From the Administration menu, select Trading Partner > Advanced > Packaging.
- 2. Under Create, next to New Packaging, click Go!
- 3. Specify the Information settings. On the Information page, complete the following fields and click **Next**:

Information Fields	Description
Name	Name for the packaging record to create for this trading profile. Required.
Message Parsable	Whether the message can be parsed. Valid values are Yes and No. Required.

4. Specify the Packaging settings. On the Packaging Settings page, complete the following fields and click **Next**:

Packaging Setting Fields	Description
Payload Type	Used only by the EDIINT Message service to create EDIINT messages. The payload is the document at the inner level of the message. The payload type describes the message format for transporting documents. Required. Valid values are:
	Plain Text – Payload is not signed and it is not encrypted.
	• Signed Detached – Payload is signed with a detached signature, according to the EDIINT specifications.
	• Encrypted – Payload is encrypted according to the EDIINT specifications.
	• Signed Detached Encrypted – Payload is signed with a detached signature and then encrypted, according to the EDIINT specifications (default).

Packaging Setting Fields	Description
MIME Type	Used only by the EDIINT Message service. Indicates how to package the lowest level of payload content (the document at the inner level of a message) to be sent. Helps to implement the EDIINT specification correctly, and provides some flexibility, because receiving programs might expect a specified MIME type and sub-type. Required. Valid values are:
	Text – For XML or text
	Application – For EDI or any other type of data
	Message
	Audio
	• Video
	Image
MIME Sub Type	Used only by the EDIINT Message service. Indicates how to package the lowest level of payload content (the document at the inner level of a message) to be sent. Required. Valid values are:
	• EDI-X12 (default)
	• EDIFACT
	EDI-Consent
	Octet-stream – For any type of data
	• XML
	• Plain
Compress Data	Used only by the EDIINT Message service. Specifies whether the payload must be compressed. Required.Valid values are:
	None
	• Low
	Medium
	• High
	Default

- 5. Click Finish to add the packaging record.
- 6. Click **Return** to continue.

Chapter 30. Create a Trading Partner Profile Record

About this task

To create a trading partner profile record:

Procedure

- 1. From the Administration menu, select Trading Partner > Advanced > Profiles.
- 2. Next to Create New Profile, click Go!
- **3**. Specify the Information settings. On the Information page, complete the following fields and click **Next**:

Information Fields	Description
Name	Name for the profile record to create for this trading profile. Required.
Identity	Unique ID that links this profile to the identity record. It must match the Name field of the identity record. Required.

4. Specify the Profile Definition settings. On the Profile Definition page, complete the following fields and click **Next**:

Profile Fields	Description
Profile Type	Type of profile used for data exchanged for this trading profile. Required. Valid values are: • EDI (Electronic Data Interchange) • AS1 (Applicability Statement 1) • AS2 (Applicability Statement 2)
	Note: The recommended method of adding an AS2 Trading Partner is located at Trading Partner > AS2 on the Admin Console.
	• RN (RosettaNet)
GLN	Global location number of this trading partner. Optional.
Delivery Channel	Unique ID that links this profile to the delivery channel record. It must match the Name field of the delivery channel record. Required.
Packaging	Unique ID that links this trading profile to the packaging record. It must match the Name field of the packaging record. Required.
Provider	Any third-party service provider name. Required.

- 5. If you selected RN for the profile type, you get another page specific to trading partners who use RosettaNet standards. Complete and click **Next** to continue.
- 6. On the Business Processes page, complete one of the following steps and click **Next**:

- To enable the predefined business process (default) to communicate with the trading partner for the specified mode, verify that **Not Applicable** is selected from the appropriate message mode list or lists (Send, Respond, Request Response).
- To select a business process other than the predefined business process (default) to communicate with the trading partner for the specified mode, select the business process from the appropriate message mode list or lists (Send, Respond, Request Response).

To communicate with a trading partner, the business process must include the B2B Send, B2B Respond, or B2B Request-Response service.

- 7. Click **Finish** to add the profile record.
- 8. Click Return to continue.

Chapter 31. Update a Basic or Advanced Trading Partner Record

About this task

To update a basic or advanced profile trading partner record:

- 1. From the **Administration** menu, select **Trading Partner > Advanced > Record Name**. Where **Record Name** is one of the following:
 - Identities
 - Transports
 - Document Exchange
 - Delivery Channels
 - Packages
 - Profiles
- 2. Use Search or List to locate the record you want to change.
- 3. Next to the record name, click Edit.
- 4. On the Information page of the trading partner record, make changes and click **Next** until you reach the Confirm page.
- 5. Click **Finish** to update the trading partner record.
- 6. Click Return to continue.

Chapter 32. Disable a Trading Partner Record

About this task

To disable a trading partner record:

- 1. From the **Administration** menu, select **Trading Partner** > **Advanced** > **Record Name**. Where **Record Name** is one of the following:
 - Identities
 - Transports
 - Document Exchange
 - Delivery Channels
 - Packages
 - Profiles
- 2. Use Search or List to locate the record you want to disable.
- 3. Next to the record name, deselect the **Enabled** box. The record is disabled.
- 4. Click Return to continue.

Chapter 33. Delete a Trading Partner Record

About this task

To delete a trading partner record:

- 1. From the **Administration** menu, select **Trading Partner > Advanced > Record Name**. Where **Record Name** is one of the following:
 - Identities
 - Transports
 - Document Exchange
 - Delivery Channels
 - Packages
 - Profiles
- 2. Use Search or List to locate the record you want to delete.
- 3. Next to the record name, click **Delete**.
- 4. In the confirmation box, click **OK**.
- 5. On the Summary page click Next.
- 6. On the Confirm page, click **Delete**. The record is deleted.
- 7. Click **Return** to continue.

Chapter 34. Create a Trading Partner Contract

About this task

To create a trading partner contract:

Procedure

- 1. From the Administration menu, select Trading Partner > Contracts.
- 2. Under Create, next to New Contract, click Go!
- **3**. Specify the Information settings. On the Information page, complete the following fields and click **Next**:

Information Fields	Description
Name	Descriptive name of the contract. Required.
Start Date	Start date of the contract. Valid value is any date in the format <i>yyyy-mm-dd</i> . Must be less than or equal to End Date. Default value is the current date. Required.
End Date	Expiration date of the contract. Valid value is any date in the format <i>yyyy-mm-dd</i> . Must be greater than or equal to Start Date. Default value is one week from the current date. Required.
Status	State of the composition/negotiation process that creates the contract. Default value is SIGNED. Required. Valid values are:
	PROPOSED – Contract being negotiated by the parties. The first stage of negotiation.
	AGREED – Contract agreed upon by the parties. The next stage of negotiation.
	SIGNED – Contract signed by the parties. The final stage of negotiation. The contract is usable.

4. Specify the Contract Definition settings. On the Contract Definition page, complete the following fields and click **Next**:

Contract Definition Fields	Description
Production Profile	Unique ID of the profile that acts as the producer in this contract. Values are displayed in format identity name-profile name . Required.
Consumption Profile	Unique ID of the profile that acts as the consumer in this contract. It must match the Name field of the profile record. Values are displayed in format identity name-profile name. Required.
Business Process	Unique ID of the business process for this contract. Optional.

- 5. Do you plan to use the contract with EDI?
 - If Yes, go to step 6 to select an EDI extension.
 - If No, select None and click Next. Click Finish to complete the contract.
- 6. On the Extensions page, select one of the following extension types:
 - X12, complete the following fields and click **Next**:

X12 Extension Fields	Description
Sender ID	Coded identifier of the company or division sending the transaction. Valid value is 12 standard characters. Optional.
Receiver ID	Coded identifier of the company or division receiving the transaction. Valid value is 12 standard characters. Optional.
Interchange Test Indicator	Mode of operation mode to use for this extension. Required. Valid values are: • Test
	Production
	Information
Group Version Release ID Code	Release identifier for this version of the group. Valid value is 12 standard characters. Required.
Transaction Set ID Code	Coded identifier of transaction set. Valid value is three standard characters. Required.

• EDIFACT, complete the following fields and click Next.

EDIFACT Extension Fields	Description
Sender ID	Interchange ID as it should appear on the interchange header segment sent to this company or division. Valid value is 12 standard characters. Optional.
Receiver ID	Interchange ID as it should appear on the message group header received from this company or division. Valid value is 12 standard characters. Optional.
Message Type	Transaction message type as determined by the information type in the header of the message group, which includes the message or by the information type in the transaction message. Valid value is six standard characters. Optional.
Message Version Number	Version number of the standard message. Valid value is three standard characters. Optional.
Message Release Number	Release number of the standard message. Valid value is three standard characters. Optional.
Interchange Test Indicator	Mode of operation mode to use for this envelope. Optional.

• CII, complete the following fields and click Next.

CII Extension Fields	Description
Sender ID	Coded name of the company or division sending the message group. Valid value is 12 standard characters. Optional.
Receiver ID	Coded identifier of the company or division receiving the message group. Valid value is 12 standard characters. Optional.
BPIDOrganization	Code identifier of organization (for example, EIAJ) that manages the standard message types. Valid value is four standard characters. Optional.
BPIDSub Organization	Code identifier of he classification for the message types. Valid value is two standard characters. Optional.
BPIDEdition	Code identifier of the version of the message types. Valid value is two standard characters. Optional.
InformationIDCode	Type of the standard message. Valid value is four standard characters. Required.

 $\bullet\,$ ebXML (Electronic Business Extensible Markup Language), complete the following fields and click Next:

EbXML Extension Fields	Description
Message Order	Whether to preserve the order in which a trading partner sends messages to another trading partner. Required. Valid values are: Guaranteed Not Guaranteed
Ack Requested	Request an acknowledgement that notifies the sender that the receiver has received an interpretable interchange transmission. Required.Valid values are:
	• Always
	NeverPer message
Ack Signature Requested	Whether the trading partner receiving messages needs to sign the acknowledgement before sending messages back to the sender. Required. Valid values are: • Always • Never • Per message
Dup Elimination	Used by the trading partner sending messages to determine whether the receiving MSH must eliminate duplicates. Required. Valid values are Yes and No.

EbXML Extension Fields	Description
Use BPSS	Whether to use Business Process Specification Schema (BPSS), which provides a standard structure for defining a business process, with this extension. Required. Valid values are Yes and No.If you select Yes , complete the following fields:
	BPSS Name
	BPSS Version
	Binary Collaboration
	Production Profile Role
	Consumption Profile Role
BPSS Name	Identifying name of the BPSS to use with this extension. Required.
BPSS Version	Version of the BPSS to use with this extension. Valid value is 1.1. Required.
Binary Collaboration	List of all the binary collaboration in the BPSS chosen above. Valid values are based on the selected BPSS. Required.
Production Profile Role	exBXML role in the profile associated with the message producer for both the receiver (requestor) and sender (provider). Required.Valid values are: • requestor • provider
Consumption Profile Pole	
Consumption Profile Role	exBXML role in the profile associated with the message consumer profile to define the sender (provider). Optional. Valid value is provider.
Time to Acknowledge Receipt (min)	Amount of time, in minutes, within which you must receive an acknowledgment. Optional.
Time to Acknowledge Acceptance (min)	Amount of time, in minutes, within which you must receive an acknowledgment. Optional.
Time to Perform (min)	Amount of time, in minutes, starting from the initiation of RequestingBusinessActivity, that the initiator of the transaction must receive a response. Optional. Note: Responses are business documents associated with the RespondingBusinesActivity transaction.
Retry Count	Sterling Integrator continues to retry attempts to complete a business transaction before timing out and waiting for receipt acknowledgement. To disable this feature, clear the check box. Optional.

• ACH (Automated Clearing House) and complete the following fields and click **Next**:

ACH Extension Fields	Description
DestinationID	Routing number of the ACH Operator or receiving point to which the message is being sent. Required.
OriginID	Routing number of the ACH Operator or sending point that is sending the message. Required.

- 7. Click **Finish** to add the extension.
- 8. Click **Return** to continue.

Chapter 35. Update a Trading Partner Contract

About this task

To update a trading partner contract:

- 1. From the **Administration** menu, select **Trading Partner > Contracts**.
- 2. Under List All, click Go!
- 3. Click Edit next to the trading partner contract you want to make changes to.
- 4. Make desired changes and click **Next**, until you have reviewed all of the contract data.
- 5. Click Save.
- 6. Click Finish.
- 7. Click **Return** to continue.

Chapter 36. Delete a Trading Partner Contract

About this task

To delete a trading partner contract:

- 1. From the **Administration** menu, select **Trading Partner > Contracts**.
- 2. Under List All, click Go!
- 3. Click **Delete** next to the trading partner contract you want to make changes to.
- 4. Confirm the delete and click **OK**.
- 5. Click Next.
- 6. Click Delete.
- 7. Click **Return** to continue.

Chapter 37. Create a Code List

About this task

To create a code list:

- 1. From the Administration menu, select Trading Partner > Code Lists.
- 2. Next to New Code List, click Go!
- 3. Specify the Naming settings. In the Naming page, complete the following fields and click **Next**:

Naming Fields	Description
Code List Name	Name of the code list. Required.
Sender Identity	Name of the sender, from the list of identity records. Optional.
Receiver Identity	Name of the receiver, from the list of identity records. Optional.

- 4. In the Codes page, click add New Code to add a new pair of codes.
- 5. Specify the Input Code Data settings. In the Input Code Data dialog box, complete the following fields, and click **Save**:

Input Code Data Fields	Description
Sender Code	Code value of the sender that is cross-referenced to the code value of the receiver (for example, Blue). Required.
Receiver Code	Code value of the receiver that is cross-referenced to the code value of the sender (for example, Green). Required.
Description	Description of what the code of the sender and receiver refers to. Required.
Text1	Description or data relating to the sender and receiver code. Optional.
Text2	Description or data relating to the sender and receiver code. Optional.
Text3	Description or data relating to the sender and receiver code. Optional.
Text4	Description or data relating to the sender and receiver code. Optional.

- 6. Repeat steps 4 5 as needed to create additional code pairs. When you are finished, click **Next**.
- 7. Click **Finish** to add the code list.
- 8. Click Return to continue.

Chapter 38. Update a Code List

About this task

Each time you edit a code list or its code pairs, you create another version of the code list or code pair. To update a code list or a code pair, from the **Administration** menu, select **Trading Partner** > **Code Lists**:

- 1. Search for the code list you want to edit.
- 2. In the Code Lists search results page, click **source manager** next to the name used to identify code lists for a specific sender and receiver.
- 3. In the Code List Source Manager page, click edit next to the code list to lock it.
- 4. In the Naming page, click **Next**.
- 5. In the Codes page, click **edit** next to the pair of codes you want to edit.
- 6. Specify the Input Code data. In the Input Code Data dialog box, complete the following fields and click **Save**:

Input Code Data Fields	Description
Sender Code	Code value of the sender that is cross-referenced to the code value of the receiver (for example, Blue). Required.
Receiver Code	Code value of the receiver that is cross-referenced to the code value of the sender (for example, Green). Required.
Description	Description of what the code of the sender and receiver refers to. Required.
Text1	Description or data relating to the sender and receiver code. Optional.
Text2	Description or data relating to the sender and receiver code. Optional.
Text3	Description or data relating to the sender and receiver code. Optional.
Text4	Description or data relating to the sender and receiver code. Optional.

- 7. In the Codes page, click **Next**. Sterling Integrator uses the previously indicated pair of codes as the default version for this sender and receiver. If you want to specify this version as the default, select the version from the list under OTHER Versions.
- 8. Click **Next** to review the code pairs and click **Finish** to update the code list.
- 9. Click Return to continue.

Chapter 39. Change the Default Version of a Code List

About this task

To change the default version of a code pair of a code list:

- 1. From the Administration menu, select Trading Partner > Code Lists.
- 2. Search for the code list for which you want to create a new version.
- 3. In the Code Lists search results page, click **version manager** next to the name used to identify code lists for a specific sender and receiver.
- 4. In the Code List Version Manager page, next to code pair you want to set as the default code pair, click **Default**.
- 5. Click **Save**. The message "Schema status has been successfully updated." confirms that you have set the new default version of the code pair.
- 6. Click **Return** to continue.

Chapter 40. Search for a Code List

About this task

To search for a code list:

Procedure

- 1. From the Administration menu, select Trading Partner > Code Lists.
- 2. Enter the search criteria. In the Search portion of the Code List page, complete one or more of the following fields, and click **Go!**

Code List Search Fields	Description
Code List Name	Partial or complete name of the code list. Optional.
Sender Identity	Name of the sender, from the list of identity records. Optional.
Receiver Identity	Name of the receiver, from the list of identity records. Optional.

3. Review the code lists that are displayed. Click **Return** to continue.

Chapter 41. Enable a Code List

Before you begin

You must enable a code list to use it in a map.

About this task

To enable a code list:

- 1. From the Administration menu, select Trading Partner > Code Lists.
- 2. Search for the code list that you want to view.
- 3. Next to the code list, click **version manager**.
- 4. Under Enabled, verify that the check box is selected.
- 5. Click Save.
- 6. Click **Return** to continue.

Chapter 42. Copy a Code List

About this task

To copy a code list:

- 1. From the Administration menu, select Trading Partner > Code Lists.
- 2. Search for the code list you want to copy.
- 3. In the Code Lists search results page, click **copy** next to the code list you want to copy.
- 4. Specify the Naming settings. In the Naming page, complete the following fields and click **Next**:

Naming Fields	Description
Code List Name	Partial or complete name of the code list. Optional.
Sender Identity	Name of the sender, from the list of identity records. Optional.
Receiver Identity	Name of the receiver, from the list of identity records. Optional.

- 5. In the Codes page, click **add New Code** to add a pair of codes to the code list or click **edit** next to the pair of codes you want to edit.
- 6. Specify the Input Code data settings. In the Input Code Data dialog box, complete or edit the following fields and click **Save**:

Input Code Data Fields	Description	
Sender Code	Code value of the sender that is cross-referenced to the code value of the receiver (for example, Blue). Required.	
Receiver Code	Code value of the receiver that is cross-referenced to the code value of the sender (for example, Green). Required.	
Description	Description of what the code value of the sender and receiver refers to. Required.	
Text1	Description or data relating to the sender and receiver code. Optional.	
Text2	Description or data relating to the sender and receiver code. Optional.	
Text3	Description or data relating to the sender and receiver code. Optional.	
Text4	Description or data relating to the sender and receiver code. Optional.	

- 7. Click **Finish** to copy the code list.
- 8. Click **Return** to continue.

Chapter 43. Create a Version of a Code List

Before you begin

When you update a code list or its code pairs, you create another version of the code list or code pair.

About this task

To create a version of a code list:

- 1. From the Administration menu, select Trading Partner > Code Lists.
- 2. Search for the code list for which you want to create a new code pair.
- 3. In the Code Lists search results page, click **source manager** next to the name used to identify code lists for a specific sender and receiver.
- 4. In the Code List Source Manager page, next to Add New Code List Version, click Go!
- 5. In the Naming page, click **Next**.
- 6. In the Codes page, click add New Code.
- 7. Specify the Input Code data settings. In the Input Code Data dialog box, complete the following fields and click **Save**:

Input Code Data Fields	Description
Sender Code	Code value of the sender that is cross-referenced to the code value of the receiver (for example, Blue). Required.
Receiver Code	Code value of the receiver that is cross-referenced to the code value of the sender (for example, Green). Required.
Description	Description of what the code of the sender and receiver refers to. Required.
Text1	Description or data relating to the sender and receiver code. Optional.
Text2	Description or data relating to the sender and receiver code. Optional.
Text3	Description or data relating to the sender and receiver code. Optional.
Text4	Description or data relating to the sender and receiver code. Optional.

- 8. On the Codes page, click **Next**. Sterling Integrator uses the previously indicated code list as the default version for this sender and receiver. If you want to specify this version as the default, select the version from the list under OTHER Versions.
- 9. Click **Next** to review the new code pairs version and click **Finish** to update the code list.
- 10. Click Return to continue.

Chapter 44. Delete a Code List

About this task

To delete code list or a code pair:

- 1. From the Administration menu, select Trading Partner > Code Lists.
- 2. Search for the code list that contains the code pair to delete.
- 3. In the Code Lists search results page, click **source manager** next to the name used to identify code pair in a specific code list.
- 4. Next to the code pair, under Delete, select the check box.
- 5. Next to Delete Selected Versions, click Go!, and then click OK.
- 6. In the Resource Summary page, review the code pair information, and then click **Next**.
- 7. In the Confirm page, **Delete** to delete the code pair from the code list.
- 8. Click **Return** to continue.

Chapter 45. Delete Versions of a Code List

About this task

You can delete an individual code list version or all versions of a code list. To delete an individual code list or versions of a code list:

- 1. From the Administration menu, select Trading Partner > Code Lists.
- 2. Search for the code list that contains the version or versions you want to delete.
- 3. Next to the code list, click source manager.
- 4. To delete an individual code list version:
 - a. Next to version, under Delete, select the check box.
 - b. Next to Delete Selected Versions, click Go!
- 5. To delete all versions of this code list, next to Delete All Versions, click Go!
- 6. Click Delete.

Chapter 46. Configure the Basic Customer Import File System Adapter

About this task

To configure the BasicCustomerImport_FSA:

- 1. From the **Deployment** menu, select **Services > Configuration**.
- 2. Next to Service Name, type Basic and click Go!
- 3. Next to BasicCustomerImport_FSA, click Edit.
- 4. On the Name page, click **Next**. Do not change the information on this page or the adapter will not work as designed.
- 5. On the Collection page, click **Next**. Do not change the information on this page or the adapter will not work as designed.
- 6. On the Business Process page, click **Next**. Do not change the information on this page or the adapter will not work as designed.
- 7. On the Schedule Type page, configure the parameters to your requirements and click **Next**.
- 8. On the Schedule Settings page, configure the parameters to your requirements and click **Next**. The parameters which are displayed depend on the selections you made for Schedule Type.
- 9. On the Schedule Exclusions page, configure the parameters to your requirements and click **Next**. The parameters which are displayed depend on the selections you made for Schedule Type.
- 10. On the Extraction page, click Next. The fields on this page (listed below for your reference) do not require configuration. The field names in parentheses represent the corresponding field names in the Graphical Process Modeler. This information is provided for your reference.
- 11. On the Confirm page, configure the parameter to your requirements and click **Finish**.
- 12. Click Return to continue.

Chapter 47. Import Trading Partner Data as a File Containing Envelopes and/or Control Numbers

About this task

To import a file containing envelopes and/or control numbers:

- 1. From the **Deployment** menu, select **Resource Manager** > **Import/Export**.
- 2. On the Import/Export page, next to Import Resources, click Go!
- 3. Type the name of the file containing the envelopes or control numbers to import, or use **Browse** to locate and select it by clicking **Open**, and click **Next**. If the import file contains errors, you can either select the file and click **Next** again to continue the import, or click **Cancel** to stop the import process.
- 4. If the exported file used a resource tag, type a name and description for the new resource tag and click **Next**.
- 5. Indicate whether you want to update objects that may already exist in Sterling Integrator with objects from the import (the default is Yes), and click **Next**.
- 6. On the TP Envelopes screen, indicate whether you want to **Keep existing control numbers** (the default is **No**, which specifies that the control numbers in the import file will be imported).
- 7. From the lists, select resources to import for each resource type, move the resources to the **To be imported list**, and click **Save** when you have selected all the necessary resources. If you select more than one resource type to import, you must repeat this step for each resource type.
 - **Note:** Some resources may require you to type the passphrase (created during export) before completing the import.
- 8. If you are importing a file or files that contains control numbers, the TP Control Numbers screen is displayed. Select the appropriate options and click **Next**.
 - **Note:** The option that you selected for **Keep existing control numbers** on the TP Envelopes screen will be used for the control numbers as well.
- 9. To update Sterling Integrator with the imported file or files, click **Finish**. This process may take several minutes, depending on the number and size of the libraries being imported.
- 10. When the message, The system update completed successfully displays, click View Import Report to see the import report. If errors occurred during import, next to Data which failed to Import, click Download to view the XML file containing the names of the objects that did not import. This option displays only when the import completed with errors.
- 11. To create a backup of the data as it existed prior to import, next to **Data in SI** before Import, click **Download**.
- 12. In the **Save As** dialog box, change the default filename, backup.xml, to a unique, meaningful name for this backup, and then click **Save**.
- 13. Click Return to continue.

Chapter 48. Import Trading Partner Data Through the Basic Import Utility

About this task

To import a file containing document envelopes or control numbers (or both) from the command line:

Procedure

- 1. Change to the *install_dir*/tp_import directory.
- 2. Run one of the following commands: ./import.sh -input [input filename] (UNIX)

import.cmd -input [input filename] (Windows)

Note: *Input filename* is the name of the XML file you want to import. This is a mandatory parameter used with the Import utility.

./import.sh -batch [input filename] (UNIX) import.cmd -batch [input filename] (Windows)

Note: *Input filename*, when you are running a batch import, indicates that each line in file name is a separate import (XML file) to run. This is a mandatory parameter used with the Import utility.

All the available parameters are listed in the following table:

Option	Description	
-input [input filename]	Specifies the name of the XML file to import. Mandatory. Example: import.sh -input testEnvelopeThis parameter is mutually exclusive from the -batch parameter (use either the -input parameter or the -batch parameter). An error will be generated if the input file name is not provided.	
-batch[input filename]	Specifies the name of the file to import. Mandatory. Example: import.sh -batch testEnvelopeThis parameter is mutually exclusive from the -input parameter (use either the -input parameter or the -batch parameter). An error will be generated if the input file name is not provided.	
-update	Indicates the system will update the existing trading partner profiles. Optional; if not present, the existing records remain unchanged.	
-backup [filename]	Name of the file in which the backup of the updated records is stored. Optional; if not present, the backup records are not saved.	
-errors [filename]	Name of the file in which records that Sterling Integrator failed to process are stored. Optional; if not present, the errors records are not saved.	

Option	Description
-passphrase [passphrase]	Password used to import entities into Sterling Integrator. Optional. Note: This is the passphrase that was used during export.
-pre32passphrase [passphrase]	Password used to import some encrypted resources into Sterling Integrator, if the file was exported Sterling Integrator prior to version 3.2. Optional. Note: This is the system passphrase of the Sterling Integrator version prior to version 3.2 from which the file was exported.
	Example: import.sh -input [input filename] -pre32passphrase [system passphrase from system where exported] -passphrase [passphrase entered by user during export]
-privatecerts	Indicates that private key certificates will be imported any are found. Optional.
-report [filename]	Specifies the path to the report file. The default is import.rpt or batchimport.rpt. Optional.
-resourcetag [resource tag]	Specifies the resource tag for the imported resources. Specify USETAGININPUTFILE to apply the resource tag contained in the input file. Optional.
-KeepExistingControlNumbers	Indicates whether you want to keep existing control numbers. If you use this parameter, it specifies that for existing envelopes and control numbers, control number values in the import file will not be imported. If a version of an envelope or control number being imported already exists in the system, the import process will overwrite the value specified in import file with the existing control number value for that envelope or control number. If you do not specify this parameter, the control numbers in the import file will be imported.
-x	Specifies not to return an exit code. Optional. By default, the utility returns an exit code.
-h -?	Displays the help screen.

Chapter 49. Import Trading Partner Data as a CSV File

Before you begin

Before you import, if you need to import partner information that will cause overwrites, perform the following steps:

- 1. Export the CSV file.
- 2. Run basicimport.sh or basicimport.cmd without the *-import* parameter to create the XML file.
- 3. Import the XML file into Sterling Integrator through the Resource Manager, which will present you with the option to specify whether objects that already exist in Sterling Integrator should be overwritten.

About this task

To import a CSV file from the command line:

Procedure

- 1. Change to the *install_dir*/tp_import directory.
- 2. Run one of the following commands: ./basicimport.sh -import [</path and input CSV filename>] (UNIX)

basicimport.cmd -import [</path and input CSV filename>] (Windows)

Note: When you run the Basic Import Utility with the -import parameter, the utility updates any existing files (if, for example, you previously imported the a CSV file with the same name as the one you are currently converting and importing). If you do not use the -import parameter, the utility will convert the CSV file to XML and you can import the XML file to Sterling Integrator using the Resource Manager Import interface. Using the Resource Manager enables you to specify not to update existing items. See *Importing Resources* for more information on using the Resource Manager.

The available parameter is listed in the following table:

Option	Description
-import []	Specifies the name of the CSV file to import. Mandatory. Example: basicimport.sh -import c:\import\CSVtestIf you do not use the -import parameter, the utility will convert the CSV file to XML and you can import the XML file to Sterling Integrator using the Resource Manager Import interface.

Chapter 50. Export Trading Partner Data Using the Command Line

About this task

To export a file from the command line:

Procedure

- 1. Change to the <code>install_dir/tp_import</code> directory.
- 2. Run one of the following commands: ./export.sh -input [input filename] (UNIX)

export.cmd -input [input filename] (Windows)

Input filename is the name of the XML file you want to export. This is a mandatory parameter.

All the available parameters are listed in the following table:

Option	Description
-input [filename]	Name of the file that contains the objects to be exported. Mandatory. The properties file describing which resources to be exported should have the following format. RESOURCE_TYPE[1] = ALLor
	RESOURCE_TYPE[1] = ResourceNameA RESOURCE_TYPE[2] = ResourceNameB RESOURCE_TYPE[3] = ResourceNameC
	The RESOURCE_TYPE is the name of the resource as defined by tp_import_export.properties. If a resource has a subtype, then the specific subtype name must be used. The following is an example properties file to export all EDI envelopes and maps from the system. DOCUMENT_ENVELOPES[1]=ALL MAPS[1]=ALL
	Available resource types include: BPDEFS, SCHEMAS, XSLTS, SERVICE_INSTANCES, USERS, GROUPS, PERMISSIONS, PGPPROFILES, SCHEDULES, SCI_CA_CERTS, SCI_TRUSTED_CERTS, SCI_PRIVATE_KEY_CERTS, MAPS, CD_NETMAPS, ProxyServers, PGP_PARTNERS, PGP_SPONSORS, BANDWIDTH_THROTTLING, COMMAND_LIMITING, LOCKOUT, DATA_LIMIT, ADAPTER_MAPPING, APP_CONFIGURATIONS, SCI_PACKAGES, SCI_ENTITIES, CONTRACTS, CODE_LISTS, XFORMS, WEB_JSP_FILES, WEB_JAVASCRIPT_FILES, WEB_HTML_FILES, WEB_IMAGES, WEB_PROPERTY_FILES, WEB_STYLESHEETS, WEB_OTHER_FILES, WSDL, MBXVIRTUAL, MBXMETA, MBXROUTING, EBXMLBPSS, EBXMLBPSSEXT, EBXMLCPA, PSERVERS, REPORT_CONFIGS, SCI_SSH_REMOTE_PROFILES, SCI_SSH_HOST_USER_IDENTITY_KEYS, SCI_SSH_AUTHORIZED_USER_KEYS, SECURITY_TOKENS, EXTENDED_RULE_LIBRARIES, POLICIES, PROXY_NETMAPS, SWIFT_NET_ROUTING_RULES, EB_Host, EB_Partner, EB_User, EB_File_Format, EB_Ord_Type, EB_Offer, Agreements, COMMUNITIES, DOCUMENT_ENVELOPES, CONTROL_NUMBERS, SWIFTNET_ROUTING_RULES, SWIFTNET_SVC_PROFILES, SWIFTNET_COPY_PROFILES, AS3Profiles, AS3Contracts
-tag [tagname]	Resource tag name to associate with the export file. This will be the default tag created when importing. Optional
-output [filename]	Name of the file that contains the exported data (use .xml as the file extension). Optional.
-report [filename]	Name of the file that contains a report if there were in errors during the export. Optional.
-doCerts [filename]	Name of the file used to export transport and certificates. Optional.
-passphrase [passphrase]	Password used to export transport and certificates. Optional. Note: This is the passphrase that was used during export.
-allversions	Used to export all versions from the system. Optional.

Chapter 51. Import Service GPM or the Workflow Context

The Import service exercises the same functionality as the Import Resources option in the Resource Manager. When using the Import service, all available resources are imported, and all imported versions are set as the defaults, where applicable.

There is a new parameter when you configure the Import service through the GPM, **Keep existing control numbers**. The default for this parameter is **No**, which specifies that the control numbers in the import file will be imported.

If you change the **Keep existing control numbers** parameter to **Yes**, then it specifies that for existing envelopes and control numbers, control number values in the import file will not be imported. If a version of an envelope or control number being imported already exists in the system, the import process will overwrite the value specified in the import file with the existing control number value for that envelope or control number.

Note: You can specify whether to keep existing control numbers in through the GPM or BPML, but you cannot alter this parameter through the Sterling Integrator user interface.

As an alternative to changing the value for the Import Service **Keep existing control numbers** parameter to **Yes**, you can add the following to the raw BPML workflow context (the workflow context (WFC) represents the business process state after each service has run):

Chapter 52. Import Trading Partner using Basic Import Utility Process

About this task

The Basic Import Utility uses the following process flow:

Procedure

- 1. Place a CSV file in the <code>install_dir/tp_import/basic_customer_import_collect</code> directory.
- 2. The BasicCustomerImport_FSA file system adapter scans this directory and picks up the CSV file on a scheduled basis.
- 3. The BasicCustomerImport_FSA file system adapter initiates the predefined business process (BasicCustomerImport.bp).
- 4. The Basic Customer Import business process runs the import translation map (BasicCustomerImport.txo) and initiates the Import service.
- 5. The Import service imports the converted XML file into Sterling Integrator.

Results

If exceptions occur when running the Basic Import Utility, Sterling Integrator includes this information in the basic import report (BasicImportReport.rpt, in XML format), located in the <code>install_dir/tp_import</code> directory, which is generated after the Basic Import utility is run.

Chapter 53. CSV File Layout

Your CSV file must conform to the file layout for the BasicCustomerImport map.

Note: Or, using the Map Editor, you can modify the BasicCustomerImport map as necessary so it conforms to your file layout (add map components, delete map components, and so forth). You will then need to compile the map (save it using the same name or modify the name of the translation map that is called by the Basic Customer Import business process) and check it in to Sterling Integrator.

The file layout is as follows:

Tag,Company_Name,Reference_URL,DUNS_Number,Address_1,Address_2,City,State,Zip_Code,
TimeZone,Country,Email address,Phone number

Note: The appropriate values for the above fields are the same as when you type information in these fields using the Sterling Integrator Trading Partner interface.

An example of data in this format is as follows:

A,RomansFloorsAndMore,www.romansfloors.com,01234567899,13
Measle Lane,2nd Floor,Powell,OH,43065,-05,US,roman@romansfloors.com,614-555-1212

Chapter 54. Exit Codes

These import utilities return the following exit codes:

Exit Code	Description	
0	The import completed with success status.	
1	The import completed with error status.	
	The Import utility reached timeout while waiting for status.	

Chapter 55. Test an HTTP Profile

You can test the HTTP profile by going to the Trading Partner Profile screen in the Admin Console and selecting **Test Now** next to the profile you want to verify. The **TestNow** option enables you to verify that a new or updated trading partner profile that uses HTTP as the communications protocol is working correctly. For additional information about TestNow, see *Using the AS2 and HTTP TestNow Feature*.

Notices

This information was developed for products and services offered in the U.S.A.

IBM® may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing

IBM Corporation

North Castle Drive

Armonk, NY 10504-1785

U.S.A.

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing

Legal and Intellectual Property Law

IBM Japan Ltd.

19-21, Nihonbashi-Hakozakicho, Chuo-ku

Tokyo 103-8510, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be

incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation

J46A/G4

555 Bailey Avenue

San Jose, CA 95141-1003

U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

All IBM prices shown are IBM's suggested retail prices, are current and are subject to change without notice. Dealer prices may vary.

This information is for planning purposes only. The information herein is subject to change before the products described become available.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work, must include a copyright notice as follows:

© IBM 2013. Portions of this code are derived from IBM Corp. Sample Programs. © Copyright IBM Corp. 2013.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

Trademarks

IBM, the IBM logo, and ibm.com[®] are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at http://www.ibm.com/legal/copytrade.shtml.

Adobe, the Adobe logo, PostScript, and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

IT Infrastructure Library is a registered trademark of the Central Computer and Telecommunications Agency which is now part of the Office of Government Commerce.

Intel, Intel logo, Intel Inside, Intel Inside logo, Intel Centrino, Intel Centrino logo, Celeron, Intel Xeon, Intel SpeedStep, Itanium, and Pentium are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

ITIL is a registered trademark, and a registered community trademark of the Office of Government Commerce, and is registered in the U.S. Patent and Trademark Office.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Java[™] and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Cell Broadband Engine is a trademark of Sony Computer Entertainment, Inc. in the United States, other countries, or both and is used under license therefrom.

Linear Tape-Open, LTO, the LTO Logo, Ultrium and the Ultrium Logo are trademarks of HP, IBM Corp. and Quantum in the U.S. and other countries.

Connect Control Center®, Connect:Direct®, Connect:Enterprise®, Gentran®, Gentran®:Basic®, Gentran:Control®, Gentran:Director®, Gentran:Plus®, Gentran:Realtime®, Gentran:Server®, Gentran:Viewpoint®, Sterling Commerce™, Sterling Information Broker®, and Sterling Integrator® are trademarks or registered trademarks of Sterling Commerce®, Inc., an IBM Company.

Other company, product, and service names may be trademarks or service marks of others.

IBM.

Product Number:

Printed in USA