## **GENTRAN:Server®**

Application Integration: HIPAA Compliance and NCPDP User's Guide

Version 6.0



## **Copyright Notice**

#### February 2002

© Copyright 2002

Sterling Commerce, Inc.

ALL RIGHTS RESERVED


## WARNING: ANY UNAUTHORIZED DUPLICATION OF THIS DOCUMENTATION SHALL BE AN INFRINGEMENT OF COPYRIGHT.

#### **Trade Secret Notice**

This documentation, the software it describes, and the information and know-how they contain constitute the proprietary, confidential and valuable trade secret information of Sterling Commerce, Inc., its affiliated companies or its or their licensors, and may not be used for any unauthorized purpose, or disclosed to others without the prior written permission of the applicable Sterling Commerce entity. This documentation and the software that it describes have been provided pursuant to a license agreement that contains prohibitions against and/or restrictions on their copying, modification and use. Duplication, in whole or in part, if and when permitted, shall bear this notice and the Sterling Commerce, Inc. copyright notice. As and when provided to any governmental entity, government contractor or subcontractor subject to the FARs, this documentation is provided with RESTRICTED RIGHTS under Title 48 CFR 52.227-19. Further, as and when provided to any governmental entity, government contractor or subcontractor subject to DFARs, this documentation and the software it describes are provided pursuant to the customary Sterling Commerce license, as described in Title 48 CFR 227-7202 with respect to commercial software and commercial software documentation.

This documentation and the software which it describes are licensed either "AS IS" or with a limited warranty, as set forth in the applicable license agreement. Other than any limited warranties provided, NO OTHER WARRANTY IS EXPRESSED AND NONE SHALL BE IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR USE OR FOR A PARTICULAR PURPOSE. The applicable Sterling Commerce entity reserves the right to revise this publication from time to time and to make changes in the content hereof without the obligation to notify any person or entity of such revisions or changes.

Product names mentioned herein may be trademarks and/or registered trademarks of their respective companies. GENTRAN and GENTRAN:Server are registered trademarks of Sterling Commerce, Inc.



# **Table of Contents**

| About T     | his Guide  |
|-------------|--|
| )<br>)<br>) | Introduction.viWhat's in This ManualviiRelated Publications.ixHow to Get Help.xiiDocumentation Conventionsxv |
| GENTR       | AN:Server  |
| HIPAA :     | Support Features   |
| )<br>Proce  | Overview   |
| •           | How to Set Up Security on a Workstation PC   |
| •           | How to Set Up Security on a UNIX Host Server and Client PCs 1-7  |
| •           | How to Access GENTRAN:Server in an Emergency1-9  |
| Introduc    | ction to Using NCPDP with GENTRAN:Server   |
| Overv       | riew   |
| •           | Terms Used in the NCPDP Standard   |
| •           | Supported NCPDP Version and Transactions   |
| •           | Transaction Types: Requests and Responses  |
| •           | NCPDP Transaction Syntax 2-10  |
| •           | Six Key Fields for Trading Partnership Code  |
| NCPD        | P Batch Transmissions  |
| •           | Overview   |
| •           | Parts of an NCPDP Batch Transmission   |
| •           | Batch Transaction Header Segment   |
| •           | Batch Detail Data Record   |
| •           | Transaction Header Segment   |
| •           | Batch Trailer Segment  |

## **Creating NCPDP Maps**

| Over    | view   |              |
|---------|--|--------------|
| •       | Introduction                                   | . 3-2        |
| Prepa   | aring for Mapping                              |              |
| •       | The NCPDP Standard Templates                   | . 3-3        |
| •       | How to Copy the NCPDP Templates                | . 3-4        |
| •       | Setting Up for NCPDP Translation               | . 3-5        |
| •       | How to Analyze the NCPDP Data                  | . 3-6        |
| Creat   | ting an NCPDP Map                              |              |
| •       | NCPDP Map Components                           | . 3-8        |
| •       | How to Create an Inbound NCPDP Map             | 3-10         |
| •       | Inbound NCPDP Translation Process              |              |
| •       | How to Create an Outbound NCPDP Map            | 3-14         |
| •       | Outbound NCPDP Translation Process             | 3-17         |
| Structu | ring an NCPDP Map                              |              |
| Over    | view   |              |
| •       | Introduction                                   | . 4-3        |
| •       | NCPDP Map Structure                            | . 4-4        |
| •       | Field Format Values                            | . 4-6        |
| Dialo   | og Boxes                                       |              |
| •       | NCPDP File Properties Dialog Box               | . 4-8        |
| •       | NCPDP Group Properties Dialog Box              | 4-14         |
| •       | NCPDP Positional Segment Properties Dialog Box | 4-19         |
| •       | NCPDP Positional Field Properties Dialog Box   | 4-26         |
| •       | NCPDP Delimited Segment Properties Dialog Box  | 4-36         |
| •       | NCPDP Delimited Field Properties Dialog Box    | 4-41         |
| •       | NCPDP Count Field Properties Dialog Box        | 4-49         |
| •       | NCPDP Counter Field Properties Dialog Box      | 4-53         |
| Proce   | edures   |              |
| •       | Defining an NCPDP Batch File                   | 4-57         |
| •       | Loading an NCPDP Template                      |              |
| •       | Manually Creating NCPDP Map Components         | 4-59         |
| •       | How to Configure NCPDP File Properties         | 4-61         |
| •       | How to Create the Batch Header Segment         | 4-65         |
| •       | How to Create the Batch Detail Data Segment    |              |
| •       | How to Create a Transaction Header Segment     |              |
| •       | How to Create the Batch Trailer Segment        | 4-72         |
| •       | How to Create a Group                          | 4-74         |
|         | How to Create a Positional Segment             | <i>1</i> _78 |

| •        | How to Create a Delimited Segment                           | 33 |
|----------|---|----|
| •        | How to Create a Positional Field                            | 38 |
| •        | How to Create a Delimited Field                             | )2 |
| •        | Repeating Fields  | )7 |
| •        | How to Create a Count Field                                 | )9 |
| •        | How to Create a Counter Field                               | 2  |
| Creating | g NCPDP Trading Partnership Records                         |    |
| Overv    | iew   |    |
| •        | Introduction 5-   | -2 |
| •        | NCPDP Trading Partnership Records                           | -3 |
| Tradir   | ng Partnership Dialog Boxes                                 |    |
| •        | Interchange Organization Dialog Box                         | -5 |
| •        | Group Organization Dialog Box                               | -7 |
| •        | Trading Partnership Editor Dialog Boxes 5-                  | -9 |
| •        | Batch Transaction Information Dialog Box                    |    |
| •        | NCPDP Transaction Request Header Information Dialog Box 5-2 |    |
| •        | NCPDP Transaction Response Header Information Dialog Box    | 23 |
| Proce    |   |    |
| •        | How to Create Inbound NCPDP Trading Partnership Records     |    |
| •        | How to Create Outbound NCPDP Trading Partnership Records    |    |
| •        | How to Set Batch Transaction Information                    |    |
| •        | How to Configure the Transaction Request Header             |    |
| •        | How to View the Transaction Response Header                 | 36 |
| Batch T  | ransaction Sets   |    |
| •        | Batch Transaction Header A-                                 | -2 |
| •        | Batch Detail Data Record                                    | -3 |
| •        | Batch Trailer Record  | -4 |
| •        | Request Transaction Header Segment                          | -5 |
| •        | Response Transaction Header Segment                         | -6 |
| Index    |   |    |



# **About This Guide**

#### **Contents**

| • | Introduction              | ٧  |
|---|---------------------------|----|
| • | What's in This Manual     | ٧  |
| • | Related Publications      | į  |
| • | How to Get Help           | Х  |
| • | Documentation Conventions | X۱ |

### Introduction

#### Welcome

Welcome to the GENTRAN:Server<sup>™</sup> for UNIX<sup>®</sup> and GENTRAN:Server for Workstation *HIPAA Compliance and NCPDP User's Guide* for the Application Integration subsystem.

NCPDP is the National Council of Prescription Drug Programs standard for the electronic exchange of documents.

HIPAA refers to the federally mandated Health Insurance Portability and Accountability Act. This legislation requires that health care providers and insurers use the NCPDP standard for electronic transmissions.

The HIPAA Compliance and NCPDP User's Guide provides you with the information you need to develop maps that translate:

- Your application files to an NCPDP standard format for documents you send to your trading partners (outbound mapping)
- An NCPDP standard format to your application format for documents that you receive from your trading partners (inbound mapping)

We believe that you will find this software and the supporting materials easy to use and directly beneficial to your business.

## What's in This Manual

#### **Assumptions**

This manual assumes that you are familiar with using a PC and with Microsoft<sup>®</sup> Windows functions, including the terminology used to describe:

- Mouse and cursor actions.
- Windows-specific attributes, such as dialog boxes, icons, windows, and buttons.

This manual also assumes that you are familiar with your internal application format, data mapping concepts, and the GENTRAN:Server for UNIX or Workstation product.

In addition, you should be familiar with the NCPDP Telecommunication Standard Format 5.0.

# Description of contents

The *HIPAA Compliance and NCPDP User's Guide* is organized into chapters. This table describes the contents.

| Chapter  | Description   |
|--|---|
| About This Guide                               | Introduces the content, organization, and conventions in this guide. This chapter also describes how to get technical support.  |
| HIPAA Compliance<br>Features                   | Describes the features of GENTRAN:Server designed to help you comply with HIPAA.  |
| Introduction to Using NCPD with GENTRAN:Server | Introduces you to the GENTRAN:Server features that support mapping and translation of data that is in the NCPDP format.   |
| Creating NCPDP<br>Maps                         | Provides instructions for creating inbound NCPDP and outbound NCPDP maps.   |
| Structuring an NCPDP Map                       | Explains how to define the components of an NCPDP batch file and provides instructions for creating special map components, such as repeating fields and binary segments. |
| Creating NCPDP Trading Partnership             | Provides instructions for creating NCPDP Trading Partnership records.   |
| Records  | (Continued on next page)  |

| (Contd)<br>Chapter | Description   |
|--------------------|---|
| Appendix A         | Describes the fields in the batch records and transaction header segments.                        |
| Glossary           | Defines the key terms used in this guide.   |
| Index              | Lists terms, concepts, functions, and processes to enable you to quickly find them in this guide. |

#### Online Help System

Additional documentation for GENTRAN:Server for UNIX is contained in the online Help system. The online Help documentation includes all the dialog box element definitions, detailed processing information, and all the "how to" information contained in this manual.

## **Related Publications**

# **GENTRAN:Server** documentation

This table describes additional documentation for the GENTRAN:Server software.

| Document  | Description  |
|---|--|
| Upgrade and<br>Conversion Guide                               | Instructions for upgrading from previous versions of GENTRAN:Server Workstation and GENTRAN:Server for UNIX. Also includes instructions for converting the files that are part of the upgrade. |
| GENTRAN:Server for<br>UNIX Installation and<br>Setup Guide    | Instructions for installing the GENTRAN:Server software and performing setup tasks, such as setting up security.   |
| GENTRAN:Server<br>Workstation<br>Installation<br>Instructions | Instructions for installing the GENTRAN:Server Workstation software and performing setup tasks.  |
| Getting Started Guide   | Instructions for starting and exiting GENTRAN:Server and for setting preferences and default values. Also includes instructions for checking files in and out and saving files.                |
| Application<br>Integration User's<br>Guide                    | Instructions for performing mapping and translation tasks.   |
| NCPCP User's Guide  | Instructions for mapping and translating NCPDP files with the Application Integration system.  |
| XML User's Guide  | Instructions for mapping and translating XML files with the Application Integration system.  |
|   | Note This guide is provided only if your organization has the GENTRAN:Server XML translation option.   |
| ODBC User's Guide   | Instructions for mapping and translating ODBC files with the Application Integration system.   |
|   | Note This guide is provided only if your organization has the GENTRAN:Server ODBC translation option.  |
|   | (Continued on next page)   |

| (Contd)<br>Document                         | Description   |
|---|---|
| GENCOD User's<br>Guide                      | Instructions for mapping and translating GENCOD files with the Application Integration system and the Visual Mapper.  |
| VDA User's Guide                            | Instructions for mapping and translating VDA files with the Application Integration system and the Visual Mapper.   |
| Technical Reference<br>Guide                | Describes processes, lists command-line commands in alphabetical order, and describes file record layouts and data type formats.  |
| Data Flow<br>Administration Guide           | User instructions for configuring data flows using the GENTRAN:Server for UNIX software.  |
|   | Note This guide is provided only if you have the GENTRAN:Server EC Workbench or higher product level.   |
| Maintenance and<br>Troubleshooting<br>Guide | Instructions for maintaining your GENTRAN:Server installation. Also provides troubleshooting information to help determine the cause and solution of problems that may occur.   |
| Advanced Data<br>Distribution Guide         | Instructions for configuring and using the GENTRAN:Server Advanced Data Distribution product.   |
|   | Note This guide is provided only if you have GENTRAN:Server with Advanced Data Distribution.  |
| FTP Daemon User's Guide                     | Instructions for configuring and using the FTP Daemon tool with the Advanced Data Distribution product.   |
| Online Help                                 | Context-sensitive help screens describing the GENTRAN:Server dialog boxes for the mapping and translation features. Also includes procedures for using the mapping and translation and the data flow administration software. |
| Readme file                                 | Information about recent enhancements included with this software release. This file is in the /readme directory on the Windows client computer.  |

# Other documentation

This table lists other documentation you may need to refer to when installing and setting up GENTRAN:Server.

| Description  | Source  |
|--|---|
| Instructions for installing and using the operating system on your computer. | Your hardware vendor  |
|  | The computer manufacturer   |
| Information about the NCPDP format   | Publications from the National Council for Prescription Drug Programs, such as:   |
|  | <ul> <li>Telecommunication Standard<br/>Implementation Guide for NCPDP</li> </ul> |
|  | <ul><li>Telecommunication Standard<br/>Specifications for NCPDP</li></ul>         |
|  | <ul><li>Batch Transaction Standard for<br/>NCPDP</li></ul>                        |
|  | <ul> <li>Batch Standard Batch<br/>Implementation Guide for NCPDP</li> </ul>       |
|  | Data dictionary for NCPDP   |

## **How to Get Help**

#### Introduction

This topic explains how to contact Sterling Commerce Product Support if you need assistance with GENTRAN:Server.

#### Scope of Support Services

Sterling Commerce Product Support can provide assistance and information for the following:

- Installing GENTRAN:Server
- GENTRAN:Server product questions
- Software revisions and upgrades
- Implementing a specific feature
- ▶ How to use GENTRAN:Server
- The status of your support call
- Requests for product enhancements

Unfortunately, Sterling Commerce Product Support cannot assist you with problems involving the following, but we may be able to suggest a next step or another vendor to call:

- Your hardware
- Your operating system or other system software
- Your application or user-written programs
- Software not developed by Sterling Commerce
- Scripts written by Sterling Commerce consultants or service partners

#### Try this first

Before you call Sterling Commerce Product Support, use your online software manuals to locate the section that documents the program or feature where you are having problems. The documentation may explain the software's behavior or give you insight to help you solve the problem.

Consult the *GENTRAN:Server Maintenance and Troubleshooting Guide* to learn if your specific problem has been addressed.

#### Copy this page

Please feel free to make a copy of this page to enable you to contact support quickly and with complete information for the Customer Support Representative.

# **Necessary** information

Be ready to provide this information when you call Product Support.

| Your name  |           |
|--|-----------|
| Your company name                                  |           |
| Your telephone number                              |           |
| Your GENTRAN:Server version number                 |           |
| Your GENTRAN:Server product level and platform     |           |
| Any software add-ons to your GENTRAN:Server system |           |
| A detailed description of the problem              | avt nage) |
| (Continued on ne                                   | ext page) |

| The sequence of steps that led to the problem                         |  |  |
|---|--|--|
|   |  |  |
|   |  |  |
|   |  |  |
|   |  |  |
|   |  |  |
| What actions you have taken to try to diagnose or resolve the problem |  |  |
|   |  |  |
|   |  |  |
|   |  |  |
|   |  |  |
|   |  |  |

# How to contact support

To determine how to contact support for your geographical location, go to the Sterling Commerce home page (www.sterlingcommerce.com) and then go to Customer Support for GENTRAN.

## **Documentation Conventions**

# Typographic conventions

This table describes the typographic conventions used in this guide.

| Convention | Use  |
|------------|--|
| Italics    | This typeface is used for titles of other manuals and documents, names of files and file extensions, and to emphasize important information. |
|            | Example GENTRAN:Server Getting Started Guide   |
| Bold       | Bold type is used for program names, menu names, button names, and entries you are to make on-screen.  |
|            | <b>Example</b> A <b>password</b> is a set of characters a user must enter to gain access to a system.  |

# **GENTRAN:**Server HIPAA Support Features

| Contents | •        | Overview  |
|----------|----------|---|
|          | Procedur | es  |
|          | •        | How to Set Up Security on a Workstation PC                    |
|          | •        | How to Set Up Security on a UNIX Host Server and Client PCs 7 |
|          | •        | How to Access GENTRAN:Server in an Emergency                  |
|          |          |   |

#### Overview

#### Introduction

The Health Insurance Portability and Accountability Act of 1996 (HIPAA) requires that various health care plans, and health care providers and clearinghouses meet certain data security and other types of mandates for electronic health care transactions.

Your GENTRAN:Server product provides features to help you meet HIPAA requirements. These are GENTRAN:Server's compliance features:

- Support for the electronic data interchange standards that HIPAA requires
- Provision for automatic logoff
- Provision for emergency access to the system

#### **IMPORTANT**

To comply with the HIPAA mandates listed above, you must implement the features as described in this guide. You will not be in compliance if you bypass or modify these features.

# Turning on HIPAA features

When you install your GENTRAN:Server product, you must choose the HIPAA compliance option to enable the HIPAA features in the product.

## Supported standards

GENTRAN:Server supports the national electronic data interchange (EDI) standards for electronic health care transactions adopted in HIPAA. These are:

- ANSI ASC X12N standards, Version 4010, for all transactions except retail pharmacy transactions. Certain ASC X12 transaction sets include binary segments. GENTRAN:Server is able to process binary segments that are part of a supported standard.
- NCPDP Telecommunications Standard, Version 5.1 (batch version). GENTRAN:Server is able to process repeating elements that are part of this standard.

#### **Automatic logoff**

The Health Insurance Portability and Accountability Act (HIPAA) requires software systems that display patient information to automatically exit when not in use. The purpose of this requirement is to prevent unauthorized persons from viewing and gaining access to the system.

**Overview** 

To help you protect the confidentiality of individual health information, GENTRAN:Server enables you to configure your system to automatically exit after a specified time has elapsed with no activity.

This feature is implemented differently in GENTRAN:Server Workstation and GENTRAN:Server for UNIX client/server products.

# **Emergency** access

HIPAA requires that software systems provide a means to by-pass security in emergency situations.

GENTRAN:Server for UNIX client/server products provide for emergency access.

## **Procedures**

## How to Set Up Security on a Workstation PC

#### Introduction

If you are running GENTRAN: Server for Workstation on a Windows NT or Windows 2000 platform, you can prevent unauthorized access through your Windows display options. These settings control security:

- Windows user ID with password
- Screen saver with password

#### **CAUTION**

You must configure both settings to protect your files.

#### Note

You may not be able to implement HIPAA security on systems that do not allow you to restrict access to drives and files.

#### **Procedure**

Use this procedure to set up security on a Windows NT or Windows 2000 computer.

| Step | Action  |  |
|------|---|--|
| 1    | When you install your GENTRAN:Server for Workstation software, select the HIPAA compliance option.              |  |
|      | Reference See your GENTRAN:Server for Workstation Installation Guide for instructions.                          |  |
| 2    | Configure your Windows display options to require a logon with a user ID and password to access the computer.   |  |
|      | Reference See your Windows documentation and online help system for instructions on configuring these settings. |  |
|      | (Continued on next page)  |  |

| (Contd)<br>Step | Action  |
|-----------------|---|
| 3               | Configure the access options so that only authorized users can view and run GENTRAN:Server.                           |
|                 | Note To implement HIPAA security, your operating system must enable you to set up users and restrict access to files. |
| 4               | Configure your system's screen saver to protect your files.   |
|                 | Select a screen saver   |
|                 | ▶ Enable the password protection option and set a password for the screen saver                                       |
|                 | Select the number of minutes your computer can remain idle<br>before it displays the password-protected screen saver. |
|                 | Reference See your Windows documentation and online help system for instructions on configuring these settings.       |

#### System checks

Because you chose the HIPAA compliance option during installation, GENTRAN:Server will verify that you have set your computer's screen saver option with a password when you start certain programs.

If the screen saver with password is not set, the system blocks your access to programs capable of displaying patient information, such as the File Browser. GENTRAN:Server displays a message to remind you that you must set the screen saver option with a password.

If you turn off the screen saver with password option after you start GENTRAN:Server, the system halts and displays a reminder message. You cannot resume until you turn on the screen saver with password

#### Regaining access

This table shows how to regain access to your system when you have security settings enabled.

| IF  | THEN   | AND you must  |
|---|--|---|
| The Windows screen saver with password option is turned off when you start GENTRAN:Server | GENTRAN:Server displays an error message and prevents access.  | enable the Windows<br>screen saver with<br>password option to<br>gain access.               |
| You turn off the screen saver with password option after you start GENTRAN:Server         | GENTRAN:Server freezes activity and displays an error message.   | enable the screen saver with password option to continue.                                   |
| When the timeout value set in your screen saver expires                                   | your computer monitor displays the screen saver configured for your computer along with a password dialog box. | type the password specified for your screen saver into the dialog box and click <b>OK</b> . |

# How to Set Up Security on a UNIX Host Server and Client PCs

#### Introduction

In GENTRAN:Server for UNIX, the security feature for the host server and the client machines are controlled at the environment level in Security Administration.

# Security functions

When the security feature is enabled, a background process monitors the idle time when an authorized user accesses GENTRAN: Server programs that are capable of displaying patient information. When 15 minutes has elapsed without activity, the process causes the programs to exit (timeout).

The system locks the programs for the user who is logged on, but does not log off the user. Background jobs continue to run during timeout.

#### **Procedure**

Use this procedure to turn on security features in a GENTRAN:Server environment.

| Step | Action   |  |
|------|--|--|
| 1    | On the host server, start Security Administration.   |  |
| 2    | Select Environment Administration from the Security Administration screen.                               |  |
|      | System Response GENTRAN:Server displays the Environment Administration screen.  (Continued on next page) |  |

| (Contd)<br>Step | Action  |
|-----------------|---|
| 3               | Move the focus to the HIPAA Compliant [Y/N] field and type Y to enable the security features.  Environment Administration  Environment: ADD Root Directory: /qabox3/server60/ADD Standards/Codes: /qabox3/server60/ADD/stds/ Implement Guides: /qabox3/server60/ADD/apps/ App/DDF Files: /qabox3/server60/ADD/apps/ Maps: /qabox3/server60/ADD/maps/ Trading Partner: /qabox3/server60/ADD/bp/ EDI History Audit: /qabox3/server60/ADD/dihist/ Data: /qabox3/server60/ADD/data/ HIPAA Features[Y/N]: Y  (ESC)-Exit F1-Help F3-Delete F10-Save |
|                 | Note Enabling security here sets the security features for the GENTRAN:Server for UNIX client machines.   |
| 4               | Press F10 to save your changes.   |

#### Changing the idle time

The default value for idle time is 15 minutes. If you want to change this value, you must edit the auto\_logout.cfg text file, which is in the EDI\_ROOT directory. The valid values are from 1 to 480 minutes. If you set a value outside that range, the system uses 15 minutes.

#### Note

The timeout value applies to all users working in the environment.

#### Regaining access

If you receive a message that a task has been logged off because it has been idle too long, you must log off your session and then log on again to regain access.

## How to Access GENTRAN: Server in an Emergency

#### Introduction

This topic explains what to do in the event your GENTRAN:Server security administrator is unavailable or unable to access the system in an emergency situation.

#### **Procedure**

To gain access to GENTRAN: Server in an emergency, you must call a Sterling Commerce support representative and explain the situation. The support representative will provide a solution.

# Introduction to Using NCPDP with GENTRAN:Server

| Contents | Overview                                      |
|----------|---|
|          | Terms Used in the NCPDP Standard              |
|          | Supported NCPDP Version and Transactions      |
|          | ▶ Transaction Types: Requests and Responses   |
|          | NCPDP Transaction Syntax                      |
|          | ▶ Six Key Fields for Trading Partnership Code |
|          | NCPDP Batch Transmissions                     |
|          | • Overview1                                   |
|          | ▶ Parts of an NCPDP Batch Transmission        |
|          | ▶ Batch Transaction Header Segment            |
|          | Batch Detail Data Record                      |
|          | ▶ Transaction Header Segment                  |
|          | ▶ Batch Trailer Segment                       |
|          |   |

## **Overview**

#### Introduction

This chapter introduces you to the basic terminology and concepts you need to know before you create NCPDP maps. It also includes an overview of the process you must follow to handle and translate NCPDP-formatted files.

#### **Key terms**

This table describes key terms used in this chapter.

| Term                          | Description   |
|-------------------------------|---|
| batch detail header record    | The segment that contains the Transaction Reference Number.   |
| batch header<br>segment       | The header segment that contains information to identify the batch file.  |
| batch mode                    | A non-interactive way of processing data transactions that have been collected in advance and combined into a single batch file.  |
| batch segment                 | A positional segment configured to be a batched type.   |
| Batch Transaction<br>Standard | A standardized file submission format that enables organizations to submit electronic transactions in a non-real-time mode.   |
| delimited segment             | A variable-length segment that uses separator characters to mark the beginning of groups, segments, or fields.  |
| key fields                    | The fields in a data file that contain the values GENTRAN:Server uses to determine the Trading Partnership code.  |
| NCPDP                         | National Council for Prescription Drug Programs   |
| positional segment            | A segment that contains fixed-length fields. In GENTRAN:Server you can use either the component length or separator characters to distinguish components in NCPDP data. |
| request (transaction)         | A claim transaction that a pharmacy or other provider submits to an insurer or other processor.   |
|                               | (Continued on next page)  |

| (Contd)<br>Term            | Description  |
|----------------------------|--|
| response<br>(transaction)  | A reply to a request transaction.  |
| separator characters       | The characters used to distinguish the start and end of data components in a file.   |
| transaction                | A group of data segments that have related data elements or fields. The group makes up a business document, such as a claim for services. The type of transaction is identified by a transaction code, such as B1 for Billing and N3 for Information Reporting Rebill. |
| transaction header segment | The segment that identifies an NCPDP transmission.   |
| transmission               | The highest level of data transfer. A transmission may contain up to three identifying segments and one to four transactions, depending on the transaction type.   |
| transmission-level segment | A segment that occurs once in a transmitted batch file.  |

### Terms Used in the NCPDP Standard

#### Introduction

This topic contains a brief summary of the terms and concepts used in the NCPDP Standard.

#### Reference

For detailed information about the NCPDP Telecommunication Standard, see the publications issued by the National Council for Prescription Drug Programs.

#### **Transmissions**

A transmission refers to the entire file that is submitted electronically. It includes telecommunication routing information, identification, and other information that applies to the entire collection of data.

A transmission can contain up to three identifying segments and up to four transactions, depending on the transaction type. All transactions must be for the same patient.

#### **Transactions**

A transaction is a collection of segments and their data fields that together comprise a business document, such as a claim for services. Within a transmission, transactions (except for Eligibility Verification transactions) are separated by the Group separator character.

#### **Segments**

A segment is a collection of related data fields. Segments are separated with the segment separator character. They are identified by a segment identifier.

Segments can not occur multiple times within a transaction, but they can occur multiple times within a transmission.

#### **Header segments**

The transaction (request) header and response header segments contain fixed-length data fields that identify a transmission. These segments do not use separators to separate the fields in the segment. In these segments, each data field is transmitted at its maximum length positionally. Data fields not needed for a particular transmission are zero or space filled as appropriate.

#### Other segments

The other (non-header) segments contain mandatory and optional fields. All data fields within these segments are separated from one another by a field separator character.

#### **Fields**

A field is a basic unit of data. It is sometimes called a data element.

#### Mandatory fields

Mandatory fields are required units of data that must come first (before optional fields) within the appropriate segment. Each mandatory field is preceded by the field separator and the field's identifier. Mandatory fields may be truncated.

#### **Optional fields**

Optional fields are used at the discretion of the provider and the provider's trading partner or processor. Each optional field is preceded by the field separator and the field's identifier. Optional fields may be truncated.

You can place optional fields in any order in a segment, as long as the field is not designated as a qualifier or in a repeating group.

#### **Qualifier fields**

A qualifier is a field that further defines or provides information about another data field. A qualifier field must be submitted before the field that is qualified.

#### Example

In a billing transaction (B1), the Patient ID Qualifier field defines the value of the Patient ID field as the patient's Social Security Number.

| Field  | Name                 | Value     | Description of Value   |
|--------|----------------------|-----------|------------------------|
| 331-CX | Patient ID Qualifier | 01        | Social Security Number |
| 332-CY | Patient ID           | 123456789 | Patient's SSN          |

#### Separator characters

The specific separator characters used to distinguish groups, segments, and fields are fixed in the NCPDP Standard.

This table lists the separator characters.

| Level of<br>Separator | Decimal<br>Representation | Hex<br>Representation | Comment                            |
|-----------------------|---------------------------|-----------------------|------------------------------------|
| Segment               | 30                        | 1E                    | Separates segments from each other |
| Group                 | 29                        | 1D                    | Separates groups from each other   |
| Field                 | 28                        | 1C                    | Separates fields from each other   |

#### Example

This example shows how separators are used in an NCPDP transaction.

<1C>AM04<1C>C2987654321<1E><1C>AM01<1C>CX01<1C>CY12345 6789<1C>C419620615<1C>C51<1C>CAJOSEPH<1C>CBSMITH<1C>C M123 MAIN STREET<1C>CNMY TOWN<1C>COCO<1C>CP34567

## **Supported NCPDP Version and Transactions**

#### **NCPDP** version

GENTRAN:Server supports version 5.1 of the NCPDP Telecommunications Standard.

#### **Supported** transactions

This table lists the NCPDP 5.1 transactions that GENTRAN:Server supports.

| Transaction Code | Transaction Name                        |
|------------------|---|
| E1               | Eligibility Verification                |
| B1               | Billing                                 |
| B2               | Reversal                                |
| В3               | Rebill                                  |
| P1               | Prior Authorization Request and Billing |
| P2               | Prior Authorization Reversal            |
| P3               | Prior Authorization Inquiry             |
| P4               | Prior Authorization Request Only        |
| N1               | Information Reporting                   |
| N2               | Information Reporting Reversal          |
| N3               | Information Reporting Rebill            |
| C1               | Controlled Substance Reporting          |
| C2               | Controlled Substance Reporting Reversal |
| C3               | Controlled Substance Reporting Reversal |

## **Transaction Types: Requests and Responses**

#### Introduction

The NCPDP standard has two main types of transactions:

- Requests, which are claim transactions that a pharmacy or other provider submits to an insurer or other processor
- Responses, which are replies to request transactions.

#### Structure of a request

This is the basic structure of a request:

- Header segment (for a request)
- Patient segment
- Insurance segment
- Transaction segment (up to four per transmission for transaction codes B1-B3, except for compounds, N1-N3, and C1-C3)
  - Claim segment
  - Pharmacy Provider segment
  - Prescriber segment
  - Coordination of benefits/Other payments segment
  - Workers' compensation segment
  - DUR/PPS segment
  - Pricing segment
  - Coupon segment
  - Compound segment
  - Prior authorization segment
  - Clinical segment

### Structure of a response

This is the basic structure of a response:

- Header segment (for a response)
- Message segment (for a response) Þ
- Insurance segment (for a response)
- Transaction response (up to four per transmission)
- Response Status Segment
  - Response Claim segment
  - Response Pricing segment
  - Response DUR/PPS segment
  - Response Prior Authorization segment

### Note

A response transmission contains an NCPDP response transaction for each request transaction received.

# **NCPDP Transaction Syntax**

#### Introduction

Transactions are a collection of segments separated by Segment separator characters. Transactions are separated within a transmission with a group separator character.

### **Transaction** syntax

This is an example of the syntax of a billing request transaction:

### **Transaction header segment**

 Transaction header fields. Fixed-length without field separators. In this segment, each data element is transmitted at its maximum length positionally.

Segment separator

### Insurance segment

- Required fields within segment, with field separators
- Optional fields within segment, with field separators

Segment separator

#### Patient segment

- Required fields within segment, with field separators
- Optional fields within segment, with field separators

Group separator

Segment separator

#### Claim segment

- Required fields within segment, with field separators
- Optional fields within segment, with field separators

Segment separator

#### **Pricing segment**

- Required fields within segment, with field separators
- Optional fields within segment, with field separators

(Continued on next page)

### **Truncation**

GENTRAN:Server provides the ability to truncate delimited data elements. If your trading partner accepts variable-length fields, you can use truncation to suppress leading zeros in numeric fields and trailing spaces in alphanumeric fields. Truncation helps decrease transmission time.

# Six Key Fields for Trading Partnership Code

### Introduction

For inbound translation, GENTRAN:Server looks for the values of six key fields in the transaction to determine the Trading Partnership code in an NCPDP batch transaction.

### Key field table

This table lists the six key fields and their locations.

| Key Field                     | Location                   |
|-------------------------------|----------------------------|
| Sender ID                     | Batch transaction header   |
| Receiver ID                   | Batch transaction header   |
| Version/Release Number        | Transaction header segment |
| Transaction Code              | Transaction header segment |
| Service Provider ID Qualifier | Transaction header segment |
| Service Provider ID           | Transaction header segment |

### References

See the <u>Batch Transaction Header</u> topic in Appendix A of this guide for the layout of the header.

See the Request Transaction Header Segment and Response Transaction Header Segment in Appendix A for the layout of the transaction header segments.

# **NCPDP Batch Transmissions**

### **Overview**

#### Introduction

GENTRAN:Server transmits NCPDP transactions in batch mode, using the NCPDP Batch Transaction Standard format.

Introduction to Using NCPDP with GENTRAN:Server

### **NCPDP Batch Transaction Standard**

The NCPDP Batch Transaction Standard is a standardized file submission format that enables organizations to submit electronic pharmacy transactions in a nonreal-time mode.

An NCPDP batch transaction has a uniform format that begins with a batch transaction header segment and ends with a trailer segment. The actual transactions are arranged in detail data records between these two segments.

#### Example

A pharmacy submitting claims to an insurer sends a batch file that contains one batch transaction header, a detail data record for each claim, and one batch trailer segment.

### Parts of an NCPDP Batch Transmission

### **Batch** transmission parts

These are the parts (records) in an NCPDP batch transmission:

- <u>Batch Transaction Header Segment</u> (segment identifier = 00)
- One or more <u>Batch Detail Data Record</u>s (segment identifier = G1)
- Batch Trailer Segment (segment identifier = 99)

### STX and ETX fields

Each part begins with a start-of-text STX field (hex 02) and ends with an end-oftext ETX field (hex03). The Start- and End-of-text fields are also used to delimit the detail data records within the file.

### Example

This example contains a batch header record, two incomplete detail data records, and a batch trailer record. The segment identifiers are in boldface type.

(STX)00T1289012345673674589022229876747199412011632T11DEABGHCF YTEWQASDXZAQ3124(ETX)

(STX)**G1**10000543219999993201.....(ETX)

(STX)**G1**10000543229999993201.....(ETX)

(STX)99487674700000000004initial Test....(ETX)

### Batch file error response

A batch transmission that does not have a detail data record is considered a response to a batch file error. A batch file error indicates that an entire batch file was rejected, usually because the file failed the processor's file integrity test.

#### Example

If the record counts in the header segment and the trailer segment do not match, the result is a batch file error.

# **Batch Transaction Header Segment**

### Introduction

Each batch file has one batch transaction header segment.

#### Type

The batch transaction header is a positional (fixed-length non-delimited) segment, 75 characters in length.

### **Contents**

The header contains information that identifies the batch file. This information includes:

- Segment identifier
- Batch Number field that contains the same value as the Batch Number field in the batch trailer segment
- Creation date
- Creation time
- Sender ID
- Receiver ID

#### Reference

See <u>Batch Transaction Header</u> in Appendix A for a description of the fields in the batch transaction header.

# Key fields for inbound translation

The Sender ID and Receiver ID in the batch transaction header are two of the six key fields used to determine the Trading Partnership code. The remaining key fields are in the <u>Transaction Header Segment</u> of the batch detail data record.

#### Reference

See the topic <u>Six Key Fields for Trading Partnership Code</u> in this chapter for a complete list of the six key fields.

### **Batch Detail Data Record**

### Introduction

A batch file contains one detail data record for each request or response transmission.

#### Contents

A batch detail data record contains an actual NCPDP transmission. Each detail data record transmitted in the batch file must follow the format defined for the transaction in the NCPDP Telecommunication Standard.

Detail data records contain both fixed-length (positional) and variable-length fields.

A batch transmission can have up to 9,999,999,997 detail data records per file.

### **Transaction** header segment

Each batch detail data record contains a Transaction Header Segment to identify the transaction set. The transaction header segment for the set begins in position 14 of a detail data record.

### Reference

See Batch Detail Data Record in Appendix A for a description of the fields in the batch detail data record.

### **Transaction Header Segment**

#### Introduction

Each detail data record in a batch file has one transaction header segment that identifies the transaction. This topic explains the role of this segment.

### **Purpose**

The transaction header segment:

- Specifies the NCPDP version number
- Identifies the type of transaction

### Examples

E1 for eligibility verification B1 for a billing transaction

Contains four of the six key fields that GENTRAN:Server uses to determine the Trading Partnership code for inbound translation.

### Key fields for inbound translation

These are the key fields in the transaction header segment that GENTRAN:Server uses to find the Trading Partnership code:

- Version/Release # (of the NCPDP Standard)
- **Transaction Code**
- Service Provider ID Qualifier
- Service Provider ID

### Segment structure and transaction type

The structure of the transaction header segment indicates whether the transaction is a request or response.

- A Request Transaction Header Segment is a fixed-length 56-character segment containing 9 fields.
- A Response Transaction Header segment is a fixed-length 31-character segment containing 7 fields.

The transaction header segment is the only segment that does not have a segment identifier. The Transaction Code field in this segment is used to identify the transaction.

(Continued on next page)

#### References

See Request Transaction Header Segment in Appendix A for a description of the fields in a Request Transaction Header segment.

See Response Transaction Header Segment in Appendix A for a description of the fields in a Response Transaction Header segment.

# **Batch Trailer Segment**

### Introduction

Each batch file has one trailer segment. The trailer segment ends the batch file.

### Segment type

The batch trailer segment is a positional segment with a length of 56 characters.

### Required field

The trailer segment contains a Batch Number field that must have the same value as the Batch Number field in the batch transaction header segment.

#### Reference

See <u>Batch Trailer Record</u> in Appendix A for a description of the fields in the batch detail data record.

# **Creating NCPDP Maps**

| Contents | Overview                              |
|----------|---------------------------------------|
|          | Introduction                          |
|          | Preparing for Mapping                 |
|          | The NCPDP Standard Templates          |
|          | ▶ How to Copy the NCPDP Templates     |
|          | Setting Up for NCPDP Translation      |
|          | How to Analyze the NCPDP Data         |
|          | Creating an NCPDP Map                 |
|          | NCPDP Map Components                  |
|          | ▶ How to Create an Inbound NCPDP Map  |
|          | ▶ Inbound NCPDP Translation Process   |
|          | ▶ How to Create an Outbound NCPDP Map |
|          | Outbound NCPDP Translation Process    |
|          |                                       |

# **Overview**

## Introduction

### In this chapter

This chapter explains how to create maps that translate data into or from an NCPDP format.

### Key terms

This table describes key terms used in this chapter.

| Term                 | Description   |
|----------------------|---|
| inbound translation  | The translation of an input file that is in an NCPDP standard format into an output file that is in another format                    |
| NCPDP template       | A file that contains the NCPDP standard components for an NCPDP transaction (B1, B2, B3, etc.) and the batch transmission components. |
| outbound translation | The translation of an input file into an output file that is in a batch NCPDP standard format   |

# **Preparing for Mapping**

## **The NCPDP Standard Templates**

#### Introduction

The Standards CD supplied with your GENTRAN:Server for UNIX or GENTRAN:Server for Workstation product has a folder that contains templates for creating NCPDP data definition files (DDFs).

Sterling Commerce provides these templates to help you develop your NCPDP maps quickly and efficiently.

#### Location

The templates for NCPDP transactions are in the folder labelled NCPDP on your Standards CD.

#### **NOTE**

The NCPDP transactions exist only in the NCPDP templates; they are not in the Standards database on the Standards CD.

# Template contents

Each NCPDP template contains:

- ▶ All standard components for the NCPDP transaction (B1, B2, B3, etc.)
- ▶ The standard components required for batch transmissions (batch header, batch trailer)

# **How to Copy the NCPDP Templates**

### Introduction

We recommend that you copy the folder that contains the NCPDP data definition files to a subdirectory in the folder that holds your file definitions (\*.ddf files) so that you can access them when you need them.

#### **Procedure**

Use this procedure to copy the folder.

| Step | Action   |
|------|--|
| 1    | Insert the Standards CD into your CD drive.  |
| 2    | Locate the NCPDP Templates folder on the CD.   |
| 3    | Use your system's copy function to copy the folder from the Standards CD to the destination directory. |

# **Setting Up for NCPDP Translation**

### Introduction

This topic provides an overview of the tasks you must perform to set up your system to translate NCPDP data.

### Stages in the set-up process

This table lists the stages in the process.

| Stage | Description  |  |
|-------|--|--|
| 1     | Analyze the format of the NCPDP data.  |  |
|       | Reference See How to Analyze the NCPDP Data.   |  |
| 2     | Create the NCPDP map.  |  |
|       | Reference See How to Create an Inbound NCPDP Map or How to Create an Outbound NCPDP Map.   |  |
| 3     | Define the input and output sides of the map.  |  |
|       | Reference See the Structuring an NCPDP Map chapter for instructions on structuring the NCPDP side of the map.                                |  |
|       | See the GENTRAN:Server Application Integration User's Guide for instructions on structuring the side of the map that is not an NCPDP format. |  |
| 4     | Create the NCPDP Trading Partnership record.   |  |
|       | Reference See the Creating NCPDP Trading Partnership Records chapter for Instructions.   |  |
| 5     | Set translation options for NCPDP data.  |  |
|       | Reference See the Running Translation chapter in the GENTRAN:Server Application Integration User's Guide for instructions.                   |  |

# **How to Analyze the NCPDP Data**

### Introduction

Before you can create a map to translate data into a NCPDP standard format, you must analyze the NCPDP format that you want to use in the map. You will use the information you gather to create a Data Definition Format (DDF) file that defines the NCPDP format you expect to receive or send.

#### Reference

For more information about Data Definition Format files, see the GENTRAN: Server Application Integration User's Guide.

### **Procedure**

Use this procedure to analyze NCPDP data.

| Step | Action  |
|------|---|
| 1    | Obtain sample data that is in the NCPDP format you will send to or receive from the processor, intermediary, or provider (trading partner).   |
| 2    | Analyze the sample data to determine the segment and element layouts and field lengths.   |
| 3    | Find out which data elements the trading partner requires.  |
| 4    | Determine the trading partner's ability to accept variable-length transactions and truncated data elements.   |
| 5    | Determine the kind of data contained in each segment and element.   |
| 6    | List the map components and layout information for your NCPDP Data Definition Format file.  |
| 7    | When you build the NCPDP side of your map, add or delete optional fields and segments as necessary to accommodate your trading partner's requirements and those of your organization. |

# **Creating an NCPDP Map**

This section describes how to create an NCPDP map. It includes these topics:

NCPDP Map Components

How to Create an Inbound NCPDP Map

**Inbound NCPDP Translation Process** 


How to Create an Outbound NCPDP Map

Outbound NCPDP Translation Process

## **NCPDP Map Components**

### **Example** inbound NCPDP map

This illustration shows an example map that translates inbound data that is in NCPDP format into an application format.



### Map component icons

This table describes the icons that GENTRAN:Server uses to visually represent the NCPDP map components:

| Icon | Description  |
|------|--|
|      | The <b>NCPDP File Format icon</b> identifies the NCPDP file. The file object is the primary component. All other map components are subordinate to the file object.  |
| g    | A <b>group</b> icon indicates a looping structure that contains related segments and groups that repeat in sequence until either the group data ends or the maximum number of times that the loop is allowed to repeat is exhausted. |
|      | A <b>segment</b> icon identifies a segment. The left side of the icon is red if the segment is positional. The left side of the icon is blue if the segment is delimited.  |
|      | (Continued on next page)   |

| (Contd)<br>Icon | Description   |  |
|-----------------|---|--|
| +               | A <b>field</b> icon represents the smallest piece of information defined in an NCPDP standard. Fields usually do not have useful meaning until they are combined into segments. Fields can be positional (blue icon) or delimited (green icon). A red indicates an NCPDP data record. |  |
| ₩               | A <b>linked field</b> icon represents a field that is linked to an element or field on the opposite side of the map.  |  |
| [c]             | A counter field icon represents a counter field.  |  |
| [6]             | A count field icon represents a count field.  |  |

# **How to Create an Inbound NCPDP Map**

#### Introduction

After you analyze the NCPDP data you expect to receive from your trading partner, you are ready to create a map that will translate the NCPDP data into another format, such as your application format.

This topic explains how to create a map for translating data that is in an NCPDP standard format into another format.

#### Reference

For more detailed instructions about creating maps, see the Creating a Map section in the Designing Your Map chapter of the GENTRAN:Server Application Integration User's Guide.

### The NCPDP DDF

file

The input side of your map must be a data definition file (DDF) that describes the layout of the incoming file. We recommend that you use the appropriate DDF template that Sterling Commerce provided on your Standards CD. The Sterling Commerce DDF templates contain the batch header and batch trailer segments as well as the transaction segments.

### **Procedure**

Use this procedure to create an NCPDP map.

| Step | Action  |
|------|---|
| 1    | Start the Application Integration mapper.   |
| 2    | From the File menu, select <b>New</b> to start the New Map Wizard.  |
| 3    | In the What kind of map are you creating field, select the option that has Standard as the input and has the appropriate output file.  Example If your output file is in an application format, select Standard-to-Application as the kind of map you are creating. |
| 4    | In the <b>What is the name of the map</b> field, type the unique name of the map, omitting the .MAP extension.  |
| 5    | Type your name if it differs from the user name that the system supplied.   |
|      | (Continued on next page)  |

| (Contd)<br>Step | Action   |   |
|-----------------|--|---|
| 6               | When prompted for the input format, use this table to determine your next step.  |   |
|                 | IF   | THEN  |
|                 | You want to use an NCPDP<br>DDF file template that Sterling<br>Commerce provided   | Click Load the data format from a saved definition and then click the Browse button to locate the DDF in the directory that you use to store your NCPDP file definitions. |
|                 | You want to create a DDF file that defines the NCPDP layout  | Click Create a new data format using the syntax and select NCPDP (National Council for Prescription Drug Programs) from the drop-down list.                               |
| 7               | When prompted for the output format, select the appropriate options.   |   |
|                 | Reference See Defining the output format in the How to Create a New Map topic in the GENTRAN:Server Application Integration User's Guide if you need more information. |   |
| 8               | Click <b>Finish</b> to begin editing your map.   |   |
| 9               | Did you select <b>Create a new data format using the syntax</b> in Step 6?   |   |
|                 | ▶ If YES, continue with Step 10  |   |
|                 | If NO, go to Step 11.  |   |
| 10              | Define the NCPDP DDF file, name it, and save it. Then continue with Step 11.   |   |
|                 | References See the Structuring an NCPDP M  | lap chapter for instructions.   |
| 11              | Do you need to define the output format?   |   |
|                 | ▶ If YES, continue with Step 12.   |   |
|                 | ▶ If NO, go to Step 13.  | (Continued on next page)  |

| (Contd)<br>Step | Action  |
|-----------------|---|
| 12              | Define the output format. You can name it and save it to use in another map. Then continue with Step 13.  |
|                 | References See the Designing Your Map chapter of the GENTRAN:Server Application Integration User's Guide for information about defining a format. |
| 13              | Complete the map by setting standard or extended rules and linking components on the input and output sides.                                      |
| 14              | Save the map.   |
| 15              | Compile the map to create a translation object.   |
|                 | References See the Designing Your Map chapter of the GENTRAN:Server Application Integration User's Guide for information about compiling a map.   |

## **Inbound NCPDP Translation Process**

### Introduction

This topic describes the process of translating an input file that is in a batch NCPDP standard format.

### **Assumptions**

The input file is a single NCPDP batch file with one batch header and one batch trailer.

### **Inbound process**

This table shows the process of inbound NCPDP translation.

| Stage | Description  |                                |
|-------|--|--------------------------------|
| 1     | The Iftran program reads the input file and determines that it is in an NCPDP standard format.   |                                |
| 2     | The lftran program validates the data in the batch header record, detail data records, and batch trailer record.                                       |                                |
|       | IF Iftran  | THEN the program               |
|       | does not find errors   | continues with Stage 3.        |
|       | finds errors   | generates a translation error. |
| 3     | The Iftran program splits the NCPDP input file into transaction sets, one for each detail data record.   |                                |
| 4     | The Iftran program uses the six key fields in the input data to locate the Trading Partnership code for each transaction set.                          |                                |
| 5     | The Iftran program passes the NCPDP transactions and Trading Partnership code to the translator.   |                                |
|       | Note The system does not create audit records for NCPDP data.  |                                |
| 6     | The translator reads the Trading Partnership record, locates the appropriate translation object (compiled map), and translates the NCPDP transactions. |                                |
| 7     | The translator directs the output files to the directories specified in the Trading Partnership record.  |                                |

## **How to Create an Outbound NCPDP Map**

#### Introduction

After you analyze the NCPDP format you send to your trading partner, you are ready to create a map that will translate your application (or other formatted) data into an NCPDP standard format.

This topic explains how to create a map for translating data into an NCPDP standard format.

#### Reference

For more detailed instructions about creating maps, see the Creating a Map section in the Designing Your Map chapter of the *GENTRAN:Server Application Integration User's Guide*.

# The NCPDP DDF file

The output side of your map must be a data definition file (DDF) that describes the layout of the output file. We recommend that you use the appropriate DDF template that Sterling Commerce provided on your Standards CD. The Sterling Commerce DDF templates contain the batch header and batch trailer segments as well as the transaction segments.

### **Procedure**

Use this procedure to create an outbound NCPDP map.

| Step | Action   |  |
|------|--|--|
| 1    | Start the Application Integration mapper.  |  |
| 2    | From the File menu, select <b>New</b> to start the New Map Wizard.   |  |
| 3    | When prompted for the kind of map, select the option that has the appropriate input file and "Standard" as the output.   |  |
|      | <b>Example</b> If your input file is in an application format, select Application-to-Standard as the kind of map you are creating.   |  |
| 4    | When prompted for the input format, select the appropriate options.  Reference See Defining the input format in the How to Create a New Map topic in the GENTRAN:Server Application Integration User's Guide if you need more information. |  |
|      | (Continued on next page)   |  |

| (Contd)<br>Step | Action   |  |  |
|-----------------|--|--|--|
| 5               | When prompted for the output format, use this table to determine your next step.                               |  |  |
|                 | IF   | THEN   |  |
|                 | You want to use an NCPDP<br>DDF file template that Sterling<br>Commerce provided                               | Click Load the data format from a saved definition and then click the Browse button to locate the DDF in the directory you use to store your NCPDP file definitions. |  |
|                 | You want to create a DDF file that defines the NCPDP layout  | Click Create a new data format using the syntax and select NCPDP (National Council for Prescription Drug Programs) from the drop-down list.                          |  |
| 6               | Click <b>Finish</b> to begin editing your map.   |  |  |
| 7               | Do you need to define or edit the input side of your map?  If YES, continue with Step 8.  If NO, go to Step 9. |  |  |
| 8               | Define or edit the input format. You in another map. Then continue wi  |  |  |
|                 | References See the Designing Your Map cha Application Integration User's Gu a format.                          |  |  |
| 9               | Did you select <b>Create a new data</b> Step 5?  | a format using this syntax in  |  |
|                 | <ul><li>If YES, continue with Step 10</li><li>If NO, edit the NCPDP format</li></ul>                           | t as necessary and go to Step 11.  |  |
| 10              | Define the NCPDP DDF file by interest the properties. You can name it a Then continue with Step 11.            |  |  |
|                 | References See the Structuring an NCPDP M  | lap chapter for instructions.  |  |
| 11              | Complete the map by adding star linking components on the input a  |  |  |
|                 |  | (Continued on next page)   |  |

| (Contd)<br>Step | Action   |  |
|-----------------|--|--|
| 12              | Save the map.  |  |
| 13              | Compile the map to create a translation object.  References See the Designing Your Map chapter of the GENTRAN:Server Application Integration User's Guide for information about compiling a map. |  |

### **Outbound NCPDP Translation Process**

Creating NCPDP Maps

### Introduction

This topic describes the process of translating an input file into an output file that is in a batch NCPDP standard format.

### **Assumptions**

The description of the outbound NCPDP translation process is based on these assumptions.

- The output file that the system produces is a single NCPDP batch file with one batch header and one batch trailer.
- ▶ Enveloping options are NOT selected. The batch file's batch header and trailer serve this function.

# Outbound process

This table shows the process of outbound NCPDP translation.

| Stage | Description  |
|-------|--|
| 1     | The lftran program reads the input file, which is in an application format.  |
| 2     | The Iftran program determines the Trading Partnership code for each transaction.   |
| 3     | The Iftran program passes the input transactions and Trading Partnership codes to the translator.  |
| 4     | The translator reads the Trading Partnership record, locates the appropriate translation object (compiled map), and translates the data. |
| 5     | The system uses the information in the Trading Partnership record to determine the values for the batch transaction header and trailer.  |
| 6     | The system generates the batch transaction detail and transaction or response header segment for each transaction.                       |
| 7     | If the header is mapped, the system merges the mapped header with the generated header.  |
|       | (Continued on next page)   |

| (Contd)<br>Stage | Description  |
|------------------|--|
| 8                | The system produces the final NCPDP output file, which consists of a batch header record, multiple batch detail records, and one batch trailer record. |
| 9                | The translator sends the output file to the directory specified in the Trading Partnership record.   |

# **Structuring an NCPDP Map**

| Contents | Overview  |  |
|----------|-----------|--|
|          | )         | Introduction                                   |
|          | •         | NCPDP Map Structure                            |
|          | •         | Field Format Values                            |
|          | Dialog Bo | oxes   |
|          | •         | NCPDP File Properties Dialog Box               |
|          | •         | NCPDP Group Properties Dialog Box              |
|          | •         | NCPDP Positional Segment Properties Dialog Box |
|          | •         | NCPDP Positional Field Properties Dialog Box   |
|          | •         | NCPDP Delimited Segment Properties Dialog Box  |
|          | •         | NCPDP Delimited Field Properties Dialog Box    |
|          | •         | NCPDP Count Field Properties Dialog Box        |
|          | •         | NCPDP Counter Field Properties Dialog Box      |
|          | Procedure | es   |
|          | •         | Defining an NCPDP Batch File                   |
|          | •         | Loading an NCPDP Template                      |
|          | •         | Manually Creating NCPDP Map Components 59      |
|          | •         | How to Configure NCPDP File Properties         |
|          | •         | How to Create the Batch Header Segment         |
|          | •         | How to Create the Batch Detail Data Segment 67 |
|          | •         | How to Create a Transaction Header Segment     |
|          | •         | How to Create the Batch Trailer Segment        |
|          | •         | How to Create a Group74                        |
|          | •         | How to Create a Positional Segment             |
|          | •         | How to Create a Delimited Segment83            |
|          | •         | How to Create a Positional Field               |

|   | How to Create a Delimited Field | 102 |
|---|---------------------------------|-----|
| • | Repeating Fields                | 107 |
| • | How to Create a Count Field     | 109 |
| • | How to Create a Counter Field   | 112 |

## **Overview**

## Introduction

#### Overview

This chapter describes how to structure the NCPDP side of a map.

You can use the instructions in this chapter to:

- Modify the NCPDP components copied from a template.
- Create all the NCPDP components in a map.

## **NCPDP Map Structure**

### Introduction

In GENTRAN:Server, an NCPDP map consists of an NCPDP File object, batch segment objects, positional segment objects, delimited segment objects, and field objects. The segments in the transaction portion of a transmission must be contained in a group.

### **Basic segments**

These are the basic segments in a batch transmission. Note that you can have up to four transactions.

- Batch Header Segment
- Batch Detail Segment
- Transaction Header Segment
- Patient Segment
- Insurance Segment
- Transaction Segment
- Transaction Segment
- Transaction Segment
- Transaction Segment
- Batch Trailer Segment

#### Segment types

There are two types of segments: positional and delimited.

These are positional (fixed-length) segments:

- Batch Header Segment
- Batch Detail Segment
- Transaction Header Segment
- Batch Trailer Segment

All other segments in an NCPDP transmission are delimited (variable-length) segments.

(Continued on next page)

### Field types

These are the types of fields that GENTRAN: Server supports for NCPDP transmissions:

- Number
- String
- Date/Time

# **Field Format Values**

This table shows the NCPDP field format values that GENTRAN:Server supports.

| Data Type | Data Format  |
|-----------|--|
| Number    | XNumeric (0 - 9)<br>An unsigned numeric. Always right-justified and zero-filled.<br>Corresponds to "N" format in the NCPDP Standard.   |
|           | Overpunch (0 - 9) A signed numeric with implied decimal position. The sign is internal and trailing; zero is always positive; field is always right-justified; and field contains a zero-filled dollar-cents amount with two positions to the right of the implied decimal point. All other positions are to the left of the implied decimal point. A dollar field with an Overpunch sign replaces the right-most digit in the field. Corresponds to "D" format in the NCPDP Standard. |
|           | Note Overpunch signs are used in dollar fields to represent positive and negative dollar amounts without expanding the size of the field to hold a plus or minus character. The right-most (least significant) digit of a dollar field must be an Overpunch sign, not a digit. The signed value designates the positive or negative status of the numeric value.   |
|           | Example The dollar field of \$99.95 is represented as 999E with truncation. A negative dollar amount of \$2.50 is represented as 25} with truncation.  |
|           | (Continued on next page)   |


### **Dialog Boxes**

### **NCPDP File Properties Dialog Box**

#### Introduction


The NCPDP File Properties dialog box is used to define information that helps the translator identify different data structures in the input or output file. It has three tabs:

- Name tab
- Segment tab
- Loop Extended Rules tab



### Name tab

The Name tab is used to define the name of the root map object. This illustration shows the Name tab.



### Name tab fields and functions


This table lists the fields of the Name tab and their functions.

| Field                            | Function                                 |
|----------------------------------|--|
| Please enter the name            | Defines the name of the root map object. |
| Please enter a short description | Describes the root map object.           |

### Segment tab

The Segment tab is used to specify segment separators and other structural information. When NCPDP is on the input side of a map, the translator uses this information to identify and validate data structures. When NCPDP is on the output side of a map, the system uses the segment information to generate correct NCPDP data structures.

This illustration shows the Segment tab.



### Segment tab fields and **functions**

This table lists the fields of the Segment tab and their functions.


| Field               | Function  |
|---------------------|---|
| Positional Segments |   |
| Use Separators      | Indicates that a separator character marks the beginning of a positional segment. |
|                     | (Continued on next page)  |

| (Contd)<br>(Contd)Field           | Function   |
|-----------------------------------|--|
| Positional and Delimited Segments |  |
| Stream Segments                   | Turns streaming on and off. When this box is checked, each output segment follows another, without a carriage return or line feed to separate them.  |
| Uppercase Strings                 | For outbound data, this option causes the system to convert all strings to uppercase characters. For inbound data, the system ignores this option.   |
| Delimited Segments                |  |
| Specify Separators                | Enables you to change the default separator characters used to delimit the data structures.  |
|                                   | IMPORTANT  |
|                                   | The NCPDP standard has required separator characters. When the User Separator option is checked, GENTRAN:Server displays these separators in the appropriate boxes. We strongly recommend that you do NOT change these values. |
| Segment                           | Specifies the character used to separate segments. The default character is Ox1E   |
| Group                             | Specifies the character used to separate groups. The default character is Ox1D   |
| Field                             | Specifies the character used to separate fields. The default character is Ox1C.  |
| Batch Segments                    |  |
| Start of Text (STX)               | Specifies the value that marks the start of the batch record within the file.  (Continued on next page)  |

| (Contd)<br>(Contd)Field | Function   |
|-------------------------|--|
| End of Text (ETX)       | Specifies the value that marks the end of the batch record within the file.  |
| Other fields            |  |
| Field ID Length         | Specifies the length of the field identifier. Default value is 2 for delimited segments.   |
| Truncate data           | Turns data truncation on and off. If this option is checked, the system removes leading zeros, fillers, padding, and spaces from data elements that are not mandatory. |

# Loop Extended Rules tab

The Loop Extended Rules tab is used to create extended rules at the file object level.



# Loop Extended Rules tab fields and functions

This table lists the fields of the Loop Extended Rules tab and their functions.

| Field         | Function  |
|---------------|---|
| On Begin      | Specifies that the extended rule is executed before the system processes the input or output side of the map. |
| On End        | Specifies that the extended rule is executed after the system processes the input or output side of the map.  |
| Full Screen   | Maximizes the dialog box.   |
| Compile       | Compiles the extended rule. Displays any warnings or errors in the Errors list.                               |
| Extended rule | Defines the extended rule.  |
| Errors        | Displays any errors generated when you clicked Compile to compile the extended rule.                          |


### **NCPDP Group Properties Dialog Box**

### Introduction

The NCPDP Group Properties dialog box is used to define information about a group structure in the file. It has four tabs:


- Name tab
- Separator tab
- Looping tab
- Loop Extended Rules tab

This illustration shows the Group Properties dialog box for an NCPDP group object.



### Name tab

The Name tab is used to define the name of the group map object. This illustration shows the Name tab.




# Name tab fields and functions

This table lists the fields of the Name tab and their functions.

| Field                            | Function                                  |
|----------------------------------|---|
| Please enter the name            | Defines the name of the group map object. |
| Please enter a short description | Describes the group map object.           |

### Separator tab

The Separator tab is used to indicate whether or not the NCPDP Group Separator is used in the file




### Separator tab fields and **functions**

This table lists the fields of the Separator tab and their functions.

| Field                     | Function  |
|---------------------------|---|
| Use NCPDP Group Separator | Turns use of the NCPDP Group Separator on and off.  |
|                           | If the group is on the input side of a map, this option causes the system to expect a group separator in the input file at the beginning of each group.                     |
|                           | If the group is on the output side of a map, this option causes the system to insert a group separator in the output file at the beginning of each occurrence of the group. |

### Looping tab

The Looping tab is used to specify that the group is part of a repeating (looping) structure. This illustration shows the Looping tab.




### Looping tab fields and **functions**

This table lists the fields of the Looping tab and their functions.

| Field                     | Function  |
|---------------------------|---|
| Minimum Usage             | Specifies the minimum number of times the loop must be repeated.  |
| Maximum Usage             | Specifies the maximum number of times the loop can be repeated.   |
| Promote records to parent | Indicates that the subordinate records and groups should be extracted and located in the parent group when the group is compiled. |

### **Loop Extended** Rules tab

The Loop Extended Rules tab is used to set extended rules for the group. This illustration shows the Loop Extended Rules tab of the NCPDP Group Properties dialog box.



### **Loop Extended** Rules tab fields and functions

This table lists the fields of the Loop Extended Rules tab and their functions.

| Field         | Function   |
|---------------|--|
| On Begin      | Specifies that the extended rule is executed before the system processes each occurrence of the group. |
| On End        | Specifies that the extended rule is executed after the system processes each occurrence of the group.  |
| Full Screen   | Maximizes the dialog box.  |
| Compile       | Compiles the extended rule. Displays any warnings or errors in the Errors list.                        |
| Extended rule | Defines the extended rule.   |
| Errors        | Displays any errors generated when you clicked Compile to compile the extended rule.                   |


### **NCPDP Positional Segment Properties Dialog Box**

### Introduction

The NCPDP Positional Segment Properties dialog box is used to define information about a positional segment. It has four tabs:


- Name tab
- Tag tab
- Key Field tab
- Looping tab

This illustration shows the NCPDP Positional Segment Properties dialog box.



### Name tab

The Name tab is used to define the name of the map object. This illustration shows the Name tab.



## Name tab fields and functions

This table lists the fields of the Name tab and their functions.

| Field                            | Function                                    |
|----------------------------------|---|
| Please enter the name            | Defines the name of the positional segment. |
| Please enter a short description | Describes the positional segment.           |


### Tag tab

The Tag tab is used to define the segment identifier or transaction code associated with the positional segment. The translator uses the tag to correctly associate a segment in the input file with its corresponding map segment.

#### Note

You must define a tag for inbound-side positional segments. This option is not used for output-side positional segments.

This illustration shows the Tag tab.



## Tag tab fields and functions


This table lists the fields of the Tag tab and their functions.

| Field            | Function  |
|------------------|---|
| Transaction Code | Used to specify a value that GENTRAN:Server can use to identify the segment in the input file.                            |
|                  | For header segments, this box is used to specify<br>the NCPDP Transaction Code associated with the<br>positional segment. |
|                  | For batch segments, this box is used to specify the<br>segment identifier.  |
|                  | (Continued on next page)  |

| (Contd)<br>Field        | Function  |
|-------------------------|---|
| Position                | For the input side of a map, specifies the character position in the data (starting from 1 or 0) that the Transaction Code or segment identifier occupies.  |
|                         | <b>Note</b> This option is not used for segments on the output side of a map.   |
| This is a batch segment | Indicates that the segment is a Batch Header<br>Segment, Batch Detail Data Segment, or Batch Trailer<br>Segment.  |
|                         | When you check this option for a batch segment on the output side of a map, this option causes the translator to insert a start-of-text (STX) character at the beginning of the segment and an end-of-text (ETX) character at the end of the segment. |

### **Key Field tab**

The Key Field tab is used to specify a second qualification in selecting a segment. (The segment name is the first qualification). This illustration shows the Key Field tab.



# Key Field tab fields and functions


This table lists the fields of the Key Field tab and their functions.

| Field                                   | Function   |  |
|---|--|--|
| Field                                   | Specifies the key field for this segment. The translator uses this value in addition to the tag as criteria to use when it is matching a data segment from an input file to a map segment. |  |
| Matching rules (input side of map only) |  |  |
| Use constant                            | Indicates that a constant is used as a matching rule. The drop-down list is used to select the constant. The <b>Edit</b> button is used to display the Map Constants dialog box.           |  |
|   | (Continued on next page)   |  |

| (Contd)<br>Field                     | Function   |
|--------------------------------------|--|
| Use codelist                         | Indicates that a codelist is used as a matching rule. The drop-down list is used to select the codelist. The Edit button is used to display the Code Lists dialog box. |
| Match record when key does not match | Instructs the system to ignore the specified key field when matching a data segment from the input file to a map segment.  |

### Looping tab

The Looping tab is used to specify that the segment is part of a repeating (looping) structure. This illustration shows the Looping tab.



# Looping tab fields and functions

This table lists the fields of the Looping tab and their functions.

| Field         | Function  |
|---------------|---|
| Minimum Usage | Specifies the minimum number of times the segment must be repeated. |
| Maximum Usage | Specifies the maximum number of times the segment can be repeated.  |
| Normal        | Not applicable to NCPDP.  |
| Loop Start    | Not applicable to NCPDP.  |
| Loop End      | Not applicable to NCPDP.  |


### **NCPDP Positional Field Properties Dialog Box**

### Introduction


The NCPDP Positional Field Properties dialog box is used to define information about a positional field. It has four tabs:

- Name tab
- Validation tab
- Position tab
- **Extended Rule tab**
- Standard Rule tab
- Conditions tab

This illustration shows the NCPDP Positional Field Properties dialog box



The Name tab is used to define the name of the positional field. This illustration shows the Name tab.




# Name tab fields and functions

This table lists the fields of the Name tab and their functions.

| Field                            | Function                            |
|----------------------------------|-------------------------------------|
| Please enter the name            | Defines the name of the map object. |
| Please enter a short description | Describes the map object.           |

### Validation tab

The Validation tab is used to set the field's data type, data format, and minimum and maximum length. This illustration shows the Validation tab.



### Validation tab fields and **functions**


This table lists the fields of the Validation tab and their functions.

| Field                                     | Function   |
|---|--|
| Check here if this field is mandatory     | Indicates that this field is required.   |
| Minimum (field length)                    | Specifies the minimum length of this field.  |
| Maximum (field length)                    | Specifies the maximum length of this field.  |
| Please choose the data type of this field | Specifies the field's data type:  String Number Date/Time (Continued on next page) |

| (Contd)<br>Field                                   | Function   |
|--|--|
| Please choose the format of the data in this field | Specifies the data format. The available formats are based on the data type. |
|  | String:  |
|  | ▶ X  |
|  | Number:  |
|  | Overpunch  |
|  | ▶ N0 - N9  |
|  | Date:  |
|  | YYYYMMDD   |
| Data is read/written as raw bytes                  | Not used for NCPDP.  |
| use little-endian byte ordering                    | Not used for NCPDP.  |
| use big-endian byte ordering                       | Not used for NCPDP.  |
| Width  | Not used for NCPDP.  |

### Position tab

The Position tab is used to set information about the position of the field in the record. This illustration shows the Position tab.



### Position tab fields and **functions**


This table lists the fields of the Position tab and their functions.

| Field  | Function  |
|--|---|
| Enter the position where this field begins in the record (starting from 1) | Specifies the starting position of this field.                |
| Enter the number of characters this field occupies in the record           | Specifies the length of this field.  (Continued on next page) |

| (Contd)<br>Field  | Function   |
|---|--|
| Enter the character used in empty portions of the field | Specifies the type of character used to occupy blank portions of the field.  |
|   | Using this field Type the character you want to use as the padding character. For example, type 0 (zero) to pad the field with zeros.  Press the space bar to use a space in |
|   | empty portions of the field. The system displays SP in the box.  |
| How is the field's data aligned in this record?         | Indicates how the data is aligned:  • beginning of the field = left-aligned  • middle of the field = centered  • end of the field - right-aligned                            |

### **Extended Rule** tab

The Extended Rule tab is used to specify an extended rule for this map object. This illustration shows the Extended Rule tab.




### **Extended Rule** tab fields and **functions**

This table lists the fields of the Extended Rule tab and their functions.

| Field                                | Function  |
|--------------------------------------|---|
| Please enter the extended rule below | Enables you to enter the extended rule you want to use for this field.          |
| Errors                               | Displays any errors that result when you compile this extended rule.            |
| Full Screen                          | Maximizes the dialog box.   |
| Compile                              | Compiles the extended rule. Displays any warnings or errors in the Errors list. |

## Standard Rule tab

The Standard Rule tab is used to specify a standard rule for this map object. This illustration shows the Standard Rule tab.




# Standard Rule tab fields and functions

This table lists the fields of the Standard Rule tab and their functions.

| Field                                  | Function   |
|--|--|
| Please select the standard rule to use | Specifies the standard rule to use for this field. |

### **Conditions tab**

The Conditions tab is used to set relational conditions to connect fields together for syntax or compliance reasons. This illustration shows the Conditions tab.



This table lists the fields of the Conditions tab and their functions.

| Field   | Function   |
|---|--|
| Please choose the type of relationship to use | Specifies the type of relationship between this field and another field.   |
|   | Paired/Multiple. If any of the<br>specified fields are present, then<br>all fields must be present.  |
|   | Required. At least one of the<br>specified fields must be present.   |
|   | Exclusion. No more than one of<br>the specified fields may be<br>present.  |
|   | ▶ Conditional. If the first Condition field is present, the rest of the fields must also be present.   |
|   | ▶ List Conditional. If the first<br>Condition field is present, at least<br>one of the specified fields must<br>also be present.                     |
| Please select the condition field             | Used to select the first field from the Condition field list. This is the field on which the conditional relationship is based.                      |
|   | Note This field is active only when the type of relationship is Conditional or List Conditional.   |
| Available fields                              | Lists the fields in the map that can be used in the relationship.  |
| Fields used in relationship                   | Specifies the fields used in the relationship. You build this list by selecting fields in the Possible Fields list and then clicking the Add button. |


### **NCPDP Delimited Segment Properties Dialog Box**

### Introduction

The NCPDP Delimited Segment Properties dialog box is used to define information about a delimited segment. It has four tabs:

- Name tab
- Tag tab
- Key Field tab
- Looping tab

This illustrations shows the NCPDP Delimited Segment Properties dialog box.



### Name tab

The Name tab is used to define the name of the delimited segment map object. This illustration shows the Name tab.




### Name tab fields and functions

This table lists the fields of the Name tab and their functions.

| Field                            | Function                            |
|----------------------------------|-------------------------------------|
| Please enter the name            | Defines the name of the map object. |
| Please enter a short description | Describes the map object.           |

### Tag tab

The Tag tab is used to define the segment identifier and segment ID value associated with the delimited segment in the map. This illustration shows the Tag tab.




# Tag tab fields and functions

This table lists the fields of the Tag tab and their functions.

| Field      | Function  |
|------------|---|
| Field ID   | Specifies the Field ID of the field that contains the segment identifier. |
| Segment ID | Specifies the Segment ID of the segment.                                  |

### **Key Field tab**

The Key Field tab is used to specify a second qualification in matching a segment in the input file with the segment in the map. (The segment name is the first qualification.) This illustration shows the Key Field tab.




# Key Field tab fields and functions

This table lists the fields of the Key Field tab and their functions.

| Field                                | Function  |
|--------------------------------------|---|
| Field                                | Selects the field to be used as the key field in this segment.  |
| Use constant                         | Indicates that a constant is used as a matching rule. The drop-down list is used to select the constant. The Edit button displays the Map Constants dialog box. |
| Use codelist                         | Indicates that a codelist is used as a matching rule. The drop-down list is used to select the codelist. The Edit button displays the Code Lists dialog box.    |
| Match record when key does not match | Instructs the system to ignore the specified key field when matching a data segment from the input file to a map segment.                                       |

### Looping tab

The Looping tab is used to specify that the segment is part of a repeating (looping) structure. This illustration shows the Looping tab.



### Looping tab fields and **functions**

This table lists the fields of the Looping tab and their functions.

| Field         | Function  |
|---------------|---|
| Minimum Usage | Specifies the minimum number of times the segment must be repeated. |
| Maximum Usage | Specifies the maximum number of times the segment can be repeated.  |
| Normal        | Not applicable to NCPDP.  |
| Loop Start    | Not applicable to NCPDP.  |
| Loop End      | Not applicable to NCPDP.  |


### **NCPDP Delimited Field Properties Dialog Box**

### Introduction

The NCPDP Delimited Field Properties dialog box is used to define information about a delimited field. It has six tabs:


- Name tab
- Tag tab
- Validation tab
- **Extended Rule tab**
- Standard Rule tab
- Conditions tab

This illustrations shows the NCPDP Delimited Field Properties dialog box.



### Name tab

The Name tab is used to define the name of the delimited field map object. This illustration shows the Name tab.




# Name tab fields and functions

This table lists the fields of the Name tab and their functions.

| Field                            | Function                            |
|----------------------------------|-------------------------------------|
| Please enter the name            | Defines the name of the map object. |
| Please enter a short description | Describes the map object.           |

Tag tab The Tag tab is used to define the field identifier associated with the delimited field. This illustration shows the Tag tab.




### Tag tab fields and functions

This table lists the fields of the Tag tab and their functions.

| Field       | Function  |
|-------------|---|
| Field ID    | Specifies the field identifier for this field.                                  |
| Fixed Order | Indicates that this field must occur in the order specified within the segment. |

### Validation tab

The Validation tab is used to set the field's data type, format, and minimum and maximum lengths. This illustration shows the Validation tab.



### Validation tab fields and **functions**


This table lists the fields of the Validation tab and their functions.

| Field  | Function  |
|--|---|
| Check here if this field is mandatory              | Indicates that this field is required.                    |
| Minimum (field length)                             | Specifies the minimum length of this field.               |
| Maximum (field length)                             | Specifies the maximum length of this field.               |
| Please choose the data type of this field          | Specifies the field's data type:  String Number Date/Time |
| Please choose the format of the data in this field | Specifies the data format.  (Continued on next page)      |

| (Contd)<br>Field                  | Function                 |
|-----------------------------------|--------------------------|
| Data is read/written as raw bytes | Not applicable to NCPDP. |
| use little-endian byte ordering   | Not applicable to NCPDP. |
| use big-endian byte ordering      | Not applicable to NCPDP. |
| Width                             | Not applicable to NCPDP. |

## Extended Rule tab

The Extended Rule tab is used to specify an extended rule for this field. This illustration shows the Extended Rule tab.




# Extended Rule tab fields and functions

This table lists the fields of the Extended Rule tab and their functions.

| Field                                | Function   |
|--------------------------------------|--|
| Please enter the extended rule below | Enables you to enter the extended rule you want to use for this field. |
| Errors                               | Displays any errors that result when you compile this extended rule.   |

### **Standard Rule** tab

The Standard Rule tab is used to specify a standard rule for this map object. This illustration shows the Standard Rule tab.




### **Standard Rule** tab fields and **functions**

This table lists the fields of the Standard Rule tab and their functions.

| Field                                  | Function   |
|--|--|
| Please select the standard rule to use | Specifies the standard rule to use for this field. |

### **Conditions tab**

The Conditions tab is used to select relational conditions to connect fields for syntax or compliance reasons. This illustration shows the Conditions tab.



### **Conditions tab** fields and **functions**

This table lists the fields of the Conditions tab and their functions.


| Field   | Function   |
|---|--|
| Please choose the type of relationship to use | Selects the type of relationship between this field and another field. |
| Please select the condition field             | Specifies the other field in the relationship.                         |
| Available fields                              | Lists the fields that can be used in the relationship.                 |
| Fields used in relationship                   | Specifies the fields used in the relationship.                         |

### Introduction

The Count Properties dialog box is used to set the properties of a count field. It has three tabs:


- Name tab
- Tag tab
- Repeat tab

This illustration shows the NCPCP Count Field Properties dialog box.



### Name tab

The Name tab is used to define the name of the count field. It is also used to describe the field. This illustration shows the Name tab.



### Name tab fields and functions


This table lists the fields of the Name tab and their functions.

| Field                            | Function                             |
|----------------------------------|--------------------------------------|
| Please enter the name            | Defines the name of the count field. |
| Please enter a short description | Describes the count field.           |

Tag tab

Structuring an NCPDP Map

The Tag tab is used to define the field identifier associated with the count field. This illustration shows the Tag tab.




# Tag tab fields and functions

This table lists the fields of the Tag tab and their functions.

| Field       | Function  |
|-------------|---|
| Field ID    | Specifies the field identifier for this field.                                  |
| Fixed Order | Indicates that this field must occur in the order specified within the segment. |

### Repeat tab

The Repeat tab is used to set the minimum and maximum times that this count field can repeat (loop). This illustration shows the Repeat tab.



### Repeat tab fields and functions

This table lists the fields of the Repeat tab and their functions.

| Field                                 | Function  |
|---------------------------------------|---|
| Minimum Usage                         | Specifies the minimum number of times this field repeats. |
| Maximum Usage                         | Specifies the maximum number of times this field repeats. |
| Treat this field as a repeating field | Indicates that this field is a repeating (looping) field. |


### **NCPDP Counter Field Properties Dialog Box**

### Introduction

The Counter Field Properties dialog box is used to set the properties of a counter field. It has four tabs:


- Name tab
- Tag tab
- Repeat tab

This illustration shows the NCPCP Counter Field Properties dialog box.



### Name tab

The Name tab is used to define the name of the counter field. It is also used to describe the field. This illustration shows the Name tab.




### Name tab fields and functions

This table lists the fields of the Name tab and their functions.

| Field                            | Function                               |
|----------------------------------|--|
| Please enter the name            | Defines the name of the counter field. |
| Please enter a short description | Describes the map object.              |

Structuring an NCPDP Map

The Tag tab is used to define the field identifier associated with the counter field. This illustration shows the Tag tab.




# Tag tab fields and functions

This table lists the fields of the Tag tab and their functions.

| Field       | Function  |
|-------------|---|
| Field ID    | Specifies the field identifier for this field.                                  |
| Fixed Order | Indicates that this field must occur in the order specified within the segment. |

### Repeat tab

The Repeat tab is used to set the minimum and maximum times that this counter field can repeat (loop). This illustration shows the Repeat tab.



### Repeat tab fields and functions

This table lists the fields of the Repeat tab and their functions.

| Field                                 | Function  |
|---------------------------------------|---|
| Minimum Usage                         | Specifies the minimum number of times this field repeats. |
| Maximum Usage                         | Specifies the maximum number of times this field repeats. |
| Treat this field as a repeating field | Indicates that is field is a repeating (looping) field.   |

### **Procedures**

### **Defining an NCPDP Batch File**

#### Introduction

This topic describes the two methods of creating the map components for an NCPDP batch file:

- Loading components from a template
- Manually creating the components

### **Loading an NCPDP Template**

### Introduction

The simplest way to create the NCPDP side of your map is to load the appropriate NCPDP template that Sterling Commerce supplied with your GENTRAN:Server product. Each template contains the required batch components as well as the transaction components. After you load the template, you can add, cut, and modify components to meet your needs.

#### Reference

See <u>How to Copy the NCPDP Templates</u> topic in the chapter <u>Creating NCPDP</u>

### **Procedure**

Use this procedure to copy components from a template.

| Step | Action   |
|------|--|
| 1    | Start the NCPDP map in the Application Integration mapper.   |
| 2    | When prompted for the format, click Load the data format from a saved definition and then click the Browse button to locate the appropriate NCPDP DDF template.  Reference                         |
|      | See the Creating NCPDP Maps chapter for instructions.  |
| 3    | Complete the NCPDP map by modifying components as necessary and linking input fields to output fields.   |
|      | Note To modify a map component, right-click the map component you want to modify and select Properties from the shortcut menu to display the properties dialog box for the component.              |
|      | Reference See the Structuring Your Map section in the Designing your Map chapter of the GENTRAN:Server Application Integration User's Guide for detailed instructions on modifying map components. |
| 4    | Save your changes.   |
| 5    | Compile the map to create a translation object.  |

### **Manually Creating NCPDP Map Components**

### Introduction

This table describes the process of defining the NCPDP components in a map. Each stage in this process table has a link to the instructions you need to complete the stage.

#### **Process**

This table describes the process for manually creating NCPDP map components.

| Stage | Description   |
|-------|---|
| 1     | Set the NCPDP File Properties.  |
|       | Reference See How to Configure NCPDP File Properties for instructions.      |
| 2     | Create the batch header.  |
|       | Reference See How to Create the Batch Header Segment for instructions.      |
| 3     | Create the groups.  |
|       | Reference See How to Create a Group for instructions.                       |
| 4     | Create the batch detail segment.  |
|       | Reference See How to Create the Batch Detail Data Segment for instructions. |
| 5     | Create the transmission header segment.                                     |
|       | Reference See How to Create a Transaction Header Segment for instructions.  |
| 6     | Create the transmission segments.   |
|       | Reference See How to Create the Batch Trailer Segment for instructions.     |
| 7     | Create the transaction groups.  |
|       | Reference See How to Create a Group for instructions.                       |
|       | (Continued on next page)  |

| (Contd)<br>Stage | Description   |
|------------------|---|
| 8                | Create the transaction segments (for example, Patient segment, Insurance segment) within the groups.  |
|                  | Reference See How to Create a Positional Segment and How to Create a Delimited Segment for instructions.  |
| 9                | Create the fields.  |
|                  | Reference See How to Create a Positional Field, How to Create a Delimited Field, and How to Create a Count Field, and How to Create a Counter Field for instructions. |
| 10               | Create the batch trailer.   |
|                  | Reference See How to Create the Batch Trailer Segment for instructions.   |


### **How to Configure NCPDP File Properties**


#### Introduction

This topic explains how to set properties at the file level of the NCPDP side of a map. When the NCPDP File object is on the input side of the map, the translator uses the properties to parse and validate input data. When the NCPDP file object is on the output side, the translator uses the properties to structure the output.

#### **Procedure**

Use this procedure to set the NCPDP File Properties.





| (Contd)<br>Step | Action   |
|-----------------|--|
| 5               | If the File object is on the input side of the map, do you expect each input segment to follow another, without a carriage return or line feed to separate them? If the File object is on the output side of the map, do you want output segments structured this way? |
|                 | ▶ If YES, select the <b>Stream Segments</b> check box. (You should select this option.)  |
|                 | ▶ If NO, continue with the next step.  |
|                 | Note If you do not select this option, GENTRAN:Server assumes that each segment starts with a carriage return or line feed.  |
| 6               | Do you want the translator to change mixed-case characters to all uppercase characters?  |
|                 | ▶ If YES, select the <b>Uppercase Strings</b> check box.   |
|                 | ▶ If NO, continue with the next step.  |
| 7               | In the <b>Delimited Segments</b> portion of the Segment tab, check the <b>Specify Separators</b> check box.  |
|                 | System Response The system displays the default separator characters for NCPDP data in the appropriate boxes.  |
| 8               | In the <b>Batch Segments</b> portion of the Segment tab, accept the default values in the <b>Start of Text</b> and <b>End of Text</b> boxes. These values mark the beginning and ending of the batch segment within the file.  |
| 9               | Accept the <b>Field ID Length</b> setting (2) as the length of the field identifiers.  |
| 10              | Do you want the system to truncate the output data, removing leading zeros, fillers, padding, and leading spaces?  |
|                 | ▶ If YES, select the <b>Truncate Data</b> check box on the Segments tab.   |
|                 | ▶ If NO, continue with the next step.  |
|                 | Note Make sure that your trading partner accepts truncated data.   |
|                 | (Continued on next page)   |

| (Contd)<br>Step | Action  |
|-----------------|---|
| 11              | <ul> <li>Do you want to set extended rules at the File level?</li> <li>If YES, click the Loop Extended Rules tab and continue with the next step.</li> <li>If NO, click OK to save your changes and exit the NCPDP File Properties dialog box.</li> </ul> |
| 12              | On the Loop Extended Rules tab, click either On Begin or On End to indicate when you want the extended rule executed (before the system processes the file or after processing).  NCPDP File Properties  Name   Segment   Loop Extended Rules             |
| 13              | Type the extended rule in the Please enter the extended rule below area.  |
| 14              | Click <b>Compile</b> to compile the extended rule.  |
| 15              | Resolve any errors displayed in the Errors portion of the dialog box.   |
| 16              | Repeat step 14 and 15 until the rule compiles without errors.   |
| 17              | Click <b>OK</b> to save your changes.   |

### **How to Create the Batch Header Segment**

#### Introduction


The batch header segment is a positional segment that contains the Sender ID and Receiver ID. Each file can have only one batch header segment.

#### Note

For inbound transmissions, you must map the Batch Number field in the batch header. This is necessary because you must use the same value in the Batch Response Header segment.

# Creating a batch header segment

Use this procedure to create the batch header segment in the NCPDP side of a map.



| (Contd)<br>Step | Action   |
|-----------------|--|
| 2               | Type the segment name in the first box on the Name tab.  |
|                 | Example Batch Header   |
| 3               | Type a description of the segment in the second box on the Name tab and then click <b>OK</b> to save your changes.               |
|                 | Example Batch Header Segment   |
| 4               | Click the Tag tab.   |
|                 | Tag Key Field Looping  Transaction Code:  Position:  This is a batch segment  OK Cancel Help                                     |
| 5               | Complete the fields on the Tag tab:  |
|                 | Type <b>00</b> in the <b>Transaction Code</b> box. This is the segment identification code for a batch header.                   |
|                 | Type <b>0</b> (the default value) in the <b>Position</b> box. This is the position of the segment identifier within the segment. |
|                 | Click the check box labeled <b>This is a batch segment</b> .   |
|                 | IMPORTANT  |
|                 | You must define the tag for an input segment.  |
| 6               | Click <b>OK</b> to save your changes.  |
| 7               | Continue with How to Create the Batch Detail Data Segment.   |

### How to Create the Batch Detail Data Segment

#### Introduction

The batch detail data segment is a positional segment that contains the Transaction Reference Number.

### Fields in the Batch Detail Data Segment

In a GENTRAN:Server NCPDP map, this segment contains only two fields:

- Segment Identifier
- Transaction Reference Number

In your map, the NCPDP Data Record described in the NCPDP Standard for a Detail Data Record follows the Batch Detail Data Segment. The Data Record begins with a Transaction Header Segment.


For inbound transmissions, you must map the Transaction Reference Number field. This is because you have to use the same number when you send the outbound response.


#### Reference

See <u>How to Create a Transaction Header Segment</u> for instructions.

### **Procedure**

Use this procedure to create a positional segment in the NCPDP side of a map.





### **How to Create a Transaction Header Segment**

### Introduction

A Transaction Header segment is a positional segment that indicates if the transaction is a request or response. This header segment contains four of the six key fields that GENTRAN:Server uses to determine the Trading Partnership code for inbound translation.


#### Location

Each Batch Detail Data record has only one transaction header. In your map, the Transaction Header segment immediately follows the Batch Detail Data segment.

### **Procedure**

Use this procedure to create a Transaction Header segment in the NCPDP side of a map.

| Step | Action  |
|------|---|
| 1    | Right-click the icon for the batch detail data segment and select Insert/Positional Segment from the shortcut menu. |
|      | System Response The system displays the NCPDP Positional Segment Properties dialog box.                             |
| 2    | Type the segment name in the first box on the Name tab.   |
|      | Example Transaction Header  |
| 3    | Type a description of the segment in the second box on the Name tab and then click <b>OK</b> to save your changes.  |
|      | Example Transaction Header Segment  |
|      | (Continued on next page)  |



### **How to Create the Batch Trailer Segment**


### Introduction

The Batch Trailer segment is a positional segment that contains the total number of segments in the batch, including the Batch Header and Batch Trailer segments. This segment also contains a message field that can be used to include information about the batch transmission. Each file can have only one Batch Trailer segment.

### **Procedure**

Use this procedure to create the batch header segment in the NCPDP side of a map.

| Step | Action   |
|------|--|
| 1    | Right-click the last icon on the NCPDP side of the map and select <b>Insert/Positional Segment</b> from the shortcut menu. |
|      | System Response The system displays the NCPDP Positional Segment Properties dialog box.                                    |
| 2    | Type the segment name in the first box on the Name tab.  |
|      | Example Batch Trailer  |
| 3    | Type a description of the segment in the second box on the Name tab and then click <b>OK</b> to save your changes.         |
|      | Example Batch Trailer Segment  |
|      | (Continued on next page)   |



### **How to Create a Group**

### Introduction

In an NCPDP map, a transaction is represented by a map group.

A group contains related segments, groups, or both that repeat in sequence until either the data ends or the maximum number of times that the loop is allowed to repeat is exhausted. The system permits up to four repetitions.

### **Group separator** character

In NCPDP transmissions, a group separator character denotes the start of a transaction (except for Eligibility Verification transactions). You can choose to have GENTRAN:Server insert the NCPDP group separator character when you create or modify a map group.


### Reference

See <u>Separator characters</u> for information about the group separator character.


#### **Procedure**

Use this procedure to create a group in a map.

| Step | Action  |
|------|---|
| 1    | Select the map component that precedes the group you are creating in the file layout.                                   |
| 2    | From the <b>Edit</b> menu select <b>Create Sub</b> or <b>Insert</b> , depending on the level.  (Continued on next page) |



| 8 In the Minimum Usage box, type the minimum usage should always be 0 (zero). For a mandatory loop, the minimum usage should be 1 or greater.  9 In the Maximum Usage box, type the maximum number of times the loop can be repeated.  10 Is this a single iteration group?  If YES, continue with Step 11.  If NO, GO TO Step 12.  11 Do you want to specify that the subordinate records and groups should be extracted and located in the parent group when the group is compiled?  If YES, select Promote records to parent; then click OK.  If NO, click OK and continue with the next step.  | (Contd)<br>Step | Action  |
|--|-----------------|---|
| 8 In the Minimum Usage box, type the minimum number of times the loop must be repeated.  Note For a conditional loop, the minimum usage should always be 0 (zero). For a mandatory loop, the minimum usage should be 1 or greater.  9 In the Maximum Usage box, type the maximum number of times the loop can be repeated.  10 Is this a single iteration group?  If YES, continue with Step 11.  If NO, GO TO Step 12.  11 Do you want to specify that the subordinate records and groups should be extracted and located in the parent group when the group is compiled?  If YES, select Promote records to parent; then click OK.  If NO, click OK and continue with the next step. | 7               | Select the Looping tab to access looping options.   |
| In the Minimum Usage box, type the minimum number of times the loop must be repeated.  Note For a conditional loop, the minimum usage should always be 0 (zero). For a mandatory loop, the minimum usage should be 1 or greater.  In the Maximum Usage box, type the maximum number of times the loop can be repeated.  Is this a single iteration group? If YES, continue with Step 11. If NO, GO TO Step 12.  Do you want to specify that the subordinate records and groups should be extracted and located in the parent group when the group is compiled?  If YES, select Promote records to parent; then click OK.  If NO, click OK and continue with the next step.             |                 | Name   Separator   Looping   Loop Extended Rules    Minimum Usage: Promote records to parent                                |
| loop must be repeated.  Note For a conditional loop, the minimum usage should always be 0 (zero). For a mandatory loop, the minimum usage should be 1 or greater.  In the Maximum Usage box, type the maximum number of times the loop can be repeated.  Is this a single iteration group?  If YES, continue with Step 11.  If NO, GO TO Step 12.  Do you want to specify that the subordinate records and groups should be extracted and located in the parent group when the group is compiled?  If YES, select Promote records to parent; then click OK.  If NO, click OK and continue with the next step.  |                 | OK Cancel Help  |
| For a conditional loop, the minimum usage should always be 0 (zero). For a mandatory loop, the minimum usage should be 1 or greater.  9  | 8               | · · · · · · · · · · · · · · · · · · ·   |
| the loop can be repeated.  10 Is this a single iteration group?  If YES, continue with Step 11.  If NO, GO TO Step 12.  11 Do you want to specify that the subordinate records and groups should be extracted and located in the parent group when the group is compiled?  If YES, select Promote records to parent; then click OK.  If NO, click OK and continue with the next step.  |                 | For a conditional loop, the minimum usage should always be 0 (zero). For a mandatory loop, the minimum usage should be 1 or |
| <ul> <li>If YES, continue with Step 11.</li> <li>If NO, GO TO Step 12.</li> <li>Do you want to specify that the subordinate records and groups should be extracted and located in the parent group when the group is compiled?</li> <li>If YES, select Promote records to parent; then click OK.</li> <li>If NO, click OK and continue with the next step.</li> </ul>  | 9               | - · · · · · · · · · · · · · · · · · · ·   |
| should be extracted and located in the parent group when the group is compiled?  If YES, select <b>Promote records to parent</b> ; then click <b>OK</b> .  If NO, click <b>OK</b> and continue with the next step.   | 10              | ▶ If YES, continue with Step 11.  |
| If NO, click <b>OK</b> and continue with the next step.  | 11              | should be extracted and located in the parent group when the  |
| ·  |                 |   |
| (Continued on next nage)   |                 | If NO, click <b>OK</b> and continue with the next step.  (Continued on next page)   |



### **How to Create a Positional Segment**


### Introduction


The fields in positional segments are always in fixed positions and do not require separators. The NCPDP Positional Segment Properties tab enables you to specify identifying value for a positional segment, loops usage and type, and constants.

### **Procedure**


Use this procedure to create a positional segment in the NCPDP side of a map.

| Step | Action   |
|------|--|
| 1    | Select the map component which precedes the segment you are creating.  |
| 2    | From the <b>Edit</b> menu select either <b>Create Sub</b> or <b>Insert</b> , depending on the level of the selected map component.   |
| 3    | Select Positional Segment from the submenu.  System Response The system displays the NCPDP Positional Segment Properties dialog box. |
|      | (Continued on next page)   |





| (Contd)<br>Step | Action   |
|-----------------|--|
| 7               | Do you want to use a key field?  |
|                 | <ul> <li>If YES, select the <b>Key Field</b> tab and then complete the appropriate fields.</li> <li>If NO, continue with the next step.</li> </ul> |
|                 | NCPDP Positional Segment Properties  |
|                 | Name Tag Key Field Looping   |
|                 | Field: posfield2 □   |
|                 | _ Matching rules   |
|                 | © Use constant  ■ Edit   |
|                 | C Use codelist   |
|                 | ☐ Match record when key does not match   |
|                 |  |
|                 |  |
|                 | OK Cancel Help   |
|                 |  |
| 8               | Is the segment a looping structure?  |
|                 | If YES, select the <b>Looping</b> tab.   |
|                 | If NO, accept the defaults and continue with Step 10.  |
|                 | (Continued on next page)   |



## **How to Create a Delimited Segment**


#### Introduction


The Patient, Insurance, Claim, Pharmacy Provider, and other transaction-level segments are delimited segments. Delimited segments and their fields require separators because their lengths are variable. The NCPDP Delimited Segment Properties dialog box enables you to create a delimited segment.


#### **Procedure**

Use this procedure to create a delimited segment in the NCPDP side of a map.

| Step | Action   |
|------|--|
| 1    | Right-click on the map component that precedes the segment you are creating.   |
| 2    | From the drop-down menu, select either <b>Create Sub</b> or <b>Insert</b> , depending on the level of the selected map component.                            |
| 3    | Select Delimited Segment from the submenu.  System Response The system displays the NCPDP Delimited Segment Properties dialog box.  (Continued on next page) |







| (Contd)<br>Step | Action   |
|-----------------|--|
| 10              | In the <b>Min Usage</b> box, type the minimum amount of times the segment must repeat.   |
|                 | Note If the Min Usage box contains a 0 (zero), the segment is conditional. If the Min Usage box contains a 1 or greater, the segment is mandatory.   |
|                 | NCPDP Delimited Segment Properties   |
|                 | Name Tag Key Field Looping   |
|                 | <u>M</u> in Usage: <b>□</b>  |
|                 | C Loop Start   |
|                 | M <u>a</u> x Usage:  1   |
|                 |  |
|                 | OK Cancel Help   |
| 11              | Do you want to specify the maximum number of times the segment can repeat?  If YES, type the maximum amount of times it can repeat in the Max Usage box and then continue with the next step.  If NO, continue with the next step. |
| 12              | Click <b>OK</b> to save changes to the segment.  |

## How to Create a Positional Field

#### Introduction

There are two ways to add positional fields to a map.

- If you have only one field to add, use the Create Sub function. This topic contains the procedure for using this function.
- If you need to add multiple positional fields to a record, use the **Positional** Field Editor. Create the fields for the first record, and then proceed with each sequential record.


#### Reference

See <u>Positional Field Editor</u> for instructions on using the Positional Field Editor to create multiple fields.


### **Create sub** procedure


Use this procedure to create a positional field in the NCPDP side of a map.


| Step | Action   |
|------|--|
| 1    | Select the positional segment that precedes the positional field you are creating.   |
| 2    | Select Create Sub from the Edit menu.  |
| 3    | Select Positional Field from the Create Sub menu.  System Response The system displays the NCPDP Positional Field Properties dialog box. |
|      | (Continued on next page)   |





Structuring an NCPDP Map





















(Continued on next page)

#### **Positional Field Editor**

Use this procedure to create positional fields for a record.



| (Contd)<br>Step | Action  |
|-----------------|---|
| 3               | In the <b>Name</b> box, type the field name.  |
|                 | Notes   |
|                 | Each application field must have a unique name. It is useful<br>to tag the end of the fields that occur in multiple records with<br>a suffix that identifies the record that contains it.   |
|                 | ▶ Do not use spaces or dashes (-) in the field name. You can<br>use the underscore (_) to separate words.   |
| 4               | Do you want to designate the field as mandatory (must be present)?  |
|                 | ▶ If YES, select the <b>Mandatory</b> check box.  |
|                 | ▶ If NO, continue with the next step.   |
| 5               | In the <b>Description</b> box, type a description of the field.   |
|                 | Note Use the description to provide a brief explanation of the field so that you can differentiate it from similar fields.  |
| 6               | From the <b>Data Type</b> list, select the type of the field.   |
|                 | Note  |
|                 | Valid values are:   |
|                 | ▶ String = alpha (A/N)  |
|                 | <ul><li>Number = signed numeric (D/overpunch) or unsigned<br/>numeric (N)</li></ul>   |
|                 | ▶ Date/Time = date or time element (DATE)   |
| 7               | From the <b>Format</b> list, select the field format.   |
|                 | Note The choices for this field depend on the type of field you selected from the Data Type list. If you choose Number or Date/Time in the Data Type box, you can select the data format from the Format list. If you selected String from the Data Type box, you should type a syntax token to denote that this field must be formatted as the specified syntax token dictates. (The default syntax token is X.) |
|                 | Reference See Field Format Values for more information on selecting your data format.   |
|                 | (Continued on next page)  |

| (Contd)<br>Step | Action  |
|-----------------|---|
| 8               | Do you want to indicate the exact position of the field in the record?  |
|                 | If YES, type the starting position of the field in the Start Pos<br>box.  |
|                 | ▶ If NO, continue with the next step.   |
|                 | Notes You want to specify field start positions if, for example, you are using only a few fields but you want them positioned exactly in the record.    |
|                 | The alternative to specifying the start position of each field is to add the fields sequentially in the record and then use the Auto Position function. |
|                 | Reference See Step 13 below for more information on the Auto Position function.   |
| 9               | In the <b>Min Length</b> box, type the minimum number of characters that is acceptable for this field.  |
| 10              | In the Max Length box, type the maximum length of the field.  |
| 11              | Click New.  |
|                 | System Response The system adds the field and creates a new field with blank values ready for you to identify.  |
| 12              | Create the rest of the fields according to your record layout.  |
|                 | Note Click Delete to stop adding fields.  |
|                 | (Continued on next page)  |

| (Contd)<br>Step | Action   |
|-----------------|--|
| 13              | After adding the last field, do you want the system to automatically position the fields in the record?  |
|                 | ▶ If YES, click Auto Position.   |
|                 | Note This option automatically calculates the start position in the record of each field. The system bases the start positions on the assumption that each field is positioned directly after the previous field and is of the length specified in the Max Length box. |
|                 | Click <b>Yes</b> to acknowledge the warning message that fields are sequenced in order.  |
|                 | Warning Use the Auto Position function only if you define a record tag, and if you define every field in the record in the sequence that each field occurs.  |
|                 | Reference See the GENTRAN:Server Application Integration User's Guide for more information on defining record tags.  |
|                 | ▶ If NO, continue with the next step   |
| 14              | Are you completely finished adding fields to the record?   |
|                 | ▶ If YES, click Close.   |
|                 | ▶ If NO, repeat Steps 2 through 13.  |
|                 | <b>Note</b> Repeat this procedure to add fields to the other records you defined.  |
|                 | References See the GENTRAN:Server Application Integration User's Guide for more information on mapping a constant to a field.  |
| 15              | Do you want to define Trading Partnership code rules for this application or definition file?  |
|                 | <ul> <li>If YES, see the chapter <u>Defining Trading Partnership Rules</u> for <u>Application Files</u> in the <i>GENTRAN:Server Application Integration Guide</i> for instructions.</li> <li>If NO, continue with another task.</li> </ul>                            |
|                 | If NO, continue with another task.   |

## How to Create a Delimited Field

#### Introduction


Each NCPDP delimited segment contains a group of logically-related data fields, separated by the field delimiter character. This topic explains how to create a delimited field.

#### Procedure:


Use this procedure to create a delimited field.

| Step | Action  |
|------|---|
| 1    | Right-click on the map object that precedes the delimited field you are creating.   |
| 2    | Depending on the level of the map object you selected, click either Create Sub or Insert from the drop-down menu and then click Delimited Field on the submenu.  System Response The system displays the NCPDP Delimited Field Properties dialog box. |
|      | Name Tag Validation Extended Rule Standard Rule Conditions  Please enter the name:  Please enter a short description:  OK Cancel Help   |
|      | (Continued on next page)  |

Structuring an NCPDP Map



| (Contd)<br>Step | Action  |
|-----------------|---|
| 12              | Select the format of the field from the <b>Format</b> list.   |
|                 | Note The choices for this field depend on the value you selected from the Data Type list. If you choose Number or Date/Time in the Data Type box, you can select the data format from the Format list. If you selected String from the Data Type box, you should type a syntax token to denote that this field must be formatted as the specified syntax token dictates. The default syntax token is X.  Reference See Field Format Values for more information about data formats. |
| 13              | Do you want to specify an extended rule for this field?   |
|                 | If YES, click the Extended Rule tab and enter the rule; then<br>continue with the next step.  |
|                 | ▶ If NO, continue with the step.  |
| 14              | Do you want to specify a standard operation rule for this field?  |
|                 | ▶ If YES, click the Standard Rule tab and enter the rule; then continue with the next step.   |
|                 | ▶ If NO, continue with the step.  |
| 15              | Do you want to set conditional relationships between this field and another field?  |
|                 | ▶ If YES, click the Conditions tab and continue with the next<br>step.  |
|                 | ▶ If NO, continue with Step 18.   |
|                 | (Continued on next page)  |



## **Repeating Fields**

#### Introduction

Repeating fields within a segment occur as logical groups and must be submitted as a set. Only fields that are designated as repeating fields (looping fields) in the NCPDP Telecommunication Standard can be repeated. Count and counter fields identify repeating fields.

- A count field is used to specify the total number of repetitions of the fields in a grouping. All repeating fields must have a count field that accompanies the repeating field in the transaction.
- A **counter field** identifies a specific repeating loop in a series of loops, in sequential order. It is synonymous with occurrence number. Counter fields may occur multiple times with their associated repeating fields.

#### Example


In a repetition of four, the first occurrence of the field or set/logical grouping is preceded by a counter field with a value of 1. The second occurrence of that field or grouping is preceded by a counter with a value of 2, and so on.

#### Reference

See your NCPDP Telecommunication Standard Implementation Guide for information about how the standard uses count and counter fields.

# Example count field in map

This example shows a count field in an NCPDP map.




(Continued on next page)

### **Example counter** field in map

This example shows a counter field in an NCPDP map.

This counter field has two subfields. The second subfield is selected.



#### Introduction


Count and counter fields are repeating fields. A **count field** is used to specify the total number of repetitions that follow of the fields in a grouping.

#### Procedure:

Use this procedure to create a count field.

| Step | Action  |
|------|---|
| 1    | Right-click on the map object that precedes the count field you are creating.   |
| 2    | Depending on the level of the map object you selected, click either Create Sub or Insert from the drop-down menu and then click Count Field on the submenu. |
|      | System Response The system displays the NCPDP Count Field Properties dialog box with the Name tab selected.   |
|      | Name Tag Repeat  Please enter the name:  Please enter a short description:  OK Cancel Help  |
|      | (Continued on next page)  |

| (Contd)<br>Step | Action   |
|-----------------|--|
| 3               | Type the name of the field in the first box on the Name tab.   |
|                 | WARNING  |
|                 | Do not use spaces or dashes in the Name box. You can use the underscore symbol (_) to separate words.  |
| 4               | Type the description of the field in the second box on the Name tab; then click <b>OK</b> .  |
|                 | <b>Tip</b> Use the description to provide a brief explanation of the field so that you can differentiate it from similar fields.   |
| 5               | Click the Tag tab and continue with the next step.   |
|                 | Name Tag Repeat  Field ID:  Fixed Qrder  OK Cancel Help  |
| 6               | Type the field identifier in the <b>Field ID</b> box.  |
| 7               | Do you want to designate that the order of this field is fixed?  If YES, click the Fixed Order check box; then click OK.  If NO, click OK and continue with the next step.  (Continued on next page) |



## How to Create a Counter Field

#### Introduction

Count and counter fields are repeating fields. A counter field identifies a specific loop in a series of loops, in sequential order. Counter fields may occur multiple times with their associated repeating fields.

#### Procedure:

Use this procedure to create a counter field.

| Step | Action  |
|------|---|
| 1    | Right-click on the map object that precedes the counter field you are creating.   |
| 2    | Depending on the level of the map object you selected, click either Create Sub or Insert from the drop-down menu and then click Counter Field on the submenu. |
|      | System Response The system displays the NCPDP Counter Field Properties dialog box with the Name tab selected.   |
|      | Name Tag Repeat  Please enter the name:  Please enter a short description:  |
|      | OK Cancel Help  (Continued on next page)  |
|      | (Continued of flext page)   |

| (Contd)<br>Step | Action   |
|-----------------|--|
| 3               | Type the name of the field in the first box on the Name tab.   |
|                 | WARNING  |
|                 | Do not use spaces or dashes in the Name box. You can use the underscore symbol (_) to separate words.  |
| 4               | Type the description of the field in the second box on the Name tab; then click <b>OK</b> .  |
|                 | <b>Tip</b> Use the description to provide a brief explanation of the field so that you can differentiate it from similar fields.   |
| 5               | Click the Tag tab and continue with the next step.   |
|                 | Name Tag Repeat  Field ID:  Fixed Order  OK Cancel Help  |
| 6               | Type the field identifier in the <b>Field ID</b> box.  |
| 7               | Do you want to designate that the order of this field is fixed?  If YES, click the Fixed Order check box; then click OK.  If NO, click OK and continue with the next step.  (Continued on next page) |

| (Contd)<br>Step | Action  |
|-----------------|---|
| 8               | Click the Repeat tab and continue with the next step.  NCPDP Counter Field Properties  Name Tag Repeat  Minimum Usage  Maximum Usage  Treat this field as a repeating field   |
|                 | OK Cancel Help  |
| 9               | Specify the minimum and maximum number of times that the field can repeat by typing values in the <b>Minimum Usage</b> and <b>Maximum Usage</b> boxes. The default value for Maximum Usage must be 1.   |
|                 | <b>Note</b> if the value in the Minimum Usage is greater than 1, then the Counter field is mandatory.   |
| 10              | If this field is part of a loop, click the <b>Treat this field as a repeating field</b> check box. This option enables you to link this field to a field that is at a different nesting level.  |
|                 | When you link fields on the input side of your map to fields on the output side, the Application Integration mapper normally requires that you link a single-occurring field to a field that is at the same level of nesting. This option allows you to link fields that are in different nesting levels. If you do not check this option, you must link this field to a field that is at the same nesting level. |
| 11              | Click <b>OK</b> to save the changes to the field.   |

# Creating NCPDP Trading Partnership Records

| Contents | Overview   |
|----------|--|
|          | Introduction   |
|          | NCPDP Trading Partnership Records  |
|          | Trading Partnership Dialog Boxes   |
|          | ▶ Interchange Organization Dialog Box  |
|          | ▶ Group Organization Dialog Box  |
|          | Trading Partnership Editor Dialog Boxes  |
|          | ▶ Batch Transaction Information Dialog Box                                     |
|          | <ul> <li>NCPDP Transaction Request Header Information Dialog Box 2</li> </ul>  |
|          | <ul> <li>NCPDP Transaction Response Header Information Dialog Box 2</li> </ul> |
|          | Procedures   |
|          | ▶ How to Create Inbound NCPDP Trading Partnership Records 2                    |
|          | ▶ How to Create Outbound NCPDP Trading Partnership Records 2                   |
|          | ▶ How to Set Batch Transaction Information                                     |
|          | ▶ How to Configure the Transaction Request Header                              |
|          | ▶ How to View the Transaction Response Header                                  |
|          |  |

## **Overview**

## Introduction

## In this chapter

This chapter describes how to create Trading Partnership records for the trading partners with whom you exchange NCPDP files.

## Key terms

This table describes key terms used in this chapter.

| Term        | Description   |
|-------------|---|
| processor   | The entity that processes a claim made for prescriptions or services.   |
| Receiver ID | The code that identifies the processor who receives the batch file. The processor or switch receiving the file assigns the Receiver ID. This ID reflects valid enrollment between trading partners for batch file submission.   |
| Sender ID   | The code that identifies the provider who sends (to a processor or switch) a batch file that contains claims or other NCPDP transactions. The processor or switch usually assigns the provider's Sender ID. This ID reflects valid enrollment between trading partners for batch file submission. |

## **NCPDP Trading Partnership Records**

## Required **Trading Partnership** records

For NCPDP trading partnerships, you must create:

- An Interchange Organization record
- A Group Organization record
- A Trading Partnership record for each inbound document you expect to
- A Trading Partnership record for each outbound document you expect to send

### Reference

See the Working with Trading Partnerships chapter in the GENTRAN:Server Application Integration User's Guide for general information about these records.

## **Supplementary** records

For outbound Trading Partnership records, you must also create these supplementary records:

- Batch Transaction information (header, detail, and trailer segments)
- Transaction Header information for Requests and Responses

## **Trading Partnership Dialog Boxes**

### In this section

This section describes the dialog boxes used to create NCPDP Trading Partnership records.


## It includes:

- Interchange Organization Dialog Box
- **Group Organization Dialog Box**
- **Trading Partnership Editor Dialog Boxes**
- **Batch Transaction Information Dialog Box**
- NCPDP Transaction Request Header Information Dialog Box
- NCPDP Transaction Response Header Information Dialog Box

## **Interchange Organization Dialog Box**

## Illustration

This illustration shows the Interchange Organization dialog box.



## Fields and **functions**

This table describes the fields of the New Interchange Organization dialog box and their functions.


| Field                       | Function   |  |  |
|-----------------------------|--|--|--|
| Organization Informa        | tion   |  |  |
| Code                        | Defines a unique organization code.  |  |  |
| Description                 | Describes the Interchange Organization.  |  |  |
| Interchange IDs             | Interchange IDs  |  |  |
| Your Interchange ID         | Defines your unique interchange identifier that is inserted into the Interchange envelope when the data is translated.                   |  |  |
| Partner's<br>Interchange ID | Defines your trading partner's unique interchange identifier that is inserted into the Interchange envelope when the data is translated. |  |  |
|                             | (Continued on next page)   |  |  |

| (Contd)<br>Field                 | Function  |
|----------------------------------|---|
| Control Numbers                  |   |
| Last Sent Control<br>Numbers     | Initializes the counter used for NCPDP batch numbers. (Outbound only)   |
| Last Received<br>Control Numbers | Initializes the counter used for NCPDP batch numbers for business documents that you receive from this trading partner. |

## **Group Organization Dialog Box**

## Illustration

This illustration shows the New Group Organization dialog box.



## Fields and functions

This table describes the fields of the New Group Organization dialog box and their functions.

| Field                       | Function  |  |
|-----------------------------|---|--|
| Organization informa        | tion  |  |
| Organization Code           | Defines a unique Group Organization code that is inserted into the Group envelope when the data is translated.                            |  |
| Organization<br>Description | Describes the Group Organization.   |  |
| Group IDs                   |   |  |
| Your ID                     | Defines the Service Provider ID Qualifier that is inserted into the group envelope when the data is translated.  (Continued on next page) |  |

| (Contd)<br>Field                 | Function  |
|----------------------------------|---|
| Partner's ID                     | Defines your trading partner's unique Service Provider ID that is inserted into the group envelope when the data is translated.           |
| Control numbers                  |   |
| Last Sent Control<br>Numbers     | Initializes the counter used for control numbers for your business documents.   |
| Last Received<br>Control Numbers | Initializes the counter used for control numbers for business documents that you receive from this trading partner.                       |
| Interchange informat             | ion   |
| Code                             | Displays the interchange organization code associated with this group.  |
| Description                      | Displays the description of the Interchange Organization.   |
| Your ID                          | Displays your unique interchange identifier that is inserted into the Interchange envelope when the data is translated.                   |
| Partner's ID                     | Displays your trading partner's unique interchange identifier that is inserted into the Interchange envelope when the data is translated. |

## **Trading Partnership Editor Dialog Boxes**

## Introduction


The Trading Partnership Editor dialog box contains several tabs.

#### Note

GENTRAN:Server displays a different set of tabs for inbound and outbound trading partnerships.

## **Trading** Partnership tab

This illustration shows an example of the Trading Partnership tab of the Trading Partnership Editor dialog box.




## Fields and **functions**

This table lists the fields of the Trading Partnership tab of the Trading Partnership Editor dialog box and their functions.

| Field                           | Function   |
|---------------------------------|--|
| Trading<br>Partnership<br>Code  | Defines a unique code for the Trading Partnership. The translator uses this code when creating the segment envelope. (maximum of 15 characters)                    |
| Trading Partnership Description | Provides a brief description of the Trading Partnership. (maximum of 30 characters)  |
| Translation                     | Defines the type of translation for the Trading Partnership.   |
| Туре                            | Note The Translation Type box is view only. You can select a translation type only when creating a new Trading Partnership.  |
| Map Name                        | Defines the compiled map (translation object) to use when translating data for the Trading Partnership. Only translation objects (TPL files) are valid selections. |
|                                 | Note   |
|                                 | To search for a specific compiled map, click the Map Search icon to the right of the Map Name text box.  |
| Map description                 | Displays the GENTRAN:Server product and version used to generate the map.  |
| File Definitions filename       | Specifies the file definition (.DDF file) that the map uses if the input file is an application file.  |
|                                 | If the input file is not an application file, this box is disabled.  |
|                                 | The browser associated with this box displays all the file definitions that reside in the App/DDF Files directory.   |
|                                 | Note   |
|                                 | This field links the Trading Partnership record to the file definition. You must complete this box when the input side of the map is an application format.        |

## Inbound EDI Information tab

This illustration shows an example of the Inbound EDI Information tab on the Trading Partnership Editor dialog box.



## Fields and **functions**

This table lists the fields of the Inbound EDI Information tab of the Trading Partnership Editor dialog box and their functions.


| Field            | Function   |
|------------------|--|
| Standard version | Lists the available EDI standards and versions. This is a key field that GENTRAN:Server uses to identify the Trading Partnership record. |
|                  | Note   |
|                  | The Trading Partnership Editor accepts a dollar sign (\$) as a wildcard indicator for this field.  |
|                  | (Continued on next page)   |

| (Contd)<br>Field                         | Function   |
|--|--|
| Document ID                              | Lists the available NCPDP transactions (EDI document types) that you may translate. This is a key field that GENTRAN:Server uses to identify the Trading Partnership record. |
|  | Note   |
|  | The Trading Partnership Editor accepts a dollar sign (\$) as a wildcard indicator for this field.  |
| Accept<br>Messages/Sets<br>with error(s) | Enables you to accept messages or transaction sets containing compliance errors from your trading partner.   |
| Control Numbers                          |  |
| Interchange                              | Initializes the counter used for control numbers for business documents that you receive from your trading partner.  |
|  | Note   |
|  | If you click <b>Maintain globally</b> on the Runtime Information tab, this field is unavailable.   |
| Validate sequence                        | Checks the Interchange control numbers to ensure that they are in sequence.  |
| Group                                    | Initializes the counter used for control numbers for business documents that you receive from this trading partner.  |
|  | Note   |
|  | If you click <b>Maintain globally</b> on the Runtime Information tab, this field is unavailable.   |
| Validate sequence                        | Checks the Group control numbers to ensure that they are in sequence.  |
| Message/Set                              | Initializes the counter used for control numbers for business documents that you receive from this trading partner.  |
| Validate sequence                        | Checks the Message or Transaction Set control numbers to ensure that they are in sequence.   |
| File generation                          | Appends a file generation number to the end of the out filename for TRADACOMs standards.   |
|  | (Continued on next page)   |

| (Contd)<br>Field  | Function  |
|-------------------|---|
| Validate sequence | Checks the File generation control numbers to ensure that they are in sequence. |
| Xref Table        | Displays the Standard Cross Reference dialog box.                               |

## **Outbound EDI** tab

This illustration shows an example of the Outbound EDI tab of the Trading Partnership Editor dialog box.



## Fields and **functions**


This table lists the fields of the Outbound EDI tab of the Trading Partnership Editor dialog box and their functions.

| Field  | Function   |  |
|--|--|--|
| Standard version   | Lists the available EDI standards and versions. This is a key field that GENTRAN:Server uses to identify the Trading Partnership record.                     |  |
|  | Note   |  |
|  | The Trading Partnership Editor accepts a dollar sign (\$) as a wildcard indicator for this field.  |  |
| Document ID  | Lists the available NCPDP transaction types that you may translate. This is a key field that GENTRAN:Server uses to identify the Trading Partnership record. |  |
|  | Note   |  |
|  | The Trading Partnership Editor accepts a dollar sign (\$) as a wildcard indicator for this field.  |  |
| Separator/Terminator In  | nformation   |  |
| Segment separator  | Displays the NCPDP character used to separate segments.  |  |
| Group separator  | Displays the NCPDP character used to separate groups.  |  |
| Field separator  | Displays the NCPDP character used to separate fields.  |  |
| Header Information   |  |  |
| Batch Transaction Information                                  | Defines the type of header segment used for the Interchange envelope.  |  |
| Transaction Header   | Defines whether the Transaction Header is a Request or Response. Default value is based on the Document ID.  |  |
| EDIFACT only (Disabled for NCPDP Trading Partnerships records) |  |  |
| Decimal mark   | This option is not available for NCPDP Trading Partnerships.   |  |
| Release character  | This option is not available for NCPDP Trading Partnerships.   |  |
|  | (Continued on next page)   |  |

| (Contd)<br>Field                       | Function   |  |
|--|--|--|
| Syntax level                           | This option is not available for NCPDP Trading Partnerships. |  |
| Generate UNA                           | This option is not available for NCPDP Trading Partnerships. |  |
| UNHAssociation assigned code           | This option is not available for NCPDP Trading Partnerships. |  |
| General information                    |  |  |
| Enable enveloping                      | This option is not available for NCPDP Trading Partnerships. |  |
| Generate Messages/<br>Sets with errors | Enables you to create output that contains errors.           |  |

## **Runtime** Information tab

This illustration shows an example of the Runtime Information tab of the Trading Partnership Editor dialog box.



## Fields and **functions**

This table lists the fields of the Runtime Information tab of the Trading Partnership Editor dialog box and their functions.

| Field                            | Function  |  |
|----------------------------------|---|--|
| Output filename                  | Defines the name of the file in which GENTRAN:Server will store the translated data.  |  |
| Change<br>translation<br>options | Displays the Translation Options dialog box, which enables you to override (for this Trading Partnership) the default translation option that appends or does not append T or P to the file name. |  |
| Maintain locally                 | Enables you to maintain control numbers at the Trading Partnership level. This is the default setting.  |  |
|                                  | Note The Maintain globally/locally options are displayed when the output file is an EDI standard.   |  |
| Maintain globally                | Enables you to maintain control numbers for an entire organization.   |  |
|                                  | Note The Maintain globally/locally options are displayed when the output file is an EDI standard.   |  |

## **Archive tab**

All options are disabled on this tab for NCPDP Trading Partnerships

## Inbound Acknowledgment tab


All options on this tab are disabled for NCPDP Trading Partnerships.

## **Outbound** Acknowledgment tab

All options on this tab are disabled for NCPDP Trading Partnerships.

## **Categories tab**

This illustration shows an example of the Categories tab of the Trading Partnership Editor dialog box.



## Fields and **functions**


The fields on the Categories tab are specific to your organization. Each field represents a category type that you can assign to the current Trading Partnership.

You must define the categories on the User Defined Category Types dialog box.

## **Batch Transaction Information Dialog Box**

## Illustration

This illustration shows the Batch Transaction Information dialog box.



## Fields and **functions**

This table shows the fields of the Batch Transaction Information dialog box and their functions.

| Field               | Function  |  |
|---------------------|---|--|
| Header Segment Info | ormation  |  |
| Segment Identifier  | Displays the segment identifier for the header segment. The code for an NCPDP File Control header is 00.  |  |
| Transmission Type   | Identifies the type of transmission.  |  |
|                     | T = Transaction (a request). Used when a provider is submitting a batch file.   |  |
|                     | R = Response (a response). Used to denote that a<br>file returned to the HIPAA provider contains<br>responses to claims.                                      |  |
|                     | ► E = Error. Used when the processor or switch has<br>rejected the entire batch file because the file failed<br>the integrity test.                           |  |
| Sender ID           | Displays the identifier that the receiving processor or switch assigns. This ID reflects valid enrollment between trading partners for batch file submission. |  |
|                     | (Continued on next page)  |  |


| (Contd)<br>Field            | Function  |  |
|-----------------------------|---|--|
| Batch Number                | The batch identifier that the sender assigns. It must match the trailer batch number. The maximum size is 7 characters.   |  |
|                             | Notes The batch number on a response batch file should be the same batch number that was used in the request batch file originally sent from the HIPAA provider. This ties the Request batch file to the Response batch file.                               |  |
|                             | This box is available only if you maintain control numbers locally and the Transmission Type is T or E.   |  |
| Creation Date               | Displays the date that the batch file was created. The date format is CCYYMMDD.   |  |
| Creation Time               | Displays the time that the batch file was created. The time format is HHMM.   |  |
| File Type                   | Indicates the type of file.  P = Production T = Test  |  |
| Version/Release #           | Identifies the two-character NCPDP version or release number of the header data.  |  |
| Receiver ID                 | Displays the processor's identification code.   |  |
| Detail Segment Inform       | mation  |  |
| Segment Identifier          | Displays the code used to identify the detail data segment. The code for a detail data record is G1.  |  |
| Transaction Ref#            | Defines the reference number that the sender (e.g., a pharmacy) assigns to uniquely identify a claim within a transmitted file. The maximum size is 10 characters.  |  |
|                             | Note The processor who receives the request file and builds the response file must include the claim's transaction reference number with each detail data record response. This enables the provider to match the response with claim originally submitted. |  |
| Trailer Segment Information |   |  |
| Segment Identifier          | Displays the code used to identify the trailer segment. The code for a trailer segment is 99.  (Continued on next page)   |  |
| 2.35                        | The code for a trailer segment is 99.   |  |

| (Contd)<br>Field | Function   |
|------------------|--|
| Batch Number     | Displays the batch number that the sender assigns. This is the same batch number used in the batch header segment.   |
| Record Count     | Displays the total number of records in the batch file, including the header and trailer records.  |
| Message          | Defines the informational message to be included in the trailer segment. Can be used to explain the reasons why the entire batch file was rejected, include information about testing, or list any other information that needs to be sent regarding the batch. The maximum size is 35 characters. |

## NCPDP Transaction Request Header Information Dialog Box

#### Illustration

This illustration shows the NCPDP Transaction Request Header Information dialog box.



## Fields and functions

This table shows the fields of the NCPDP Transaction Request Header Information dialog box and their functions.


| Field              | Function  |  |
|--------------------|---|--|
| BIN Number         | Defines the issuer ID or bank ID number used for network routing.                   |  |
| Version/Release#   | Identifies the two-character NCPDP version or release number of the header data.    |  |
| Transaction Code   | Displays the NCPDP Transaction Code, which indicates the type of document or claim. |  |
| Processor Control# | Defines the processor control number.   |  |
| Transaction Count  | Displays the number of transactions included in the transmission.                   |  |
|                    | (Continued on next page)  |  |

| (Contd)<br>Field                     | Function  |
|--------------------------------------|---|
| Service Provider ID<br>Qualifier     | Displays the code that qualifies the Service Provider ID.  Reference See your NCPDP Data Dictionary for values. |
| Service Provider ID                  | Displays the ID assigned to the pharmacy or service provider.   |
| Date of Service                      | Displays the date that the prescription was filled or professional service was rendered.                        |
| Software Vendor/<br>Certification ID | Defines the ID that the processor assigned to identify the source of the software.                              |

## NCPDP Transaction Response Header Information Dialog Box

#### Illustration

This illustration shows the NCPDP Transaction Response Header Information dialog box.



## Fields and functions

This table shows the fields of the NCPDP Transaction Request Header Information dialog box and their functions.

| Function  |  |  |
|---|--|--|
| Identifies the two-character NCPDP version or release number of the header data.                  |  |  |
| Displays the NCPDP Transaction Code, which identifies the type of document or claim.              |  |  |
| Displays the number of transactions included in the transmission.                                 |  |  |
| Displays the status of the transmission.  • A = Accepted • R = Rejected  (Continued on next page) |  |  |
|   |  |  |

| (Contd)<br>Field                 | Function  |
|----------------------------------|---|
| Service Provider ID<br>Qualifier | Displays the code that qualifies the Service Provider ID.  Reference See your NCPDP Data Dictionary for values. |
| Service Provider ID              | Displays the ID assigned to the pharmacy or service provider.   |
| Date of Service                  | Displays the date that the prescription was filled or professional service was rendered.                        |

## **Procedures**

## **How to Create Inbound NCPDP Trading Partnership** Records

#### Introduction


This topic briefly describes how to create a Trading Partnership record when the translation input is in an NCPDP standard format.

#### Reference

See the Working with Trading Partnerships chapter in the GENTRAN:Server Application Integration User's Guide for detailed instructions on creating Trading Partnership records.

#### **Procedure**

Use this procedure to create a Trading Partnership record.



| (Contd)<br>Step | Action Inbound EDI tab                                      |   |  |
|-----------------|---|---|--|
|                 |   |   |  |
|                 | Field   | Value   |  |
|                 | Standard Version  | Select an NCPDP version from the drop-down list.  |  |
|                 | Document ID   | Specify the NCPDP transaction code.<br>Select one from the list or enter it in<br>the Document ID box.                          |  |
|                 |   | Note "Q" at the end of the document ID indicates that the document is a request. "R" indicates that the document is a response. |  |
| 6               | Click <b>Finish</b> to save the Trading Partnership record. |   |  |

## **How to Create Outbound NCPDP Trading Partnership Records**

### Introduction

This topic briefly describes how to create a Trading Partnership record when the output of translation is in an NCPDP standard format.

#### Reference

See the Working with Trading Partnerships chapter in the GENTRAN:Server Application Integration User's Guide for detailed instructions on creating Trading Partnership records.

## **Procedure**

Use this procedure to create a Trading Partnership record.

| Step | Action   |  |
|------|--|--|
| 1    | Start the Trading Partnership editor.  |  |
| 2    | Create the Interchange Organization record, if it does not exist.  Note The Control numbers fields are used for batch numbers in NCPDP trading partnership records.                  |  |
|      | New Interchange Organization  Organization information Code  Description  Interchange IDs Your ID Partner's ID  Control numbers  Last sent  OK Cancel Help  (Continued on next page) |  |

| (Contd)<br>Step | Action  |  |   |
|-----------------|---|--|---|
| 3               | Create the Group Orga following values in the               |  | t does not exist. Use the   |
|                 | Field   | Value  |   |
|                 | Your ID   | Type the Ser   | vice Provider ID Qualifier.   |
|                 | Partner's ID  | Type the Ser   | vice Provider ID.   |
|                 | Service Provider ID Qualifier Service Provider ID  Columbia | New Group Organization  Organization information Code  Description  Group IDs  Your ID  Partner's ID  Control numbers  Last sent   0  Last received   0  Interchange information Code: 6145552121  Description: Space Savers, Inc. Your ID: 6145552000  Partner's ID: 6145552121 |   |
| 4               | Start the Trading Partnership wizard.                       |  |   |
| 5               |   | Complete the series of dialog boxes in the Trading Partnership wizard. Note the field requirements for the following dialog boxes.   |   |
|                 | Trading Partnership   |  |   |
|                 | Field   | Value  |   |
|                 | Map name  | Specify the n  | ame of the NCPDP map.   |
|                 | File Definition filename                                    |  | ame of the NCPDP input if you used a DDF file to ap).  (Continued on next page) |


| (Contd)<br>Step | Action  |   |  |
|-----------------|---|---|--|
|                 | Outbound EDI  |   |  |
|                 | Field   | Value   |  |
|                 | Standard Version  | Select the current NCPDP version from the drop-down list.   |  |
|                 | Document ID   | Specify the NCPDP transaction code.<br>Select one from the list or enter it in<br>the Document ID box.  |  |
|                 | Batch Transaction Header                                    | NCPDP is displayed in the box when you choose an NCPDP standard.  |  |
|                 |   | Reference To change the settings for the Batch Header, click Edit and then see the How to Set Batch Transaction Information topic for detailed instructions.                          |  |
|                 | Transaction Header  | Either <b>Request</b> or <b>Response</b> is displayed in this box, based on the value in the <b>Document ID</b> box.  |  |
|                 |   | Reference If you want to change the settings for the Transaction Header, click Edit and then see the How to Configure the Transaction Request Header topic for detailed instructions. |  |
|                 |   | Note You can view, but you cannot edit, a response transaction header. See How to View the Transaction Response Header.   |  |
| 6               | Click <b>Finish</b> to save the Trading Partnership record. |   |  |


#### Introduction

This topic describes how to define Batch Transaction information used for outbound NCPDP files that you send to this trading partner. There are three segments to define: Header segment, Detail segment, and Trailer segment.

#### **Procedure**

Use this procedure to configure the batch transaction information for this Trading Partnership.





| (Contd)<br>Step | Action  |
|-----------------|---|
| 4               | Do you want to change the file type?  |
|                 | <ul> <li>If YES, type the correct value in the File Type box and then continue with the next step. The valid values are:</li> <li>P = Production</li> </ul> |
|                 | — T = Test  |
|                 | ▶ If NO, continue with the next step.   |
| 5               | Do you want to change the version release number?   |
|                 | If YES, type the correct value in the <b>Version/Release#</b> box and then continue with the next step.   |
|                 | ▶ If NO, continue with the next step.   |
| 6               | Do you want to change the transaction reference number?   |
|                 | If YES, type the correct value in the <b>Transaction Ref#</b> box and then continue with the next step.   |
|                 | ▶ If NO, continue with the next step.   |
| 7               | Do you want to change the text of the message in the trailer segment?   |
|                 | ▶ If YES, type the new message in the <b>Message</b> box and then continue with the next step.  |
|                 | ▶ If NO, continue with the next step.   |
| 8               | Click <b>OK</b> to save your changes.   |
|                 | System Response The system returns to the Outbound EDI dialog box.  |

## How to Configure the Transaction Request Header

## Introduction


This topic describes how to configure the settings of the transaction header used for outbound NCPDP request transactions that you send to this trading partner.


#### Note

You can use this procedure to view the settings for a response transaction header, but you cannot change them. See How to View the Transaction Response Header for information.

#### **Procedure**

Use this procedure to configure the transaction request header information for this Trading Partnership.





## How to View the Transaction Response Header


#### Introduction


This topic describes how to view the settings of the transaction header used for outbound NCPDP response transactions that you send to this trading partner.

You can view the settings for a Transaction Response Header, but you cannot change them.

## **Procedure**

Use this procedure to view the Transaction Response Header information for this Trading Partnership.







# **Batch Transaction Sets**

#### Contents

| Þ | Batch Transaction Header            | 2 |
|---|-------------------------------------|---|
| • | Batch Detail Data Record            | 3 |
| • | Batch Trailer Record                | 4 |
| • | Request Transaction Header Segment  | 5 |
| • | Response Transaction Header Segment | 6 |
|   |                                     |   |

### **Batch Transaction Header**

Format: fixed-length (non-delimited)

Length: 75 characters

Segment ID: 2-characters (00)

| Field  | Field Name                    | Туре | Length | Key<br>Field | Value   |
|--------|-------------------------------|------|--------|--------------|---|
| 880-K4 | Text Indicator                | A/N  | 1      |              | Start of text (STX) = X'02'   |
| 701    | Segment<br>Identifier         | A/N  | 2      |              | 00  |
| 880-K6 | Transmission<br>Type          | A/N  | 1      |              | T = Transaction R = Response E = Error  |
| 880-K1 | Sender ID                     | A/N  | 24     | Yes          | Defined by processor or switch  |
| 806-5C | Batch<br>Number               | N    | 7      |              | Number that the sender<br>assigns. Matches Batch<br>Number in Trailer. To be<br>returned in Response or<br>Error file from processor/<br>switch |
| 880-K2 | Creation Date                 | N    | 8      |              | Format = CCYYMMDD   |
| 880-K3 | Creation<br>Time              | N    | 4      |              | Format = HHMM   |
| 702    | File Type                     | A/N  | 1      |              | P = Production T = Test   |
| 102-A2 | Version/<br>Release<br>Number | A/N  | 2      |              | Version/release number of Header data   |
| 880-K7 | Receiver ID                   | A/N  | 24     | Yes          | Identifier defined by processor or switch   |
| 880-K4 | Text Indicator                | A/N  | 1      |              | End of text (ETX)-X'03'   |

### **Batch Detail Data Record**

Format: variable-length (contains both fixed- and variable-length fields)

Segment ID: 2-character segment ID (G1)

| Field  | Field Name                          | Туре | Length | Key<br>Field | Value  |
|--------|-------------------------------------|------|--------|--------------|--|
| 880-K4 | Text Indicator                      | A/N  | 1      |              | Start of text (STX) = X'02'  |
| 701    | Segment<br>Identifier               | A/N  | 2      |              | G1   |
| 880-K5 | Transmission<br>Reference<br>Number | A/N  | 1      |              | Reference number that the provider assigns to the batch transmission |
|        | NCPDP Data<br>Record                |      | Varies |              |  |
| 880-K4 | Text Indicator                      | A/N  | 1      | Yes          | End of text (ETX)-X'03'  |

### **Batch Trailer Record**

Format: fixed-length

Length: 56 characters

Segment ID: 2-character (99)

| Field  | Field Name            | Туре | Length | Key<br>Field | Value  |
|--------|-----------------------|------|--------|--------------|--|
| 880-K4 | Text Indicator        | A/N  | 1      |              | Start of text (STX) = X'02'  |
| 701    | Segment<br>Identifier | A/N  | 2      |              | 99   |
| 806-5C | Batch<br>Number       | N    | 7      |              | Number that the sender assigns to the batch. Matches Batch Number in Header. |
| 751    | Record Count          | N    | 10     |              | Total number of enrollment segments in the entire file                       |
| 504-F4 | Message               | A/N  | 35     |              | Free-form message  |
| 880-K4 | Text Indicator        | A/N  | 1      | Yes          | End of text (ETX)-X'03'  |

## **Request Transaction Header Segment**

Format: fixed-length

Length: 56 characters

| Field  | Field Name                                 | Туре  | Length | Key<br>Field | Value  |
|--------|--|-------|--------|--------------|--|
| 101-A1 | BIN Number                                 | 9(6)  | 6      |              | Card issuer ID or bank ID number used for network routing.                               |
| 102-A2 | Version/<br>Release#                       | X(2)  | 2      | Yes          | 01,03,3151 (51 is version 5.1)   |
| 103-A3 | Transaction<br>Code                        | X(2)  | 2      | Yes          | E1, B1, B2, B3, C1, C2,<br>C3, N1, N2, N3, P1, P2,<br>P3, P4                             |
| 104-A4 | Processor<br>Control #                     | X(10) | 10     |              | Control number assigned by the processor   |
| 109-A9 | Transaction<br>Count                       | X(1)  | 1      |              | Blank or 1, 2, 3, 4  |
| 202-B2 | Service<br>Provider ID<br>Qualifier        | X(2)  | 2      | Yes          | 01, 02,, 13, 14, 99 (07 is NCPDP Provider ID)  |
| 201-B1 | Service<br>Provider ID                     | X(15) | 15     | Yes          | Pharmacy number or provider identifier   |
| 401-D1 | Date of<br>Service                         | 9(8)  | 8      |              | Format = CCYYMMDD  |
| 110-AK | Software<br>Vendor/<br>Certification<br>ID | X(10) | 10     |              | Identifier that the switch<br>or processor assigns to<br>identify the software<br>source |

## **Response Transaction Header Segment**

Format: fixed-length

Length: 31 characters

| Field  | Field Name                          | Туре  | Length | Key<br>Field | Value  |
|--------|-------------------------------------|-------|--------|--------------|--|
| 102-A2 | Version/<br>Release#                | X(2)  | 2      | Yes          | 01,03,3151 (51 is version 5.1)                               |
| 103-A3 | Transaction<br>Code                 | X(2)  | 2      | Yes          | E1, B1, B2, B3, C1, C2,<br>C3, N1, N2, N3, P1, P2,<br>P3, P4 |
| 109-A9 | Transaction<br>Count                | X(1)  | 1      |              | Blank or 1, 2, 3, 4  |
| 501-F1 | Header<br>Response<br>Status        | X(1)  | 1      |              | A = Accept R = Reject  |
| 202-B2 | Service<br>Provider ID<br>Qualifier | X(2)  | 2      | Yes          | 01, 02,, 13, 14, 99 (07 is NCPDP Provider ID)                |
| 201-B1 | Service<br>Provider ID              | X(15) | 15     | Yes          | Pharmacy number or provider identifier                       |
| 401-D1 | Date of<br>Service                  | 9(8)  | 8      |              | Format = CCYYMMDD  |

## Index

| A  | count field <i>4-107, 4-109</i>                |
|--|--|
| access   | counter field <i>4-107, 4-112</i>              |
| regaining after time-out 1-8                               | Counter Properties dialog box                  |
| App Source Filename 5-10                                   | Name tab 4-50, 4-54                            |
| auto_logout.cfg 1-8  | Repeat tab 4-52, 4-56                          |
|  | creating                                       |
| В  | Batch Detail Data segment 4-67                 |
| batch detail data record 2-16                              | Batch Header segment 4-65                      |
| contents of 2-16   | batch trailer segment 4-72                     |
| Batch Detail Data segment                                  | delimited field 4-102                          |
| creating 4-67  | group <i>4-74</i>                              |
| fields in 4-67   | inbound NCPDP Trading Partnership record 5-25  |
| batch file   | NCPDP batch file 4-58                          |
| defining 4-57  | NCPDP components in a map 4-59                 |
| manually creating 4-59                                     | outbound NCPDP Trading Partnership records 5-  |
| batch file error 2-14                                      | 28   |
| batch file error response 2-14                             | positional field 4-88                          |
| Batch Header segment                                       | positional segment <i>4-78</i>                 |
| creating 4-65  | repeating field <i>4-107</i>                   |
| batch mode 2-13  | transaction header segment 4-70                |
| Batch Number 5-19  | <b></b>  |
| batch trailer segment                                      | D  |
| creating 4-72  | data element 2-5                               |
| batch transaction header <i>5-3</i>                        | Date of Service 5-22, 5-24                     |
| configuring 5-31   | delimited field                                |
| key fields in <i>2-15</i>                                  | creating 4-102                                 |
| batch transaction header segment 2-15                      | delimited segment                              |
| contents of 2-15   | creating 4-83                                  |
| Batch Transaction Information dialog box <i>5-18</i>       | in an NCPDP batch transmission 4-4             |
| batch transmission 2-14                                    | detail data record 2-16                        |
| delimited segments in 4-4                                  | dollar sign (\$) <i>5-11, 5-12, 5-14</i>       |
| positional segments in 4-4                                 | ασιια: σιθτ. (φ) σ 77, σ 72, σ 77              |
| BIN Number 5-21  | E  |
| binary segment 1-2   | element 2-5                                    |
| billary segment 1-2  | ETX field 2-14                                 |
| C  | LIX Hold Z 14                                  |
|  | F  |
| carriage returns in output 4-63                            | field 2-5                                      |
| Categories tab 5-17  | creating delimited 4-102                       |
| configuring  | creating positional 4-88                       |
| batch transaction header 5-31                              | creating positional with Create Sub 4-88       |
| NCPDP File properties 4-61                                 | creating repeating 4-107                       |
| Request Transaction Header for a Trading                   | creating with the Positional Field Editor 4-98 |
| Partnership 5-34   | separator character 2-6                        |
| Response Transaction Header for a Trading Partnership 5-36 | field separator character 2-5, 2-6             |
| E ALLICESTIIU 3-30   | nois opporator origination 2 0, 2 0            |

| fields                                   | NCPDP Delimited Field Properties dialog box   |
|--|---|
| mandatory 2-5                            | 4-41  |
| optional 2-5                             | Conditions tab 4-48                           |
| File Browser 1-5                         | Extended Rule tab 4-46                        |
| File properties                          | Name tab 4-42                                 |
| setting NCPDP 4-61                       | Standard Rule tab 4-47                        |
|  | Tag tab <i>4-4</i> 3                          |
| G  | Validation tab 4-44                           |
| group                                    | NCPDP Delimited Segment Properties dialog box |
| creating 4-74                            | 4-36  |
| maximum repetitions of 4-74              | Key Field tab 4-39                            |
| separator character 2-6                  | Looping tab 4-40                              |
| Group Organization dialog box 5-7        | Name tab <i>4-37</i>                          |
| group separator 4-74                     | Tag tab <i>4</i> -38                          |
| group separator character 2-6, 2-10      | NCPDP File properties                         |
| group copulates character = 0, = 10      | configuring 4-61                              |
| H  | NCPDP File Properties dialog box 4-8          |
| Header Response Status 5-23              | Loop Extended Rules tab 4-13                  |
| header segment 2-4                       | Name tab 4-9                                  |
| Tioddol doginalit 2 7                    | Segment tab 4-10                              |
| I  | NCPDP Group Properties dialog box 4-14        |
| idle time                                | Looping tab 4-17                              |
| changing 1-8                             | Name tab 4-15                                 |
| Inbound EDI Information tab 5-11         | NCPDP map                                     |
| Interchange Organization dialog box 5-5  | component icons 3-8                           |
| interchange Organization dialog box 5-5  | creating 3-7                                  |
| K  | creating an inbound map 3-10                  |
| Key Field tab <i>4-81, 4-86</i>          | creating an outbound map 3-14                 |
| Ney 1 leid tab 4-01, 4-00                | example inbound 3-8                           |
| M  | NCPDP map components 3-8                      |
|  | NCPDP map structure 4-4                       |
| map components icons 3-8                 | NCPDP Positional Field dialog box 4-26        |
| ICOIIS 3-0                               | NCPDP Positional Field Properties dialog box  |
| N  | Conditions tab 4-34                           |
|  | Extended Rule tab 4-32                        |
| NCPDP batch file                         | Name tab 4-27                                 |
| creating 4-57                            | Standard Rule tab 4-33                        |
| manually creating components of 4-59     |   |
| NCPDP Batch Transaction Standard 2-13    | Validation tab 4-28                           |
| NCPDP batch transmission 2-14            | NCPDP Positional Segment Properties dialog    |
| parts of 2-14                            | box 4-19                                      |
| NCPDP Counter Properties dialog box 4-49 | Key Field tab 4-23                            |
| NCPDP data                               | Looping tab 4-25                              |
| analyzing 3-6                            | Name tab 4-20                                 |
| NCPDP DDF file 3-10, 3-14                | Tag tab 4-21                                  |
| NCPDP DDF template                       | NCPDP standard                                |
| copying components from 4-58             | overview 2-4                                  |
|  | separator characters 2-6                      |
|  | supported transactions 2-7                    |
|  | supported version 2-7                         |

| NCPDP templates                                   | Runtime Information tab 5-15                              |
|---|---|
| contents 3-3                                      | 6   |
| installing 3-3                                    | S   |
| NCPDP Transaction Request Header Information      | screen saver 1-5  |
| dialog box 5-21                                   | segment 2-4   |
| NCPDP Transaction Response Header                 | creating Batch Detail Data 4-67                           |
| Information dialog box 5-23                       | creating Batch Header 4-65                                |
| NCPDP transaction syntax 2-10                     | creating batch trailer 4-72 creating delimited 4-83       |
| example 2-10 NCPDP translation                    | creating delimited 4-63 creating positional 4-78          |
| set up tasks 3-5                                  | creating positional 4-76 creating transaction header 4-70 |
| set up tasks 5-5                                  | in a batch transmission 4-4                               |
| 0   | separator character 2-6                                   |
| ODBC map components 3-8                           | segment separator character 2-6                           |
| ODBC option 2-7                                   | Sender ID <i>5-18</i>                                     |
| Outbound EDI tab 5-13                             | in batch transaction header 2-15                          |
| Overpunch format 4-6                              | separator characters 2-6                                  |
| overpanen ieimat / c                              | example 2-6   |
| P   | Service Provider ID 5-22, 5-24                            |
| padding character 4-31                            | Service Provider ID Qualifier 5-22, 5-24                  |
| positional field                                  | Software Vendor/Certification ID 5-22                     |
| creating 4-88                                     | SP 4-31   |
| creating with the Create Sub function 4-88        | STX field 2-14  |
| Positional Field Editor 4-88                      | syntax tokens 4-7   |
| positional fields                                 | _   |
| creating with the Positional Field Editor 4-98    | Т   |
| positional segment                                | Trading Partnership code                                  |
| creating 4-78                                     | key fields in NCPDP batch transaction 2-12                |
| in an NCPDP batch transmission 4-4                | Trading Partnership dialog box 5-9                        |
| Processor Control# 5-21                           | Trading Partnership Editor                                |
|   | Categories tab 5-17                                       |
| Q   | Inbound EDI tab 5-11                                      |
| qualifier field                                   | Outbound EDI tab 5-13                                     |
| definition 2-5                                    | fields and functions 5-14                                 |
| R   | Runtime Information tab 5-15 fields and functions 5-16    |
| Receiver ID                                       |   |
| in batch transaction header 2-15                  | Trading Partnership tab 5-9 fields and functions 5-10     |
| repeating field                                   | Trading Partnership record                                |
| creating 4-107                                    | creating inbound NCPDP 5-25                               |
| Request transaction 2-8                           | Trading Partnership records 5-1                           |
| structure of 2-8                                  | creating outbound NCPDP 5-28                              |
| Request Transaction Header                        | Trading Partnership tab <i>5-9</i>                        |
| configuring for a Trading Partnership <i>5-34</i> | transaction 2-4   |
| Response transaction 2-8                          | Transaction Code 5-21, 5-23                               |
| structure of 2-9                                  | Transaction Count 5-21, 5-23                              |
| Response Transaction Header                       | Transaction Header 5-3                                    |
| configuring for a Trading Partnership 5-36        |   |

transaction header segment 2-16, 2-17, 4-70
creating 4-70
key fields in 2-17
location 4-70
purpose of 2-17
request 2-17
response 2-17
Transaction Reference Number field 4-67
translation process
inbound NCPDP 3-13
outbound NCPDP 3-17
transmission 2-4
Transmission Type 5-18

truncation definition 2-11

#### V

Version/Release# 5-21, 5-23

#### W

wildcard

Group/Application ID *5-11*, *5-12*, *5-14* Interchange ID *5-11*, *5-12*, *5-14* Set ID *5-11*, *5-12*, *5-14* Standard Version *5-11*, *5-12*, *5-14* wildcard indicator *5-11*, *5-12*, *5-14*