Sterling Standards Library

Using AUTACK Messages with EDIFACT

Version 5.3



Sterling Commerce, Inc.	2
Supprignt 2007-2008 Sterning Commerce, Inc. All rights reserved.	
© Copyright 2007-2008 Sterling Commerce, Inc. All rights reserved.	

Contents

Using AUTACK Messages with EDIFACT in Application	4
Prerequisite Knowledge	4
Using AUTACK with Application	4
EDIFACT Inbound Syntax 4 UNB UNZ Envelope Properties, Interchange Level	7
EDIFACT Inbound Syntax 4 UNG UNE Envelope Properties, Group Level	10
EDIFACT Inbound Syntax 4 UNH UNT Envelope Properties, Transaction Level	12
EDIFACT Outbound Syntax 4 UNB UNZ Envelope Properties, Interchange Level	26
EDIFACT Outbound Syntax 4 UNG UNE Envelope Properties, Group Level	32
EDIFACT Outbound Syntax 4 UNH UNT Envelope Properties, Transaction Level	34

Using AUTACK Messages with EDIFACT in Application

Application supports the use of AUTACK messages for EDIFACT. AUTACK is a secure authentication and acknowledgement message that is used to:

- ♦ Authenticate an interchange being sent
- ◆ Ensure integrity of content by hashing and signing the entire set of transaction messages in the interchange
- ♦ Ensure non-repudiation of origin by the sender's digital signature against an EDIFACT structure in the interchange document

Note: Application currently supports secure authentication and non-repudiation of origin. Application does not support the acknowledgement of AUTACK messages or non-repudiation of receipt.

Prerequisite Knowledge

The audience using this software should be familiar with Application and the AUTACK messages.

This documentation is not intended to explain AUTACK specifications; for more information, access this web site:

http://www.gefeg.com/jswg/

Using AUTACK with Application

The following conditions apply when using AUTACK in Gentran Integration Suite:

- ◆ Certificates along with all other security features exist at the transaction or group level.
- ◆ An AUTACK can be used to secure either a group or a transaction, but it cannot be used to secure both within a single interchange.
- ◆ Only one AUTACK can exist in an interchange.
- ♦ You can use AUTACK in Gentran Integration Suite in two ways within an interchange:
 - At the transaction level, AUTACK messages can secure one or multiple transactions in the interchange.
 - At the group level, AUTACK messages can secure multiple groups.

When an AUTACK message is used, the security occurs on the transaction envelope for transactions and the group envelopes for groups. Security must be on by selecting Use Security on the envelope wizard to view the security screens.

For outbound envelopes, two parameters control what type of functionality is used: Security and message body and Whole related message, package, group, or interchange. These determine whether the AUTACK is embedded in the transaction or if it is referencing the data transaction or group it is securing. If referencing the data transaction or group, AUTACKs require their own group enveloping. An envelope parameter in the group envelope, AutackGroupEnvelope, indicates (when selected) that this is an AUTACK Group Envelope.

For inbound envelopes, you need two transaction envelopes: one for the message data to turn security on, and one for the AUTACK message where additional security settings are configured. Authentication for inbound and outbound messages using AUTACK works as follows:

For Inbound Messages using AUTACK Application:

- 1. Reads the scope on the AUTACK transaction envelope to determine which functionality to reference.
- 2. Reads a specific certificate on the AUTACK transaction envelope, or generates a certificate name from the data.
- 3. Verifies the signature in the USY segment.

Note: Hash total is built into signature in the USY segment. The hash total and signature are verified, and it is the hash total that authenticates document content.

For Outbound Messages using AUTACK Application:

- 1. Reads the envelope parameters
- 2. Calculates hash total of interchange content, which is used as input when calculating digital signature. The results are then encrypted using the originator's private key.

AUTACK messages use security header groups (USH) and security trailer groups (UST) as shown below.

```
LIN+333333++9996543210:BP1
PIA+1+22222222222:UP1
IMD+++:::THIS IS ITEM 2 DESCRIPTION'
QTY+12:50:EA1
QTY+21:50:EA1
MOA+146:0.11
UNS+S'
CNT+2:21
MOA+128:1051
UNT+29+11
UNH+2+AUTACK:4:1:UN'
USH+7+1+3+1+2+2+1+++1:20060808:0336451
USA+1:16:1:16:1'
USC++3:B2BHttp:anatu:5754f673:10cea3e7051:-7fb5:2+31
USA+6:16:1:10:1'
USB+1+5+20060808:033645+PETTEST1:14+PETTEST1:141
USX+4+PETTES<u>T1:14+PETTEST1:14++++1</u>'
USY+1+1:3E9E154F554667BAC17703FBE06434D3A18C0D8FF6F456482136C7F2708FAEB6DC63FBCE{
UST+1+5'
UNT+10+2'
UNZ+2+3'
```

To use AUTACK with Application, you must complete the following tasks:

1. Create the appropriate inbound and outbound envelopes with security for each message type you are sending and receiving. To initiate AUTACK, follow these steps:

- For inbound and outbound UNG/UNE envelopes select **Yes** for the Use Security option in the envelope wizard.
- Create a group envelope for AUTACK and select Yes for both security and AutackGroupEnvelope options.
- For inbound and outbound UNH/UNT envelopes, create an envelope for the AUTACK message by typing AUTACK in the Message Type field, and select Yes for the Use Security option.
- 2. If you are creating an inbound UNH/UNT transaction envelope with a message type of AUTACK you can configure the trusted certificate you want to use when validating the digital signature. You must select one of two options in the Scope of Security Application list. If you are configuring a non-AUTACK message type envelope, then the security configuration ends.
 - 1 Security and message body. Use this option if you want the AUTACK embedded in the transaction that it is securing.
 - 3 Whole related message, package, group, or interchange. Use this option if you want the AUTACK to reference the data transaction or the group it is securing. When selecting this option, you have two options for selecting the name of the certificate:
 - Use a certificate in USC segment or generate a certificate name. Use this option to generate a certificate name based on security configurations that you specify.
 - Use a specified certificate only

EDIFACT Inbound Syntax 4 UNB UNZ Envelope Properties, Interchange Level

Note: An (*) asterisk indicates that a wildcard value can be used with that parameter (for mandatory fields, the wildcard value is an (*) asterisk and for optional fields, the wildcard value is leaving the field blank). For Inbound envelopes, a wildcard value in the envelope matches any value in the input document, while an empty value in the envelope matches only an empty value in the input document. For Outbound envelopes, a wildcard value is equivalent to an empty value in the envelope.

The following table describes EDIFACT inbound Syntax 4 UNB UNZ envelope properties at the interchange level:

schronledgement	
Field	Description
* Sender ID	Interchange ID as it should appear on the interchange header segment sent to this company or division. Valid value is 12 standard characters. Required.
* Identification Code Qualifier (Sender ID)	Coded qualifier of the sender ID as it should appear on the interchange header segment sent to this company or division. Valid value is four standard characters. Optional.
* Interchange Sender Internal Identification	Internal interchange ID as it should appear on the interchange header segment sent to this company or division. Valid value is 12 standard characters. Optional.
* Interchange Sender Internal Sub-identification	Subinterchange ID as it should appear on the interchange header segment sent to this company or division. Valid value is 12 standard characters. Optional.
* Recipient ID	Interchange ID as it should appear on the interchange header segment received from this company or division. Valid value is 12 standard characters. Required.
* Identification Code Qualifier (Recipient ID)	Coded qualifier of the recipient ID as it should appear on the interchange header segment received from this company or division. Valid value is four standard characters. Optional.
* Interchange Recipient Internal Identification	Internal interchange ID as it should appear on the interchange header segment received from this company or division. Valid value is 12 standard characters. Optional.
* Interchange Recipient Internal Sub-identification	Subinterchange ID as it should appear on the interchange header segment received from this company or division. Valid value is 12 standard characters. Optional.
* Test Indicator	Mode of operation mode to use for this envelope. Required. Valid values are:
	None (default)
	◆ Test
	Syntax Only Test
	◆ Echo Request
	◆ Echo Response
	◆ Any Indicator (wildcard)

Field	Description
Use global control number	Whether this envelope definition must use a global control number to uniquely identify transactions. No indicates that the envelope definition must use its own local control number. Required. Valid values are:
	 Yes (default)
	 Yes (and generate name from data)
	◆ No
Perform Control Number Sequence Checking	Compare the sequence of control numbers in the data with the Control Number parameter for this envelope. Required. Valid values are Yes and No (default).
Perform Duplicate Control Number Checking	Determine control number duplications. Required. Valid values are Yes and No (default).
If sequence or duplicate checking, EDI Post Processor should	How the EDI Post Processor service should perform sequence and duplicate checking. When multiple interchanges for the same trading partner are processed in parallel, subprocesses for transactions will always be a direct child to the process that did the deenveloping. If the interchange is out of sequence, the post processor re-runs until the time-out is reached. Required. Valid values:
	 Process all interchanges in the EDI Sequence Check Queue (recommended and the default)
	Process only the current interchange
Maximum age of Control Number History Records in days	Maximum days to retain a history of control numbers to use for duplication determinations. Valid value is nine standard characters. Optional.
Retain Enclosing Envelope	Copy the envelope segments (UNB and UNZ) into each group or message extracted from the interchange. Required. Valid values are Yes and No.
Business Process for Non-Compliant Documents	Business process to be used when non-compliant documents are encountered. Required.
Primary Name Format	Information to include when generating a name for a global number and finding the correct number to assign based on that name. Optional. Information options include the following:
	Test Indicator
* Global Interchange Control Reference	Interchange control reference number used globally. Select a previously defined number to reference. Valid value is nine standard characters. Required.
Handling of non-compliant Interchanges	Process to follow when non-compliant interchanges are encountered. Required. Valid values:
	◆ Accept
	• Reject (default)
Generate an acknowledgement	Generate an acknowledgement that notifies the sender that the receiver has received either a non-compliant interchange or an interpretable interchange transmission. Required. Valid values are Yes (default) and No.

Field	Description
Acknowledgement Detail Level	Level of detail to which acknowledgements are sent. If you select Segment level, the segment and message levels are acknowledged. Optional. Valid values are:
	◆ Interchange Level
	Group Level
	Message Level
	◆ Segment Level
	Data Element Level (default)
Send acknowledgement immediately	Send specified level of acknowledgement immediately after interchange transmission occurs. Valid values are Yes and No (default). Required.
Acceptor Lookup Alias format for	Optional. Valid values are:
generated CONTRLs	◆ CONTRL (default)
	◆ CONTRL_[syntax version]
	CONTRL_[test_indicator]
	CONTRL_[syntax version]_[test_indicator]
	• [message type (first one if multiple)]
* Local Interchange Control Reference	Interchange control reference number used locally. Select a previously defined number to reference. Valid value is nine standard characters. Required.
Write S002 and S003 subelements	Whether to write the S002 and S003 subelements. Valid values are Yes and No (default). Required.
Syntax 1,2,3 Action Response (UCI 0083)	If using EDIFACT Syntax 3 lower, and UNB 0031 is "1" or Generate Acknowledgements is selected. Allows you to send receipt for UCI 0083. Optional. Valid values are:
	 Acknowledged or Rejected (compliance based) (default)
	◆ Received

EDIFACT Inbound Syntax 4 UNG UNE Envelope Properties, Group Level

Note: An (*) asterisk indicates that a wildcard value can be used with that parameter (for mandatory fields, the wildcard value is an (*) asterisk and for optional fields, the wildcard value is leaving the field blank). For Inbound envelopes, a wildcard value in the envelope matches any value in the input document, while an empty value in the envelope matches only an empty value in the input document. For Outbound envelopes, a wildcard value is equivalent to an empty value in the envelope.

The following table describes EDIFACT inbound Syntax 4 UNG UNE envelope properties at the group level:

Field	Description
* Sender ID	Interchange ID as it should appear on the message group header sent to this company or division. Valid value is 12 standard characters. Required.
* Identification Code Qualifier (Sender ID)	Coded qualifier of the sender ID as it should appear on the message group header sent to this company or division. Valid value is four standard characters. Optional.
* Recipient ID	Interchange ID as it should appear on the message group header received from this company or division. Valid value is 12 standard characters. Required.
* Identification Code Qualifier (Recipient ID)	Coded qualifier of the recipient ID as it should appear on the message group header received from this company or division. Valid value is four standard characters. Optional.
Use global control number	Whether this envelope definition must use a global control number to uniquely identify message group headers. No indicates that the envelope definition must use its own global control number. Required. Valid values are:
	◆ Yes (default)
	Yes (and generate name from data)
	◆ No
Perform Control Number Sequence Checking	Compare the sequence of control numbers in the data with the Control Number parameter for this envelope. Required. Valid values are Yes and No (default).
Perform Duplicate Control Number Checking	Determine control number duplications. Required. Valid values are Yes and No (default).
Maximum age of Control Number History Records in days	Maximum days to retain a history of control numbers to use for duplication determinations. Valid value is nine standard characters. Optional.
Retain Enclosing Envelope	Copy the envelope segments (UNB and UNZ) into each message extracted from the message group header. Required. Valid values are Yes and No.

Field	Description
Primary Name Format	Information to include when generating a name for a global number and finding the correct number to assign based on that name. Optional. Information includes:
	◆ Message Type
	 Message Version and Release Number
	◆ Test Indicator
	Check each that you want to use in the format.
First Backup Name Format	Check boxes to indicate what information to include when generating a name for a global number and finding the correct number to assign based on that name. Optional. Information includes:
	Message type
	 Message version and release number
	Test Indicator
	Check each that you want to use in the format.
Second Backup Name Format	Check boxes to indicate what information to include when generating a name for a global number and finding the correct number to assign based on that name. Optional. Information includes:
	Message type
	 Message version and release number
	◆ Test Indicator
	Check each that you want to use in the format.
Handling of Non-Compliant Groups	Process to follow when non-compliant message group headers are encountered. Required. Valid values are:
	◆ Accept
	◆ Reject (default)
Business Process for Non-Compliant Documents	Business process to be used when non-compliant documents are encountered. Required.
Use Security	Turns on AUTACK security for the group. The AUTACK inbound transaction envelope will store the certificate reference or the way the certificate can be generated from the data used in validating the digital signature for the group.
	Use previously checked in trusted certificates to verify a secured document transmission. Valid values are Yes and No (default). Required.
	Note: This option must be set to Yes when using secure AUTACK messages in EDIFACT.
This is the AUTACK Group Envelope	Specify whether this envelope is the AUTACK group envelope. Valid values are Yes and No (default). Required.
	Note: Only displayed if Use Security is set to Yes.

EDIFACT Inbound Syntax 4 UNH UNT Envelope Properties, Transaction Level

Note: An (*) asterisk indicates that a wildcard value can be used with that parameter (for mandatory fields, the wildcard value is an (*) asterisk and for optional fields, the wildcard value is leaving the field blank). For Inbound envelopes, a wildcard value in the envelope matches any value in the input document, while an empty value in the envelope matches only an empty value in the input document. For Outbound envelopes, a wildcard value is equivalent to an empty value in the envelope.

The following table describes EDIFACT inbound Syntax 4 UNH UNT envelope properties at the transaction level:

Field	Description
* Sender ID (from group or interchange)	Interchange ID as it should appear on the transaction sent to this company or division. Valid value is 12 standard characters. Required.
Identification Code Qualifier (Sender ID) (from group or interchange)	Coded qualifier of the sender ID as it should appear on the from group or interchange header segment sent to this company or division. Valid value is four standard characters. Optional.
* Recipient ID (from group or interchange)	Interchange ID as it should appear on the transaction received from this company or division. Valid value is 12 standard characters. Required.
Identification Code Qualifier (Recipient ID) (from group or interchange)	Coded qualifier of the recipient ID as it should appear on the from group or interchange header segment sent to this company or division. Valid value is four standard characters. Optional.
* Message Type	Transaction message type as determined by the information type in the header of the message group, which includes the message or by the information type in the transaction message. Valid value is six standard characters. Required. If using AUTACK, create a separate AUTACK inbound transaction envelope with a message type of AUTACK so you can configure the trusted certificate you want to use when validating the digital signature.
* Message Version Number	Version number of the standard message. Valid value is three standard characters. Required.
* Message Release Number (Required for EDIFACT, optional for ODETTE)	Release number of the standard message. Valid value is three standard characters. Required for EDIFACT. Optional for ODETTE.
* Controlling Agency, Coded	Agency controlling the code representing the name of the sending EDI service provider and relaying the message group on the sending side. Valid value is alphanumeric code with three standard characters. Optional.
* Association Assigned Code	Assigned associated code for the agency controlling the name of the sending EDI service provider and relaying the message group on the sending side. Valid value is alphanumeric code with six standard characters. Optional.
* Message Type Sub-Function Identification	Coded identifier of a sub-function of a message type. Valid value is six standard characters. Optional.

Field	Description
Use global control number	Whether this envelope definition must use a global control number to uniquely identify transactions. No indicates that the envelope definition must use its own global control number. Required. Valid values are:
	◆ Yes
	 Yes (and generate name from data)
	◆ No
Test Indicator	Operation mode to use for this envelope. Required. Valid values are:
	◆ None (default)
	◆ Test
	Syntax Only Test
	◆ Echo Request
	◆ Echo Response
	Any Indicator (wildcard)
Perform Control Number Sequence Checking	Compare the sequence of control numbers in the data with the Control Number parameter for this envelope. Required. Valid values are Yes and No (default).
Perform Duplicate Control Number Checking	Determine control number duplications. Required. Valid values are Yes and No (default).
Maximum age of Control Number History Records in days	Maximum days to retain a history of control numbers to use for duplication determinations. Valid value is nine standard characters. Optional.
Retain Enclosing Envelope	Copy the envelope segments (UNB and UNZ) into each message extracted from the transaction. Required. Valid values are Yes (default) and No.
Batch transactions received within a functional group into one output document.	Put all similar transactions from a functional group into one output document. For example, all invoices would be put into one document. Valid values are Yes (default) and No. The default is to output each transaction to a separate document. Required.

Field	Description
Primary Name Format	Check boxes to instruct what information to include when generating a name for a primary global control number and finding the correct number to assign based on that name. Optional.
	Select from:
	 Message Type
	 Message Version and Release Number
	Test Indicator
	Note: If you are using a generated global control number (Use global control number is set to Yes (and generate name from data)), Application tries to generate and match the following control numbers:
	 First, it tries to generate and match the control number in the primary name format (replacing the values that are selected for the corresponding value in the message).
	 Second, it tries to generate and match the First Backup Name.
	 Third, it tries to generate and match the Second Backup Name.
	 Fourth, if there is not an existing control number that matches the names generated in steps 1-3, a control number with the name assigned in the first step is created.
First Backup Name Format	The first backup name format to use when generating a global control number. The system allows for two alternatives if the Primary Name Format is not found—checking for the First Backup Name Format and then, if that is not found, checking for the Second Backup Name Format. Optional. Select from:
	Message Type
	Message Version and Release Number
	◆ Test Indicator
	Note: If you are using a generated global control number (Use global control number is set to Yes (and generate name from data)), Application tries to generate and match the following control numbers:
	 First, it tries to generate and match the control number in the primary name format (replacing the values that are selected for the corresponding value in the message).
	 Second, it tries to generate and match the First Backup Name.
	 Third, it tries to generate and match the Second Backup Name.
	 Fourth, if there is not an existing control number that matches the names generated in steps 1-3, a control number with the name assigned in the first step is created.

Field	Description
Second Backup Name Format	The second backup name format to use when generating a global control number. The system allows for two alternatives if the Primary Name Format is not found—checking for the First Backup Name Format and then, if that is not found, checking for the Second Backup Name Format. Optional.
	Select from:
	◆ Message Type
	Message Version and Release Number
	◆ Test Indicator
	Note: If you are using a generated global control number (Use global control number is set to Yes (and generate name from data)), Application tries to generate and match the following control numbers:
	 First, it tries to generate and match the control number in the primary name format (replacing the values that are selected for the corresponding value in the message).
	 Second, it tries to generate and match the First Backup Name.
	 Third, it tries to generate and match the Second Backup Name.
	 Fourth, if there is not an existing control number that matches the names generated in steps 1-3, a control number with the name assigned in the first step is created.
Global Message Reference Number	Transaction group control reference number used globally. Select a previously defined number to reference. Valid value is nine standard characters. Required.
Handling of non-compliant Messages	Process to follow when non-compliant transactions are encountered. Required. Valid values are:
	Accept compliant and non-compliant transactions
	◆ Accept compliant transactions, reject non-compliant transactions (default)
Compliance Check Document	Check the transaction set body for compliance. Valid values are Yes (default) and No. Required.
	Note: This only applies to data compliance, not to security/certificate compliance.
Map Name Mode	How to determine which map to use to perform a compliance check. Required. Valid values are:
	◆ Specify (default)
	 Generate from data (this is useful if you want to share across envelopes)
	Note: If you select this option, you must select at least one parameter for Primary Name Format.
Map Name	Which map to use to perform a compliance check (if Compliance Check document is set to Yes and Map Name Mode set to Specify). The map must already be checked in to Application. Optional.

Field	Description
i ieiu	Description
Primary Name Format	Check boxes to instruct what information to include when generating and matching a name for the map. Optional. Select from:
	EDI Standard
	Sender ID Code Qualifier
	◆ Sender ID
	◆ Recipient ID Code Qualifier
	◆ Recipient ID
	◆ Message Type
	◆ Message Version and Release Number
	◆ Test Indicator
	Note: If you are using a generated map name (Map Name Mode is set to Generate from data), Application tries to generate and match the following maps:
	 First, it tries to generate and match the map in the primary name format (replacing the values that are selected for the corresponding value in the message).
	• Second, it tries to generate and match the First Backup Name.
	◆ Third, it tries to generate and match the Second Backup Name.
	• Fourth, if there is not an existing map that matches the names generated in steps 1-3, an error is generated.
	Note: Only occurs if Generate an error if no matching map is found is set to Yes.

Field Description First Backup Name Format The first backup name format to use when generating a map name. The system allows for two alternatives if the Primary Name Format is not found—checking for the First Backup Name Format and then, if that is not found, checking for the Second Backup Name Format. Optional. Select from: **EDI Standard** Sender ID Code Qualifier Sender ID Recipient ID Code Qualifier Recipient ID Message Type Message Version and Release Number Test Indicator Note: If you are using a generated map name (Map Name Mode is set to Generate from data), Application tries to generate and match the following maps: • First, it tries to generate and match the map in the primary name format (replacing the values that are selected for the corresponding value in the message). Second, it tries to generate and match the First Backup Name. Third, it tries to generate and match the Second Backup Name. Fourth, if there is not an existing map that matches the names generated in steps 1-3, an error is generated. Note: Only occurs if Generate an error if no matching map is found is set to Yes.

Field	Description
Second Backup Name Format	The second backup name format to use when generating a map name. The system allows for two alternatives if the Primary Name Format is not found—checking for the First Backup Name Format and then, if that is not found, checking for the Second Backup Name Format. Optional.
	Select from:
	EDI Standard
	Sender ID Code Qualifier
	Sender ID
	Recipient ID Code Qualifier
	◆ Recipient ID
	Message Type
	Message Version and Release Number
	Test Indicator
	Note: If you are using a generated map name (Map Name Mode is set to Generate from data), Application tries to generate and match the following maps:
	 First, it tries to generate and match the map in the primary name format (replacing the values that are selected for the corresponding value in the message).
	 Second, it tries to generate and match the First Backup Name.
	 Third, it tries to generate and match the Second Backup Name.
	 Fourth, if there is not an existing map that matches the names generated in steps 1-3, an error is generated.
	Note: Only occurs if Generate an error if no matching map is found is set to Yes.
Generate an error if no generated map name exists in the system	Specifies whether to generate an error if the Map Name selected is not found. Valid values are Yes (default) and No.
	Note: Only displayed if Map Name Mode is set to Generate from data.
Translate transactions	Generate transactions according to the standard format from data groups in an EDI system and carry out reverse processing. By choosing to translate documents from within the envelope, you can reduce document processing time because you do not need to specify a separate Translation service step in the business process. Valid values are Yes and No (default).
Validate translation output	Validate translated output (that is, documents sent to trading partners). Valid values are Yes (default) and No. Required.

Field	Description
Determine the Business Process by	Select a business process that should run with messages as the primary document. Optional.
	Valid values are:
	◆ Looking up contract dynamically
	 Specifying a contract
	 Specifying a business process
	 Generating the business process name from the data
For each document	As specified in the Determine the Business Process. Required. Valid values are:
	 Invoke the business process
	 Set the business process name in the process data
Primary Name Format	Check boxes to instruct what information to include when generating and matching a name for the business process. Optional.
	Select from:
	EDI Standard
	Sender ID Code Qualifier
	◆ Sender ID
	◆ Recipient ID Code Qualifier
	◆ Recipient ID
	◆ (0065) Message Type
	 Message Version and Release Number
	◆ Test Indicator
	Note: If you are using a generated business process name (Determine the Business Process By is set to Generating the business process name from the data), Application tries to generate and match the following business process:
	 First, it tries to generate and match the business process in the primary name format (replacing the values that are selected for the corresponding value in the message).
	 Second, it tries to generate and match the first Backup Name.
	 Third, it tries to generate and match the second Backup Name.
	 Fourth, if there is not an existing business process that matches the names generated in steps 1-3, an error is generated.
	Note: Only occurs if Generate an error if no generated business process name exists in the system is set to Yes.

Field Description First Backup Name Format The first backup name format to use when generating a business process name. The system allows for two alternatives if the Primary Name Format is not found—checking for the First Backup Name Format and then, if that is not found, checking for the Second Backup Name Format. Optional. Select from: **EDI Standard** Sender ID Code Qualifier Sender ID Recipient ID Code Qualifier Recipient ID (0065) Message Type Message Version and Release Number Test Indicator **Note:** If you are using a generated business process name (**Determine** Business Process Name By is set to Generating a Business Process name from the data), Application tries to generate and match the following business process: First, it tries to generate and match the business process in the primary name format (replacing the values that are selected for the corresponding value in the message). Second, it tries to generate and match the First Backup Name. Third, it tries to generate and match the Second Backup Name. Fourth, if there is not an existing business process that matches the names generated in steps 1-3, an error is generated. Note: Only occurs if Generate an error if no generated business process name exists in the system is set to Yes.

Field	Description
Second Backup Name Format	The second backup name format to use when generating a business process name. The system allows for two alternatives if the Primary Name Format is not found—checking for the First Backup Name Format and then, if that is not found, checking for the Second Backup Name Format. Optional.
	Select from:
	EDI Standard
	Sender ID Code Qualifier
	◆ Sender ID
	Recipient ID Code Qualifier
	◆ Recipient ID
	• (0065) Message Type
	Message Version and Release Number
	Test Indicator
	Note: If you are using a generated business process name (Determine Error Business Process Name By is set to Generating a Business Process name from the data), Application tries to generate and match the following business process:
	 First, it tries to generate and match the business process in the primary name format (replacing the values that are selected for the corresponding value in the message).
	 Second, it tries to generate and match the First Backup Name.
	 Third, it tries to generate and match the Second Backup Name.
	 Fourth, if there is not an existing business process that matches the names generated in steps 1-3, an error is generated.
	Note: Only occurs if Generate an error if no generated business process name exists in the system is set to Yes.
Generate an error if no generated business process name exists in	Specify whether to generate an error if there is no match to the generated business process name in the system. Valid values are Yes (default) and No.
the system	Note: Only displayed if Determine the Business Process By is set to Generating the business process name from the data.
Contract List	Select a previously created contract to associate with this envelope.
Business Process List	Select a previously created business process to associate with this envelope Optional.
	Displayed only if Determine the Business Process Name is set to Specifying the business process.
Extraction Options	Business process data extraction. Required.
	Valid values:
	 Determined by business process (default)
	Extract to a file system directory
	Extract to a mailbox

Field	Description
Data Extraction Directory	Directory for data extraction. Optional.
Data Extraction Filename	Filename for data extraction. Optional.
Data Extraction Mailbox	Mailbox for data extraction. Required.
Data Extraction Mailbox Message Name	Mailbox message name for data extraction. Optional.
Error Business Process Mode	How to determine the business process name to use if there were errors in the compliance check. Required. Valid values are:
	 Specifying a Business Process name (default)
	 Generating a Business Process name from the data (this is useful if you want to share across envelopes)
	Note: If you select this option, you must select at least one parameter for Primary Name Format. The generated name will end with FIN.
Primary Name Format	Check boxes to instruct what information to include when generating and matching a name for the error business process name. Optional. Select from:
	◆ EDI Standard
	◆ Sender ID Code Qualifier
	◆ Sender ID
	◆ Recipient ID Code Qualifier
	◆ Recipient ID
	◆ (0065) Message Type
	 Message Version and Release Number
	◆ Test Indicator
	Note: If you are using a generated error business process name (Error Business Process Mode is set to Generate from data), Application tries to generate and match the following business process:
	 First, it tries to generate and match the business process in the primary name format (replacing the values that are selected for the corresponding value in the message).
	 Second, it tries to generate and match the First Backup Name.
	 Third, it tries to generate and match the Second Backup Name.
	 Fourth, if there is not an existing business process that matches the names generated in steps 1-3, an error is generated.
	Note: Only occurs if Generate an error if no generated business process name exists in the system is set to Yes.

Field	Description
First Backup Name Format	The first backup name format to use when generating an error business process name. The system allows for two alternatives if the Primary Name Format is not found—checking for the First Backup Name Format and then, if that is not found, checking for the Second Backup Name Format. Optional.
	Select from:
	◆ EDI Standard
	◆ Sender ID Code Qualifier
	◆ Sender ID
	Recipient ID Code Qualifier
	◆ Recipient ID
	• (0065) Message Type
	 Message Version and Release Number
	Test Indicator
	Note: If you are using a generated error business process name (Error Business Process Mode is set to Generate from data), Application tries to generate and match the following business process:
	 First, it tries to generate and match the business process in the primary name format (replacing the values that are selected for the corresponding value in the message).
	 Second, it tries to generate and match the First Backup Name.
	 Third, it tries to generate and match the Second Backup Name.
	• Fourth, if there is not an existing business process that matches the names generated in steps 1-3, an error is generated.
	Note: Only occurs if Generate an error if no generated business process name exists in the system is set to Yes.

Field	Description
Second Backup Name Format	The second backup name format to use when generating an error business process name. The system allows for two alternatives if the Primary Name Format is not found—checking for the First Backup Name Format and then, if that is not found, checking for the Second Backup Name Format. Optional.
	Select from:
	EDI Standard
	Sender ID Code Qualifier
	Sender ID
	Recipient ID Code Qualifier
	Recipient ID
	• (0065) Message Type
	 Message Version and Release Number
	Test Indicator
	Note: If you are using a generated error business process name (Error Business Process Mode is set to Generate from data), Application tries to generate and match the following business process:
	• First, it tries to generate and match the business process in the primary name format (replacing the values that are selected for the corresponding value in the message).
	 Second, it tries to generate and match the First Backup Name.
	 Third, it tries to generate and match the Second Backup Name.
	• Fourth, if there is not an existing business process that matches the names generated in steps 1-3, an error is generated.
	Note: Only occurs if Generate an error if no generated business process name exists in the system is set to Yes.
Generate an error if no generated business process name exists in	Specify whether to generate an error if there is no match to the generated business process name in the system. Valid values are Yes (default) and No.
the system	Note: Only displayed if Error Business Process Mode is set to Generate from data.
Business Process List	Select a previously created business process to associate with this envelope. Optional.
	Displayed only if Determine Error Business Process Name By is set to Specifying the business process.
Use Security	Use previously checked in trusted certificates to verify a secured document transmission. Valid values are Yes and No (default). Required.
	Note: This option must be set to Yes when using secure AUTACK messages in EDIFACT.

Field	Description
Scope of Security Application	Used for AUTACK security only. Security header and message body referenced in the digital certificate. Required. Valid values are:
	 1 - Security header and message body. Use this option if you want the AUTACK embedded in the transaction that it is securing.
	3 - Whole related message, package, group, or interchange. Use this option if you want the AUTACK to reference the data transaction or the group it is securing. When selecting this option, you have two options for certificate parameters:
	Use a certificate in USC segment or generate a certificate nameUse a specified certificate only
Security Certificate	Select a previously checked in system certificate to associate with this envelope. Required.

EDIFACT Outbound Syntax 4 UNB UNZ Envelope Properties, Interchange Level

Note: An (*) asterisk indicates that a wildcard value can be used with that parameter (for mandatory fields, the wildcard value is an (*) asterisk and for optional fields, the wildcard value is leaving the field blank). For Inbound envelopes, a wildcard value in the envelope matches any value in the input document, while an empty value in the envelope matches only an empty value in the input document. For Outbound envelopes, a wildcard value is equivalent to an empty value in the envelope.

The following table describes EDIFACT outbound Syntax 4 UNB UNZ envelope properties at the interchange level:

Field	Description
* Syntax Identifier	Coded identifier of syntax rules. Valid value is four standard characters. Required.
* Syntax Version Number	Version number of syntax rules. Typically, this value is 1. Valid value is one standard characters. Required.
* Service Code List Directory Version Number	Version number of the service code list directory. Optional.
* Character Encoding, Coded	Coded character encoding used in the interchange. Optional.
* Sender ID	Coded identifier of the company or division sending the interchange. Valid value is 12 standard characters. Required.
* Identification Code Qualifier (Sender ID)	Coded qualifier of the sender ID as it should appear on the interchange header segment sent to this company or division. Valid value is four standard characters. Optional.
* Interchange Sender Internal Identification	Internal interchange ID as it should appear on the interchange header segment sent to this company or division. Valid value is 12 standard characters. Optional.
* Interchange Sender Internal Sub-identification	Internal interchange sub ID as it should appear on the interchange header segment sent to this company or division. Valid value is 12 standard characters. Optional.
* Recipient ID	Coded identifier of the company or division receiving the interchange. Valid value is 12 standard characters. Required.
* Identification Code Qualifier (Recipient ID)	Coded qualifier of the recipient ID as it should appear on the interchange header segment sent to this company or division. Valid value is three standard characters. Optional.
* Interchange Recipient Internal Identification	Internal interchange ID as it should appear on the interchange header segment received from a company or division. Valid value is 12 standard characters. Optional.
* Interchange Recipient Internal Sub-identification	Internal interchange sub ID as it should appear on the interchange header segment received from a company or division. Valid value is 12 standard characters. Optional.

Field	Description
Use global control number	Whether this envelope definition must use a global control number to uniquely identify transactions. No indicates that the envelope definition must use its own global control number. Optional. Valid values are:
	Yes (default)
	 Yes (and generate name from data)
	◆ No
* Recipient Reference/Password	Reference or password as agreed between the communicating trading partners. Optional.
* Recipient Reference/Password Qualifier	Coded qualifier and password of the receiver as it should appear on the message group header sent to this company or division. Valid value is four standard characters. Optional.
* Application Reference	Reference identifier of the application used by the sender. Valid value is 15 standard characters. Optional.
* Processing Priority Code	Code determined by the sender requesting processing priority for the interchange. Optional.
* Acknowledgement Request	Request an acknowledgement that notifies the sender that the receiver has received an interpretable interchange transmission. Optional.
* Acknowledgement overdue after (hours)	Amount of time, in hours, within which you must receive an acknowledgement. Valid value is four numeric characters. Optional.
* Acknowledgement overdue after (minutes)	Amount of time, in minutes, within which you must receive an acknowledgement. Valid value is four numeric characters. Optional.
* Interchange Agreement Identifier	Identification by name or code of the type of agreement under which the interchange takes place. Optional.
* Test Indicator	The structural level in the envelope containing the test indicator is a test. Optional.
* Global Interchange Control Reference	Interchange control reference number used globally. Select a previously defined number to reference. Valid value is nine standard characters. Required.
* Local Interchange Control Reference	Interchange control reference number used locally. Select a previously defined number to reference. Valid value is nine standard characters. Required. Default is 1.
Primary Name Format	Information to include when generating a name for a primary global number and finding the correct number to assign based on that name. Information includes:
	Test Indicator
	Check the appropriate information to use in the format. Optional.
Specify Non-Standard delimiters	Delimiters other than the default delimiters. Valid values are Yes and No (default). Required.
* UNA Segments	Incorporate UNA segments in this envelope. Valid values are Yes and No (default). Required.
Stream Segments	Insert an end-of-line character after each segment record. Valid values are Yes and No (default). Required.

Field	Description
Data Element Separator	EDI delimiter to use to separate elements. Optional.
Segment Terminator	EDI delimiter to use to indicate the end of segments. Optional.
Component Element Separator	EDI delimiter used to separate components. Optional.
Release Character	Character to use to release an EDI delimiter. Optional.
Repetition Separator	Character to use to separate a group of repeated elements. Optional.
Decimal Separator	Character to use to identify different multi details. Optional.
Encode Document	Whether to specify character encoding for the document. Required. Valid values are Yes and No (default).
Encoding	Type of character encoding for the message group that includes this header. This field is used with the Encoding field. Valid value is six standard characters. Required only if Encode Document is set to Yes.
Determine the Business Process by	Select a business process that should run with extracted EDIFACT outbound Syntax 4 UNB/UNZ messages as the primary document. Required. Valid values: Looking up contract dynamically Specifying a contract Generating the business process name from the data
Business Process List	Select a business process to run when this envelope is processed. Optional.
Contract List	
Contract List	Select a previously created contract to associate with this envelope. Optional.

Field	Description
Primary Name Format	Information to include when generating a name for a primary global number and finding the correct number to assign based on that name. Information includes:
	◆ EDI Standard
	◆ Sender ID Code Qualifier
	◆ Sender ID
	◆ Recipient ID Code Qualifier
	◆ Recipient ID
	• (0065) Message Type
	 Message Version and Release Number
	Test Indicator
	Check the appropriate information to use in the format. Optional.
	Note: If you are using a generated map name (Generating the business process name from the data is set to Generate from data), Application tries to generate and match the following maps:
	 First, it tries to generate and match the map in the primary name format (replacing the values that are selected for the corresponding value in the message).
	 Second, it tries to generate and match the First Backup Name.
	 Third, it tries to generate and match the Second Backup Name.
	 Fourth, if there is not an existing map that matches the names generated in steps 1-3, an error is generated.
	Note: Only occurs if Generate an error if no generated business process name exists in the system is set to Yes.

Field	Description
First Backup Name Format	Information to include when generating a name for a backup global number and finding the correct number to assign based on that name. Information includes:
	◆ EDI Standard
	Sender ID Code Qualifier
	◆ Sender ID
	Recipient ID Code Qualifier
	◆ Recipient ID
	◆ (0065) Message Type
	 Message Version and Release Number
	Test Indicator
	Check the appropriate information to use in the format. Optional.
	Note: If you are using a generated map name (Generating the business process name from the data is set to Generate from data), Application tries to generate and match the following maps:
	 First, it tries to generate and match the map in the primary name format (replacing the values that are selected for the corresponding value in the message).
	 Second, it tries to generate and match the First Backup Name.
	 Third, it tries to generate and match the Second Backup Name.
	 Fourth, if there is not an existing map that matches the names generated in steps 1-3, an error is generated.
	Note: Only occurs if Generate an error if no generated business process name exists in the system is set to Yes.

Field	Description
Second Backup Name Format	Information to include when generating a name for a secondary backup global number and finding the correct number to assign based on that name. Information includes:
	◆ EDI Standard
	◆ Sender ID Code Qualifier
	◆ Sender ID
	◆ Recipient ID Code Qualifier
	◆ Recipient ID
	◆ (0065) Message Type
	 Message Version and Release Number
	◆ Test Indicator
	Check the appropriate information to use in the format. Optional.
	Note: If you are using a generated map name (Generating the business process name from the data is set to Generate from data), Application tries to generate and match the following maps:
	 First, it tries to generate and match the map in the primary name format (replacing the values that are selected for the corresponding value in the message).
	 Second, it tries to generate and match the First Backup Name.
	 Third, it tries to generate and match the Second Backup Name.
	• Fourth, if there is not an existing map that matches the names generated in steps 1-3, an error is generated.
	Note: Only occurs if Generate an error if no generated business process name exists in the system is set to Yes.
Generate an error if no generated business process name exists in the system	Generate an error message if it cannot locate the specified business process name. Valid values are Yes (default) and No.
Extraction Options	Required. Valid values are:
	 Determined by a business process (default)
	Extract to a file system directory
	◆ Extract to a mailbox
Data Extraction Directory	Directory for data extraction. Optional.
Data Extraction Filename	Filename for data extraction. Optional.
Data Extraction Mailbox	Mailbox for data extraction. Required.
Data Extraction Mailbox Message Name	Mailbox message name for data extraction. Optional.

EDIFACT Outbound Syntax 4 UNG UNE Envelope Properties, Group Level

Note: An (*) asterisk indicates that a wildcard value can be used with that parameter (for mandatory fields, the wildcard value is an (*) asterisk and for optional fields, the wildcard value is leaving the field blank). For Inbound envelopes, a wildcard value in the envelope matches any value in the input document, while an empty value in the envelope matches only an empty value in the input document. For Outbound envelopes, a wildcard value is equivalent to an empty value in the envelope.

The following table describes EDIFACT outbound Syntax 4 UNG UNE envelope properties at the group level:

Field	Description
Next Envelope	Specifies envelope to use after this envelope. Required.
Create Next Envelope	Adds group level envelope to use as next envelope or edits an exiting envelope. Optional.
* Sender ID	Coded identifier of the company or division sending the message group. Valid value is 12 standard characters. Required.
* Identification Code Qualifier (Sender ID)	Coded qualifier of the sender ID as it should appear on the interchange header segment sent to this company or division. Valid value is four standard characters. Optional.
* Recipient ID	Coded identifier of the company or division receiving the message group. Valid value is 12 standard characters. Required.
* Identification Code Qualifier (Recipient ID)	Coded qualifier of the recipient ID as it should appear on the interchange header segment sent to this company or division. Valid value is four standard characters. Optional.
Use global control number	Whether this envelope definition must use a global group number to uniquely identify transactions. No indicates that the envelope definition must use its own global group number. Required. Valid values are:
	◆ Yes
	 Yes - Generate name from data
	◆ No
* Controlling Agency, Coded	Agency controlling the code representing the name of the sending EDI service provider and relaying the message group on the sending side. Valid value is alphanumeric code with three standard characters. Optional.
* Application Password	Password used to access the application of the receiver. Valid value is 15 standard characters. Optional.
* Global Group Reference Number	Interchange control reference number used globally. Select a previously defined number to reference. Valid value is nine standard characters. Optional.

Field	Description
Use Security	Use previously checked in trusted certificates to verify a secured document transmission. Valid values are Yes and No. Required.
	Note: This option must be set to Yes when using secure AUTACK messages in EDIFACT.
This is the AUTACK Group Envelope	Specify whether this envelope is the AUTACK group envelope. Valid values are Yes and No (default). Required.
	Note: Only displayed if Use Security is set to Yes.
Security Certificate	The security certificate. Default is B2BHttp. Required.
	Note: Only displayed if Use Security is set to Yes and This is the AUTACK Group Envelope is also set to Yes.
Security Algorithm	The algorithm for security purposes. Default is MD5 with RSA. Required.
	Note: Only displayed if Use Security is set to Yes and This is the AUTACK Group Envelope is also set to Yes.
Use of Algorithm	How the algorithm should be used. Default is 1-Owner Hashing. Required.
	Note: Only displayed if Use Security is set to Yes and This is the AUTACK Group Envelope is also set to Yes.
Security Service	The service provided by the selected security. Default is Non-repudiation of origin. Required.
	Note: Only displayed if Use Security is set to Yes and This is the AUTACK Group Envelope is also set to Yes.
Scope of Security Application	The scope of the security application (what it checks). Default is 3 - Whole related message, package, group or interchange. Required.
	Note: Only displayed if Use Security is set to Yes and This is the AUTACK Group Envelope is also set to Yes.s.
Response Type	The type of response. Default is 1- No acknowledgement. Required.
	Note: Only displayed if Use Security is set to Yes and This is the AUTACK Group Envelope is also set to Yes.
Filter Function	The type of filter used. Default is 2 - Hexadecimal Filter. Required.
	Note: Only displayed if Use Security is set to Yes and This is the AUTACK Group Envelope is also set to Yes.

EDIFACT Outbound Syntax 4 UNH UNT Envelope Properties, Transaction Level

Note: An (*) asterisk indicates that a wildcard value can be used with that parameter (for mandatory fields, the wildcard value is an (*) asterisk and for optional fields, the wildcard value is leaving the field blank). For Inbound envelopes, a wildcard value in the envelope matches any value in the input document, while an empty value in the envelope matches only an empty value in the input document. For Outbound envelopes, a wildcard value is equivalent to an empty value in the envelope.

The following table describes EDIFACT outbound Syntax 4 UNH UNT envelope properties at the transaction level:

Field	Description
Sender ID	Coded identifier of the company or division sending the transaction. Valid value is 12 standard characters. Required.
* Identification Code Qualifier (Sender ID)	Coded qualifier of the sender ID as it should appear on the interchange header segment sent to this company or division. Valid value is four standard characters. Optional.
Recipient ID	Coded identifier of the company or division receiving the interchange. Valid value is 12 standard characters. Required.
* Identification Code Qualifier (Recipient ID)	Coded qualifier of the recipient ID as it should appear on the interchange header segment sent to this company or division. Valid value is three standard characters. Optional.
Next Envelope	Envelope to apply after this envelope. Required.
Create Next Envelope	Adds transaction level envelope to use as the next envelope. Optional. Valid values are:
	◆ UNG/UNE Syntax 4
	◆ UNB/UNZ Syntax 4
Control number handling	How to handle control numbers. Required. Valid values are:
	◆ Global (default)
	Global (and generate name from data)
	◆ Local
	◆ Always start with 1
* Message Type	Transaction message type as determined by the information type in the header of the message group, which includes the message or by the information type in the transaction message. Valid value is six standard characters. Required.
* Message Version Number	Version number of the standard message. Valid value is three standard characters. Required.
* Message Release Number (Required for EDIFACT, optional for ODETTE)	Release number of the standard message. Valid value is three standard characters. Required for EDIFACT and AUTACK. Optional for ODETTE.

Field	Description
* Controlling Agency, Coded	Agency controlling the code representing the name of the sending EDI service provider and relaying the message group on the sending side. Valid value is alphanumeric code with three standard characters. Optional.
* Association Assigned Code	Assigned associated code for the agency controlling the name of the sending EDI service provider and relaying the message group on the sending side. Valid value is alphanumeric code with six standard characters. Optional.
* Code List Directory Version Number	Previously defined version number of a code list to implement in this message. Valid value is numeric code with six limited standard characters. Optional.
* Message Type Sub-Function Identification	Coded identifier of a sub-function of a message type. Valid value is six standard characters. Optional.
* Common Access Reference	Key used for referencing related all subsequent transfers of data to the same business case or file. Optional.
* Sequence Of Transfers	Number assigned by the sender indicating the transfer sequence of a message related to the same topic. The message could be an addition or a change to an earlier transfer related to the same topic. Valid value is two standard characters. Optional.
* First And Last Transfer	First and last message in a sequence of messages related to the same topic. Valid value is one standard character. Optional.
* Message Subset Identification	Coded identifier of a message subset by its identifier, version, release, and source. Valid value is 15 standard characters. Optional.
* Message Subset Version Number	Version number of the message subset. Valid value is three standard characters. Optional.
* Message Subset Release Number	Release number of the message subset. Valid value is three standard characters. Optional.
Message Subset Controlling Agency, Coded	Agency controlling the code representing the name of the message subset. Valid value is alphanumeric code with three standard characters. Optional.
* Message Implementation Guideline Identification	Coded identifier of a message implementation guideline by its identifier, version, release, and source. Valid value is 14 standard characters. Optional.
* Message Implementation Guideline Version Number	Version number of a message implementation guideline. Valid value is three standard characters. Optional.
* Message Implementation Guideline Release Number	Release number of a message implementation guideline. Valid value is three standard characters. Optional.
*Message Implementation Controlling Agency, Coded	Agency controlling the code representing the name of the message implementer. Valid value is alphanumeric code with three standard characters. Optional.
* Scenario Identification	Coded identifier of a scenario by its identifier, version, release, and source. Valid value is 14 standard characters. Optional.
* Scenario Version Number	Version number of a scenario. Valid value is three standard characters. Optional.
* Scenario Release Number	Release number of a scenario. Valid value is three standard characters. Optional.

Field	Description
Message Scenario Controlling Agency, Coded	Agency controlling the code representing the message scenario. Valid value is alphanumeric code with three standard characters. Optional.
Accepter Lookup Alias	Identifying string used with the sender ID and the receiver ID to look up this envelope with the EDI Encoder service. This alias associates a document with the service it requires. Valid value must be at least one limited standard character. Required.
Specify Non-Standard Delimiters	Whether you want to specify non-standard delimiters. Valid values are Yes and No (default). Required.
Data Element Separator	EDI delimiter to use to separate elements. Optional.
Segment Terminator	EDI delimiter to use to indicate the end of segments. Optional.
Component Element Separator	EDI delimiter used to separate components. Optional.
Release Character	Character to use to release an EDI delimiter. Optional.
Repetition Separator	Character to use to separate a group of repeated elements. Optional.
Decimal Separator	Character to use to identify different multi details. Optional.
Stream Segments	Insert an end-of-line character after each segment record. Valid values are Yes and No (default). Required.
Primary Name Format	Information to include when generating a name for a global number and finding the correct number to assign based on that name. Optional. Information includes:
	◆ Message Type
	 Message Version and Release Number
	◆ Test Indicator
	Check each that you want to use in the format.
First Backup Name Format	Check boxes to indicate what information to include when generating a name for a global number and finding the correct number to assign based on that name. Optional. Information includes:
	 Message type
	 Message version and release number
	Test Indicator
	Check each that you want to use in the format.
Second Backup Name Format	Check boxes to indicate what information to include when generating a name for a global number and finding the correct number to assign based on that name. Optional. Information includes:
	 Message type
	 Message version and release number
	◆ Test Indicator
	Check each that you want to use in the format.

Field	Description
Global Message Reference Number	Message control reference number used globally. Select a previously defined number to reference. Valid value is nine standard characters. Required.
Local Message Reference Number	Message control reference number used locally. Select a previously defined number to reference. Valid value is nine standard characters. Required.
Map Name Mode	Mode in which to specify the map to use to perform a compliance check. Valid values are: Specify
	◆ Generate from data
Map Name	Select the map to be used to perform a compliance check. The map must already be checked in. Optional.
Primary Name Format	Information to include when generating a name for a map and finding the correct number to assign based on that name. Information may include some or all of the following:
	◆ EDI Standard
	 Sender ID Code Qualifier
	◆ Sender ID
	◆ Recipient ID Code Qualifier
	◆ Recipient ID
	Message Type
	 Message Version and Release Number
	Test Indicator
	Check all that you want to use in the format. Optional.
First Backup Name Format	Information to include when generating a name for a map and finding the correct number to assign based on that name. Information may include some or all of the following:
	◆ EDI Standard
	◆ Sender ID Code Qualifier
	◆ Sender ID
	Recipient ID Code Qualifier
	◆ Recipient ID
	Message Type
	Message Version and Release Number
	Test Indicator
	Check all that you want to use in the format. Optional.

Field	Description
Second Backup Name Format	Information to include when generating a name for a map and finding the correct number to assign based on that name. Information may include some or all of the following:
	◆ EDI Standard
	Sender ID Code Qualifier
	◆ Sender ID
	Recipient ID Code Qualifier
	◆ Recipient ID
	Message Type
	Message Version and Release Number
	Test Indicator
	Check all that you want to use in the format. Optional.
Generate an error if no generated map name exists in the system	Generate an error message if it cannot locate the specified map name. Valid values are Yes and No. Required.
Validate translation input	Whether to validate the translation input. Valid values are Yes (default) or No. Required.
Validate translation output	Whether to validate the translation output. Valid values are Yes (default) or No. Required.
Use Security	Use previously checked in trusted certificates to verify a secured document transmission. Valid values are Yes and No (default). Required.
	Note: This option <i>must</i> be set to Yes when using secure AUTACK messages in EDIFACT.
Scope of Security Application	Security header and message body referenced in the digital certificate. Required. Valid values are:
	 1 - Security header and message body (default)
	• 3 - Whole related message, package, group, or interchange
	Note: Only displayed if Use Security is set to Yes.
Security Certificate	Select a previously checked in trusted certificate to associate with this envelope. Required.
	Note: Only displayed if Use Security is set to Yes.
Security Algorithm	Strength of the algorithm used to encrypt data and provides a key length your trading partner can support. Required. Valid values are:
	 MD5 with RSA – Message digest algorithm that verifies the integrity of data through a 128-bit message digest. Default.
	 SHA1 with RSA – Secure hash algorithm that verifies the integrity of data through a 160-bit (20 byte) message digest. Transmission may be a bit slower that MD5; however, the larger message digest size offers a more secure data transference.
	Note: Only displayed if Use Security is set to Yes.

Field	Description
Use of Algorithm	Defines when the algorithm is used. Required. Valid values are:
	 1 - Owner Hashing (default)
	• 6 - Owner Signing
	Note: Only displayed if Use Security is set to Yes.
Security Service	Whether the message sender must sign the message with a digital certificate. Required.
	Note: Only displayed if Use Security is set to Yes.
Response Type	Whether you required an acknowledgement for transmitted digital certificates. Required.
	Note: Only displayed if Use Security is set to Yes.
Filter Function	The function of the filter. Default is Hexadecimal filter. Required.