

Gentran:Server[®] for Windows[®]

Message Forwarder Gateway Configuration Guide

Version 5.2

Sterling Commerce
An IBM Company

Copyright Notice

Gentran:Server for Windows

© Copyright 1995–2008
Sterling Commerce, Inc.
ALL RIGHTS RESERVED

Sterling Commerce Software Trade Secret Notice

THE GENTRAN:SERVER FOR WINDOWS SOFTWARE ("STERLING COMMERCE SOFTWARE") IS THE CONFIDENTIAL AND TRADE SECRET PROPERTY OF STERLING COMMERCE, INC., ITS AFFILIATED COMPANIES OR ITS OR THEIR LICENSORS, AND IS PROVIDED UNDER THE TERMS OF A LICENSE AGREEMENT. NO DUPLICATION OR DISCLOSURE WITHOUT PRIOR WRITTEN PERMISSION. RESTRICTED RIGHTS.

This documentation, the Sterling Commerce Software it describes, and the information and know-how they contain constitute the proprietary, confidential and valuable trade secret information of Sterling Commerce, Inc., its affiliated companies or its or their licensors, and may not be used for any unauthorized purpose, or disclosed to others without the prior written permission of the applicable Sterling Commerce entity. This documentation and the Sterling Commerce Software that it describes have been provided pursuant to a license agreement that contains prohibitions against and/or restrictions on their copying, modification and use. Duplication, in whole or in part, if and when permitted, shall bear this notice and the Sterling Commerce, Inc. copyright notice.

As and when provided to any governmental entity, government contractor or subcontractor subject to the FARs, this documentation is provided with RESTRICTED RIGHTS under Title 48 CFR 52.227-19. Further, as and when provided to any governmental entity, government contractor or subcontractor subject to DFARs, this documentation and the Sterling Commerce Software it describes are provided pursuant to the customary Sterling Commerce license, as described in Title 48 CFR 227-7202 with respect to commercial software and commercial software documentation.

These terms of use shall be governed by the laws of the State of Ohio, USA, without regard to its conflict of laws provisions. If you are accessing the Sterling Commerce Software under an executed agreement, then nothing in these terms and conditions supersedes or modifies the executed agreement.

Product names mentioned herein may be trademarks and/or registered trademarks of their respective companies. Gentran and Gentran:Server are registered trademarks of Sterling Commerce, Inc.

Third Party Software:

Portions of the Sterling Commerce Software may include products, or may be distributed on the same storage media with products, ("Third Party Software") offered by third parties ("Third Party Licensors").

Warranty Disclaimer

This documentation and the Sterling Commerce Software which it describes are licensed either "AS IS" or with a limited warranty, as set forth in the Sterling Commerce license agreement. Other than any limited warranties provided, NO OTHER WARRANTY IS EXPRESSED AND NONE SHALL BE IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR USE OR FOR A PARTICULAR PURPOSE. The applicable Sterling Commerce entity reserves the right to revise this publication from time to time and to make changes in the content hereof without the obligation to notify any person or entity of such revisions or changes.

The Third Party Software is provided 'AS IS' WITHOUT ANY WARRANTY AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. FURTHER, IF YOU ARE LOCATED OR ACCESSING THIS SOFTWARE IN THE UNITED STATES, ANY EXPRESS OR IMPLIED WARRANTY REGARDING TITLE OR NON-INFRINGEMENT ARE DISCLAIMED.

Sterling Commerce, Inc.
4600 Lakehurst Court Dublin, OH 43016-2000 * 614/793-7000
© Copyright 1995–2008—Sterling Commerce, Inc.

Table of Contents

Preface	About This Guide	
	▶ Introduction	iv
	▶ Description of Contents	v
	▶ Getting Support	vi
Chapter 1	HTTP Message Forwarder Overview	
	▶ Overview	1-2
	▶ HTTP Message Forwarder	1-3
	▶ HTTP Message Forwarder Flow	1-4
Chapter 2	Configuring Communications	
	Overview	2-2
	▶ Introduction	2-2
	Properties	2-3
	▶ HTTP Message Forwarder Properties	2-3
	Procedures	2-5
	▶ Configuration process	2-5
	▶ How to Configure the HTTP Message Forwarder	2-7
	▶ How to Modify HTTP Message Forwarder Properties	2-9

About This Guide

Contents

- ▶ Introductioniv
 - ▶ Description of Contentsv
 - ▶ Getting Supportvi
-



Introduction

Overview This manual contains the tasks you must follow to configure the HTTP Message Forwarder.

Intended audience The intended audience for this manual is Gentran:Server system administrators.

Prerequisite knowledge The audience using this software should be familiar with your operating system.

Description of Contents

Introduction

This guide is organized into the tasks that you complete when configuring communications for the HTTP Message Forwarder.

Organization of chapters

The guide is organized into chapters. A brief description of each chapter's contents follows.

- About This Guide explains the content, organization, and conventions in this guide.
 - HTTP Message Forwarder Overview provides a high-level overview of the HTTP Message Forwarder.
 - Configuring Communications explains the process for configuring the HTTP Message Forwarder.
-

Getting Support

Introduction The Sterling Commerce Gentran:Server software is supported by trained product support personnel who are available to help you with product questions or concerns.

Note

Gentran:Server Customer Support does not support non-Sterling Commerce products (e.g., SQL Server, Oracle, etc.), but can assist you in configuring non-Sterling Commerce products to work with Gentran:Server.

Phone number For assistance, please refer to your *Getting Started Guide* to determine which support phone number you should use.

Before calling support

To help us provide prompt service, we ask that you do the following:

- Attempt to recreate any problem that you encounter and record the exact sequence of events.
- When you call product support, you should be prepared to provide us with the information below.

Information	Description
Identification	Your company name, your name, telephone number and extension, and the case number (if the question refers to a previously reported issue).
System Configuration	The Gentran:Server version (and any service packs installed) and information about the primary Gentran system controller and all machines experiencing problems, including: the Windows operating system version, amount of memory, available disk space, database version, Microsoft Data Access (MDAC) version, and Internet Explorer version. Also, please describe any recent changes in your hardware, software, or the configuration of your system.
System Data Store	Which machines contain folders in the system data store?
Error Messages	Record the exact wording of any error messages you receive and the point in the software where the error occurred, as well as any log files.
Attempted Solutions	Record any steps that you took attempting to resolve the problem and note all the outcomes, and provide an estimate on how many times the problem occurred and whether it can be reproduced.

**Accessing the
Sterling
Commerce
Support Web Site**

The Sterling Commerce Customer Support Web Site contains valuable information about getting support for Gentran:Server for Windows, including the:

- scope of support services
- customer support policies
- call prioritizing
- customer support phone directory
- how to create new Support on Demand cases
- how to check the status of Support on Demand cases
- how to add information to Support on Demand cases

The Customer Support Web Site is constantly updated and all Sterling Commerce customers have access to it. This web site also contains the most recent product updates and is a valuable source of product information.

Reference

Refer to the *Getting Started Guide* for information on how to access the Customer Support Web Site.

Documentation

The Customer Support Web Site contains a documentation library, which has the entire Gentran:Server for Windows documentation set. You can download the product manuals in PDF format from this library at any time.

HTTP Message Forwarder Overview

Contents

- ▶ Overview 1 - 2
 - ▶ HTTP Message Forwarder 1 - 3
 - ▶ HTTP Message Forwarder Flow 1 - 4
-

Overview

In this chapter

This chapter provides you with a high-level overview of the Gentran:Server HTTP Message Forwarder.

HTTP Message Forwarder

Introduction

The HTTP Message Forwarder facilitates the flow of files through a dual firewall, in through one firewall and out through another.

Use with HTTP Gateway

By using the HTTP Gateway and the HTTP Message Forwarder in concert, you can receive and send messages of any format from outside your enterprise using the HTTP or HTTPS transport methods in environments with double firewalls.

Reference

See the *HTTP Gateway Configuration Guide* for more information on the Gentran:Server HTTP Gateway.

HTTP Message Forwarder Flow

Introduction

The sender of a message packages and sends the data as an HTTP POST request, which sends the request to a URL configured on the HTTP server for the HTTP Message Forwarder. The HTTP server receives the request and forwards it to the HTTP Message Forwarder, which takes the incoming message and forwards it to the message destination via an HTTP POST request.

Then, the HTTP Message Forwarder keeps the incoming HTTP connection open until the message destination returns with the appropriate HTTP status code. This status code and any response data is then returned to the sender via the open HTTP connection with any data that the destination provides. If the HTTP Message Forwarder is unable to forward the incoming message to the message destination, the appropriate HTTP status code indicating this error is returned to the sender. Once the status code and the response data, if any, is returned to the sender, the HTTP connection for the incoming message will be closed.

Inbound message flow

This table describes the inbound flow of messages through the HTTP Message Forwarder.

Stage	Process
1	The incoming message is sent to the HTTP server via an HTTP or HTTPS POST request, using the SCHttpMessageForwarder.dll. An example URL is: <code>http://www.gensys1.com/MessageForwarder/SCHttpMessagForwarder.dll</code>
2	Microsoft IIS routes the request to the HTTP Message Forwarder.
3	The HTTP Message Forwarder parses the URL and looks for a routing parameter. If one is found and configured, the POST is forwarded to the destination URL that is configured for that routing parameter. If the routing parameter is not found, the default destination URL is used. If the routing parameter is not configured, the incoming POST is discarded. All forwarding is performed via an HTTP POST or an HTTPS POST.
4	This HTTP status code is sent to the sender of the incoming message.

Message destination

The destination of the message is any valid URL.

Error notifications

If an E-mail address is configured to receive error notifications, the HTTP Message Forwarder uses this E-mail address to report any errors that occur when receiving or forwarding incoming messages. One E-mail message is used for each error occurrence.

The following information is included in the body of the E-mail message:

- Local date time stamp when the error occurred
 - Free form text describing the error
-

Configuring Communications

Contents	▶ Introduction	2 - 2
	Properties	2 - 3
	▶ HTTP Message Forwarder Properties	2 - 3
	Procedures	2 - 5
	▶ Configuration process	2 - 5
	▶ How to Configure the HTTP Message Forwarder	2 - 7
	▶ How to Modify HTTP Message Forwarder Properties	2 - 9

Overview

Introduction

In this chapter

This chapter describes the tasks that you must complete to configure the HTTP Message Forwarder.

Properties

HTTP Message Forwarder Properties

Introduction The HTTP Message Forwarder user interface enables you to configure the HTTP Message Forwarder properties.

Parts and functions This table describes the parts of the HTTP Message Forwarder UI and their functions.

Part	Function
Send E-mail Notifications	Specifies (if checked) that E-mail notifications are sent. Note Only Error messages are E-mailed.
To	Specifies the E-mail address where all notifications are sent.
From	Specifies the E-mail address of the sender of the notification. Note This entry is displayed in the “From” line of all E-mail notifications.
Subject	Specifies the subject for all E-mail notifications. Note This entry is displayed in the “Subject” line of all E-mail notifications.
SMTP Server	Specifies the host name for the SMTP server to use for sending E-mail notifications.
SMTP Port	Specifies the port number for the SMTP server.
Logging Level	Specifies the level of logging to use when receiving and forwarding messages. Valid selections are: <ul style="list-style-type: none"> • Errors only • Detailed • Errors and Warnings Note The log messages are located in the XML log file accessible by clicking View Log File . <p style="text-align: right; color: green;">(Continued on next page)</p>

(Contd) Part	Function
View Log File	Accesses the HTTP Message Forwarder log file, which enables you to view error message information including: <ul style="list-style-type: none"> • date and time of message, • severity of message (i.e., informational, warning, error), and • error message text.
Purge the Log File	Specifies (if checked) that the contents of the log file are purged and the number of entries is set to zero at the next attempt to add an entry to the log file.
Save Incoming POST Data	Specifies (if checked) that a byte for byte copy of the incoming POST request is saved.
Routing Parameter	The routing parameter for the associated destination URL (the URL listed to the right of this routing parameter). Note At a minimum, you must configure the default routing parameter/ URL mapping.
URL	The message destination URL. Note At a minimum, you must configure the default routing parameter/ URL mapping.
Test URL	Enables you to test the connection to the URL listed to the left of this button.
Delete	Deletes (if checked) the routing parameter to the left of the check box (after you click Save Settings).
Save Settings	Allows you to save the HTTP Message Forwarder Configuration settings.

Procedures

Configuration process

HTTP Message Forwarder process

This table lists the stages in configuring communications for use with HTTP Message Forwarder.

Stage	Description
1	<p>Install the Gentran:Server HTTP Message Forwarder.</p> <p>Reference Refer to the Gentran:Server <i>Options Pack Installation Card</i> for more information.</p>
2	<p>Note the directory in which you installed the HTTP Message Forwarder.</p>
3	<p>Manually set up one virtual directory pointing to the directory you noted in Stage 2. You must set the access permissions for this virtual directory to: Read, Run scripts, and Execute.</p> <p>For the HTTP Message Forwarder Gateway to work properly with IIS 6.0, the schttpmessageforwarder.dll file must be allowed in the ISAPI Web Service Extensions.</p> <p>Reference Refer to your Microsoft IIS documentation for more information on creating this virtual directory.</p>
4	<p>Modify the access permissions for the messageforwarderconfig.asp file (located in the same directory you noted in Stage 2) to turn off (deactivate) “Anonymous Access” and turn on (activate) Integrated Windows Authentication to access this file.</p> <p>Reference Refer to your Microsoft documentation for more information on modifying access permissions for this file.</p>
5	<p>From Windows Explorer, access the properties of the directory in which you installed the HTTP Message Forwarder, and modify the NTFS access permissions for the local IWAM_pcName user to grant this user “Write” access.</p> <p>Example If the machine name is “GENSYS,” the IWAM_pcName user is “IWAM_GENSYS” (no quotes).</p> <p>Reference Refer to your Microsoft documentation for more information on modifying access permissions for this user.</p> <p style="text-align: right;">(Continued on next page)</p>

	Description
6	Configure the HTTP Message Forwarder. Reference See <i>How to Configure the HTTP Message Forwarder</i> on page 2 - 7 for more information.

How to Configure the HTTP Message Forwarder

Introduction You must configure the HTTP Message Forwarder. At a minimum you must configure a default routing parameter/URL mapping so the HTTP Message Forwarder can determine where to route the incoming messages if the message doesn't specify a destination URL.

Procedure Use this procedure to configure HTTP Message Forwarder.

Step	Action
1	<p>Access the HTTP Message Forwarder configuration.</p> <p>Note The URL to access the HTTP Message Forwarder configuration is in the form of the following:</p> <pre>http:\\server_name\virtual_directory_name\ messageforwarderconfig.asp</pre>
2	<p>Do you want to send E-mail notifications?</p> <ul style="list-style-type: none"> ▶ If <i>yes</i>, select the Send E-Mail Notifications check box and continue with the next step. ▶ If <i>no</i>, continue with the next step.
3	In the To box, type the E-mail address where all notifications are sent.
4	In the From box, type the E-mail address of the sender of the notification.
5	In the Subject box, type the subject for all E-mail notifications.
6	In the SMTP Server box, type the host name for the SMTP server to use for sending E-mail notifications.
7	In the SMTP Port box, type the port number for the SMTP server.
8	From the Log Settings list, select the level of log settings you want to see.
9	<p>Do you want to purge the log file?</p> <ul style="list-style-type: none"> ▶ If <i>yes</i>, select the Purge the log file check box and continue with the next step. ▶ If <i>no</i>, continue with the next step. <p>Note If you want to view the HTTP Message Forwarder log file, click View Log File.</p>
10	<p>Do you want to save incoming POST data?</p> <ul style="list-style-type: none"> ▶ If <i>yes</i>, select the Save Incoming POST Data check box and continue with the next step. ▶ If <i>no</i>, continue with the next step. <p style="text-align: right;">(Continued on next page)</p>

(Contd) Step	Action
11	<p>In the Message Forwarder URL Routing Table section, type the routing parameter/URL mappings.</p> <p>Notes</p> <ul style="list-style-type: none">▶ At a minimum, you must configure a default routing parameter/URL mapping.▶ Click Test URL to test the connection to the URL listed to the left of this button.▶ If you want to delete a routing parameter/URL mapping (other than the default one), select the Delete check box to the right of that mapping.
12	<p>Click Save Settings to save your HTTP Message Forwarder configuration.</p> <p>System response You are prompted with a message informing you that the save is complete.</p>

How to Modify HTTP Message Forwarder Properties

Introduction This section describes how to modify HTTP Message Forwarder properties.

Procedure Use this procedure to modify HTTP Message Forwarder properties.

Step	Action
1	<p>Access the HTTP Message Forwarder configuration.</p> <p>Note The URL to access the HTTP Message Forwarder configuration is in the form of the following:</p> <pre>http:\\server_name\virtual_directory_name\messageforwarderconfig.asp</pre>
2	<p>Do you want to send E-mail notifications?</p> <ul style="list-style-type: none"> ▶ If <i>yes</i>, select the Send E-Mail Notifications check box and continue with the next step. ▶ If <i>no</i>, continue with the next step.
3	In the To box, type the E-mail address where all notifications are sent.
4	In the From box, type the E-mail address of the sender of the notification.
5	In the Subject box, type the subject for all E-mail notifications.
6	In the SMTP Server box, type the host name for the SMTP server to use for sending E-mail notifications.
7	In the SMTP Port box, type the port number for the SMTP server.
8	From the Log Settings list, select the level of log settings you want to see.
9	<p>Do you want to purge the log file?</p> <ul style="list-style-type: none"> ▶ If <i>yes</i>, select the Purge the log file check box and continue with the next step. ▶ If <i>no</i>, continue with the next step. <p>Note If you want to view the HTTP Message Forwarder log file, click View Log File.</p>
10	<p>Do you want to save incoming POST data?</p> <ul style="list-style-type: none"> ▶ If <i>yes</i>, select the Save Incoming POST Data check box and continue with the next step. ▶ If <i>no</i>, continue with the next step. <p style="text-align: right;">(Continued on next page)</p>

(Contd) Step	Action
11	<p>In the Message Forwarder URL Routing Table section, type the routing parameter/URL mappings.</p> <p>Notes</p> <ul style="list-style-type: none">▶ At a minimum, you must have a default routing parameter/URL mapping configured. You cannot delete the default routing parameter/URL mapping, but you can change it.▶ Click Test URL to test the connection to the URL listed to the left of this button.▶ If you want to delete a routing parameter/URL mapping (other than the default one), select the Delete check box to the right of that mapping.
12	Click Save Settings to save your HTTP Message Forwarder configuration.
