

IBM Sterling Gentrans:Server for Microsoft Windows

Communications Gateway Configuration Guide

Version 5.3



Copyright

This edition applies to the 5.3 Version of IBM® Sterling Gentran:Server® for Microsoft Windows and to all subsequent releases and modifications until otherwise indicated in new editions.

Before using this information and the product it supports, read the information in Notices on page N-1.

Licensed Materials - Property of IBM

IBM® Sterling Gentran:Server® for Microsoft Windows

© Copyright IBM Corp. 1996, 2011. All Rights Reserved.

US Government Users Restricted Rights - Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Table of Contents

Preface	About This Guide	
	• Introduction	iv
	• Description of Contents	v
	• Online Help	vi
	• Getting Support	vii
Chapter 1	Communications Gateway Overview	
	• Overview	1-2
	• Sterling Gentran:Server Communications Gateway	1-3
	• Sterling Gentran:Server Communications Gateway Mailboxes	1-6
Chapter 2	Configuring Communications	
	Overview	2-2
	• Introduction	2-2
	• Sterling Gentran:Server Communications Gateway Properties	2-3
	• Mailbox Gateway Properties	2-11
	• Mailbox Properties	2-36
	Procedures	2-41
	• Configuration process	2-41
	• How to Configure Your Communications Gateway	2-42
	• How to Start the Communications Service	2-45
	• How to Stop the Communications Service	2-46
	• How to Create Communications Mailboxes	2-47
	• How to Modify Mailbox Properties	2-55
Appendix A	Error Messages	
	• Overview	A-2
	• Communications Gateway Messages	A-3
Appendix B	Working with OFTP	
	• Overview	B-2
	• Defining the SSID and SFID Commands	B-3
	• How to Create a Partner Definition (OFTP Remote VAN Users)	B-4
	• Defining the Virtual Filename and Data Format	B-6



Contents

Notices

About This Guide

Contents

- ▶ Introductioniv
 - ▶ Description of Contentsv
 - ▶ Online Helpvi
 - ▶ Getting Supportvii
-

Introduction

Overview

This document contains the tasks you must follow to:

- configure the Communications Gateway
- create Communications Gateway mailboxes for your Trading Partners

Intended audience

The intended audience for this document is:

- IBM® Sterling Gentran:Server® for Microsoft Windows system administrators
- advanced Sterling Gentran:Server users

Prerequisite knowledge

The audience using this software should be familiar with:

- Microsoft® Windows®
 - Sterling Gentran:Server
 - Communications protocols
-

Description of Contents

Introduction

This guide is organized into the tasks that you complete when configuring communications for the Communications Gateway.

Organization of chapters

The guide is organized into chapters. A brief description of each chapter's contents follows.

- ▶ *About this Guide* explains the content and organization of this guide.
 - ▶ *Communications Gateway Overview* provides a high-level overview of the Communications Gateway.
 - ▶ *Configuring Communications* explains the process for configuring the Communications Gateway. This chapter also provides the procedures you must follow to configure your Communications Gateway mailboxes.
 - ▶ *Error Messages* describes the gateway error messages and suggested user actions.
 - ▶ *Working with OFTP* explains set up considerations for use with OFTP (Odette File Transfer Protocol).
-

Related topic

The *IBM® Sterling Gentran:Server® for Microsoft Windows Script Language Reference Guide* describes the script language provided for use with the Sterling Gentran:Server communications subsystem.

Reference

See the “Script Language Reference” chapter of the *IBM® Sterling Gentran:Server® for Microsoft Windows Script Language Reference Guide* for additional information.

Online Help

Introduction

The majority of the documentation for this gateway is contained in the online Help system. This includes all the dialog box element definitions, detailed processing information, and all the “how to” information that is contained in this manual.

Field-level Help

To view field-level descriptions for Mailbox Server gateways, navigate to the component for which you want field-level descriptions. Press **F1** to display a parts and functions table.

Getting Support

Introduction Sterling Gentran:Server is supported by trained product support personnel who are available to help you with product questions or concerns.

Phone number For assistance, please refer to your *IBM® Sterling Gentran:Server® for Microsoft Windows Getting Started Guide* to determine which support phone number you should use.

Before calling support To help us provide prompt service, we ask that you do the following:

- Attempt to recreate any problem that you encounter and record the exact sequence of events.
- When you call product support, you should be prepared to provide us with the information below.

Information	Description
Identification	Your company name, your name, telephone number and extension, and the case number (if the question refers to a previously reported issue).
System Configuration	The Sterling Gentran:Server version (and any service packs installed) and information about the primary Sterling Gentran:Server system controller and all machines experiencing problems, including: the Microsoft Windows operating system version, amount of memory, available disk space, database version, Microsoft Data Access (MDAC) version, and Internet Explorer version. Also, please describe any recent changes in your hardware, software, or the configuration of your system.
System Data Store	Which machines contain folders in the system data store?
Error Messages	Record the exact wording of any error messages you receive and the point in the software where the error occurred, as well as any log files.
Attempted Solutions	Record any steps that you took attempting to resolve the problem and note all the outcomes, and provide an estimate on how many times the problem occurred and whether it can be reproduced.

How To Get Help

IBM® Sterling Customer Center provides a wealth of online resources that are available around the clock to enrich your business experience with IBM® Sterling Gentran®. By using Sterling Customer Center, you gain access to many self-support tools, including a Knowledge-Base, Documentation, Education, and Case Management. Access this site at: Sterling Customer Center. (<http://customer.sterlingcommerce.com>)

Once logged in, select **Support Center** from the top navigation menu, and then locate Sterling Gentran:Server product-specific support information from the left navigation menu.

Additionally, our Customer Support Reference Guide outlines our support hours, contact information, and key information that will enhance your support experience with us. For detailed information about Customer Support, please refer to the Customer Support Reference Guide accessible from the login page. (<http://customer.sterlingcommerce.com>)

Communications Gateway Overview

Contents

- ▶ Overview 1 - 2
 - ▶ Sterling Gentran:Server Communications Gateway 1 - 3
 - ▶ Sterling Gentran:Server Communications Gateway Mailboxes 1 - 6
-

Overview

In this chapter This chapter provides you with a high-level overview of the Communications Gateway.

What is a gateway? Gateways are software components that control the transmission of messages between two parties. The gateway is responsible for using the correct protocols to transfer messages between the sender and receiver.

You are responsible for defining the properties of the gateways that you use.

What is a mailbox? Mailboxes store messages that are being transferred between mail recipients. Like a mailbox for paper mail, the messages are stored in the mailbox until they are transferred to the addressee.

There are two types of Sterling Gentran:Server mailboxes:

- non-gateway mailboxes
- gateway mailboxes

Non-gateway mailboxes

When you installed Sterling Gentran:Server, a default, non-gateway mailbox was created called the Sterling Gentran:Server Application mailbox. This mailbox is used by Mailbox Server to hold messages that are being transferred between Sterling Gentran:Server and your Trading Partners.

Gateway mailboxes

You are responsible for creating gateway mailboxes. When you create gateway mailboxes you associate the mailbox with a gateway. The properties you define for each gateway mailbox determines how messages are transferred to your Trading Partners.

Related Topic See the Communications Overview chapter of the *IBM® Sterling Gentran:Server® for Microsoft Windows Communications User Guide* for detailed information on the Mailbox Server system.

Sterling Gentran:Server Communications Gateway

Introduction The Sterling Gentran:Server Communications Gateway is used when you exchange business documents with your Trading Partners through a Value Added Network (VAN) or directly to your Trading Partner's computer system.

Purpose The purpose of the Sterling Gentran:Server Communications Gateway is to establish a communications session with a VAN or Trading Partner computer. This gateway uses communications scripts to log on to the VAN or Trading Partner computer, and to send and to receive messages.

Communications scripts Communications processes are controlled by Mailbox Server and by a suite of communications scripts provided by IBM. The basic Mailbox Server that is delivered as part of Sterling Gentran:Server provides you with the ability to communicate with your Trading Partners.

Content type and subtype The content type and subtype values are used to indicate the Internet media type of the information being transmitted. The content type determines the mechanism to use to display the data.

You determine which action the system performs on each type of data by the values selected on the Mailbox tab of the System Configuration dialog box.

Example

Application/EDI is an application program type with a subtype of EDI (representing Electronic Data Interchange data). When Sterling Gentran:Server receives a message with an Application/EDI content type and subtype, it runs the GDW_Process_MBFile command on the message.

Note

Messages containing undefined content types remain in the Sterling Gentran:Server Application mailbox until the content type has been defined.

Reference

See the *IBM® Sterling Gentran:Server® for Microsoft Windows Administration Guide* for information on the Mailbox tab of the System Configuration dialog box.

Acceptable content types and subtypes

Sterling Gentran:Server accepts, by default, the following content type / subtype combinations:

- Application/EDI
- Application/Import
- Application/Document-EDI


Configuring the gateway

You must configure the Sterling Gentran:Server Communications Gateway before you can begin to transfer messages to a Trading Partner. This procedure involves selecting the:

- communications controller that services the modem or network card you are using to communicate with your Trading Partners
- device pool containing the modem or network card you intend to use with this gateway
- attachment content type defaults to be assigned to messages that are transferred through this gateway

Message flow diagram

This diagram shows the flow of messages using the Sterling Gentran:Server Communications Gateway. The numbers in this diagram correspond to the stages listed in *Message flow description* on page 1 - 5.



Message flow description

This table describes the flow of messages using the Sterling Gentran:Server Communications Gateway.

Stage	Description
1	All messages going to and from Sterling Gentran:Server are stored in the Sterling Gentran:Server Application mailbox.
2	Messages are transferred between the Sterling Gentran:Server Application mailbox and the Trading Partner mailboxes that you have created on Mailbox Server.
3	The Trading Partner mailbox properties determine how your messages are transferred to your Trading Partners.
4	The Sterling Gentran:Server Communications Gateway connects to your Trading Partner's VAN, or directly to your Trading Partner's system and routes messages to the appropriate mailbox. A communications session may send, receive, or send and receive messages.

Sterling Gentran:Server Communications Gateway Mailboxes

Introduction

When you configure a mailbox to be used with the Sterling Gentran:Server Communications Gateway, you define the following:

- transport properties for this mailbox, such as:
 - Asynchronous
 - Bisynchronous
 - TCP/IP (Transmission Control Protocol / Internet Protocol)
 - FTP (File Transfer Protocol)
 - WS_FTP Pro File Transfer Program
 - ISDN (Integrated Services Digital Network)
 - EICON X.25T

These properties determine the format, timing, and error control for data transmission.

- communications script to use with this mailbox
- default message content types
- a list of message recipients

Reference

See *Configuring Communications*, chapter 2 of this guide, for complete instructions on configuring Sterling Gentran:Server Communications Gateway mailboxes.

Configuring Communications

Contents	Overview	2 - 2
	▶ Introduction.....	2 - 2
	▶ Sterling Gentran:Server Communications Gateway Properties.....	2 - 3
	▶ Mailbox Gateway Properties.....	2 - 11
	▶ Mailbox Properties.....	2 - 36
	Procedures	2 - 41
	▶ Configuration process.....	2 - 41
	▶ How to Configure Your Communications Gateway.....	2 - 42
	▶ How to Start the Communications Service.....	2 - 45
	▶ How to Stop the Communications Service.....	2 - 46
	▶ How to Create Communications Mailboxes.....	2 - 47
	▶ How to Modify Mailbox Properties.....	2 - 55

Overview

Introduction

In this chapter

This chapter describes the tasks that you must complete to configure your Communications Gateway and Communications Gateway mailbox.

Key Terms


This table describes key terms used in this chapter.

Term	Description
pool	A collection of communications devices.
communications controller	A computer that controls communications sessions.
communications gateway	Software or a computer running software that enables two different computers to communicate.
mailbox	A folder or set of folders used to store messages.

Sterling Gentran:Server Communications Gateway Properties

Introduction The Sterling Gentran:Server Communications Gateway dialog box is used to configure telecommunications with your Trading Partners.

Servers tab This illustration shows an example of the Servers tab of the Sterling Gentran:Server Communications dialog box.




Parts and functions This table describes the parts of the Servers tab of the Sterling Gentran:Server Communications dialog box and their functions.

Part	Function
Servers	Displays the communications controllers available to Mailbox Server. You may have multiple communications controllers in your Mailbox Server system.
Devices	Displays the devices available for use with Mailbox Server. The devices shown in this list are the devices for each respective communications controller.

(Contd) Part	Function
System Log	Views the log information for a specific communications controller.
Remove	Removes the selected communications controller from the list.
Start	Starts communications services on the selected controller.
Stop	Stops communications services on the selected controller.
Select All	Selects all devices for the selected controller.
Unselect All	Unselects all devices for the selected controller.
OK	Saves and applies changes; exits the dialog box.
Cancel	Cancels changes; exits dialog.
Apply	Applies changes.
Help	Launches the online Help system.

Pools tab

This illustration shows an example of the Pools tab of the Sterling Gentran:Server Communications dialog box.




Parts and functions

This table describes the parts of the Pools tab of the Sterling Gentran:Server Communications dialog box and their functions.

Part	Function
Pools	Lists user-defined device pools.
Devices	Lists the devices assigned to a specific pool.
New	Adds a new device pool.
Delete	Removes a device pool.
Script	Allows you to select and edit a communications script. (This button is available only for Host or Host and Remote pools.)
Add	Adds devices that are not already part of another pool.
Remove	Removes devices from a pool.
Move Up	Moves a device up in the list order.
Move Down	Moves a device down in the list order.
OK	Saves and applies changes; exits the dialog box.
Cancel	Cancel changes; exits dialog.
Apply	Applies changes.
Help	Launches the online Help system.

New Pool

This illustration shows an example of the New Pool dialog box.




Parts and Functions

This table describes the parts of the New Pool dialog box and their function.

Part	Function
Pool Device	Choose a pool device from the list. This list determines the type of communications device you are using.
Pool Type	Choose a pool type from the list. This type determines whether you are initiating, receiving, or initiating and receiving communications sessions.
Pool Name	Type a unique identifier for this pool in this field.
OK	Closes this dialog and saves any changes you have made.
Cancel	Closes this dialog without saving any changes you have made.
Help	Click this button to display the online help.

Hosts tab

This illustration shows an example of the Hosts tab of the Sterling Gentran:Server Communications dialog box.




Parts and functions

This table describes the parts of the Hosts tab of the Sterling Gentran:Server Communications dialog box and their functions.

Part	Function
Mailboxes	Displays the list of mailboxes. A check mark next to the mailbox denotes that it has been set up as a host mailbox.
Host Password	Defines the password your Trading Partner must use to access the selected mailbox.
Select All	Selects all mailboxes.
Unselect All	Clears all check boxes.
Script	Defines the Advanced Data Distribution communications script to use with the selected host mailbox.
Defaults	Defines the default message content type and subtype for the selected mailbox, and the default message recipients.
OK	Saves changes; exits dialog box.
Cancel	Cancels changes; exits dialog box.
Apply	Applies changes.
Help	Launches online Help.

Sessions tab

This illustration shows an example of the Sessions tab of the Sterling Gentran:Server Communications dialog box.


**Parts and functions**

This table describes the parts of the Sessions tab of the Sterling Gentran:Server Communications dialog box and their functions.

Part	Function
Queued	Shows all communications sessions in a queued or running state for all communications controllers.
Completed	Shows all communications sessions with a status of successful or failed for all communications controllers.
Log	Displays the log for all completed sessions.
Refresh	Repaints the screen updating the display with new information.
Delete	Deletes the selected completed session from the log.
OK	Saves and applies changes; exits the dialog box.
Cancel	Cancels changes; exits dialog.
Apply	Applies changes.
Help	Launches the online Help system.

Miscellaneous tab

This illustration shows an example of the Miscellaneous tab of the Sterling Gentran:Server Communications dialog box.

**Parts and functions**

This table describes the parts of the Miscellaneous tab of the Sterling Gentran:Server Communications dialog box and their function.


Part	Function
Default content type	Defines the default MIME content type and subtype for mailboxes that use this gateway.
Automatically purge communication logs	Defines whether communication logs will be purged. The default is to leave this option disabled.
Purge logs older than __ days	Defines the number of days that Mailbox Server retains communication logs before purging them.
Purges will be performed at	Sets the time at which communication logs will be purged.
OK	Saves and applies changes; exits the dialog box.
Cancel	Cancel Changes; exits dialog.

(Contd) Part	Function
Apply	Applies changes.
Help	Launches the online Help system.

Mailbox Gateway Properties

Introduction The Gateway Properties dialog box defines the properties for the mailbox that you created.

Gateway Properties This illustration shows an example of the Gateway Properties dialog box.




Parts and functions This table describes the parts of the Gateway Properties dialog box and their functions.

Part	Function
Transport	Enables you to select transport type.
Properties	Enables you to define properties for the transport type that you selected.
Script	Launches Script Editor.
Defaults	Launches the Message Defaults dialog box; enables you to set default Content type for messages and attachments.
Auto Send	Enables you to define Auto Send properties.
Tradanet	Enables you to define Tradanet properties.
OK	Saves and applies changes; exits the dialog box.
Cancel	Cancels changes; exits dialog.

(Contd) Part	Function
Apply	Applies changes.
Help	Launches the online Help system.

TAPI Properties

This illustration shows an example of the TAPI Properties dialog box.




TAPI Properties

This table describes the parts of the TAPI Properties dialog box and their function.

Part	Function
Device Pool	Choose a communications device pool from the list.
Phone Number	Type the phone number of the computer you want to contact in this field.
Dial Retries	Select the number of times you want Mailbox Server to redial the telephone number.
Session Retries	Select the number of times you want Mailbox Server to re-start the session.
OK	Closes this dialog and saves any changes you have made.
Cancel	Closes this dialog without saving any changes you have made.
Help	Click this button to display the online help.

Bisync Properties

This illustration shows an example of the Bisync Properties dialog box.


**Bisync Properties**

This table describes the parts of the Bisync Properties dialog box and their function.

Part	Function
Device Pool	Type a Communications Device Pool or choose an item from the list.
Phone Number	Type the phone number for the VAN or Trading Partner.
OK	Closes this dialog and saves any changes you have made.
Cancel	Closes this dialog without saving any changes you have made.
Help	Click this button to display the online help

CAPI Properties - B - Channel Option selected

This illustration shows an example of the CAPI Properties (with the B - Channel option selected) dialog box.



Parts and Functions


This table describes the parts of the CAPI Properties (with the B - Channel option selected) dialog box and their function.

Part	Function
Device Pool	Type a Communications Device Pool or choose an item from the list.
Called party Number	Type the ISDN phone number for the VAN or Trading Partner.
Called party subaddress (optional)	An optional entry used for ISDN multipoint connections.
Facilities (optional)	Unavailable. Does not apply to B - Channel usage.
Call User Data (optional)	Unavailable. Does not apply to B - Channel usage.

(Contd) Part	Function
ISDN Channel Usage	Determines which channel the system uses to for communications. Reference See <i>CAPI Properties - D - Channel Option selected</i> on page 2 - 15 for a description of that dialog box.
OK	Closes this dialog and saves any changes you have made.
Cancel	Closes this dialog without saving any changes you have made.
Help	Click this button to display the online help

**CAPI Properties -
D - Channel Option
selected**

This illustration shows an example of the CAPI Properties (with the D - Channel option selected) dialog box.



Parts and Functions

This table describes the parts of the CAPI Properties (with the D - Channel option selected) dialog box and their function.

Part	Function
Device Pool	Type a Communications Device Pool or choose an item from the list.
Called DTE Address NUA	Specifies the VAN or trading partner's Network User Address.
Calling DTE Address NUA (optional)	Specifies <i>your</i> Network User Address.
Facilities (optional)	In an X.25 packet switching data network, an optional field that the data terminal equipment (DTE) uses to convey call information to the network.
Call User Data (optional)	In X.25 communications, optional data that the user application includes in the call-request packet.
ISDN Channel Usage	Determines which channel the system uses for communications. Reference See <i>CAPI Properties - B - Channel Option selected</i> on page 2 - 14 for a description of that dialog box.
OK	Closes this dialog and saves any changes you have made.
Cancel	Closes this dialog without saving any changes you have made.
Help	Click this button to display the online help

FTP Properties

This illustration shows an example of the FTP Properties dialog box.


Parts and Functions

This table describes the parts of the FTP Properties dialog box and their function.

Part	Function
Device Pool	Choose a device pool from the list.
Dialup Networking Phonebook Entry	Select the phone book entry that you use for dialup networking.
Server	Type the name of an FTP server or choose an item from the list.
FTP Address	Type the IP (Internet Protocol) address of the FTP server in the form XXX.XXX.XXX.XXX.
User Name	Type your User Name on the FTP Server.
Password	Type your Password on the FTP Server.
OK	Closes this dialog and saves any changes you have made.
Cancel	Closes this dialog without saving any changes you have made.
Help	Click this button to display the online help.

Socket Properties

This illustration shows an example of the Socket Properties dialog box.


**Parts and Functions**

This table describes the parts of the Socket Properties dialog box and their function.

Part	Function
Device Pool	Choose a device pool from the list.
Dialup Networking Phonebook Entry	Select the phonebook entry that you use for dialup networking.
Server	Choose a communications server from the list.
Socket Address	Type IP (Internet Protocol) address of the computer you want to contact.
Socket	Type the IP socket (port) number in this field.
OK	Closes this dialog and saves any changes you have made.
Cancel	Closes this dialog without saving any changes you have made.
Help	Click this button to display the online help.

Gateway Email Addresses

This illustration shows an example of the Gateway Email Addresses dialog box.




Parts and Functions

This table describes the parts of the Gateway Email Addresses dialog box and their function.

Part	Function
Email address list	Type Email address on the VAN or Trading Partner's computer.
Email Addresses list	This list contains all the mail addresses on the VAN or Trading Partner's computer who will receive messages.
OK	Closes this dialog and saves any changes you have made.
Cancel	Closes this dialog without saving any changes you have made.
Add	Click this button to add an Email Address.
Remove	Click this button to remove the selected Email Address.
Help	Click this button to display the online help.

Script dialog box

This illustration shows an example of the Script dialog box.


**Parts and Functions**

This table describes the parts of the Script dialog box and their function.

Part	Function
Script Name	Choose a communications script from the list.
Script Variables	Define the values for the selected script.
OK	Closes this dialog and saves any changes you have made.
Cancel	Closes this dialog without saving any changes you have made.
Help	Click this button to display the online help.
Edit	Click this button to edit the script.
New	Click this button to create a new script.
Trace	Select this option to save trace data for the communications session.

New Script dialog box

This illustration shows an example of the New Script dialog box.




Parts and Functions

This table describes the parts of the New Script dialog box and their function.

Part	Function
Script Name	Type the name of the communications script you want to use in this field.
OK	Closes this dialog and saves any changes you have made.
Cancel	Closes this dialog without saving any changes you have made.
Help	Click this button to display the online help.

Compiler Output

This illustration shows an example of the New Script dialog box.




Parts and Functions

This table describes the parts of the Compiler Output dialog box and their function.

Part	Function
Compiler Output	A display of the output from the compiler.
Help	Click this button to display the online help.
Close	Click this button to close this dialog box.

Message Defaults

This illustration shows an example of the Message Defaults dialog box.


**Message Defaults**

This table describes the parts of the Message Defaults dialog box and their function.

Part	Function
Use MIME Content Type for each attachment	Select this option to use MIME (Multipurpose Internet Mail Extension) content types for each attachment.
Use this Content Type for all attachments	Type a Content Type and Subtype to be used for all attachments. Example Application/EDI
Use the Content Type of the first attachment for each message	Select this option to use the Content Type of the first attachment in a message as the Content Type of the whole message.
Use this Content Type for all messages	Type a Content Type and Subtype to be used for all messages. Example Application/EDI
Edit Recipients	Click this button to select the recipients to send the message to.
OK	Closes this dialog and saves any changes you have made.
Cancel	Closes this dialog without saving any changes you have made.
Help	Click this button to display the online help.

Edit Recipients

This illustration shows an example of the Edit Recipients dialog box.



Parts and Functions

This table describes the parts of the Edit Recipients dialog box and their function.

Part	Function
Type a name or select from the list	Type a mail address or choose an item from the list.
Recipient	Displays a list of Email addresses.
To	Click this button to make this mail address a primary recipient.
CC	Click this button to make this mail address a secondary recipient.
BCC	Click this button to make this mail address a secondary recipient. This mail address will not appear in the list of mail recipients that goes with the message.
OK	Closes this dialog and saves any changes you have made.
Cancel	Closes this dialog without saving any changes you have made.
Help	Click this button to display the online help.

Tradanet TSP User tab

This illustration shows an example of the Tradanet TSP User tab.

The screenshot shows a dialog box titled "Tradanet Properties - Using TSP commands" with a close button (X) in the top right corner. The "User" tab is selected, with other tabs being "DELF", "GO/NG", and "NEWREL". The dialog contains the following fields and controls:

- TSP Syntax: A dropdown menu with "ANA" selected.
- Sender ID: An empty text input field.
- Password: A text input field containing "PASSWORD".
- New Password: An empty text input field.
- LISTM: A dropdown menu with "Always" selected.
- LISTP: A dropdown menu with "Always" selected.
- LISTR: A dropdown menu with "Always" selected.

Below the fields, there is a note: "If new password entered, NEWP will be sent." At the bottom of the dialog are three buttons: "OK", "Cancel", and "Help".

Parts and functions


This table describes the parts of the Tradanet TSP User tab and their functions.

Part	Function
TSP Syntax	Defines the standard data syntax used with this gateway mailbox. Valid values are: <ul style="list-style-type: none"> • ANA • ANAA • DSHB
Sender ID	Identifies the Sender using an EDI number or OFTP ID defined on the Tradanet Network.
Password	Defines the Sender's Password on the Tradanet Network.
New Password	Defines a new password for the user. If specified, a NEWP command is sent.
LISTM	Lists incoming messages in the users Tradanet Network Mailbox. Valid values are: <ul style="list-style-type: none"> • Never—never send this command. • Always—always send this command. • Once—send this command one time only.

(Contd) Part	Function
LISTP	Lists outgoing messages in the users Tradanet Network Postbox. Valid values are: <ul style="list-style-type: none"> ▶ Never—never send this command. ▶ Always—always send this command. ▶ Once—send this command one time only.
LISTR	Lists Tradanet Network relationships the user has defined. Valid values are: <ul style="list-style-type: none"> ▶ Never—never send this command. ▶ Always—always send this command. ▶ Once—send this command one time only.
OK	Saves and applies changes; exits the dialog box.
Cancel	Cancel changes; exits dialog.
Help	Launches the online Help system.

**Tradanet TSP
DELF tab**

This illustration shows an example of the Tradanet TSP DELF tab. DELF is used to delete files.




Parts and functions

This table describes the parts of the Tradanet TSP DELF tab and their functions.

Part	Function
Send DELF commands	Defines when you want to send DELF commands. Valid values are: <ul style="list-style-type: none"> ▶ Never—never send this command. ▶ Always—always send this command. ▶ Once—send this command one time only
*ALL	Deletes all previously extracted files.
TYPE	Deletes all previously extracted files with the specified data type (APRF).
Add	Adds entries to the associated list.
Delete	Deletes entries from the associated list.
*BEFORE	Deletes all previously extracted files older than the specified number of days.
*FILES	Deletes only the previously extracted files that you specify.
Add	Adds entries to the associated list.
Delete	Deletes entries from the associated list.
*UNWANTED	Deletes only the unextracted files that you specify.
Add	Adds entries to the associated list.
Delete	Removes entries from the associated list.
OK	Saves changes; exits dialog box.
Cancel	Cancels changes; exits dialog box.
Help	Launches online Help system.

Tradanet TSP GO/NG tab

This illustration shows an example of the Tradanet TSP GO/NG tab.



Parts and functions


This table describes the parts of the Tradanet TSP GO/NG tab and their functions.

Part	Function
Send GO/NG	Defines when you want to send GO/NG commands. Valid values are: <ul style="list-style-type: none"> ▶ Never—never send this command. ▶ Always—always send this command. ▶ Once—send this command one time only.
Using	Selects whether to use the GO or NG command to receive files.
*All	Specifies that all unextracted files will be received.
TYPE	Receives all unextracted files with the specified data type (APRF).
Add	Adds entries to the associated list.
Delete	Removes entries from the associated list.
User	Receives all unextracted files from the specified user. If this command is selected, all other options will be disabled since this command cannot use the SELF (Select Files) command.

(Contd) Part	Function
*FILES	Receives only the unextracted files that you specify.
Add	Adds entries to the associated list.
Delete	Removes entries from the associated list.
*AGAIN	Receives only the previously extracted files that you specify.
Add	Adds entries to the associated list.
Delete	Removes entries from the associated list.
OK	Saves changes; exits dialog box.
Cancel	Cancel changes; exits dialog box.
Help	Launches online Help system.

Tradnet TSP NEWREL tab

This illustration shows an example of the Tradnet TSP NEWREL tab.



Parts and functions

This table describes the parts of the Tradanet TSP NEWREL tab and their functions.

Part	Function
Send NEWREL commands	Defines when to send NEWREL commands. Valid options are: <ul style="list-style-type: none"> ▶ Never—never send this command. ▶ Once—send this command one time only.
Direction	Defines the direction that files are transmitted with the Relationship. Valid values are send and receive.
Action	Defines action to be taken with the relationship. Valid values are establish and cancel.
Data Type	Defines the type of data to be transmitted to the Trading Partner. Valid values are Any or a user-defined value.
Partner	Defines the name of the new Trading Partner. Valid values are Anybody or a user-defined value.
Add	Adds relationships to the list.
Change	Enables you to change a relationship in the list.
Delete	Deletes a relationship from the list.
OK	Saves changes; exits the dialog box.
Cancel	Cancels changes; exits the dialog box.
Help	Launches the online Help system.

Tradanet TIP User tab

This illustration shows an example of the Tradanet TIP User tab.

Parts and functions


This table describes the parts of the Tradanet TIP User tab and their functions.

Part	Function
Sender ID	Identifies the Sender using an EDI number or OFTP ID defined on the Tradanet Network.
Password	Defines the Sender's Password on the Tradanet Network.
New Password	Defines a new password for the user. If specified, a NEWP command will be sent.
LISTM	Lists incoming messages in the users Tradanet Network Mailbox. Valid values are: <ul style="list-style-type: none"> • Never—never send this command. • Always—always send this command. • Once—send this command one time only.
LISTP	Lists outgoing messages in the users Tradanet Network Postbox. Valid values are: <ul style="list-style-type: none"> • Never—never send this command. • Always—always send this command. • Once—send this command one time only.

(Contd) Part	Function
LISTR	Lists Tradanet Network relationships the user has defined. Valid values are: <ul style="list-style-type: none"> • Never—never send this command. • Always—always send this command. • Once—send this command one time only.
OK	Saves and applies changes; exits the dialog box.
Cancel	Cancels Changes; exits dialog.
Help	Launches the online Help system.

**Tradanet TIP
DELF tab**

This illustration shows an example of the Tradanet TIP DELF tab.




Parts and functions

This table describes the parts of the Tradanet TIP DELF tab and their functions.

Part	Function
Send DELF commands	Defines when you want to send DELF commands. Valid values are: <ul style="list-style-type: none"> ▶ Never—never send this command. ▶ Always—always send this command. ▶ Once—send this command one time only
*ALL	Deletes all previously extracted files.
*TYPE	Deletes all previously extracted files with the specified data type (APRF).
Add	Adds entries to the associated list.
Delete	Deletes entries from the associated list.
*BEFORE	Deletes all previously extracted files older than the specified number of days.
*USER	Deletes all previously extracted files from a specified service reference.
Add	Adds entries to the associated list.
Delete	Deletes entries from the associated list.
Service Reference	Deletes files with the specified service reference.
Add	Adds entries to the associated list.
Delete	Deletes entries from the associated list.
OK	Saves changes; exits dialog box.
Cancel	Cancels changes; exits dialog box.
Help	Launches online Help system.

Tradanet TIP GO tab

This illustration shows an example of the Tradanet TIP GO tab.



Parts and functions


This table describes the parts of the Tradanet GO tab and their functions.

Part	Function
Send GO commands	Defines when you want to send GO commands. Valid values are: <ul style="list-style-type: none"> ▶ Never—never send this command. ▶ Always—always send this command. ▶ Once—send this command one time only
GO NEXT	Receives all unextracted files.
Sender (optional) list	Specifies that the service return the next logical file from the specific Sender designated. If set to blank spaces, the service retrieves the next logical file. This field can be used in conjunction with APRF (optional) list.
APRF (optional) list	Specifies that the service return the next logical file with an Application Reference that matches the APRF value entered. If set to blank spaces, the service retrieves the next logical file. This field can be used in conjunction with Sender (optional) list.
Add	Adds entries to the associated list.

Part	Function
Delete	Deletes entries from the associated list.
GO FILE	Retrieves the next logical file with the specified application Reference regardless of its status on the service.
Application Reference (APRF) list	List of Application References received.
Add	Adds entries to the associated list.
Delete	Deletes entries from the associated list.
OK	Saves changes; exits dialog box.
Cancel	Cancels changes; exits dialog box.
Help	Launches online Help system.

Tradanet TIP NEWREL tab

This illustration shows an example of the Tradanet TIP NEWREL tab.



Parts and functions

This table describes the parts of the Tradanet TIP NEWREL tab and their functions.

Part	Function
Send NEWREL commands	Defines when to send NEWREL commands. Valid options are: <ul style="list-style-type: none"> ▶ Never—never send this command. ▶ Once—send this command one time only.
Direction	Defines the direction that files are transmitted with the Relationship. Valid values are send and receive.
Action	Defines action to be taken with the relationship. Valid values are establish and cancel.
Data Type	Defines the type of data to be transmitted to the Trading Partner. Valid values are Any or a user-defined value.
Partner	Defines the name of the new Trading Partner. Valid values are Anybody or a user-defined value.
Add	Adds a relationship to the list.
Change	Enables you to change relationship in the list.
Delete	Deletes a selected relationship from the list.
OK	Saves changes; exits the dialog box.
Cancel	Cancels changes; exits the dialog box.
Help	Launches the online Help system.

Mailbox Properties

Introduction The Mailbox Properties dialog box defines the properties of the mailbox.

Addressing Tab This illustration shows an example of the Addressing tab of the Mailbox Properties dialog box.




Parts and functions This table describes the parts of the Addressing tab of the Mailbox Properties dialog box and their functions

Part	Function
Name	Defines the name of the mailbox.
Gentran e-mail address	Defines the Sterling Gentran:Server e-mail address for messages sent from the mailbox.
OK	Saves changes; exits dialog.
Cancel	Closes dialog without saving changes.
Help	Enables access to online help.

Gateway Tab

This illustration shows an example of the Gateway tab of the Mailbox Properties dialog box.




Parts and functions

This table describes the parts of the Gateway tab of the Mailbox Properties dialog box and their functions.

Part	Function
Gateway	Specifies whether the mailbox is or is not a gateway. Options are: <ul style="list-style-type: none"> ▶ This mailbox is not a gateway ▶ This mailbox is a gateway
Type	Specifies type of gateway. Active when “This mailbox is a gateway” radio button is selected.
Configure	Enables you to configure properties for a selected gateway.
OK	Saves changes; exits dialog.
Cancel	Closes dialog without saving changes.
Help	Enables access to online help.

Delivery Rules Tab

This illustration shows an example of the Delivery Rules tab of the Mailbox Properties dialog box.

**Parts and functions**


This table describes the parts of the Delivery Rules tab of the Mailbox Properties dialog box and their functions.

Part	Function
Name	Defines the name of the Delivery Rule.
Direction	Identifies if the rule is run when sending or receiving a message.
Sender/Recipient	Identifies the mailbox of the sender or recipient. The mail address can be specified in addition to the mailbox name.
Agent	Identifies the name of the delivery agent to be run.
New	Creates new Delivery Rules.
Edit	Edits existing Delivery Rules.
Delete	Deletes Delivery Rules.
Move Up	Moves the selected Delivery Rule up.
Move Down	Moves the selected Delivery Rule down.
OK	Saves changes; exits dialog.

(Contd) Part	Function
Cancel	Closes dialog without saving changes.
Help	Enables access to online help.

Security Tab

This illustration shows an example of the Security tab of the Mailbox Properties dialog box.



Parts and functions

This table describes the parts of the Security tab of the Mailbox Properties dialog box and their functions.

Part	Function
User list	Defines users and groups that have access to mailbox.
Type of Access	Designates level at which a user can interact with a mailbox. Values are: <ul style="list-style-type: none"> ▶ Full control ▶ Read ▶ Write
Add	Enables you to grant users or groups mailbox access.

(Contd) Part	Function
Remove	Enables you to take away user or group mailbox access.
OK	Saves changes; exits dialog.
Cancel	Closes dialog without saving changes.
Help	Enables access to online help.

Procedures

Configuration process

Configuration stages

This table lists the stages in configuring your communications for use with a VAN or a direct connection to a Trading Partner.

Stage	Description
1	<p>Define your communications hardware using the Microsoft Windows® modems applet in the Control Panel.</p> <p>Reference Refer to your Microsoft Windows documentation for more information on defining communications hardware.</p>
2	<p>Configure the Sterling Gentran:Server Communications Gateway.</p> <p>Reference See <i>How to Configure Your Communications Gateway</i> on page 2 - 42 for more information.</p>
3	<p>Create the mailboxes you intend to use.</p> <p>Reference See <i>How to Create Communications Mailboxes</i> on page 2 - 47 for more information.</p>

How to Configure Your Communications Gateway

Introduction This section describes how to configure your Sterling Gentran:Server Communications Gateway. This gateway is used for dialing out of the Sterling Gentran:Server system.

Before you begin Ensure that the communications devices you are using for Sterling Gentran:Server communications have been defined on the Communications Controller.

Procedure Use this procedure to configure your Sterling Gentran:Server Communications Gateway.

Step	Action
1	Start the Mailbox Server Manager . System Response The system displays the Server Manager browser.
2	Select Gentran:Server Mailbox in the Server Manager pane, then right-click, and select Register Server . System Response The system displays the Register Server dialog box.
3	Type the name of your Mailbox server, and click OK .
4	Expand your Mailbox Server directory tree.
5	Select Gentran:Server Communications from the Gateway folder.
6	Right-click and select Properties to define the properties for this gateway. System Response The system displays the Servers tab of the Sterling Gentran:Server Communications properties dialog box.
7	Select the communications controller you are configuring from the Servers list. System Response A list of available communications devices for that communications controller appears in the Devices list.
8	Click the check box in front of the device to be made available for pooling from the Devices list.

(Contd) Step	Action
9	<p>Repeat Steps 1 through 8 for each communications controller in your Mailbox Server system.</p> <p>Comment Steps 1 through 8 make the communications devices on each communications controller available for use by any of the computers in the Mailbox Server system.</p> <p>Example You want to make a 56 kbps modem on CommServ1 and a 28.8kbps modem on CommServ2 available for use by any computer in your Mailbox Server system. You start the Mailbox Server Manager on CommServ1, select CommServ1 from the Servers list, and select the 56 kbps modem from the Devices list. You start the Mailbox Server Manager on CommServ2, select CommServ2 from the Servers list and select the 28.8 kbps modem from the Devices list. These modems are now available for use in device pools on the Mailbox Server system.</p>
10	<p>Select the Pools tab, and click New to add a new Pool.</p> <p>Note You can select any client in the Mailbox Server System.</p> <p>System Response The system displays the New Pool dialog box.</p>
11	Select a device from the Pool Devices list.
12	Select Remote Only from the Pool Type list.
13	Type a unique name for this pool in the Pool Name box, and click OK .
14	<p>Click Add to add the device that you selected in Step 8 to the pool.</p> <p>System Response The system displays the Add device(s) to pool dialog box.</p>
15	<p>Highlight the Server and Device name that you want to add to the pool, and click OK.</p> <p>System Response You return to the Pools tab dialog box; the device that you added displays in the Devices list.</p>
16	Click OK to complete the configuration of this gateway.
17	<p>Stop the Sterling Gentran:Server Communications service on each communications controller.</p> <p>Reference See <i>How to Start the Communications Service</i> on page 2 - 45 for more information.</p>

(Contd) Step	Action
18	Stop the Sterling Gentran:Server Mailbox service. Reference See How to Stop the Mailbox Service in the <i>IBM® Sterling Gentran:Server® for Microsoft Windows Communications User Guide</i> for more information.
19	Restart the Sterling Gentran:Server Mailbox service. Reference See How to Start the Mailbox Service in the <i>IBM® Sterling Gentran:Server® for Microsoft Windows Communications User Guide</i> for more information.
20	Restart the Sterling Gentran:Server Communications service on each communications controller. Reference See <i>How to Start the Communications Service</i> on page 2 - 45 for more information. You are now ready to create mailboxes to use with this gateway.

How to Start the Communications Service

Introduction Normally, you must start the Sterling Gentran:Server Communications service manually when you start the Sterling Gentran:Server Executive service on the Primary System Controller. The Sterling Gentran:Server Communications service is dependent upon the Sterling Gentran:Server Mailbox service.

You may use the services applet in the Microsoft Windows Control Panel to start the Sterling Gentran:Server Communications service.

Reference

See How to Start the Mailbox Service in the *IBM® Sterling Gentran:Server® for Microsoft Windows Communications User Guide* for additional information.

Procedure Use this procedure to start the Sterling Gentran:Server Communications service.

Step	Action
1	Start the Mailbox Server Manager . System Response The system displays the Server Manager browser.
2	Select the Gentran:Server Communications from the Gateway folder.
3	Right-click and select Properties to alter the properties for this gateway. System Response The system displays the Sterling Gentran:Server Communications gateway properties dialog box.
4	Select the communications controller you want to start and click Start . System Response The selected communications controller begins transmitting and receiving queued messages.
5	Repeat Step 4 for each communications controller.
6	Click OK .

How to Stop the Communications Service

Introduction The Sterling Gentran:Server Communications service controls communications sessions between Mailbox Server and your Trading Partners.

The Sterling Gentran:Server Communications service is dependent upon the Sterling Gentran:Server Mailbox service. You may use the services applet in the Microsoft Windows Control Panel to stop the Sterling Gentran:Server Communications service.

Reference

See How to Stop the Mailbox Service in the *IBM® Sterling Gentran:Server® for Microsoft Windows Communications User Guide* for additional information.

When to use Use this procedure when you change the Pool type assigned to a device pool.

Example

You want to change a Pool that has been defined as a Remote Only Pool to be a Host pool. You must stop and restart the Sterling Gentran:Server Communications service before the modems assigned to that Pool can answer incoming calls.

Procedure Use this procedure to stop the Sterling Gentran:Server Communications service.

Step	Action
1	Start the Mailbox Server Manager . System Response The system displays the Server Manager browser.
2	Select Gentran:Server Communications from the Gateway folder.
3	Right-click and select Properties to alter the properties for this gateway. System Response The system displays the Sterling Gentran:Server Communications gateway properties dialog box.
4	Select the communications controller you want to halt, and click Stop . System Response All communications using the selected communications controller ceases.
5	Repeat Step 4 for each communications controller.
6	Click OK .

How to Create Communications Mailboxes

Introduction After you have configured the Sterling Gentran:Server Communications gateway, you must create mailboxes for each trading partner you exchange documents with.


Before you begin Before you begin creating mailboxes for your trading partners you need to have the following pieces of information:

- Trading Partner name
- Trading Partner EDI code or your trading partner's email address

This information is stored in the Sterling Gentran:Server Trading Partner Editor.

Procedure Use this procedure to create mailboxes.

Step	Action
1	Start the Mailbox Server Manager .
2	Select the Mailboxes folder.
3	Right-click the mouse, and select Create . System Response The system displays the Create Mailbox Wizard dialog box.
4	Type the name of the mailbox you are creating and click Next twice. System Response The system displays a dialog asking whether you want to use the mailbox as a gateway to another messaging system.
5	Click Yes, use this mailbox as a gateway .
6	Select Gentran:Server Communications as the type of gateway to use with this mailbox, and click Next . System Response The system displays the Create Mailbox Wizard - Summary dialog box.

(Contd) Step	Action
7	<p>Is the information that you entered correct?</p> <ul style="list-style-type: none"> ▶ If yes, click Finish. ▶ If no, click the Back button to correct the information. <p>System Response The system displays the Gateway Properties dialog box.</p>  <p>Note If you attempt to create a mailbox and the data store is missing, the system generates an error message box informing you that the mailbox cannot be created. Click OK to exit the message box and click Cancel to exit the Create Mailbox Wizard.</p>

(Contd) Step	Action	
8	Use this table to determine your next step.	
	IF you are using...	THEN select...
	asynchronous communications	TAPI from the Transport list.
	bisynchronous communications	BISYNC from the Transport list.
	TCP/IP	SOCKETS from the Transport list.
	File Transfer Protocol	FTP from the Transport list.
	WS_FTP Pro File Transfer Program Note You must install the WS_FTP program before you can begin to use this protocol to transfer messages.	WSFTP from the Transport list.
	ISDN	CAPI from the Transport list.
	Eicon X.25 communications Note You must install the Eicon X.25 hardware and software before you can begin to use this protocol to transfer messages.	EICONX.25 from the Transport list.
9	Click the Properties button and define the Transport properties. System Response The system displays the properties page for the transport type that you selected.	
10	Fill in the fields as necessary, and click OK .	

(Contd) Step	Action
11	<p>Click Script to define the script and variable values.</p> <p>System Response The system displays the Script dialog box.</p> <p>Reference See Script Language Reference in the <i>IBM® Sterling Gentran:Server® for Microsoft Windows Script Language Reference Guide</i> for a description of the script language provided for use with the Sterling Gentran:Server communications subsystem.</p>
12	Click New .
13	<p>Type a unique script name, and click OK.</p> <p>System Response The system displays the Script Editor.</p>
14	<p>Select Import from the File menu.</p> <p>System Response The system displays the Import Script dialog box.</p>
15	<p>Select a script, and click Open.</p> <p>System Response A copy of the script file is loaded into the Script editor.</p>
16	<p>Select Compile from the File menu.</p> <p>System Response The new script is compiled. The system displays a dialog box that shows you that the script compiled with no errors or warnings. You are also prompted to save the changes to the file.</p> <p>Note 1 Contact Product Support if you receive errors during compilation.</p> <p>Note 2 Compiled scripts are stored with the mailbox. The original script files stored in the CommScr folder remain unaltered. This allows you to have multiple copies of the same script available for use with this mailbox.</p>
17	Close the compile dialog box, and click Yes to save the compiled script.
18	<p>Select Exit from the File menu, and click Yes at the prompt to save changes.</p> <p>System Response You are returned to the Script dialog box.</p>

(Contd) Step	Action
19	Select the variable you want to define and type the appropriate value in the value box.
20	<p>Have you entered values for all of the variables for this script?</p> <ul style="list-style-type: none"> ▶ If no, repeat Step 20 for each variable. Click OK to return to the Gateway Properties dialog box. ▶ If yes, click OK to return to the Gateway Properties dialog box.
21	<p>Click Defaults to define the message defaults for this gateway.</p> <p>System Response The system displays the Message Defaults dialog box.</p>
22	Type Application/EDI in the Use this Content Type for all attachments box.
23	Type Application/EDI in the Use this Content Type for all messages box.
24	<p>Click Edit Recipients.</p> <p>System Response The system displays the Edit Recipients dialog box.</p>
25	<p>Select Gentran Application and click To to forward message that you receive to Sterling Gentran:Server.</p> <p>System Response The system displays the EMail Addresses dialog box.</p>
26	<p>Do you want to specify an E-mail address?</p> <ul style="list-style-type: none"> ▶ If yes, type the value in the box. Click Add. Repeat this step for each e-mail address that you want to specify. Click OK to return to the Edit Recipients dialog box. Proceed to the next step. ▶ If no, Click OK to return to the Edit Recipients dialog box. Proceed to the next step.
27	<p>Click OK.</p> <p>System Response You return to the Message Defaults dialog box.</p>
28	<p>Click OK.</p> <p>System Response You return to the Gateway Properties dialog box.</p>

(Contd) Step	Action	
29	Do you want to Auto Send messages? <ul style="list-style-type: none"> ▶ If yes, select the Auto Send check box. Select the Auto Send option that you want. Proceed to the next Step. ▶ If no, proceed to the next Step. 	
30	Are you using Tradanet? <ul style="list-style-type: none"> ▶ If yes, select the Enable Tradanet commands check box. Select the command type that you want to use. Valid options are TSP and TIP. Click Configure. Proceed the next Step. ▶ If no, click OK to save your changes and to exit the Gateway Properties dialog box. 	
31	Use the following table to determine your next Step.	
	If you selected this Tradanet command type...	Then proceed to...
	TSP	<i>How to configure Tradanet TSP properties on page 2 - 52.</i>
	TIP	<i>How to configure Tradanet TIP properties on page 2 - 54.</i>

How to configure Tradanet TSP properties

Use this procedure to configure Tradanet TSP properties.

Step	Action
1	From the Tradanet Properties - Using TSP Commands dialog box, select the syntax you want to use. Recommendation We recommend that you select ANA syntax.
2	Type your EDI number or ANA User ID in the Sender box.
3	Type your Tradanet Network Password in the Password box.
4	To type a new password, type the value in the New Password box.
5	Select when to send LIST commands from the appropriate list. Valid values are: Always, Never, Once.

(Contd) Step	Action
6	<p>Select the DELF tab and complete the DELF dialog box.</p> <p>Recommendation The default number of days for deleting files is 3 days for files that have been extracted. The Tradanet Network charges for storage of entries that are more than 5 days old. We recommend that you delete extracted files that are 3 days old every day.</p>
7	<p>Select the GO/NG tab and complete the GO/NG dialog box.</p>
8	<p>Select the NEWREL tab and complete the NEWREL dialog box.</p> <p>Note Use the NEWREL dialog box only when creating or removing trading relationships on the Tradanet Network.</p>
9	<p>Click Add.</p> <p>System Response The system displays the NewRel - Add dialog box.</p>
10	<p>Select the Direction.</p>
11	<p>Select the Action.</p>
12	<p>Select the Data Type.</p>
13	<p>Select the Trading Partner.</p>
14	<p>Click OK.</p> <p>System Response You return to the Tradanet Properties dialog box.</p>
15	<p>Click OK to save your changes and to return to the Gateway Properties dialog box.</p>
16	<p>Click OK to exit the Gateway Properties dialog box.</p>

How to configure Tradanet TIP properties

Use this procedure to configure Tradanet TIP properties.

Step	Action
1	From the Tradanet Properties - Using TIP Commands dialog box, type your ANA User ID in the Sender ID box.
2	Type your Tradanet Network Password in the Password box. Note Your password is not displayed as you type it. To type a new password, type the value in the New Password box.
3	Select when to send LIST commands from the appropriate list. Valid values are: Always, Never, Once.
4	Select the DELF tab and complete the DELF dialog box. Recommendation The default number of days for deleting files is 3 days for files that have been extracted. The Tradanet Network charges for storage of entries that are more than 5 days old. We recommend that you delete extracted files that are 3 days old every day.
5	Select the GO tab and complete the GO dialog box.
6	Select the NEWREL tab and complete the NEWREL dialog box. Note Use the NEWREL dialog box only when creating or removing trading relationships on the Tradanet Network.
7	Click Add . System Response The system displays the NewRel - Add dialog box.
8	Select the Direction .
9	Select the Action .
10	Select the Data Type .
11	Select the Trading Partner .
12	Click OK . System Response You return to the Tradanet Properties dialog box.
13	Click OK to save your changes and to return to the Gateway Properties dialog box.
14	Click OK to exit the Gateway Properties dialog box.

How to Modify Mailbox Properties

Introduction This section describes how to modify mailbox properties that were created using the Create Mailbox Wizard.

Procedure Use this procedure to modify mailbox properties.

Step	Action	
1	Start the Mailbox Server Manager .	
2	Expand the Mailboxes folder.	
3	Select the mailbox for which you want to add or modify properties.	
4	Right-click and select Properties from the short-cut menu. System Response The system displays the Mailbox Properties dialog box.	
5	Use this table to determine your next step.	
	IF you want to change the mailbox's...	THEN click this tab...
	<ul style="list-style-type: none"> ▶ name ▶ Sterling Gentran:Server E-mail address 	Addressing
	<ul style="list-style-type: none"> ▶ Gateway properties ▶ Configuration properties 	Gateway
	delivery rules	Delivery Rules
	user security permissions	Security
6	Make the appropriate modifications and click OK to save changes and to exit the dialog box.	

Error Messages

Contents

- ▶ Overview A - 2
 - ▶ Communications Gateway Messages A - 3
-

Overview

In this appendix

This appendix describes the messages that this gateway generates. If you are working with the communications subsystem through the Mailbox Server Manager, the user interface displays messages interactively.

Communications Gateway Messages

Introduction This topic provides you with the error messages that the Communications Gateway writes to the Audit Log.

Reference

See Configuring Communications, chapter 2 in this guide, for more information on configuration procedures.

Messages This table describes error messages associated with this gateway.

Msg ID	Message Text	Explanation/Your Action
5	StartServiceCtrlDispatcher failed: [(numeric error code)] [(error message description)].	<p>Explanation This error occurs if the service fails to start.</p> <p>Your Action Contact customer support.</p>
8	OpenSCManager failed: [(numeric error code)] [(error message description)].	<p>Explanation This error occurs when the system is unable to open the service control manager when performing an install or remove service command line function.</p> <p>Your Action Contact customer support.</p>
9	GetModuleFileName failed: [(numeric error code)] [(error message description)].	<p>Explanation This error occurs when an attempt is made to get the module name to perform an install or remove service command line function.</p> <p>Your Action Contact customer support.</p>
10	CreateService [(service name)] failed: [(numeric error code)] [(error message description)].	<p>Explanation This error occurs when calling the CreateService function to perform an install service command line function.</p> <p>Your Action Contact customer support.</p>
11	CLAPIInitialise failed.	<p>Explanation The CLAPI interface used to communicate with the Sterling Gentran:Server system failed to initialize.</p> <p>Your Action Contact customer support.</p>

(Contd)	Message Text	Explanation/Your Action
12	OpenService [(service name)] failed: [(numeric error code)] [(error message description)].	<p>Explanation This error occurs when calling the OpenService function to perform a remove service command line function.</p> <p>Your Action Contact customer support.</p>
13	DeleteService [(service name)] failed: [(numeric error code)] [(error message description)].	<p>Explanation This error occurs when calling the DeleteService function to perform a remove service command line function.</p> <p>Your Action Contact customer support.</p>
15	RegisterServiceCtrlHandler failed: [(numeric error code)] [(error message description)].	<p>Explanation This error occurs if the call to register the service control handler fails in service main.</p> <p>Your Action Contact customer support.</p>
16	RPC failed to connect to Primary Controller.	<p>Explanation This error occurs if an RPC connection to the primary controller could not be established.</p> <p>Your Action Contact customer support.</p>
18	Gentran:Server Communications requires Windows Version 4.0 (Build 1381) or higher.	<p>Explanation An incompatible version of Microsoft Windows was detected.</p> <p>Your Action Install or upgrade to Microsoft Windows 4.0 (Build 1381) or higher with the latest service pack.</p>
50000	[(mailbox function)] failed with code [(error code number)] at line [(line in the code caused the error)].	<p>Explanation This is a generic error message used when calls to mailbox fail.</p> <p>Your Action Contact customer support.</p>

(Contd)	Message Text	Explanation/Your Action
50001	CArchive exception occurred at line [(line in the code that caused the error)].	<p>Explanation This is a generic error message used when a CArchive exception occurs.</p> <p>Your Action Contact customer support.</p>
50002	RpcServerUseProtseqEp (Named Pipe) failed at line [(line in the code that caused the error)]: [(RPC error)].	<p>Explanation This is a generic error message used when calls to the RPC server fail.</p> <p>Your Action Contact customer support.</p>
50003	RpcServerUseProtseqEp (Local) failed at line [(line in the code that caused the error)]: [(RPC error)].	<p>Explanation This is a generic error message used when calls to the RPC server fail.</p> <p>Your Action Contact customer support.</p>
50004	RpcServerInqBindings failed at line [(line in the code that caused the error)]: [(RPC error)].	<p>Explanation This is a generic error message used when calls to the RPC server fail.</p> <p>Your Action Contact customer support.</p>
50005	UuidFromString failed at line [(line in the code that caused the error)]: [(RPC error)].	<p>Explanation This is a generic error message used when calls to the RPC server fail.</p> <p>Your Action Contact customer support.</p>
50006	RpcEpRegister failed at line [(line in the code that caused the error)]: [(RPC error)].	<p>Explanation This is a generic error message used when calls to the RPC server fail.</p> <p>Your Action Contact customer support.</p>
50007	RpcBindingVectorFree failed at line [(line in the code that caused the error)]: [(RPC error)].	<p>Explanation This is a generic error message used when calls to the RPC server fail.</p> <p>Your Action Contact customer support.</p>

(Contd)	Message Text	Explanation/Your Action
50008	RpcServerRegisterIf failed at line [(line in the code that caused the error)]: [(RPC error)].	<p>Explanation This is a generic error message used when calls to the RPC server fail.</p> <p>Your Action Contact customer support.</p>
50009	RpcStringBindingCompose failed at line [(line in the code that caused the error)]: [(RPC error)].	<p>Explanation This is a generic error message used when calls to the RPC server fail.</p> <p>Your Action Contact customer support.</p>
50010	RpcBindingFromStringBinding failed at line [(line in the code that caused the error)]: [(RPC error)].	<p>Explanation This is a generic error message used when calls to the RPC server fail.</p> <p>Your Action Contact customer support.</p>
50011	RpcException occurred at line [(line in the code that caused the error)]: [(RPC error)].	<p>Explanation This is a generic error message used when calls to the RPC server fail.</p> <p>Your Action Contact customer support.</p>
50012	Invalid device pool version.	<p>Explanation This error occurs if the version of the device pool information is incompatible with the version of software that you are running.</p> <p>Your Action Delete and rebuild your device pool.</p>
50013	CreateThread [(thread name)] failed at line [(line in the code caused the error)]: [(numeric error code)] [(error message description)].	<p>Explanation This is a generic error message used when calling the CreateThread function.</p> <p>Your Action Contact customer support.</p>
50014	CreateEvent [(event name)] failed at line [(line in the code caused the error)]: [(numeric error code)] [(error message description)].	<p>Explanation This is a generic error message used when calling the CreateEvent function.</p> <p>Your Action Contact customer support.</p>

(Contd)	Message Text	Explanation/Your Action
50015	SetCurrentDirectory [(directory name)] failed at line [(line in the code caused the error)]: [(numeric error code)] [(error message description)].	<p>Explanation This is a generic error message used when calling the SetCurrentDirectory function.</p> <p>Your Action Contact customer support.</p>
50016	CreateFile [(file name)] failed at line [(line in the code caused the error)]: [(numeric error code)] [(error message description)].	<p>Explanation This is a generic error message used when calling the CreateFile function.</p> <p>Your Action Contact customer support.</p>
50017	ReadFile [(file name)] failed at line [(line in the code caused the error)]: [(numeric error code)] [(error message description)].	<p>Explanation This is a generic error message used when calling the ReadFile function.</p> <p>Your Action Contact customer support.</p>
50018	WaitForObject failed at line [(line in the code caused the error)]: [(numeric error code)] [(error message description)].	<p>Explanation This is a generic error message used when calling the WaitForObject function.</p> <p>Your Action Contact customer support.</p>
50019	RpcMgmtIsServerListening failed at line [(line in the code caused the error)]: [(RPC error)].	<p>Explanation This is a generic error message used when calls to the RPC server fail.</p> <p>Your Action Contact customer support.</p>
50020	RpcServerUnregisterIf failed at line [(line in the code caused the error)]: [(RPC error)].	<p>Explanation This is a generic error message used when calls to the RPC server fail.</p> <p>Your Action Contact customer support.</p>
50021	RpcEpUnregister failed at line [(line in the code caused the error)]: [(RPC error)].	<p>Explanation This is a generic error message used when calls to the RPC server fail.</p> <p>Your Action Contact customer support.</p>

(Contd)	Message Text	Explanation/Your Action
50022	RpcMgmtStopServerListening failed at line [(line in the code caused the error)]: [(RPC error)].	Explanation This is a generic error message used when calls to the RPC server fail. Your Action Contact customer support.
50023	RpcServerListen failed at line [(line in the code caused the error)]: [(RPC error)].	Explanation This is a generic error message used when calls to the RPC server fail. Your Action Contact customer support.

Working with OFTP

Contents

- ▶ Overview B - 2
 - ▶ Defining the SSID and SFID Commands B - 3
 - ▶ How to Create a Partner Definition (OFTP Remote VAN Users) B - 4
 - ▶ Defining the Virtual Filename and Data Format. B - 6
-

Overview

Introduction

This topic contains some special instructions when working with OFTP (Odette File Transfer Protocol).

Defining the SSID and SFID Commands

Introduction

The OFTP protocol uses the SSID and SFID commands to control the flow of data during an OFTP communications session. These commands are created dynamically by Mailbox Server at the start of a communications session. Mailbox Server uses the values you assign to the communications script to create the SSID and SFID commands.

Script variables

You must assign values to the following script variables when you create the Communications Gateway mailbox:

- The sender's OFTP ID - This is the sender's OFTP code (SSID).
- The sender's OFTP Password.
- The sender's new OFTP Password, if he or she is changing the password.

Sample OFTP Remote.script

OFTP Remote.script is a sample script that you can use when sending or receiving data by means of the OFTP protocol.

This script is installed when Sterling Gentran:Server is installed. The default file location is: GENSRVNT\CommScr\Samples.

Script Example

This is an example of the Sample OFTP Remote.script that is installed with Sterling Gentran:Server.

```
// Sample OFTP Remote Script

// define user editable variables
scriptvar string[10] MailboxID;
scriptvar string[10] MailboxPassword;
string[80] LogonCard;
LogonCard = "LOGON MBX=" + MailboxID + " PSW=" + MailboxPassword
+ "^OD";

// logon procedure
AsciiSndCtl(LogonCard);
AsciiRcvCtl("LODETTE FTP_READY ^OD");
OftpRemote("OFTPID", "OFTP PSW", "");
SetStatus(SUCCESS);
```

OFTPID = The sender's OFTP code (SSID)

OFTP PSW = The sender's OFTP password

Related Documentation

See OftpRemote in the *IBM® Sterling Gentran:Server® for Microsoft Windows Script Language Reference Guide* for additional information.

How to Create a Partner Definition (OFTP Remote VAN Users)

Introduction

This section describes how to create a new partner definition for use when sending data using the OFTP protocol.

When sending data using the OFTP protocol, you must define the recipient's OFTP ID (also known as SFID) in the Email address in the Sterling Gentran:Server Partner Definition.

Reference

See the Partner Editor topic in the Sterling Gentran:Server online help file for more information on creating new Partner Definitions.

Before you begin


Before you begin this procedure, verify that you have the following information:

- Your trading partner's OFTP SFID. This is typically your trading partner's Mailbox ID
- Your trading partner's application code.

Procedure

Use this procedure to create a new partner definition for use with OFTP.

Step	Action
1	In Sterling Gentran:Server, select Partners from the appropriate area of The Desk. System Response The system displays the Partner Editor dialog box.
2	Click New .

(Contd) Step	Action
3	<p>Complete the following:</p> <ul style="list-style-type: none"> ▶ Profile ID: Enter your trading partner's internal system identification information. ▶ Name: Enter the name of how you want Sterling Gentran:Server Partner Editor to identify your trading partner. ▶ EDI Code: Enter your trading partner's EDI code (SFID). ▶ Application Code: Enter your trading partner's application code (outbound). ▶ Mailbox: From the drop-down list, select the appropriate Mailbox Server mailbox. ▶ E-mail Address: Enter your trading partner's SFID code. <p>System Response Your Partner Definition - New dialog box should look similar to the following.</p> 
4	Click Save .
5	Click Exit to exit the dialog box.

Defining the Virtual Filename and Data Format

Introduction

You can use the content type of the message attachment to:

- override the OFTP filename being created on the remote OFTP machine.
 - define the data format.
-

Procedure

Use this procedure to define the virtual filename or data format.

Step	Action
1	Select Partners from The Desk. System Response The system displays the Partner Editor dialog box.
2	Select your Partner, and click Outbound .
3	From the Relationship description drop-down list, select the outbound relationship.
4	Click Interchanges .
5	Select the outbound interchange and click Edit . System Response The system displays the Outbound Interchange Entry dialog box.
6	Click Advanced .

(Contd) Step	Action
7	<p>To override the filename, enter FileName_xx in the Content Type box. where: xx is the filename you want to create on the remote OFTP machine.</p> <p>To specify a data format, enter DataFormat_xx in the Content Type box. where: xx is the data format.</p> <p>To specify both, enter FileName_xx/DataFormat_xx.</p> <p>Note The Content Type field value is in the form of Content type/Content Sub Type. The Content type is a mandatory value, which must be followed by a forward slash (/). A Sub Content Type value must be preceded by a Content Type and a forward slash (/).</p> <p>Example FileName_out161/ or DataFormat_v/FileName_xx</p>
8	Click Save to return to the Outbound Interchange Select dialog box.
9	Click Exit to return to the Outbound Relationship dialog box.
10	Click Save .
11	Click Exit twice to return to The Desk.

Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing

IBM Corporation

North Castle Drive

Armonk, NY 10504-1785

U.S.A.

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual

Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing

Legal and Intellectual Property Law

IBM Japan Ltd.

1623-14, Shimotsuruma, Yamato-shi

Kanagawa 242-8502 Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation

J46A/G4

555 Bailey Avenue

San Jose, CA__95141-1003

U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems.

Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information is for planning purposes only. The information herein is subject to change before the products described become available. This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work, must include a copyright notice as follows:

© IBM 2011. Portions of this code are derived from IBM Corp. Sample Programs.
© Copyright IBM Corp. 2011.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

Trademarks

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "[Copyright and trademark information](http://www.ibm.com/legal/copytrade.shtml)" at www.ibm.com/legal/copytrade.shtml.

Adobe, the Adobe logo, PostScript, and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

IT Infrastructure Library is a registered trademark of the Central Computer and Telecommunications Agency which is now part of the Office of Government Commerce.

Intel, Intel logo, Intel Inside, Intel Inside logo, Intel Centrino, Intel Centrino logo, Celeron, Intel Xeon, Intel SpeedStep, Itanium, and Pentium are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

ITIL is a registered trademark, and a registered community trademark of the Office of Government Commerce, and is registered in the U.S. Patent and Trademark Office.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Cell Broadband Engine is a trademark of Sony Computer Entertainment, Inc. in the United States, other countries, or both and is used under license therefrom.

Linear Tape-Open, LTO, the LTO Logo, Ultrium and the Ultrium Logo are trademarks of HP, IBM Corp. and Quantum in the U.S. and other countries.

Connect Control Center®, Connect:Direct®, Connect:Enterprise, Gentran®, Gentran:Basic®, Gentran:Control®, Gentran:Director®, Gentran:Plus®, Gentran:Realtime®, Gentran:Server®, Gentran:Viewpoint®, Sterling Commerce™, Sterling Information Broker®, and Sterling Integrator® are trademarks or registered trademarks of Sterling Commerce, Inc., an IBM Company.

Other company, product, and service names may be trademarks or service marks of others.
