

IBM Sterling Connect:Direct for z/OS



Facilities Guide

Version 5.2

IBM Sterling Connect:Direct for z/OS



Facilities Guide

Version 5.2

Note

Before using this information and the product it supports, read the information in "Notices" on page 101.

This edition applies to Version 5 Release 2 of IBM Sterling Connect:Direct and to all subsequent releases and modifications until otherwise indicated in new editions.

© **Copyright IBM Corporation 1999, 2014.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Chapter 1. IBM Sterling Connect:Direct for z/OS Facilities Overview 1

Chapter 2. ARS Report Examples 3

IBM Sterling Connect:Direct for z/OS Activity Report	3
IBM Sterling Connect:Direct for z/OS Summary Report	4
IBM Sterling Connect:Direct Exception Report	6
Security Violations Report	8
Sterling Connect:Direct for z/OS Function Reports	9
IBM Sterling Connect:Direct for z/OS Non-PDS Copy Report	9
IBM Sterling Connect:Direct for z/OS PDS Copy Report	11
IBM Sterling Connect:Direct for z/OS Run Job Report	12
Run Task Report	13
IBM Sterling Connect:Direct for z/OS Submit Within a Process Report	14

Chapter 3. Activity Reporting System 17

ARS and Sterling Connect:Direct	17
Business Solutions Using ARS	18

Chapter 4. Requesting ARS Statistical Reports 19

Requesting Reports Using ARS Screens	19
ARS Connect:Direct Requirements Screen	22
ARS SAS Requirements Screen and Fields	23
Job Streams Created	24
Running the Job	25

Chapter 5. Requesting Multiple ARS Reports or Scheduled Processing 27

Modifying the Sample Job Stream	27
Job Stream Definitions	28
Sample Sterling Connect:Direct Process That Submits Job Stream	29
Multiple Reports to an Output Data Set	30

Chapter 6. ARS Record Layouts 31

Description of an SAS Variable	32
Authorization Event Record	32
Change Process Termination Record	33
Copy Termination Record	34
Delete Process Termination Record	36
Display Statistics Record	36
Flush/Suspend Process Termination Record	37
PDS Member Copy Record	38
Process Submit Statistics Record	38
Process Termination Record	39
Run Job Termination Record	40
Run Task Termination Record	41
Signon/Signoff Statistics Record	42

Start Sterling Connect:Direct Command Record	42
Stop Sterling Connect:Direct Statistics Record	43
Write to Operator (WTO) Statistics Record	43

Chapter 7. The Operator Interface 45

Sample Sterling Connect:Direct for z/OS CLISTs	45
Rules for Setting Up Sterling Connect:Direct for z/OS CLISTs	46
Sterling Connect:Direct for z/OS Commands	47
CLIST Examples	47
Operation Messages	49
Stopping Sterling Connect:Direct	50
Stopping a Sterling Connect:Direct/Plex Manager and All Servers	50
Stopping an Individual Sterling Connect:Direct/Plex Server	50
About Tape Mount Messages	50
Tape Pre-mount Message	51
Tape Mount Messages	51
Setting Up Sterling Connect:Direct for z/OS Tape Pre-mount Messages	51
Setting Up Sterling Connect:Direct for z/OS Tape Mount Messages	51
Sterling Connect:Direct for z/OS Tape Pre-mount Messages	52
Sterling Connect:Direct for z/OS Tape Mount Messages	52
Tape Device Allocation	52
Terminating the Tape Mount	53
Verifying Volume Requests	53
Handling Multivolume Files	53
Sterling Connect:Direct for z/OS Messages on 3480 Display	53

Chapter 8. Event Services Support. 55

ESS Concepts and Components	55
Event Services Support Architecture	56
ESS Data Flow Using CICS API	58
Deciding What Event Data to Collect	59
ESS Event Record Examples	59
Using ESS with the CICS API	61
Using ESS with the ESS User Exit	61
Using the ESS Exit	62
Issuing Event Services Commands	62
CICS ESS Customization	70
Event Services Record Descriptions	75

Chapter 9. Spool Transfer Facility 79

Spool Transfer Components	79
VTAM Printer Support	80
Sterling Connect:Direct API	81
Process Names	82
Sample Process to Display Attributes in the SUBMIT Statement	83
DGAPGNER Job	86

Symbolic Definitions	88
Customizing VPSSCDI.	89

Chapter 10. Transferring Data to the JES Reader or Spool. 91

Output to the JES Reader.	91
Examples of JCL Output	91
Output to JES Spool Files.	92
Sterling Connect:Direct Banners	92

Sterling Connect:Direct COPY Process	93
COPY TO Syntax to Support Spool Transfer	95
Symbolic Definitions for the SYSOUT Keyword	95
Sample Process for SYSOUT.	98

Notices 101

Index 105

Chapter 1. IBM Sterling Connect:Direct for z/OS Facilities Overview

IBM® Sterling Connect:Direct® for z/OS® links technologies and moves information between networked systems and computers. It manages high-performance transfers by providing:

- Automation
- Reliability
- Efficient use of resources
- Application integration
- Ease of use

Note: Examples and source are mentioned in this document. Make any modifications and customizations in a site private PDS and not in an SMP/E target PDS, unless you make them via a USERMOD.

Sterling Connect:Direct offers choices in communications protocols, hardware platforms, and operating systems. It provides the flexibility to move information among mainframes, midrange systems, desktop systems, and LAN-based workstations.

The following facilities are provided to fill specific needs:

- The Activity Reporting System (ARS) works with Sterling Connect:Direct for z/OS to produce reports of Sterling Connect:Direct activity using the SAS System.
- The Console Operator interface enables you to issue all Sterling Connect:Direct for z/OS commands from a z/OS console by using a MODIFY command.
- Event Services Support (ESS) generates events asynchronously in Sterling Connect:Direct and can be used by external management and automated operations applications that require real-time notification of Sterling Connect:Direct activities.
- The Spool Transfer facility enables you to transfer Job Entry Subsystem (JES) spool files by copying from JES spool files, to JES print queues, and to JES reader queues.

Chapter 2. ARS Report Examples

IBM Sterling Connect:Direct for z/OS Activity Report

You can request reports in the following ways:

- Through ARS screens using TSO/ISPF
- Through a Sterling Connect:Direct Process that is defined to automatically request reports
- Through a pre-defined batch job stream that is run by a job scheduling subsystem

The IBM Sterling Connect:Direct for z/OS Activity Report lists Sterling Connect:Direct activity by Process step. The ARS software sorts the steps for each secondary node (SNODE) location by user ID and then by Process number, for a specified time period.

You can specify the start date and time and the stop date and time. Following is an example of the IBM Sterling Connect:Direct for z/OS Activity Report:

Connect:Direct ACTIVITY REPORT (ARS00001) 17:12 WEDNESDAY, JUNE 24, 2010 1										
NODE = CD.BOSTON										
USERID	PROC #	PROC NAME	STEP NAME	FUNCTION	ELAPSE TIME	PNODE	CC	EXC	MSG ID	DATE
-----SNODE=CD.BOSTON-----										
ALPHA	46	COPY1	STEP01	COPY	0:00:01.89	CD.BOSTON	00000000		SCFA0001	06/17/2010
ALLEN	63	COPY2	STEP01	COPY	0:00:02.08	CD.CHICAGO	00000000		SRFA0001	06/17/2010
BETA	87	RUNJOB	LAB	RUNJOB	0:00:01.26	CD.CHICAGO	00000000		SRJA0001	06/17/2010
ETERN	89	RUNJOB	SUBSTEP	RUNJOB	0:00:00.68	CD.JERSEY	00000000		SRJA0001	06/17/2010
LEWIS	9	RUNT	STEP1	RUNTASK	0:00:00.11	CD.JERSEY	00000000		SRTA0001	06/17/2010
LOUIS	95	SUB	SUBSTEP	SUBMIT	0:00:01.34	CD.JERSEY	00000008		SSUB001	06/17/2010
MULLEN	96	COPY05	STEP1	COPY	0:00:01.57	CD.MIAMI	80013000		SCFA0001	06/17/2010
WARD	99	COPY05	STEP1	COPY	0:00:02.06	CD.MIAMI	80806000		SCFA0001	06/17/2010
WARREN	379	SUB	SUBSTEP	SUBMIT	0:00:00.86	CD.MIAMI	00000008	***	SSUB0051	06/17/2010
-----SNODE=CD.JERSEY-----										
JONES	544	RUNT	STEP1	RUNTASK	0:00:00.18	CD.BOSTON	80806000	***	SRTA0041	06/18/2010
-----SNODE=CD.MIAMI-----										
USERID	PROC #	PROC NAME	STEP NAME	FUNCTION	ELAPSE TIME	PNODE	CC	EXC	MSG ID	DATE
ALLEN	413	COPY05	COPY01	COPY	0:00:06.96	CD.BOSTON	00000000		SCFA0001	06/17/2010
ALLEN	414	RUNTASK	LABRNJ2	RUNJOB	0:00:01.18	CD.BOSTON	00000000		SRJA0001	06/17/2010
BURNS	416	RUNT	STEP1	RUNTASK	0:00:00.28	CD.BOSTON	00000000		SRTA0001	06/17/2010
BURNS	418	SUB	SUBSTEP	SUBMIT	0:00:01.79	CD.BOSTON	00000000		SSUB0001	06/17/2010
GEORGE	420	FDSCOPY	COPY01	COPY	0:00:05.42	CD.BOSTON	00000000		SCFA0001	06/17/2010
JONES	421	FDSCOPY	COPY01	COPY	0:00:03.21	CD.BOSTON	00000008	***	SIES0781	06/17/2010
LISA	422	RUNJOB	LABRNJ2	RUNJOB	0:00:00.34	CD.BOSTON	80013000	***	SVGS0101	06/17/2010
MILLER	423	RUNT	STEP1	RUNTASK	0:00:00.15	CD.BOSTON	80806000	***	SRTA0041	06/17/2010
RYAN	426	SUB	SUBSTEP	SUBMIT	0:00:00.68	CD.BOSTON	00000008	***	SSUB0051	06/17/2010
RYAN	427	RUNJOB	LABRNJ2	RUNJOB	0:00:00.39	CD.BOSTON	80013000	***	SVGS0101	06/19/2010
RYAN	428	RUNJOB	LABRNJ2	RUNJOB	0:00:01.54	CD.BOSTON	00000000	***	SRJA0001	06/19/2010
RYAN	429	RUNLO	STEP1	RUNTASK	0:00:00.25	CD.BOSTON	80806000	***	SRTA0041	06/19/2010
SMITH	430	RUNZ0	STEP1	RUNTASK	0:00:00.09	CD.BOSTON	00000000	***	SRTA0001	06/19/2010
SMITH	431	SUBACT	SUBSTEP	SUBMIT	0:00:01.19	CD.BOSTON	00000004	***	SEFA0161	06/19/2010
TURNER	432	SUBSTAT	SUBSTEP	SUBMIT	0:00:01.89	CD.BOSTON	00000008	***	SFG00021	06/19/2010
WARREN	433	SUBSALE	SUBSTEP	SUBMIT	0:00:02.47	CD.BOSTON	00000000	***	SSUB0001	06/19/2010

The following table contains a description of the report fields.

Report Field	Description
NODE	Sterling Connect:Direct node where the statistics file is being examined.
SNODE	Sterling Connect:Direct secondary node.
USERID	Sterling Connect:Direct user ID.
PROC #	Sterling Connect:Direct Process number.
PROC NAME	Sterling Connect:Direct Process name.
STEP NAME	Name (or label) assigned to the Process step.
FUNCTION	Sterling Connect:Direct activity. Valid Process steps are COPY, RUN JOB, RUN TASK, and SUBMIT (within a Process).
ELAPSE TIME	Function duration time in hh:mm:ss.hh format.
PNODE	Sterling Connect:Direct primary node.

Report Field	Description
CC	Sterling Connect:Direct completion code in hexadecimal format.
EXC	Exception field is displayed "****" when a Process step does not complete successfully.
MSG ID	Sterling Connect:Direct message ID.
DATE	When activity began. Date format is mm/dd/yyyy. Process start date does not conform to the DATEFORM initialization parameter.

IBM Sterling Connect:Direct for z/OS Summary Report

The IBM Sterling Connect:Direct for z/OS Summary Report summarizes activity for the node where the statistics file are examined. The report categorizes Sterling Connect:Direct activity by SNODE for a specified time period and a summary for all SNODEs.

Information includes:

- Total Process steps run
- Total COPY steps run
- Total RUN JOB steps run, and RUN JOB steps submitted at this node
- Total RUN TASK steps run, RUN TASK steps executed at this node
- Total SUBMIT (within a Process) steps run and number of Processes submitted at this node
- Number of successful steps and unsuccessful steps
- Total bytes tested, written, sent, and received by this node
- Total elapsed time for all Process steps in this time period
- Average time to complete a Process step
- Total elapsed time for all COPY steps
- Average time to complete a COPY step
- Effective send and receive rates

You can specify the start date and time and the stop date and time.

Following is an example of the IBM Sterling Connect:Direct for z/OS Summary Report

```

-----IBM Sterling Connect:Direct for z/OS Summary Report
0 SNODE = SC.DUB.MWATL1
- FIRST FUNCTION BEGAN EXECUTING ON 02/25/2011 AT 12:40:41.51
- LAST FUNCTION FINISHED EXECUTING ON 02/25/2011 AT 12:44:27.90
-
- 18 PROCESS STEPS WERE COMPLETED FOR THIS TIME PERIOD.
-
- 6 TOTAL COPY STEPS OR 33.3 % OF TOTAL STEPS RUN WERE COPIES
- 1 TOTAL RUNJOB STEPS OR 5.6 % OF TOTAL STEPS RUN WERE RUNJOBS
0 1 RUNJOBS WERE SUBMITTED ON SC.DUB.MWATL1
-
- 4 TOTAL RUNTASK STEPS OR 22.2 % OF TOTAL STEPS RUN WERE RUNTASKS
0 4 RUNTASKS WERE ATTACHED ON SC.DUB.MWATL1
-
- 7 TOTAL SUBMIT STEPS OR 38.9 % OF TOTAL STEPS RUN WERE SUBMITS
0 7 SUBMITS (WITHIN A PROCESS) ON SC.DUB.MWATL1
-
- 14 SUCCESSFUL STEPS OR 77.8 % OF TOTAL STEPS RUN COMPLETED WITH A ZERO RETURN CODE
0 4 UNSUCCESSFUL STEPS OR 22.2 % OF TOTAL STEPS RUN COMPLETED WITH A NON-ZERO RETURN CODE
1

IBM Sterling Connect:Direct for z/OS Summary Report
0 SNODE = SC.DUB.MWATL1
-
0 183,726,180 TOTAL BYTES WERE READ
0 143,315,988 TOTAL BYTES WERE SENT
0 0 TOTAL BYTES WERE WRITTEN
0 0 TOTAL BYTES WERE RECEIVED
-
0 0:00:47.82 WAS THE TOTAL "FUNCTION" TIME (SPENT PERFORMING FUNCTIONS)
- 0:00:02.66 WAS THE AVERAGE TIME TO COMPLETE A FUNCTION
- 0:00:47.38 WAS THE TOTAL "COPY" TIME (SPENT TRANSFERRING DATA)
- 0:00:07.90 WAS THE AVERAGE TIME TO COMPLETE A COPY
-
1514808.033 BYTES/SECOND = EFFECTIVE SEND RATE
0 BYTES/SECOND = EFFECTIVE RECEIVE RATE

```

The following table contains a description of the report fields.

Report Field	Description
NODE	Node where the statistics file is being examined.
SNODE	Sterling Connect:Direct secondary node.
FIRST FUNCTION	Actual date/time that first Process step began executing during specified time period. Includes any step that started before specified time, but is under way or completes during the time period.
LAST FUNCTION	Actual date/time last Process step finished executing during specified time period. If a step started during specified time period but ended after requested stop time or stop date, it is not included in this report.
PROCESS STEPS COMPLETED	Total number of Process steps completed in time period.
TOTAL COPY STEPS	Total number of COPY steps run.
% TOTAL STEPS RUN WERE COPIES	Percentage of total steps run that are COPY steps.
TOTAL RUNJOB STEPS	Total number of RUN JOB steps run.
% TOTAL STEPS RUN WERE RUNJOB	Percentage of total steps run that are RUN JOB steps.
# RUNJOBS SUBMITTED	Number of RUN JOB steps submitted to run at "NODE."
TOTAL RUNTASK STEPS	Total RUN TASK steps run.
% TOTAL STEPS RUN WERE RUNTASKS	Percentage of total steps run that are RUN TASK steps.
# RUNTASKS ATTACHED	Number of RUN TASK steps that are attached on "NODE."
TOTAL SUBMIT STEPS	Total number of SUBMIT steps run.
% TOTAL STEPS RUN WERE SUBMITS	Percentage of total steps run that are SUBMIT (within a Process) steps.
# SUBMITS (WITHIN A PROCESS)	Number of SUBMIT (within a Process) steps submitted to run at "NODE."
SUCCESSFUL STEPS	Total number of successful steps.

Report Field	Description
% OF TOTAL STEPS RUN WITH ZERO RETURN CODE	Percentage of total successful steps.
UNSUCCESSFUL STEPS	Total number of unsuccessful steps.
% OF TOTAL STEPS RUN WITH NON-ZERO RET CD	Percentage of total unsuccessful steps.
TOTAL BYTES WERE READ	Total number of bytes read by "NODE."
TOTAL BYTES WERE SENT	Total number of bytes sent by "NODE."
TOTAL BYTES WERE WRITTEN	Total number of bytes written by "NODE."
TOTAL BYTES WERE RECEIVED	Total number of bytes received by "NODE."
WAS TOTAL "FUNCTION" TIME	Sum of elapsed times of all individual Process steps. The elapsed time for this calculation is the time period between when the step started and when the step completed.
WAS AVERAGE TIME TO COMPLETE A FUNCTION	Total function time divided by number of Process steps run.
WAS TOTAL "COPY" TIME	Sum of elapsed times for all individual COPY steps. The elapsed time for this calculation is the time period between when the step started and when the step completed.
WAS AVERAGE TIME TO COMPLETE A COPY	Total COPY time divided by the total number of COPY steps run.
EFFECTIVE SEND RATE	Total bytes sent divided by elapsed time. For this calculation, the elapsed time is the time between when the first COPY step in the data set began and the last COPY step in the data set completed.
EFFECTIVE RECEIVE RATE	Total bytes received divided by elapsed time. For this calculation, the elapsed time is the time between when the first COPY step in the data set began and the last COPY step in the data set completed.

IBM Sterling Connect:Direct Exception Report

The IBM Sterling Connect:Direct Exception Report lists Process steps that did not complete successfully. The ARS software sorts Process steps by SNODE, by user ID, and by Process number. The report displays information unique to the executed Process step. For example, information displayed for a failed COPY step differs from that of a failed RUN TASK step. A summary of exception cases is listed at the end of the report.

```

-----
IBM Sterling Connect:Direct for z/OS Exception Report
NODE = SC.DUB.MRATL1
EXCEPTION INFORMATION
*****
- USERID   PROC #   PROC NAME  STEP NAME  ** NON-PDS COPY **
- MRATL1   2       OS9901     STEP01
02/25/2011 PNODE = SC.DUB.MRATL1  SNODE = SC.DUB.MRATL1
COMPLETION CODE = 0000000C  MSG ID = SCPA6461E
SENDING NODE ==> SC.DUB.MRATL1
SRC DSNAME ==> DEVST02.HOST.DMDSU1.TSTFILE
RECEIVING NODE ==> SC.DUB.MRATL1
DEST DSNAME ==> MRATL1.SMSTEST.HOST.DMDSU1.A9A0669E
PROCESS HAS BEEN SUSPENDED BY USER/OPERATOR REQUEST.

-----
-1
MRATL1 2 OS9901 STEP01 ** NON-PDS COPY **
02/25/2011 PNODE = SC.DUB.MRATL1  SNODE = SC.DUB.MRATL1
COMPLETION CODE = 0000000C  MSG ID = SCPA6461E
SENDING NODE ==> SC.DUB.MRATL1
SRC DSNAME ==> DEVST02.HOST.DMDSU1.TSTFILE
RECEIVING NODE ==> SC.DUB.MRATL1
DEST DSNAME ==> MRATL1.SMSTEST.HOST.DMDSU1.A9A0669E
PROCESS HAS BEEN SUSPENDED BY USER/OPERATOR REQUEST.

-----
-1
MRATL1 4 PDS STEP01 ** PDS COPY **
02/25/2011 PNODE = SC.DUB.MRATL1  SNODE = SC.DUB.MRATL1
COMPLETION CODE = 00000000  MSG ID = SVP60161E
SENDING NODE ==> SC.DUB.MRATL1
SRC DSNAME ==> MRATL1.JCL.LIB
RECEIVING NODE ==> SC.DUB.MRATL1
DEST DSNAME ==> MRATL1.JCL.LIB
PDS ERROR - DIRECTORY FULL/NON-EXISTENT MEMBER/WRONG DSOBG.

-----
-1
MRATL1 4 PDS STEP01 ** PDS COPY **
02/25/2011 PNODE = SC.DUB.MRATL1  SNODE = SC.DUB.MRATL1
COMPLETION CODE = 00000004  MSG ID = SCPA6001E
SENDING NODE ==> SC.DUB.MRATL1
SRC DSNAME ==> MRATL1.JCL.LIB
RECEIVING NODE ==> SC.DUB.MRATL1
DEST DSNAME ==> MRATL1.JCL.LIB
COPY STEP SUCCESSFUL.

-----
-1

1E
IBM Sterling Connect:Direct for z/OS Exception Report
NODE = SC.DUB.MRATL1

SUMMARY INFORMATION
*****
-1
4 NON-SUCCESSFUL STEPS IN 18 PROCESS STEPS RUN CR
0--> 22.2 % OF TOTAL PROCESS STEPS RUN COMPLETED WITH A NON-ZERO RETURN CODE
-1
04 NON-SUCCESSFUL COPIES IN 6 COPY STEPS RUN CR
0--> 66.7 % OF TOTAL COPY STEPS RUN COMPLETED WITH A NON-ZERO RETURN CODE
-1
00 NON-SUCCESSFUL RUNJOBS IN 1 RUNJOB STEPS RUN CR
0--> 0 % OF TOTAL RUNJOB STEPS RUN COMPLETED WITH A NON-ZERO RETURN CODE
-1
00 NON-SUCCESSFUL RINTASKS IN 4 RINTASK STEPS RUN CR
0--> 0 % OF TOTAL RINTASK STEPS RUN COMPLETED WITH A NON-ZERO RETURN CODE
-1
-----

```

You specify the start date and time and stop date and time. Following are the report fields.

Report Field	Description
NODE	Sterling Connect:Direct node where the statistics file is being examined.
USERID	Sterling Connect:Direct user ID.
PROC #	Sterling Connect:Direct Process number.
PROC NAME	Sterling Connect:Direct Process name.
STEP NAME	Name (or label) assigned to the Process step.
function type	Sterling Connect:Direct activity. Valid Process steps are PDS COPY, NONPDS COPY, RUN JOB, RUN TASK, and SUBMIT (within a Process).
mm/dd/yyyy	Data Process step began executing.
PNODE	Sterling Connect:Direct primary node.
SNODE	Sterling Connect:Direct secondary node.
COMPLETION CODE	Sterling Connect:Direct completion code in hexadecimal format.
MSG ID	Sterling Connect:Direct message ID.
SENDING NODE	(COPY) Sending Sterling Connect:Direct node location name.
SRC DSNAME	(COPY) Source data set name.
RECEIVING NODE	(COPY) Receiving Sterling Connect:Direct node location name.
DEST DSNAME	(COPY) Destination data set name.
DATASET CONTAINING JOB	(RUNJOB) Data set containing job.

Report Field	Description
INTENDED NODE FOR JOB SUBMISSION	(RUNJOB) Intended node location where the job is submitted.
PROGRAM NAME	(RUNTASK) Program name.
INTENDED NODE FOR PROGRAM EXECUTION	(RUNTASK) Intended attach node where the program is run.
DATASET CONTAINING PROCESS	(SUBMIT) Data set containing Process.
INTENDED NODE FOR PROCESS SUBMISSION	(SUBMIT) Intended node location where the Process is submitted.
message	Error message for Sterling Connect:Direct message ID.
NON-SUCCESSFUL STEPS	Total number of unsuccessful Process steps.
PROCESS STEPS RUN	Total number of Process steps run.
% TOTAL PROCESS STEPS WITH NON-ZERO CODE	Percentage of Process steps unsuccessful.
NON-SUCCESSFUL COPIES	Number of unsuccessful COPY steps.
COPY STEPS RUN	Total number of COPY steps run.
% TOTAL RUN JOB STEPS WITH NON-ZERO CODE	Percentage of RUN JOB steps unsuccessful.
NON-SUCCESSFUL RUNTASKS	Number of unsuccessful RUN TASK steps.
RUNTASK STEPS RUN	Total number of RUN TASK steps run.
% TOTAL RUNTASK STEPS WITH NON-ZERO CODE	Percentage of RUN TASK steps unsuccessful.
NON-SUCCESSFUL SUBMITS	Number of unsuccessful SUBMIT (within a Process) steps.
SUBMIT STEPS RUN	Total number of SUBMIT (within a Process) steps run.
% TOTAL SUBMIT STEPS WITH NON-ZERO CODE	Percentage of SUBMIT (within a Process) steps unsuccessful.

Security Violations Report

The IBM Sterling Connect:Direct for z/OS Security Violations Report lists the following types of violations for a specified time period:

Signon security failures—Failure caused by an invalid user ID or password that signed on to Sterling Connect:Direct. Each violation is recorded.

Process security failures—This failure is caused when a Process does not run due to an invalid security authorization. An example is a Process that does not run because the user is not defined in the Sterling Connect:Direct authorization file at the remote node.

Data set access security failures—Failure due to insufficient authority to access a data set.

A sample report follows:

1	IBM Sterling Connect:Direct Security Violations Report					2
	NODE = SC.DUB.MWATL1		13:35 Friday, February 25, 2011			
			VIOLATION			
	USERID	CC	MSG ID	DATE	TIME	TYPE
	MyCCente	00000008	RACF001I	02/25/2011	12:21:12.5	SIGNON
	MWATL1	00000008	RACF097I	02/25/2011	12:23:04.4	SIGNON

You can specify the start date and time and the stop date and time.

Included in these reports are security message IDs generated by any security subsystem used with Sterling Connect:Direct. Security subsystems supported include:

- IBM Resource Access Control Facility (RACF)
- CA-ACF2 and CA-TOP SECRET by Computer Associates, Inc.

The following table contains a description of the report fields:

Report Field	Description
NODE	Sterling Connect:Direct node where the statistics file is examined.
USERID	Sterling Connect:Direct user ID that created the security violation.
CC	Sterling Connect:Direct completion code in hexadecimal format.
MSG ID	Security system message ID: Sterling Connect:Direct, ACF2, RACF, or TOP SECRET.
DATE	Date security violation occurred.
TIME	Time security violation occurred.
VIOLATION TYPE	Type of security violation. Valid types are SIGNON, PROCESS, and DATASET.

Sterling Connect:Direct for z/OS Function Reports

The Function Reports provide detailed information about specific Process steps for a specified time period. The following reports are included:

- IBM Sterling Connect:Direct for z/OS Non-PDS Copy Report
- IBM Sterling Connect:Direct PDS Copy Report
- IBM Sterling Connect:Direct Run Job Report
- IBM Sterling Connect:Direct Run Task Report
- IBM Sterling Connect:Direct for z/OS Submit Within a Process Report

You can request the start date and time and the stop date and time when requesting one of the Sterling Connect:Direct for z/OS Function Reports.

IBM Sterling Connect:Direct for z/OS Non-PDS Copy Report

The IBM Sterling Connect:Direct for z/OS Non-PDS Copy Report provides information about COPY steps involving these transfers:

- Non-PDS data set <-----> Non-PDS data set
- Non-PDS data set <-----> PDS data set member
- PDS data set member <-----> Non-PDS data set

Following is an example of the IBM Sterling Connect:Direct for z/OS Non-PDS Copy Report.

```

IBM Sterling Connect:Direct for z/OS Non-PDS Copy Report
NODE = SC.DUB.MWATL1
- USERID      PROC #   PROC NAME   STEP NAME   TRANSMISSION INFORMATION
- MWATL1      1       OS9903    FUSH01     02/25/2011 PNODE = SC.DUB.MWATL1  SNODE = SC.DUB.MWATL1
                                           TRANSMISSION TIME = 0:00:00.04  COMPLETION CODE = 00000000 MSG ID = SCPA000I
                                           COPY STEP SUCCESSFUL.
=====
SRC DSNAME IS MWATL1.TCFIP.DATA.FILE
DEST DSNAME IS MWATL1.FTST.A7BEO4E
SENDING NODE ==> SC.DUB.MWATL1  RECEIVING NODE ==> SC.DUB.MWATL1
BYTES READ ==> 266              BYTES WRITTEN ==> 266
BLOCKS READ ==> 1              BLOCKS WRITTEN ==> 1
RECS READ ==> 0               RECS WRITTEN ==> 0
BYTES SENT ==> 270            BYTES RECEIVED ==> 270
COMPRESSION% ==> -1.5         COMPRESSION% ==> -1.5
VOLSER ==> USER15            VOLSER ==> WRKPK2
-----
MWATL1      1       OS9903    FUSH01     02/25/2011 PNODE = SC.DUB.MWATL1  SNODE = SC.DUB.MWATL1
                                           TRANSMISSION TIME = 0:00:00.04  COMPLETION CODE = 00000000 MSG ID = SCPA000I
                                           COPY STEP SUCCESSFUL.
=====
SRC DSNAME IS MWATL1.TCFIP.DATA.FILE
DEST DSNAME IS MWATL1.FTST.A7BEO4E
SENDING NODE ==> SC.DUB.MWATL1  RECEIVING NODE ==> SC.DUB.MWATL1
BYTES READ ==> 266              BYTES WRITTEN ==> 266
BLOCKS READ ==> 1              BLOCKS WRITTEN ==> 1
RECS READ ==> 0               RECS WRITTEN ==> 0
BYTES SENT ==> 270            BYTES RECEIVED ==> 270
COMPRESSION% ==> -1.5         COMPRESSION% ==> -1.5
VOLSER ==> USER15            VOLSER ==> WRKPK2
-----
MWATL1      2       OS9901    STEP01     02/25/2011 PNODE = SC.DUB.MWATL1  SNODE = SC.DUB.MWATL1
                                           TRANSMISSION TIME = 0:00:03.53  COMPLETION CODE = 0000000C MSG ID = SCPA046I
                                           PROCESS HAS BEEN SUSPENDED BY USER/OPERATOR REQUEST.
=====
SRC DSNAME IS DEVSPG2.HOST.SMSUS1.TSTFILE
DEST DSNAME IS MWATL1.SMSTEST.HOST.SMSUS1.ASA0668
SENDING NODE ==> SC.DUB.MWATL1  RECEIVING NODE ==> SC.DUB.MWATL1
BYTES READ ==> 21426504         BYTES WRITTEN ==> 21403484
BLOCKS READ ==> 1366          BLOCKS WRITTEN ==> 1365
RECS READ ==> 0              RECS WRITTEN ==> 0
BYTES SENT ==> 11199488       BYTES RECEIVED ==> 11199488
COMPRESSION% ==> 64.4         COMPRESSION% ==> 64.3
VOLSER ==> SMSUS1            VOLSER ==> SMSUS2
=====

```

This report includes all NonPDS COPY step transmissions for a specified time period. The ARS software sorts COPY information for each SNODE by user ID and then in ascending order by Process number. The following table contains a description of the report fields.

Report Field	Descriptions
NODE	Sterling Connect:Direct node where the statistics file is examined
USERID	Sterling Connect:Direct user ID
PROC #	Sterling Connect:Direct Process number
PROC NAME	Sterling Connect:Direct Process name
STEP NAME	Name (or label) assigned to a COPY step
mm/dd/yyyy	Date COPY step began executing
PNODE	Sterling Connect:Direct primary node
SNODE	Sterling Connect:Direct secondary node
TRANSMISSION TIME	Elapsed time between the COPY step start and the COPY step completion
COMPLETION CODE	Sterling Connect:Direct completion code in hexadecimal format
MSG ID	Sterling Connect:Direct message ID
message	Short message for Sterling Connect:Direct message ID
SRC DSNAME	Source data set name
DEST DSNAME	Destination data set name
REPORT FIELD	Description of report
SENDING NODE	Name of node sending the data set
RECEIVING NODE	Name of node receiving the data set
BYTES READ	Number of bytes read by sending node
BYTES WRITTEN	Number of bytes written by receiving node

Report Field	Descriptions
BLOCKS READ	Number of blocks read by sending node
BLOCKS WRITTEN	Blocks written by receiving node (either blocks or records is displayed)
RECS READ	Number of records read by sending node
RECS WRITTEN	Number of records written by receiving node
BYTES SENT	Number of bytes sent by sending node
BYTES RECEIVED	Number of bytes received by receiving node
COMPRESSION%	Compression percentage for sending data set
COMPRESSION%	Compression percentage for receiving data set
VOLSER	Sending volume serial number
VOLSER	Receiving volume serial number

IBM Sterling Connect:Direct for z/OS PDS Copy Report

The IBM Sterling Connect:Direct for z/OS PDS Copy Report provides information for each COPY step involving the PDS data set to PDS data set transfer.

Following is an example of the IBM Sterling Connect:Direct for z/OS PDS Copy Report.

```

IBM Sterling Connect:Direct for z/OS PDS Copy Report
NOE = SC.DUB.MWATL1
TRANSMISSION INFORMATION
- USERID      PROC #  PROC NAME  STEP NAME
*****      *      *      *      *
- MWATL1      4      PDS      STEP01
02/25/2011  PNODE = SC.DUB.MWATL1  SNODE = SC.DUB.MWATL1
TRANSMISSION TIME = 0:00:19.82  COMPLETION CODE = 00000008 MSGID= SVSG016I
PDS ERROR - DIRECTORY FULL/NON-EXISTENT MEMBER/WRONG DSOrg.
=====
SRC DSNAME IS MWATL1.JCL.LIB
DEST DSNAME IS MWATL1.JCL.LIB3
SENDING NODE ==> SC.DUB.MWATL1  RECEIVING NODE ==> SC.DUB.MWATL1
BYTES READ   ==> 60436320        BYTES WRITTEN ==> 60436320
BLOCKS READ  ==> 5479           BLOCKS WRITTEN ==> 5479
RECS READ    ==> 0              RECS WRITTEN  ==> 0
BYTES SENT   ==> 60458236       BYTES RECEIVED ==> 60458236
COMPRESSION% ==> 0              COMPRESSION%  ==> 0
VOLSER       ==> USER34        VOLSER        ==> USER03

1
IBM Sterling Connect:Direct for z/OS PDS Copy Report
NOE = SC.DUB.MWATL1
TRANSMISSION INFORMATION
- USERID      PROC #  PROC NAME  STEP NAME
*****      *      *      *      *
- MWATL1      4      PDS      STEP01
02/25/2011  PNODE = SC.DUB.MWATL1  SNODE = SC.DUB.MWATL1
TRANSMISSION TIME = 0:00:19.82  COMPLETION CODE = 00000004 MSGID= SCPA000I
COPY STEP SUCCESSFUL.
=====
SRC DSNAME IS MWATL1.JCL.LIB
DEST DSNAME IS MWATL1.JCL.LIB3
SENDING NODE ==> SC.DUB.MWATL1  RECEIVING NODE ==> SC.DUB.MWATL1
BYTES READ   ==> 60436320        BYTES WRITTEN ==> 60436320
BLOCKS READ  ==> 5479           BLOCKS WRITTEN ==> 5479
RECS READ    ==> 0              RECS WRITTEN  ==> 0
BYTES SENT   ==> 60458236       BYTES RECEIVED ==> 60458236
COMPRESSION% ==> 0              COMPRESSION%  ==> 0
VOLSER       ==> USER34        VOLSER        ==> USER03

MEMBER LIST
=====
$$$SPACE    TO $$$SPACE
$$$SPACE    TO $$$SPACE

```

This report lists all PDS COPY step transmissions by Process number for a specified time period. It lists sending data set members names with each destination data set member name.

The accuracy of the data in this report is not guaranteed if you restart Sterling Connect:Direct using the TCQ=COLD initialization parameter during the time period specified. ARS uses the Process number in the statistics file to match PDS member names with a specific COPY step. Because a COLD restart begins numbering Processes from 1, ARS may not associate PDS member names correctly with the appropriate PDS Copy step.

The following table describes the report fields.

Report Field	Description
NODE	Sterling Connect:Direct node where the statistics file is examined
USERID	Sterling Connect:Direct user ID
PROC #	Sterling Connect:Direct Process number
PROC NAME	Sterling Connect:Direct Process name
STEP NAME	Name (or label) assigned to a COPY step
mm/dd/yyyy	Date COPY step began executing
PNODE	Name of primary node
SNODE	Name of secondary node
TRANSMISSION TIME	Time between the COPY step start and the COPY step completion
COMPLETION CODE	Sterling Connect:Direct completion code in hexadecimal format
MSG ID	Sterling Connect:Direct message ID
message	Short message for Sterling Connect:Direct message ID
SRC DSNAME	Source data set name
DEST DSNAME	Destination data set name
SENDING NODE	Name of node sending the data set
REPORT FIELD	Description of report
RECEIVING NODE	Name of node receiving the data set
BYTES READ	Number of bytes read by sending node
BYTES WRITTEN	Number of bytes written by receiving node
BLOCKS READ	Number of blocks read by sending node
BLOCKS WRITTEN	Number of blocks written by receiving node (blocks or records is displayed)
RECS READ	Number of records read by sending node
RECS WRITTEN	Number of records written by receiving node
BYTES SENT	Number of bytes sent by sending node
BYTES RECEIVED	Number of bytes received by receiving node
COMPRESSION%	Compression percentage for sending data set
COMPRESSION%	Compression percentage for receiving data set
VOLSER	Sending volume serial number
VOLSER	Receiving volume serial number
MEMBER LIST	List of sending member names and receiving member names

IBM Sterling Connect:Direct for z/OS Run Job Report

The IBM Sterling Connect:Direct for z/OS Run Job Report lists the jobs submitted for execution using the Sterling Connect:Direct RUN JOB statement. Jobs are listed for a specified time period. Following is an example of the IBM Sterling Connect:Direct for z/OS Run Job Report.

```

1      IBM Sterling Connect:Direct for z/OS RUNJOB Report
      NODE = SC.DUB.MWATL1
USERID  PROC #  PROC NAME  STEP NAME  RUNJOB INFORMATION
*****  *****  *****  *****  *****
MWATL1  6      MWCOPY    RJ        02/25/2011 PNODE = SC.DUB.MWATL1  SNODE = SC.DUB.MWATL1
      COMPLETION CODE = 00000000      MSG ID = SRJA0001
      C:D RUN JOB FUNCTION COMPLETED SUCCESSFULLY.
      =====
      DSNAME ==> MWATL1.JCL.LIB(NDMBAT1)
      JOB # ==> 93960
      JOB SUBMITTED ON SC.DUB.MWATL1

```

The ARS software sorts all RUN JOB steps for each SNODE by userid and then in ascending order by Process number.

The following table contains a description of the report fields.

Report Field	Description
NODE	Sterling Connect:Direct node where the statistics file is being examined
USERID	Sterling Connect:Direct user ID
PROC #	Sterling Connect:Direct Process number
PROC NAME	Sterling Connect:Direct Process name
STEP NAME	Name (or label) assigned to a RUN JOB step
mm/dd/yyyy	Date RUN JOB step submitted to run
PNODE	Sterling Connect:Direct primary node
REPORT FIELD	Description of report
SNODE	Sterling Connect:Direct secondary node
COMPLETION CODE	Sterling Connect:Direct completion code in hexadecimal format
MSG ID	Sterling Connect:Direct message ID
message	Short message for Sterling Connect:Direct message ID
DSNAME	Data set name containing job stream to be submitted
JOB #	Number assigned to job by operating system
JOB SUBMITTED ON	Sterling Connect:Direct node where the job is submitted to run

Run Task Report

The IBM Sterling Connect:Direct for z/OS Run Task Report tracks all tasks (programs) for a specified time period that executed under the control of the Sterling Connect:Direct RUN TASK statement. Following is an example of the IBM Sterling Connect:Direct for z/OS Run Task Report.

```

IBM Sterling Connect:Direct for z/OS RUNTASK Report
- USERID      PROC #   PROC NAME   STEP NAME   RUNTASK INFORMATION
*****      *****
- MWATL1      7       RTBR14     STEP1      02/25/2011 ENODE = SC.DUB.MWATL1   SNODE = SC.DUB.MWATL1
              COMPLETION CODE = 00000000      MSG ID = SRTA000I
              C:D RUN TASK FUNCTION SUCCESSFULLY COMPLETED.
              =====
              PROGRAM NAME ==> IEFBR14
              PROGRAM ATTACHED ON SC.DUB.MWATL1
0
-----
- MWATL1      8       RTBR14     STEP1      02/25/2011 ENODE = SC.DUB.MWATL1   SNODE = SC.DUB.MWATL1
              COMPLETION CODE = 00000000      MSG ID = SRTA000I
              C:D RUN TASK FUNCTION SUCCESSFULLY COMPLETED.
              =====
              PROGRAM NAME ==> IEFBR14
              PROGRAM ATTACHED ON SC.DUB.MWATL1
0
-----
- MWATL1      9       RTBR14     STEP1      02/25/2011 ENODE = SC.DUB.MWATL1   SNODE = SC.DUB.MWATL1
              COMPLETION CODE = 00000000      MSG ID = SRTA000I
              C:D RUN TASK FUNCTION SUCCESSFULLY COMPLETED.
              =====
              PROGRAM NAME ==> IEFBR14
              PROGRAM ATTACHED ON SC.DUB.MWATL1
0
-----
- MWATL1      10      RTBR14     STEP1      02/25/2011 ENODE = SC.DUB.MWATL1   SNODE = SC.DUB.MWATL1
              COMPLETION CODE = 00000000      MSG ID = SRTA000I
              C:D RUN TASK FUNCTION SUCCESSFULLY COMPLETED.
              =====
              PROGRAM NAME ==> IEFBR14
              PROGRAM ATTACHED ON SC.DUB.MWATL1

```

The ARS software sorts all RUN TASK steps for each SNODE by userid and then in ascending order by Process number.

The following table contains a description of the report fields.

Report Field	Description
NODE	Sterling Connect:Direct node where the statistics file is being examined
USERID	Sterling Connect:Direct user ID
PROC #	Sterling Connect:Direct Process number
PROC NAME	Sterling Connect:Direct Process name
STEP NAME	Name (or label) assigned to a RUN TASK step
mm/dd/yyyy	Date RUN TASK step attached and executed
PNODE	Sterling Connect:Direct primary node
REPORT FIELD	Description of report
SNODE	Sterling Connect:Direct secondary node
COMPLETION CODE	Sterling Connect:Direct completion code in hexadecimal format
MSG ID	Sterling Connect:Direct message ID
message	Short message for Sterling Connect:Direct message ID
PROGRAM NAME	Name of program module attached
PROGRAM ATTACHED ON	Sterling Connect:Direct node where the task is attached and executed

IBM Sterling Connect:Direct for z/OS Submit Within a Process Report

The IBM Sterling Connect:Direct for z/OS Submit Within a Process Report lists Processes that are submitted to Sterling Connect:Direct for execution using the Sterling Connect:Direct Submit (within a Process) statement for a specified time period. Following is an example of the IBM Sterling Connect:Direct for z/OS Submit Within a Process Report.

IBM Sterling Connect:Direct for z/OS Submit within a Process Report				NODE = SC.DUB.MWATL1	
USERID	PROC #	PROC NAME	STEP NAME	SUBMIT INFORMATION	
- USERID	*****	*****	*****	*****	
- MWATL1	1	OS3903	STEP01	02/25/2011 PNODE = SC.DUB.MWATL1 SNODE = SC.DUB.MWATL1 COMPLETION CODE = 00000000 MSG ID = SSUB000I THE SUBMIT CONTROL BLOCK HAS BEEN SUCCESSFULLY CONSTRUCTED. =====	
				DSNAME ==> MWATL1.NDM.PROCESS.LIB(OS3903) PROCESS SUBMITTED ON SC.DUB.MWATL1	
0	-----				
MWATL1	4	PDS	STEP2	02/25/2011 PNODE = SC.DUB.MWATL1 SNODE = SC.DUB.MWATL1 COMPLETION CODE = 00000000 MSG ID = SSUB000I THE SUBMIT CONTROL BLOCK HAS BEEN SUCCESSFULLY CONSTRUCTED. =====	
				DSNAME ==> MWATL1.NDM.PROCESS.LIB(PDS) PROCESS SUBMITTED ON SC.DUB.MWATL1	
0	-----				
MWATL1	4	PDS	STEP2	02/25/2011 PNODE = SC.DUB.MWATL1 SNODE = SC.DUB.MWATL1 COMPLETION CODE = 00000000 MSG ID = SSUB000I THE SUBMIT CONTROL BLOCK HAS BEEN SUCCESSFULLY CONSTRUCTED. =====	
				DSNAME ==> MWATL1.NDM.PROCESS.LIB(PDS) PROCESS SUBMITTED ON SC.DUB.MWATL1	
0	-----				
MWATL1	7	RTBR14	STEP2	02/25/2011 PNODE = SC.DUB.MWATL1 SNODE = SC.DUB.MWATL1 COMPLETION CODE = 00000000 MSG ID = SSUB000I THE SUBMIT CONTROL BLOCK HAS BEEN SUCCESSFULLY CONSTRUCTED. =====	
				DSNAME ==> MWATL1.NDM.PROCESS.LIB(RTBR14) PROCESS SUBMITTED ON SC.DUB.MWATL1	
0	-----				
MWATL1	8	RTBR14	STEP2	02/25/2011 PNODE = SC.DUB.MWATL1 SNODE = SC.DUB.MWATL1 COMPLETION CODE = 00000000 MSG ID = SSUB000I THE SUBMIT CONTROL BLOCK HAS BEEN SUCCESSFULLY CONSTRUCTED. =====	
				DSNAME ==> MWATL1.NDM.PROCESS.LIB(RTBR14) PROCESS SUBMITTED ON SC.DUB.MWATL1	
0	-----				
MWATL1	9	RTBR14	STEP2	02/25/2011 PNODE = SC.DUB.MWATL1 SNODE = SC.DUB.MWATL1 COMPLETION CODE = 00000000 MSG ID = SSUB000I THE SUBMIT CONTROL BLOCK HAS BEEN SUCCESSFULLY CONSTRUCTED. =====	
				DSNAME ==> MWATL1.NDM.PROCESS.LIB(RTBR14) PROCESS SUBMITTED ON SC.DUB.MWATL1	

The ARS software sorts all SUBMIT steps for each SNODE by userid and then in ascending order by Process number.

The following table contains a description of the report fields.

Report Field	Description
NODE	Sterling Connect:Direct node where the statistics file is being examined
USERID	Sterling Connect:Direct user ID
PROC #	Sterling Connect:Direct Process number
PROC NAME	Sterling Connect:Direct Process name
STEP NAME	Name (or label) assigned to a SUBMIT (within a Process) step
mm/dd/yyyy	Date SUBMIT (within a Process) step ran
PNODE	Sterling Connect:Direct primary node
REPORT FIELD	Description of report
SNODE	Sterling Connect:Direct secondary node
COMPLETION CODE	Sterling Connect:Direct completion code in hexadecimal format
MSG ID	Sterling Connect:Direct message ID
message	Short message for Sterling Connect:Direct message ID

Report Field	Description
DSNAME	Data set name containing the Sterling Connect:Direct Process Only available when SUBNODE=PNODE.
PROCESS SUBMITTED ON	Sterling Connect:Direct node where the Process was submitted to run

Chapter 3. Activity Reporting System

The Activity Reporting System (ARS) produces reports of Sterling Connect:Direct activity. While Sterling Connect:Direct produces statistics, ARS enables you to access more information and provides sorting capabilities.

You can request ARS reports in three ways:

- Through ARS screens using IBM Time Sharing Option/Interactive System Productivity Facility (TSO/ISPF)
- Automatically through a Sterling Connect:Direct Process
- Schedule a batch job through a job scheduling subsystem

With ARS, you do not have to pass data to z/OS system management facilities (SMF) or write SAS requests to print Sterling Connect:Direct activity reports. Use ARS as a standard reporting format throughout a network for tracking Sterling Connect:Direct activity.

Note: ARS requires a SAS base running under z/OS and Sterling Connect:Direct for z/OS must be active.

ARS and Sterling Connect:Direct

Sterling Connect:Direct automatically collects statistical data and stores it in a data set. ARS can access this statistical data and produce the following reports for a selected time period:

- IBM Sterling Connect:Direct Activity Report lists activity by Process step
- IBM Sterling Connect:Direct Summary Report summarizes all activity
- IBM Sterling Connect:Direct Exception Report lists all Process steps that are not successful
- IBM Sterling Connect:Direct Security Violations Report lists security violations by signon security failures, Process security failures, and data set access security failures
- IBM Sterling Connect:Direct Function Reports provides the activity reports for the following types of Process steps:
 - Non-Partitioned Data Set (PDS) COPY
 - PDS COPY
 - RUN JOB
 - RUN TASK
 - Submit Within a Process

Following are two methods to request ARS reports:

- Through the ARS screens where you can create a job stream that requests reports. The screens automatically build the job or allow you to edit the sample report job stream.
- By using the sample JCL member that is provided with ARS.

Business Solutions Using ARS

ARS provides data center management with additional tools to monitor and track Sterling Connect:Direct usage. Use the information in the reports to track attempted security violations, analyze capacity planning related data, examine Sterling Connect:Direct utilization, and isolate failed Sterling Connect:Direct Processes.

The following table describes how to use ARS.

Function	Description
Data Center Management	The data center manager wants to keep track of Sterling Connect:Direct activities. The IBM Sterling Connect:Direct Activity Report lists all Process steps that occurred in this data center during a time period. The IBM Sterling Connect:Direct NonPDS Copy Report and IBM Sterling Connect:Direct PDS Copy Report provide additional information on all COPY steps performed.
Security Violations	A system administrator requests a list of any Sterling Connect:Direct-related security violations on a daily basis. The IBM Sterling Connect:Direct Security Violations Report lists the following violations: <ul style="list-style-type: none">• Sign on security failures• Processes not run due to lack of authorization• Data set access security violations
Capacity Planning	The capacity planner at a data center needs to know how many bytes are transferring between this data center and other data centers and the total transmission times. The IBM Sterling Connect:Direct Summary Report provides this type of information by remote data center for a specified time period.
Sterling Connect:Direct Utilization	The data center administrator studies Sterling Connect:Direct utilization by examining how many application programs are submitted or invoked using Sterling Connect:Direct. The administrator uses this information with a job scheduling system to produce a comprehensive analysis of all jobs run at a data center. Two ARS reports provide this type of utilization summary. The IBM Sterling Connect:Direct Run Job Report provides information about all jobs submitted by Sterling Connect:Direct. The IBM Sterling Connect:Direct Run Task Report provides information about all programs executed under the control of Sterling Connect:Direct.
Problem Isolation	The IBM Sterling Connect:Direct Exception Report is an excellent tool for researching why a Process does not run. This report lists each failed Process for a requested time period along with the reason for the failure.

Chapter 4. Requesting ARS Statistical Reports

To request ARS statistical reports, complete the following procedures:

- Request the ARS report using ARS screens
- Run the job

ARS screens build a job stream to produce any of the ARS reports. For this reason, the screens are most useful in cases where you need individual reports instead of volume reports.

After ARS screens build the job stream and submit it to run, the job performs the following:

- Signs on to Sterling Connect:Direct
- Creates a temporary data set to hold the specified statistics
- Accesses the Sterling Connect:Direct statistics file and copies statistics to a temporary data set
- Executes the ARS report routine using the Sterling Connect:Direct statistics as input data
- Sends the report to the selected output location
- Deletes the temporary data set

Requesting Reports Using ARS Screens

About this task

The ARS screens identify the information to build the job. Certain information is retained between sessions to prevent the need to enter the same information each time you request a report.

To access the ARS screens through the IUI:

Select ADMIN from the Primary Options Menu.

```

node.name          IBM Sterling Connect:Direct for z/OS
                    PRIMARY OPTIONS MENU
CMD ==>  ADMIN
SELECT ONE OF THE FOLLOWING:                                More:      +

CF  - COPY A FILE                                           *****
SB  - SUBMIT A PREDEFINED PROCESS                           *          *
DF  - DEFINE A PROCESS USING ISPF EDIT                       * TODAY: 02.24.2011 *
SS  - VIEW STATISTICS FOR A COMPLETED PROCESS              * TIME: 09:06      *
MB  - SUBMIT A BATCH TO Connect:Enterprise for z/OS        *          *
CP  - CHANGE CHARACTERISTICS OF A PROCESS                   *****
DP  - DELETE A NON-EXECUTING PROCESS
FP  - FLUSH AN EXECUTING PROCESS
SP  - VIEW DATA ABOUT AN EXECUTING PROCESS
PS  - SUSPEND AN EXECUTING PROCESS
MSG - VIEW Connect:Direct MESSAGE TEXT
SW  - SWAP AMONG CONCURRENT Connect:Direct SESSIONS
SD  - VIEW/CHANGE YOUR Connect:Direct SIGNON INFORMATION DEFAULTS
NM  - VIEW INFORMATION IN THE Connect:Direct NETWORK MAP
WHO - VIEW CHARACTERISTICS OF YOUR Connect:Direct IUI ENVIRONMENT
SPF - ENTER ISPF/PDF
AUTH - VIEW YOUR Connect:Direct FUNCTION AUTHORIZATION
MS  - SIGN ON TO MULTIPLE Connect:DIRECT NODES CONCURRENTLY
ADMIN - PERFORM Connect:Direct ADMINISTRATIVE FUNCTIONS

```

Procedure

1. From the Administrative Options Menu, select ARS.

```

node.name          Connect:Direct ADMINISTRATIVE OPTIONS MENU
                    CMD ==>
SELECT ONE OF THE FOLLOWING:
ST  - VIEW TYPE RECORD                                     *****
IT  - INSERT/UPDATE TYPE RECORD                           *          *
DT  - DELETE TYPE RECORD                                  * TODAY: 02.24.2011 *
SU  - VIEW USER AUTHORIZATION RECORD                      * TIME: 10:26      *
IU  - INSERT/UPDATE USER AUTHORIZATION RECORD            *          *
DU  - DELETE USER AUTHORIZATION RECORD                   *****
TS  - VIEW Connect:Direct TASKS
TF  - FLUSH A Connect:Direct TASK
S   - Execute Secure Plus Commands
MD  - MODIFY Connect:Direct TRACE CHARACTERISTICS
C   - ENTER A NATIVE Connect:Direct COMMAND
SN  - TERMINATE Connect:Direct
ARS - ARS REPORTING FACILITY
NM  - VIEW THE CONTENTS OF THE Connect:Direct NETWORK MAP
UNM - UPDATE THE Connect:Direct NETWORK MAP
INQ - INQUIRE ABOUT DTF INTERNAL STATUS
STAT - PERFORM STATISTICS FUNCTIONS

```

2. To request the report, provide signon data, and specify the time period for the report, continue with the following steps.
3. To submit the job stream without changing any data, type SUB (submit) at the CMD field and then press Enter.

```

$cd.node          Connect:Direct for z/OS - ARS REPORT OPTIONS
CMD ==>
                AC - ACTIVITY                      PS - NON-PDS COPY
                SM - SUMMARY                       PO - PDS COPY
                EX - EXCEPTION                     RJ - RUNJOB
                SC - SECURITY                      RT - RUNTASK
                                                SB - SUBMIT

REPORT TYPE ==>          EDIT JCL ==>  (Y,N)
Connect:Direct SIGNON PARAMETERS
-----
USER ID      ==> $uid
PASSWORD     ==>
NETMAP NAME  ==> $cd.netmap
TRANSPORT    ==> NET
COMMUNICATION ADDRESS ==> (      ,          )
REPORTING RANGE
-----
START DATE   ==>          START TIME ==>
STOP DATE    ==>          STOP TIME  ==>

```

The following table contains a description of the screen fields.

Field	Description
REPORT TYPE	Specifies the ARS report.
EDIT JCL	Specifies an option to edit JCL.
USER ID	Specifies the userid for signing on to Sterling Connect:Direct, if your security environment requires it. (optional)
PASSWORD	Specifies the password needed to access Sterling Connect:Direct. (optional)
NETMAP NAME	Specifies the name of the Sterling Connect:Direct Network Map.
TRANSPORT	Enables override of signon defaults for DGADBATC transport type.
COMMUNICATION ADDRESS	Specifies port number and IP address with TRANSPORT=TCP.
REPORTING RANGE	Identifies the date, day or time period that you want the requested report to cover. (optional) If all four fields are blank, the contents of the statistics file is used.

Field	Description
START DATE or STOP DATE	<p>Specifies the date or day that the statistics records are selected for the ARS report.</p> <p>You can specify the day (dd), month (mm), and year (yy for 2-digit year and yyyy for 4-digit year). Use periods or backslashes (\) to separate the components of a date value.</p> <p>You can specify the date (dd), month (mm), and year (yy) in one of the following formats: yymmdd or yyyyymmdd; yy/mm/dd or yyyy/mm/dd; yy.mm.dd or yyyy.mm.dd; mmddy or mmdyyyy; mm/dd/yy or mm/dd/yyyy; mm.dd.yy or mm.dd.yyyy; or the Julian date, yyddd or yyyyddd; yy/ddd or yyyy/ddd; or yy.ddd or yyyy.ddd. If you only specify the date, the time defaults to 00:00.</p> <p>This date must have the same format as specified in the DATEFORM initialization parameter.</p> <p>You can also use day in these fields to indicate day of the week for which the statistics records are searched. Valid names include MOnDay, TUEsday, WEDnesday, THURsday, FRIday, SATurday, and SUNday.</p> <p>You can also specify TODAY, which searches for the statistics records today; or TOMORROW, which searches for statistics records the next day; or YESTER, which searches for statistics records for yesterday.</p>
START TIME or STOP TIME	<p>Specifies the time of day in hours (hh), minutes (mm), and seconds (ss) when the statistics records are selected for the ARS report. Specify AM or PM. You can express the time of day using the 24-hour clock or the 12-hour clock. If you use the 24-hour clock, valid times are 00:00-24:00. If you use the 12-hour clock, you can express 1:00 hours as 1:00AM, and you can express 1:00 PM as 13:00 hours. If you do not use AM and PM, the 24-hour clock is assumed. You do not need to specify minutes and seconds.</p> <p>You can also specify NOON, which searches for the statistics records at noon, or MIDNIGHT, which searches for the statistics records at midnight.</p> <p>The default for the time is 00:00:00, the beginning of the day.</p> <p>If you do not specify START TIME and STOP TIME but you do specify the START DATE and STOP DATE, the time range default is 00:00 to 24:00.</p>

ARS Connect:Direct Requirements Screen

The ARS Connect:Direct Requirements screen in the following figure identifies specific job stream parameters for the job card and Sterling Connect:Direct-related information.

```

$cd.node          Connect:Direct for z/OS - ARS (Job and File Requirements)
CMD ==>
UP TO 3 LINES FOR JOBCARD INFO
==> _____
==> _____
==> _____
STEPLIB DATA SET NAME FOR Connect:Direct PROGRAMS (OPTIONAL):
==> _____
==> _____
Connect:Direct PUBLIB PROCESS LIBRARIES (1 REQUIRED):
==> _____
==> _____
Connect:Direct MESSAGE DATA SET NAME (REQUIRED):
==> _____
UNIT SPECIFICATION FOR Connect:Direct TEMPORARY DATASET:
==> _____

```

The following table contains a description of the screen fields.

Field	Description
JOBCARD INFO	Typical job card information. Use the COND=(0,NE) for best results, meaning the job does not run if an error is found when configuring the job.
STEPLIB DATA SET NAME FOR Connect:Direct PROGRAMS	Name of the library containing the Sterling Connect:Direct load modules. You can type two libraries in this section (optional).
Connect:Direct PUBLIC PROCESS LIBRARIES	Specifies the name of the library containing Sterling Connect:Direct Processes.
Connect:Direct MESSAGE DATA SET NAME	Specifies the name of the message data set containing the Sterling Connect:Direct messages.

ARS SAS Requirements Screen and Fields

The ARS SAS Requirements screen in the following figure identifies specific JCL parameters for SAS-related information.

```

$cd.node          Connect:Direct for z/OS - ARS (SAS Files and Output)
CMD ==>
SAS CATALOGED PROCEDURE (REQUIRED):
==> _____
DATASET NAME CONTAINING SAS ROUTINES (REQUIRED):
==> _____
ONE OF THE FOLLOWING MUST BE PROVIDED :
OUTPUT DATA SET NAME :
==> _____
OUTPUT (SYSOUT) CLASS :
==> _

```

The following table contains a description of the screen fields.

Field	Description
SAS CATALOGED PROCEDURE	Identifies the name of the SAS cataloged procedure, which is a collection of JCL statements required to execute SAS for batch processing at your installation.
DATA SET NAME CONTAINING SAS ROUTINES	Specifies where the ARS routines (\$CD.SDGAMAP) that interact with SAS are located.

Field	Description
OUTPUT DATA SET NAME	You must preallocate the sequential data set designated in this field with the following attributes: RECFM=FBA LRECL=240 BLKSIZE=3120 If this field is left blank, you must specify the OUTPUT (SYSOUT) CLASS field.
OUTPUT (SYSOUT) CLASS	Specifies the SYSOUT class that automatically sends the output to a designated printer queue (optional). If you leave this field blank, you must specify the OUTPUT DATASET NAME field. Note: If you are requesting the Sterling Connect:Direct Summary report and routing it to a data set, ensure that the data set is empty. If the data set is not empty, this report is placed after the data already in the data set. The Sterling Connect:Direct Summary Report is automatically allocated with DISP=MOD instead of DISP=SHR.

Job Streams Created

After completing the procedure, ARS builds a job stream, as in the following example. If you requested EDIT, ARS displays the job after completing the screens.

You can review the job stream before submitting it. Following is an example of the JCL which is generated using member DGAJARS from \$CD.SDGASENU.

```
//JOBNAME JOB (ACCT), 'NAME', NOTIFY=TSOID,TIME=((1),
// REGION=0M,MSGCLASS=X,CLASS=B
//*
//*
//DGADBATC EXEC PGM=DGADBATC,PARM='YYSLN'
//STEPLIB DD DISP=SHR,DSN=$CD.SDGalINK
//SYSUDUMP DD SYSOUT=*
//DMPUBLIB DD DISP=SHR,DSN=$CD.SDGAPROC
//DMMSGFIL DD DISP=SHR,DSN=$CD.MSG
//TEMPDSN DSN=&CDAPI,DISP=(NEW,PASS),UNIT=PTEMP,
// DCB=(DSORG=PS,RECFM=VBA,LRECL=4100,BLKSIZE=4104),
// SPACE=(4104,(70,13))
//DMPRINT DD SYSOUT=*
//SYSIN DD *
SIGNON USERID=(NAME,,) -
NETMAP=$CD.NETMAP TMPDD=TEMPDSN
SEL STAT WHERE (STARTT = (06/1/2010,12:00AM) -
STOPT = 07/1/2010,11:59PM) ) FILE
SIGNOFF
/*
//*
///SASTEP EXEC $SASPROC,
// OPTIONS='DQUOTE MACRO MACROGEN MERROR MISSING="-"'
//WORK DD UNIT=PTEMP,SPACE=(CYL,(20,10))
//NDMX0001 DD DISP=(OLD,DELETE),DSN=&CDAPI
//DMMSGFIL DD DISP=SHR,DSN=$CD.MSG
//FT20F001 DD DISP=SHR,DSN=$OUTPUT.DATASET.NAME
//SYSIN DD DISP=SHR,DSN=$CD.SDGAMAP(ACTIVITY)
```

Running the Job

When a job runs, it performs the following:

- Signs on to Sterling Connect:Direct
- Creates a temporary data set to hold the specified statistics
- Copies statistics to the temporary data set
- Executes the ARS report routine using the Sterling Connect:Direct statistics as input data
- Sends the report to the selected output location
- Deletes the temporary data set

Chapter 5. Requesting Multiple ARS Reports or Scheduled Processing

You can request ARS reports without using the ARS screens. You can submit multiple ARS reports at one time or submit ARS reports for scheduled processing.

You can request ARS reports without using ARS screens by editing a sample job stream to specify processing requirements and report types. Also, when the output of a multiple report request is routed to a data set, some ARS report routines can require a minor edit change.

Modifying the Sample Job Stream

Modify the sample job stream in \$CD.SDGAJCL(DGAJARS2) in order to customize the job stream with your companies information.

About this task

These steps provide line-by-line instructions for modifying the sample job stream. These modifications are also detailed in the \$CD.SDGAJCL(DGAJARS2) file.

Procedure

1. Modify the job card to uniquely identify your job.
2. Change \$CD.SDGALINK to the appropriate Sterling Connect:Direct load library name.
3. Change \$CD.SDGAPROC to the appropriate Sterling Connect:Direct Process library name.
4. Change all occurrences of \$CDVSAM.MSG to the Sterling Connect:Direct message data set name.
5. Change \$UID to your Sterling Connect:Direct user ID. Also add the password, if needed.
6. Change \$CDVSAM.NETMAP to your Network Map data set name.
7. Change all occurrences of \$UNITNAME to the valid unit name.
8. Change \$SASPROC to the name of the SAS cataloged procedure used at your installation.
9. Route the output to one of the two options:
 - Route to the SYSOUT class. Look for FT20F001 DD.
 - Change all occurrences of \$OUTPUT.DATASET.NAME to the name of the data set where you route the output. Preallocate this data set as FBA with an LRECL of 240 and BLKSIZE of 3120. Ensure that the data set is empty before running this job. Complete the instructions in Multiple Reports to an Output Data Set.
10. Change \$CD.SDGAMAP to the name of the data set containing the SAS programs.

Note: If you would like to define the time span that will be reported, modify the SEL Statistics command in the SYSIN stream of the DMBATCH step to include start and stop times. The default is a report on the entire STAT file.

Job Stream Definitions

The following table defines the parameters and SAS options for the sample job stream.

Report Field	Definition
JOB CARD INFO	Specifies the typical job card information. Use the COND=(0,NE) for best results. This means that the second step of the job does not run if an error occurs in the first step.
DGADBATC	Specifies the program name of the Sterling Connect:Direct batch interface.
STEPLIB	Specifies the library containing the Sterling Connect:Direct load modules.
DMPUBLIB	Specifies the library containing the Sterling Connect:Direct Processes.
DMMSGFIL	Specifies the Sterling Connect:Direct message data set that accesses the messages.
TEMPDSN	Specifies the temporary data set containing the extract from the Sterling Connect:Direct statistics file that is used as input to SAS. This is always specified as (NEW, PASS) so that when you create the data set, the extracted data is saved in it, and then passed on to the next step.
DMPRINT (Optional)	Specifies where the job output from DGADBATC goes. This is useful if an error occurs in DGADBATC.
SYS PRINT	Specifies where the job execution messages goes.
SYSIN	Contains the Sterling Connect:Direct control statements to extract from the statistics file. Represent SYSIN as a sequential data set, PDS member, or instream data set.
SASTEP	Specifies the name of the SAS cataloged procedure used at your installation with the following options: DQUOTE specifies that the system accepts double quotes. MACRO specifies that the SAS macro library is available. MACROGEN specifies that the system can print SAS macros. MERROR specifies that a warning message is produced if a name is prefixed with a percent sign to indicate a SAS macro, but the name is not a valid SAS macro. MISSING specifies that dashes (-) are inserted when a numeric character is missing in the report field.
WORK	Specifies the work area used by SAS for processing.
NDMX0001	Specifies the temporary data set that contains the extract from the Sterling Connect:Direct statistics file. Specify the data set parameters (OLD, DELETE) so that the data set is deleted automatically after processing.
DMMSGFIL	Specifies the name of the Sterling Connect:Direct message data set.
SASPROGS	Identifies the name of the data set containing the SAS routines to produce the reports. See %INCLUDE parameter in this table.
FT20F001	Specifies the DD statement used by SAS to route output. This DD statement can be either output to a data set or SYSOUT class. If it is to a data set, you must preallocate the data set, it must be sequential, and have the following attributes: RECFM=FBA; LRECL=240; BLKSIZE=3120.
SYSIN	Specifies SYSIN for SAS.

Report Field	Definition
%INCLUDE	<p>Contains a special SAS control statement that enables you to execute SAS programs that are stored separately from their JCL. The first name after SASPROGS identifies the DD name that references the location of the SAS programs. The requested ARS report routine names are placed inside of the parentheses:</p> <p>DGAACTIV specifies the IBM Sterling Connect:Direct for z/OS Activity Report</p> <p>DGAAEXEC specifies the IBM Sterling Connect:Direct for z/OS PDS Copy Report</p> <p>DGAARUNJ specifies the IBM Sterling Connect:Direct for z/OS Run Job Report.</p> <p>DGAARUNT specifies the IBM Sterling Connect:Direct for z/OS Run Task Report.</p> <p>DGAASEC specifies the IBM Sterling Connect:Direct for z/OS Security Violations Report.</p> <p>DGAASUB specifies the IBM Sterling Connect:Direct for z/OS Submit Within a Process Report.</p> <p>DGAASUM specifies the IBM Sterling Connect:Direct for z/OS Summary Report.</p>

Sample Sterling Connect:Direct Process That Submits Job Stream

The DGAXRPRC member in \$CD.SDGASAMP in the following figure contains a Sterling Connect:Direct Process that runs the job stream discussed in the previous section, Modifying the Sample Job Stream.

You can set up the sample Process to run automatically on a specified time interval, by submitting this Process with the Sterling Connect:Direct SUBMIT command, specifying the STARTT parameter and RETAIN=YES parameter.

```

RPTPROC          -
* THIS PROCESS WILL SUBMIT FOR EXECUTION THE JCL TO RUN ARS
* CHANGE $SECONDARY.NODE TO THE DESIRED SNODE NAME FOR THE PROCESS
* CHANGE $TSOID TO YOUR TSO ID
* CHANGE $CD.SDGACNTL(DGAJARS) TO THE DATA SET NAME CONTAINING THE JCL
*      TO RUN ARS
PROCESS          -
  SNODE=$SECONDARY.NODE  -
  NOTIFY=$TSOID
STEPONE
  RUN JOB (      -
    DSN=$CD.SDGACNTL(DGAJARS)  -
  )

```

You need to modify the following items if you choose to use this sample Process. Copy DGAXRPRC from \$CD.SDGASAMP to your process library before editing it.

1. Change \$SECONDARY.NODE to the appropriate SNODE.
2. Change \$TSOID to your TSO ID.

3. Change \$CD.SDGAJCL(DGAJARS) to the data set name containing the job that runs ARS.

Multiple Reports to an Output Data Set

Complete this procedure only when you request multiple ARS report types in one job and the reports are sent to an output data set. The IBM Sterling Connect:Direct Activity Report and Security Violations Report require a minor edit change in the ARS routine if you include them in a multiple report request.

Before modifying the ARS routines, make a copy of the \$CD.SDGAMAP, which contains all report routines. Use the first copy when you request one report (in batch mode or using the ARS screens). The second copy can contain the modified routines when you make multiple report requests in a job.

CAUTION:

\$CD.SDGAMAP contains members ALIASed. If you edit an alias, it becomes a member.

You can submit the ARS report routines using TSO. The routines are in the \$CD.SDGAMAP. The following table lists the types of reports and the corresponding members in the \$CD.SDGAMAP that require modification.

Report Type	Member Name
IBM Sterling Connect:Direct Activity Report	DGAACTIV
IBM Sterling Connect:Direct Security Violations Report	DGAASEC

Modify the PROC PRINTTO statement listed in the members so that the output from one report appends rather than overlaying output from the previous report in the designated output file. Change the ARS report routine from:

```
PROC PRINTTO NEW UNIT=20
```

to:

```
PROC PRINTTO UNIT=20;
```

Chapter 6. ARS Record Layouts

To customize ARS reports, modify the ARS reports or develop new reports. Examples include:

- Change ARS report headings, spacing, field titles, and output format
- Access additional information from the Sterling Connect:Direct statistics file to enhance ARS reports or to develop new reports

The ARS routines do not use all of the Sterling Connect:Direct fields in the Sterling Connect:Direct statistics records. The SAS Informat variables for these records are located in the \$CD.SDGAMAP library. Access the information by the member names listed in the following table.

Note: Use two-character designations for records types when browsing the Sterling Connect:Direct statistics file.

Member Name	Contents of Member	Record Types
DGAAAER	Authorization Event Record	IU=INSErt USER UU=UPDate USER SU=SELEct USER DU=DELEte USER
DGAACPTR	Change Process Termination Record	CH=CHange PROCess
DGAACTR	Copy Termination Record	CT=COPIY
DGAADPTR	Delete Process Termination Record	DP=DELEte PROCess
DGAADTR	Display Statistics Record	SP=SELEct PROCess DT=SELEct TASK FT=FLUSH TASK SS=SELEct STATistics SN=SELEct NETmap
DGAAFPTR	Flush Process Termination Record	FP=FLUSH PROCess
DGAAFMCR	PDS Member Copy Record	MC=PDS member COPY
DGAAPPSR	Process Submit Statistics Record	PS=SUBmit statement SW=SUBmit command
DGAAPTR	Process Termination Record	PT=PROCess
DGAARJTR	Run Job Termination Record	RJ=RUN JOB
DGAARTTR	Run Task Termination Record	RT=RUN TASK
DGAASFR	Signon/Signoff Statistics Record	SI=SIGNON SO=SIGNOFF
DGAASDCR	Start Sterling Connect:Direct Command Record	SD=Start Sterling Connect:Direct
DGAASTDC	Stop Sterling Connect:Direct Statistics Record	ST=STOP Sterling Connect:Direct
DGAAWTOS	Write to Operator (WTO) Statistics Record	WT=Write to Operator

Description of an SAS Variable

The SAS Informat variables for these records are located in the \$CD.SDGAMAP library. An example of an SAS Informat variable is @5 SASFIELD PK1. Variable descriptions for this example are listed in the following table.

Variable	Description
@n	Identifies the position of the variable in the Sterling Connect:Direct statistics record (relative to 1). Always identified by an @.
SASFIELD	Specifies the SAS name for the corresponding Sterling Connect:Direct field name. The SAS name variable must follow the position variable (@n).
PK1	Specifies the type and length of the SAS Informat variable used in the maps. The type variable must follow the name variable (SASFIELD). Type variable used in the maps are: HEX—numeric hexadecimal IB—integer binary PD—packed decimal PIB—positive integer binary PK—packed unsigned \$n—standard character \$CHAR—characters with blanks \$HEX—character hexadecimal \$VARYING—variable-length values

Authorization Event Record

The following table shows each field available in the Authorization Event record. The DGAAAER member of the \$CD.SDGAMAP library contains the SAS maps of the Sterling Connect:Direct statistics record.

Field Names	Field Description
AERECLN	Length of this record.
AERTYPE	Record type indicates specific data in statistics record: IU=INsert; UU=UPDate USER; SU=SElect USER; and DU=DElete USER.
AERTIME	Time that event was recorded in hh/mm/ss/tt format.
AEDATE	Date that event was recorded in Julian date format (yyyydddf).
AEPROCNM	Process name.
AEPROCNO	Process number.
AEUNODE	User node of the submitter.
AEUID	Userid of the submitter.
AESTEP	Step name or label.
AESTIME	Time that Process started in hh/mm/ss/tt format.
AESDATE	Date that Process started in Julian date format (yyyydddf).
AESCC	Step completion code.
AEMSGID	Message ID.
AESDSNL	Length of data set name.
AESDSN	Source data set name.
AESDSTYP	Data set type (LIB, DSN).
AEEVENT	Event code.
AEEVENTQ	Event code qualifier.

Change Process Termination Record

The following table shows each field available in the Sterling Connect:Direct Change Process Termination record. The DGAACPTR member of the \$CD.SDGAMAP library contains the SAS maps of the Sterling Connect:Direct statistics record.

Field Names	Field Description
CHRECLN	Length of this record.
CHRTYPE	Record type – CH indicates the Change Process Termination Record.
CHTIME	Time that CHange PROCess command completed in hh/mm/ss/tt format.
CHDATE	Date that CHange PROCess command completed in Julian date format (yyyymmdd).
CHPROCNM	Process name.
CHPROCNO	Process number.
CHSTEP	Step name or label.
CHUNODE	User node ID of the submitter.
CHUID	Userid of the submitter.
CHSTIME	Time that CHange PROCess command started in hh/mm/ss/tt format.
CHSDATE	Date that CHange PROCess command started in Julian date format (yyyymmdd).
CHSCC	Step completion code-displays normal completion code.
CHMSGID	Message ID.
CHRMNID	Node where message routed.
CHRMUID	Userid where message routed.
CHSCHTME	Time that Process was scheduled in hh/mm/ss/tt format.
CHSCHDTE	Date that Process was scheduled in Julian date format (yyyymmdd).
CHSCHDAY	Day that Process was scheduled.
CHPRTY	New Process priority in the Sterling Connect:Direct Transmission Control Queue (TCQ).
CHRETAIN	Keeps copy in TCQ after execution.
CHPROC	ALL/PROCNAME/PROCNUMBER.
CHNDEST	New destination node.
CHHOLD	Process status in hold queue: Q=quiesce or I=immediate.
CHNPRTY	New priority.
CHREL	Release Processes=R.
CHRET	Retain Processes=R.
CHNRMNID	New node ID messages to be routed.
CHNRMUID	New userid messages to be routed.
CHNEWTME	New scheduled time in hh/mm/ss/tt format.
CHNEWDTE	New scheduled date in Julian date format (yyyymmdd).

Copy Termination Record

The following table shows each field available in the Copy Termination record. The DGAACR member of the \$CD.SDGAMAP library contains the SAS maps of the statistics record.

Field Names	Field Description
CTRECLN	Length of this record.
CTRTYPE	Record type – CT indicates the Copy Termination record.
CTTIME	Time that COPY step completed in hh/mm/ss/tt format.
CTDATE	Date that COPY step completed in Julian date format (yyyydddf).
CTSTIME	Time that COPY step started in hh/mm/ss/tt format.
CTSDATE	Date that COPY step started in Julian date format (yyyydddf).
CTSCC	Step completion code. Displays normal completion code.
CTMSGID	Message ID.
CTPROCNM	Process name.
CTPROCNO	Process number.
CTSTEP	Step name or label.
CTUNODE	User node ID of the submitter.
CTUID	Userid of the submitter.
CTPNODE	Name of the node examining its Sterling Connect:Direct statistics file.
CTSNODE	Name of the other node.
CTNODE	This node is P(node) or S(node).
CTFROM	Direction of data: Snode to Pnode or Pnode to Snode
CTTRANS	File translation. Includes: ASCII-TO-EBCDIC; EBCDIC-TO-ASCII; EBCDIC-TO-ASCII DIF; compressed; and compacted.
CTTRANS2	Transmission options. Includes: PDS-to-PDS copy; error originated on other node; sending PDS member to sequential DSN; sending DSN sequential DSN to PDS member; and COPY is restarted.
CTRUSZ	Request/response unit (RU) size.
CTPACCT#	Displacement to Pnode account data length.
CTSACCT#	Displacement to Snode account data length.
CTINBYTE	Number of bytes read from data set.
CTINRECN	Number of records read from data set.
CTINBLK	Number of blocks read from data set.
CTSBYTES	Number of bytes sent.
CTOBYTE	Number of bytes written to data set.
CTOTRECN	Number of records written to data set.
CTOTBLK	Number of blocks written to data set.

Field Names	Field Description
CTRBYTES	Number of bytes received.
CTNOKB	Number of kilobytes sent.
CTNOMEMS	Number of members sent.
CTNOALIS	Number of aliases sent.
CTNOMEMX	Number of members selected but not sent.
CTNOALIX	Number of aliases selected but not sent.
CTNOMEMR	Number of members received.
CTNOALIR	Number of aliases received.
CTCMPTBL	The compaction table name.
CTSDSTYP	Source data set type: ESDS, KSDS, RRDS, PDS, SAM, or LIB.
CTSDISP1	Source data set disposition status: O=OLD and S=SHR.
CTSDISP2	Source data set disposition normal termination: D=DELETE and K=KEEP.
CTSDISP3	Source data set disposition abnormal termination: D=DELETE and K=KEEP.
CTSDSNL	Length of the source data set name.
CTSDSN	Source data set name.
CTTYPE	Type file key, if Type is specified in a Process step.
CTDDSTYP	Destination data set type.
CTDDISP1	Destination data set disposition status: M=MOD; N=NEW; O=OLD; and S=SHR.
CTDDISP2	Destination data set disposition normal termination: C=CATLG and K=KEEP.
CTDDISP3	Destination data set disposition abnormal termination: C=CATLG; K=KEEP; and D=DELETE.
CTDDSNL	Length of destination data set name.
CTDDSN	Destination data set name.
CTMEMBER	Member name for PS to PO copies.
CTOMSGID	Message ID from other node.
CTRTRNCD	Return code from other node.
CTNVTAMS	Number of VTAM sends.
CTNVTAMR	Number of VTAM receives.
CTDSPVLR	Displacement of receiving VOLSER list.
CTDSPVLS	Displacement of sending VOLSER list.
CTTBOFS	TCP buffer size used.
CTV2BUF5	V2 buffer size.
CTNEGBF	Negotiated V2 buffer size.
CTSUBJOB	Submitter's jobname
CTSUBJID	Submitter's jobid

Delete Process Termination Record

The following table shows fields available in the Delete Process Termination record. The DGAADPTR member of the \$CD.SDGAMAP library contains the SAS maps of the statistics record.

Field Names	Field Description
DPRECLN	Length of this record.
DPRTYPE	Record type—DP indicates the Delete Process Termination record.
DPTIME	Time that DELEte PROCess command completed in hh/mm/ss/tt format.
DPDATE	Date that DELEte PROCess command completed in Julian date format (yyyydddf).
DPPROCNM	Process name.
DPPROCNO	Process number.
DPSTEP	Step name or label.
DPUNODE	User node iD of the submitter.
DPUID	Userid of the submitter.
DPSTIME	Time that DELEte PROCess command started in hh/mm/ss/tt format.
DPSDATE	Date that DELEte PROCess command started in Julian format (yyyydddf).
DPSCC	Step completion code. Displays normal completion code.
DPMSGID	Message ID.
DPDPRNM	Name of the deleted Process.
DPDPRNOP	Number of the deleted Process.
DPRMNID	Route message node of deleted Process.
DPRMUID	Route message userid of deleted Process.

Display Statistics Record

The following table contains each field available in the Display Statistics record. The DGAADTR member of the \$CD.SDGAMAP library contains the SAS maps of the statistics record.

Field Name	Field Description
DTRECLN	Length of this record.
DTRTYPE	Record type indicates specific data in statistics record: SP=SELEct PROCess; DT=SELEct TASK; FT=FLUSH TASK; SS=SELEct STATistics; and SN=SELEct NETMAP.
DTTIME	Time that command completed in hh/mm/ss/tt format.
DTDATE	Date that command completed in Julian date format (yyyydddf).
DTPROCNM	Process name.
DTPROCNO	Process number.
DTSTEP	Step name or label.
DTUNODE	User node ID of the submitter.
DTUID	Userid of the submitter.

Field Name	Field Description
DTSTIME	Time that command started in hh/mm/ss/tt format.
DTSDATE	Date that command started in Julian date format (yyyymmdd).
DTSCC	Step completion code. Displays normal completion code.
DTMSGID	Message ID.
DTDFLNM	Name of the displayed data set.
DTNVTAMS	Number of VTAM sends.
DTNVTAMR	Number of VTAM receives.
DTGETS	Number of GETS.
DTPUTS	Number of PUTS.

Flush/Suspend Process Termination Record

The following table shows each field in the Flush Process/Suspend Process Termination record. The DGAAFPTR member of the \$CD.SDGAMAP library contains the SAS maps of the statistics record.

Field Names	Field Description
FPRECLN	Length of this record.
FPRTYPE	Record type—FP indicates the Flush Process Termination record.
FPTIME	Time that FLUSH PROCess command completed in hh/mm/ss/tt format.
FPDATE	Date that FLUSH PROCess command completed in Julian date format (yyyymmdd).
FPPROCNM	Process name.
FPPROCNO	Process number.
FPSTEP	Step name or label.
FPUNODE	User node ID of the submitter.
FPUID	Userid of the submitter.
FPSTIME	Time that FLUSH PROCess command started in hh/mm/ss/tt format.
FPSDATE	Date that FLUSH PROCess command started in Julian date format (yyyymmdd).
FPSCC	Step completion code. Displays normal completion code.
FPMMSGID	Message ID.
FPDPRNM	Name of the flushed Process.
FPDPRNOP	Number of the flushed Process.
FPRMNID	Route message node of flushed Process.
FPRMUID	Route message userid of flushed Process.

PDS Member Copy Record

The following table shows each field available in the PDS Member Copy record. The DGAAFMCR member of the \$CD.SDGAMAP library contains the SAS maps of the statistics record.

Field Names	Field Description
MCRECLN	Length of this record.
MCRTYPE	Record type—MC indicates the PDS Member Copy record.
MCTIME	Time that COPY step completed in hh/mm/ss/tt format.
MCDATE	Date that COPY step completed in Julian date format (yyyymmdd).
MCSTIME	Time that member processing started in hh/mm/ss/tt format.
MCSDATE	Date that member processing started in Julian date format (yyyymmdd).
MCSCC	Step completion code. Displays normal completion code.
MCMSGID	Message ID.
MCPROCNM	Process name.
MCPROCNO	Process number.
MCSTEP	Step name or label.
MCUNODE	User node ID of the submitter.
MCUID	Userid of the submitter.
MCPNODE	The Pnode name for this Process.
MCSNODE	The Snode name for this Process.
MCNODE	This node is P(node) or S(node).
MCFROM	Direction of data: P(node) to Snode or S(node) to Pnode.
MCTNAME	Name of member on destination PDS.
MCFNAME	Name of member on source PDS (if different).
MCANAME	Name of member for which node is an alias.
MCNRECS	The number of records.
MCNBLKS	The number of blocks.

Process Submit Statistics Record

The following table describes fields in the Process Submit Statistics record. The DGAAPSR member of the \$CD.SDGAMAP library contains the SAS maps of the statistics record.

Field Names	Field Description
PSSRECLN	Length of this record.
PSSRTYPE	Record type indicates specific data in statistics record: PS=SUBmit statement and SW=SUBmit command within a Process.
PSSCTIME	Time that Process completed in hh/mm/ss/tt format.
PSSCDATE	Date that Process completed in Julian date format (yyyymmdd).
PSSSTIME	Time that Process started in hh/mm/ss/tt format.

Field Names	Field Description
PSSSDATE	Date that Process started in Julian date format (yyyydddf).
PSSSCC	Step completion code. Displays normal completion code.
PSSMSGID	Message ID.
PSSPRCNM	Process name.
PSSPRCNO	Process number.
PSSSTEP	Step name or label.
PSSUNODE	Submitter's symbolic node name.
PSSUID	Userid of the submitter.
PSSPNODE	Pnode name for this Process.
PSSSNODE	Snode name for this Process.
PSSNODE	This node is P(node) or S(node).
PSSFROM	Direction of data: P(node) to Snode or S(node) to Pnode.
PSSROSIZ	The number of bytes in the Process.
PSSRMNID	Route message userid of Process.
PSSFUNCD	The function code for the SUBMIT.
PSSSYNTAX	The syntax error in SUBmit command.
PSSPARSE	The parse error in SUBmit command.
PSSPACT#	Displacement to Pnode account data.
PSSSACT#	Displacement to Snode account data.
PSSDSN#	Displacement to data set name.
PSSSUBJOB	Submitter's jobname
PSSSUBJID	Submitter's jobid

Process Termination Record

The following table describes fields in the Process Termination record. The DGAAPTR member of the \$CD.SDGAMAP library contains the SAS maps of the Sterling Connect:Direct statistics record.

Field Names	Field Description
PTRECLN	Length of this record.
PTRTYPE	Record type—PT indicates the Process Termination record.
PTTIME	Time that Process completed in hh/mm/ss/tt format.
PTDATE	Date that Process completed in Julian date format (yyyydddf).
PTSTIME	Time that Process started in hh/mm/ss/tt format.
PTSDATE	Date that Process started in Julian date format (yyyydddf)
PTSCC	Step completion code. Displays normal completion code.
PTMSGID	Message ID.
PTPROCNM	Process name.
PTPROCNO	Process number.
PTSTEP	Step name or label.
PTUNODE	Submitter's symbolic node name.

Field Names	Field Description
PTUID	Userid of the submitter.
PTPNODE	Pnode name for this Process.
PTSNODE	Snode name for this Process.
PTNODE	This node is P(node) or S(node).
PTFROM	Direction of data: P(node) to Snode or S(node) to Pnode.
PTUNPRNO	Process number unique to submitter's node.
PTRMID	Route message userid of Process.
PTRMUID	Userid where message is routed.
PTSUBTME	Time that Process was submitted in hh/mm/ss/tt format.
PTSUBDTE	Date that Process submitted in Julian date format (yyyymmdd).
PTSCHTME	Time that Process was scheduled in hh/mm/ss/tt format.
PTSCHDTE	Date that Process was scheduled in Julian date format (yyyymmdd).
PTSCHDAY	Day Process was scheduled.
PTSTMTN	Number of statements.
PTPRTY	Process selection priority.
PTSUBJOB	Submitter's jobname
PTSUBJID	Submitter's jobid

Run Job Termination Record

The following table describes fields in the Run Job Termination record. The DGAARJTR member of the \$CD.SDGAMAP library contains the SAS maps of the statistics record.

Field Names	Field Description
RJRECLN	Length of this record.
RJRTYPE	Record type—RJ indicates the Run Job Termination record.
RJTIME	Time that RUN JOB step completed in hh/mm/ss/tt format.
RJDATE	Date that RUN JOB step completed in Julian date format (yyyymmdd).
RJSTIME	Time that RUN JOB step started in hh/mm/ss/tt format.
RJSDATE	Date that RUN JOB step started in Julian date format (yyyymmdd).
RJSCC	Step completion code. Displays normal completion code.
RJMSGID	Message ID.
RJPROCNM	Process name.
RJPROCNO	Process number.
RJSTEP	Step name or label.
RJUNODE	Submitter's symbolic node name.
RJUID	Userid of the submitter.
RJPNODE	Pnode name for this Process.
RJSNODE	Snode name for this Process.

Field Names	Field Description
RJNODE	This node is P(node) or S(node).
RJFROM	Direction of data: P(node) to Snode or S(node) to Pnode.
RJJOBNM	Job name.
RJJOBNO	Job number.
RJSYRCD	System return code.
RJDDSN	Displacement to data set name.
RJPACCT#	Displacement to Pnode account data.
RJSACCT#	Displacement to Snode account data.
RJSUBJOB	Submitter's jobname
RJSUBJID	Submitter's jobid

Run Task Termination Record

The following table shows each field in the Run Task Termination record. The DGAARTTR member of the \$CD.SDGAMAP library contains the SAS maps of the statistics record.

Field Names	Field Description
RTRECLN	Length of this record.
RTRTYPE	Record type—RT indicates the Run Task Termination record.
RTTIME	Time that RUN TASK step completed in hh/mm/ss/tt format.
RTDATE	Date that RUN TASK step completed in Julian date format (yyydddff).
RTSTIME	Time that RUN TASK step started in hh/mm/ss/tt format.
RTSDATE	Date that RUN TASK step started in Julian date format (yyydddff).
RTSCC	Step completion code. Displays normal completion code.
RTMSGID	Message ID.
RTPROCNM	Process name.
RTPROCNO	Process number.
RTSTEP	Step name or label.
RTUNODE	Submitter's symbolic node name.
RTUID	Userid of the submitter.
RTPNODE	Pnode name for this Process.
RTSNODE	Snode name for this Process.
RTNODE	This node is P(node) or S(node).
RTFROM	Direction of data: P(node) to Snode or S(node) to Pnode.
RTMODNM	Name of the RUN TASK program.
RTSYSRTN	System return code.
RTPARMLN	Length of the parameter list.
RTPACCT#	Displacement to Pnode account data.
RTSACCT#	Displacement to Snode account data.
RTSUBJOB	Submitter's jobname

Field Names	Field Description
RTSUBJID	Submitter's jobid

Signon/Signoff Statistics Record

The following table shows each field in the Signon/Signoff Statistics record. The DGAASFR member of the \$CD.SDGAMAP library contains the SAS maps of the statistics record.

Field Names	Field Description
SIRECLN	Length of this record.
SIRTYPE	Record type indicates specific data in the statistics record: SI=SIGNON command and SO=SIGNOFF command.
SITIME	Time that SIGNON/SIGNOFF command completed in hh/mm/ss/tt format.
SIDATE	Date that SIGNON/SIGNOFF command completed in Julian date format (yyyymmdd).
SIUNODE	User symbolic node ID.
SIUID	Userid of the submitter.
SISCC	Step completion code. Displays normal completion code.
SIMSGID	Message ID.

Start Sterling Connect:Direct Command Record

The following table shows each field available in the Start Sterling Connect:Direct Command record. The DGAASDCR member of the \$CD.SDGAMAP library contains the SAS maps of the Sterling Connect:Direct statistics record.

Field Names	Field Description
SDRECLN	Length of this record.
SDRTYPE	Record type--SD indicates the Start Sterling Connect:Direct Command record.
SDTIME	Time that Start Sterling Connect:Direct command completed in hh/mm/ss/tt format.
SDDATE	Date that Start Sterling Connect:Direct command completed in Julian date format (yyyymmdd).
SDPROCNM	Process name.
SDPROCNO	Process number.
SDSTEP	Step name or label.
SDUNODE	Submitter's symbolic node name.
SDUID	Userid of the submitter.
SDSTIME	Time that Start Sterling Connect:Direct command was issued in hh/mm/ss/tt format.
SDSDATE	Date the Start Sterling Connect:Direct command was issued in Julian date format (yyyymmdd).
SDSCC	Step completion code. Displays normal completion code.
SDMSGID	Message ID.

Stop Sterling Connect:Direct Statistics Record

The following table shows each field available in the Stop Statistics record. The DGAASTDC member of the \$CD.SDGAMAP library contains the SAS maps of the statistics record.

Field Names	Field Description
TDRECLN	Length of this record.
TDRTYPE	Record type—ST indicates the Stop Sterling Connect:Direct Statistics record.
TDTIME	Time that STOP Sterling Connect:Direct command completed in hh/mm/ss/tt format.
TDDATE	Date that STOP Sterling Connect:Direct command completed in Julian date format (yyyymmdd).
TDPROCNM	Process name.
TDPROCNO	Process number.
TDSTEP	Step name or label.
TDUNODE	User node of the submitter.
TDUID	Userid of the submitter.
TDSTIME	Time that STOP Sterling Connect:Direct command was issued in hh/mm/ss/tt format.
TDSDATE	Date that STOP Sterling Connect:Direct command was issued in Julian date format (yyyymmdd).
TDSCC	Step completion code. Displays normal completion code.
TDSTOP	Sterling Connect:Direct shutdown types: W=Step shutdown; X=Immediate shutdown; Y=Quiescent shutdown; and Z=Forced shutdown by an abend.
TDMSGID	Message ID.

Write to Operator (WTO) Statistics Record

The following table shows each field available in the WTO Statistics record. The DGAAWTOS member of the \$CD.SDGAMAP library contains the SAS maps of the statistics record.

Field Names	Field Description
WTRECLN	Length of this record.
WTRTYPE	Record type—WT indicates the WTO Statistics record.
WTCTIME	Time that Process completed in hh/mm/ss/tt format.
WTCDATE	Date that Process completed in Julian date format (yyyymmdd).
WTSTIME	Time that function started in hh/mm/ss/tt format.
WTSDATE	Date that function started in Julian date format (yyyymmdd).
WTSCC	Step completion code. Displays normal completion code.
WTMSGID	Message ID.
WTPROCNM	Process name.
WTPROCNO	Process number.
WTSTEP	Step name or label.
WTUNODE	Submitter's symbolic node name.

Field Names	Field Description
WTUID	Userid of the submitter.
WTPNODE	The Pnode name for this Process.
WTSNODE	The Snode name for this Process.
WTNODE	This node is P(node) or S(node).
WTFROM	Direction of data: P(node) to Snode or S(node) to Pnode.
WTTASKNO	Task number that issued the WTO.

Chapter 7. The Operator Interface

The Operator Interface enables you to issue Sterling Connect:Direct for z/OS commands from a z/OS console using a MODIFY command.

Access the Operator Interface after Sterling Connect:Direct initializes if you specify the initialization parameters MCS.CLIST and MCS.SIGNON.

Following is the syntax for the MCS.CLIST and MCS.SIGNON initialization parameters:

```
MCS.CLIST=console operator's CLIST library (dsn)
MCS.SIGNON=(SIGNON USERID=(userid,password)      -
            CASE=YES | NO -
            NETMAP=network map file name)
```

An automatic signon is issued after the first Sterling Connect:Direct CLIST is invoked using the information in MCS.SIGNON. This session is active until you submit a CLIST that contains a Sterling Connect:Direct SIGNOFF command.

Note: The NETMAP used by the MCS.SIGNON must be the same as the NETDSN in the INITPARMs for this DTF. If a different NETMAP is used, LOCAL.NODE information from that NETMAP will be used for a SIGNON, and the commands to this DTF will be executed on the other DTF if it is running.

You can create easy to remember customized Sterling Connect:Direct commands with the Operator Interface through a CLIST-type facility. The software supports symbolic substitution and CLIST-type parameters allowing you to alter Sterling Connect:Direct commands without changing the CLIST.

In a Sterling Connect:Direct/Plex, if you issue a console operator command to a Sterling Connect:Direct/Server, the console interface actually signs on to the Sterling Connect:Direct/Manager. As a result, any commands issued to Sterling Connect:Direct/Server are actually issued to the Sterling Connect:Direct/Manager, which is the only Sterling Connect:Direct/Plex member that accepts operator commands.

Sample Sterling Connect:Direct for z/OS CLISTs

The Sterling Connect:Direct sample CLIST library, SDGAOPLS, contains the sample CLISTs included in the following table. Use these CLISTs to build customized Sterling Connect:Direct commands with symbolic parameters that allow you to customize the CLIST at submission time. Sample operator commands for each CLIST are listed in the comment section.

CLIST Name	Command	Description
DGAOCMD	CMD	Provides a general format for issuing a Sterling Connect:Direct command.
DGAODP	DELETE PROCESS	Shows six ways to delete a Process using this CLIST.

CLIST Name	Command	Description
DGAODUMP	STOP CD (Force)	Stops Sterling Connect:Direct using the FORCE parameter and produces abnormal ending (abend) 4095 and a dump.
DGAOIPRM	DISPLAY INITPARMS	Displays initialization parameters to the operator console. In a PLEX environment, it works as follows: <ul style="list-style-type: none"> • Displays the global initialization parameters • Defaults to the manager's local initialization parameters • Allows the name of a server to display the server's global and local initialization parameters
DGAOMSG	SELECT MSG	Shows a detail of the Sterling Connect:Direct message requested.
DGAONM	SELECT NETMAP	Displays entire NETMAP or it allows for one parameter – a node name.
DGAORLSE	CHANGE PROCESS	Shows three ways to release a Process.
DGAOSOFF	SIGNOFF	Signs the operator off Sterling Connect:Direct.
DGAOSON	SIGNON	Connects the operator to Sterling Connect:Direct.
DGAOSP	SELECT PROCESS	Shows six ways to display Process status information.
DGAOSS	SELECT STATISTICS	Shows seven ways to select statistics for display.
DGAOSTAT	SELECT STATISTICS	Shows three ways to select statistics for display covering a specific time period.
DGAOSTOP	STOP CD	Stops Sterling Connect:Direct using the STOP IMMEDIATE command. To perform an immediate shutdown in a PLEX environment from the operator console, issue the following command: F CD,STOP CDPLEX. To stop a specific server, use this command: F CD,STOP WHERE(SERVER=name)
DGAOSUB	SUBMIT PROCESS	Shows two ways to submit a Process.
DGAOSUSP	SUSPEND PROCESS	Shows four ways to suspend a Process.
DGAOSWAP	SWAP NODE	Swaps operator to another node in a multiple session environment.
DGAOTS	SELECT TASK	Shows active tasks.
DGAOVP	VIEW PROCESS	Displays a specific Process.

Rules for Setting Up Sterling Connect:Direct for z/OS CLISTs

The following rules apply when setting up an operator CLIST:

- All operator CLISTs must have a PROC record as the first record in the CLIST. The PROC record defines the parameters and keywords that are passed to the CLIST.
- You can stack multiple Sterling Connect:Direct commands in one CLIST, but you only need one PROC statement.
- A number between 0 and 24 (inclusive) must follow the PROC identifier. This number indicates the number of positional parameters used by the CLIST.

- Parameter names (one to eight characters each) that correspond to each positional parameter follow the number. If no positional parameters exist, specify PROC 0.
- If you define more than one positional parameter on the PROC statement, you do not need to specify trailing positional parameters in the command unless you also specify a keyword parameter.
- Use commas to indicate null values.
- A positional parameter is terminated by the first blank encountered.
- You can specify optional keyword parameters after the positional parameters. Enclose default values in parentheses after each keyword name.
- Use a hyphen (-) to indicate that a Sterling Connect:Direct command continues on the next line. An example follows.

```
PROC 1 PNUM
SELECT PROCESS WHERE(      -
                        PNUM=&PNUM)
```

- You can use comments in the CLIST only if you include an asterisk (*) in the first column.
- Sequence numbers are not allowed.

Sterling Connect:Direct for z/OS Commands

Submit the Sterling Connect:Direct commands to the Operator Interface using the MODIFY command interface. This operator command lets you submit a CLIST containing Sterling Connect:Direct commands, and modify the Sterling Connect:Direct commands by substituting symbolic parameters with real values.

The command format is:

```
F jobname,clist [options]
```

Following is a description of the parameters:

Parameter	Description
F	The short form of the Administrator MODIFY command.
jobname	The name on the job statement of the job stream that brings up the DTF. Caution: If jobname is a Sterling Connect:Direct/Server, the command is redirected to the Sterling Connect:Direct/Manager.
clist	The name of the CLIST containing the Sterling Connect:Direct command.
options	Optional positional and keyword parameters to be passed to the CLIST.

CLIST Examples

The following are CLIST examples and operator commands that submit the CLIST examples. As some examples show, you can use symbolic parameters to modify the Sterling Connect:Direct command at the time of submission. For example purposes, CDDTF is the jobname.

CLIST with Command and No Parameters

The following CLIST SELX command contains one command and no parameters:

```
PROC 0 SEL PROC WHERE(QEUE=EXEC)
```

To execute SELX, type the following operator command.

```
F CDDTF,SELX
```

When you issue the operator command, a Select Process command for Processes on the executing queue initiates. As a result, a list of these Processes is displayed.

CLIST with Command and One Parameter

In this example, the CLIST SELQ contains one command and one positional parameter (SUBD).

```
PROC 1 SUBD SEL PROC WHERE(QEUE=&SUBD)
```

The following options present two ways to submit SELQ:

- When you issue the following command, TIMER (timer queue) is substituted for &SUBD. This command displays all Processes on the timer queue.

```
F CDDTF,SELQ TIMER
```

- When you issue the following command, ALL is substituted for &SUBD in the CLIST SELQ. This command displays all Processes on all queues.

```
F CDDTF,SELQ ALL
```

CLIST with Command and Multiple Parameters

In this example, the CLIST SUB contains one command, two positional parameters (PROC and PARMS), and one keyword parameter (SNODE).

```
PROC 2 PROC PARMS SNODE(OTHER.NODE) SUB PROC=&PROC SNODE=&SNODE &PARMS
```

The following options present four ways to execute SUB:

- When you issue the following command, PAYROLL is substituted for &PROC. This substitution causes the Process PAYROLL to be submitted.

```
F CDDTF,SUB PAYROLL
```

- Because no SNODE is specified, the SNODE defaults to OTHER.NODE.
- When you issue the following command, CHECKS is substituted for &PROC and HOLD=YES is substituted for &PARMS. These cause the Process CHECKS to be submitted as a held Process.

```
F CDDTF,SUB CHECKS HOLD=YES
```

Because no SNODE is specified, the SNODE defaults to OTHER.NODE.

- When you issue this command, ORDERS is substituted for &PROC and CD.CHICAGO is substituted for &SNODE. These cause the Process ORDERS to be submitted to run in session with the secondary node called CD.CHICAGO.

```
F CDDTF,SUB ORDERS,,SNODE=(CD.CHICAGO)
```

Because PROC and PARMS are positional parameters, commas are required.

- When you issue the following command, CONFIRM is substituted for &PROC and HOLD=NO,STARTT=(FRIDAY,NOON) is substituted for &PARMS. These submit the Process CONFIRM so that it runs at noon on Friday.

```
F CDDTF,SUB CONFIRM HOLD=NO,STARTT=(FRIDAY,NOON)
```

The SNODE defaults to OTHER.NODE because no SNODE is specified.

CLIST with Command and %IF %ELSE %EIF

In this example, the CLIST NM contains 1 command and 1 positional parameter.

```
PROC 1 NODE
  %IF &NODE = ,
  SEL NETMAP WHERE (NODE=*)
  %ELSE
  SEL NETMAP WHERE (NODE=&NODE)
  %EIF
```

If you enter no operands it displays the entire netmap. If you enter a node it displays that node only.

Operation Messages

Sterling Connect:Direct operation diagnostic messages are formatted into multiple lines so that errors and exception conditions are easy to read. Operator messages are sent to:

- The route code given in the Sterling Connect:Direct initialization parameters
 - The ddname NDMLOG, if it is allocated
- The COPY termination message (SVTM052I) is displayed in four lines, as follows:
- The first line shows the step label, the operation (COPY), the Process name and number, the associated node name, and the session class.
 - The second line shows the FROM file name.
 - The third line shows the TO file name.
 - The fourth line shows the completion code and message ID. If the COPY does not complete successfully, the first four positions of the last line contain the "####" flag.

When session errors occur, the error message is formatted into two lines, as follows:

- The first line gives as much information as possible in the same format as the COPY termination message (Process name and number, and associated node name).
- The second line gives the text of the error message. The first four positions of the second line contain the "****" flag.

The following example shows two Sterling Connect:Direct operation error messages following a COPY termination message.

```
SVTM052I STEP1 COPY PROCESS1( 126)PNODE=CD.NODE.A (002)
FROM SYSA.SAM.DATA.SET
TO SYSB.TEST.SAM.DATA.SET
#### COMPLETED 00000010/SCPA010I
SVTM045I PROCESS1( 126)PNODE=CD.NODE.A
**** RPLERRCK:CD/CD SESSION FAILURE
SVTM050I PROCESS1( 126)PNODE=CD.NODE.A
**** PROCESS INTERRUPTED:RECOVERY INITIATED
```

Stopping Sterling Connect:Direct

To stop Sterling Connect:Direct for z/OS, use the following command, which executes the STOP CLIST using the Operator Interface.

```
F jobname,STOP
```

Following is a description of the parameters:

Parameter	Description
F	The short form of the Administrator MODIFY command.
jobname	The name on the job statement of the job stream that brings up the DTF. Caution: If jobname is a Sterling Connect:Direct/Server, the command is redirected to the Sterling Connect:Direct/Manager.
clist	The name of the CLIST containing the Sterling Connect:Direct command.
options	Optional positional and keyword parameters to be passed to the CLIST.

Stopping a Sterling Connect:Direct/Plex Manager and All Servers

To stop a Sterling Connect:Direct/Plex from the console, use the following command which executes the STOP CLIST using the Operator Interface:

```
F jobname,STOP [Q|S|I|R|F,] CDPLEX [,RECOVER]
```

Stopping an Individual Sterling Connect:Direct/Plex Server

To stop a Sterling Connect:Direct/Plex Server from the console, use the following command which executes the STOP CLIST using the Operator Interface:

```
F jobname,STOP [Q|S|I|R|F,] WHERE(SERVER=name) [,RECOVER]
```

About Tape Mount Messages

Sterling Connect:Direct for z/OS supports the transmission of tape files. Sterling Connect:Direct implements separate and distinct messages to control tape management, providing the greatest flexibility to operators in managing tape transfers.

Tape Pre-mount Message

This optional message is issued prior to allocating a tape device. It tells you that Sterling Connect:Direct requires a specific volume on a specific device type. With this message, you can:

- Control the number of tape units available to Sterling Connect:Direct for tape transfers.
- Locate the volumes before the transfer occurs.

You are required to respond to this message when the required resources are available.

Tape Mount Messages

These messages are also optional. The first message (WTO) is in the format of the z/OS mount message. The second message is issued as a WTOR to inform the operator to mount a specific volume on a specific device. The third message is issued only if TAPE.PRE MOUNT=LIST. Message SVST00C is displayed listing all volume-serial numbers of the requested file. If you are unable to satisfy the specific request, you can reply CANCEL to cancel the request. This message is also used to drive the visual display devices attached to 3480-type devices.

Note: If you use tape silos in your environment, search for Tapemount Exit. To prevent the Sterling Connect:Direct environment from locking up due to an outstanding tape mount request, the Sterling Connect:Direct tapemount exit provides an interface to StorageTek Tape Silo Software to query the silo to determine that all VOLS required for a tape file are present.

Setting Up Sterling Connect:Direct for z/OS Tape Pre-mount Messages

Procedure

To issue the Sterling Connect:Direct tape pre-mount messages, specify TAPE.PRE MOUNT=YES | LIST in the Sterling Connect:Direct initialization parameter file.

Setting Up Sterling Connect:Direct for z/OS Tape Mount Messages

- Issue the Sterling Connect:Direct tape mount messages in place of the z/OS mount message. The Sterling Connect:Direct mount messages consist of a z/OS-format mount message followed by a WTOR issued to the descriptor and route codes specified by the DESC.TAPE and ROUTCDE.TAPE.
- You can suppress the Sterling Connect:Direct message by specifying ROUTCDE.TAPE=(0) in the initialization parameters. The defaults are DESC.TAPE=(2) ROUTCDE.TAPE=(5,11). If you suppress Sterling Connect:Direct tape mount messages, the standard z/OS mount messages are issued with related serialization during mount processing.
- If you specify ROUTCDE.TAPE=(0), causing Sterling Connect:Direct not to issue the mount messages, then the normal z/OS mount message is issued when the dataset is opened. The z/OS mount processing holds an ENQ on the SYSZTIOT resource. This ENQ causes all other Sterling Connect:Direct Processes to hang at allocation, open, and deallocation until the tape is mounted.

- If you use the Sterling Connect:Direct tape mount message, the tape already is on the tape drive at open time and z/OS mount processing does not hold the SYSZTIOT resource.

Sterling Connect:Direct for z/OS Tape Pre-mount Messages


Following is the format of a Sterling Connect:Direct tape pre-mount message.

```
SVST000B - C:D REQUIRES VOL=SCRATCH TYPE=TAPE 6250/1600BPI
REPLY "GO" WHEN READY
```

To continue processing, reply GO to the message. While this message is outstanding, no unit is allocated. However, the session for this transfer request remains active.

Sterling Connect:Direct for z/OS Tape Mount Messages

Following is the format of a Sterling Connect:Direct tape mount message issued during a specific tape request.



If no tape is available or if you want to end the copy, reply CANCEL to the tape mount message.

Tape Device Allocation

After the GO reply to a pre-mount message, and following the pre-mount processing, Sterling Connect:Direct allocates a tape device using Defer mounting. If an allocation error occurs, and the allocation error code is in the ALLOC.CODES parameter of the Sterling Connect:Direct initialization parameters, Sterling Connect:Direct retries the operation.

When device allocation completes successfully, Sterling Connect:Direct issues a z/OS-format Open mount message to allow tape management and visual display routines to process the request. The format of the message follows.

```
IEC501A M,cuu,volser,s1,,jobn,dsn,pnum,pnam,step
```

Following the IEC501A message, Sterling Connect:Direct issues a WTOR to allow you to mount the tape or cancel the request.

Terminating the Tape Mount

A COPY step within a Process requiring a tape to be mounted causes the tape mount message to display. You can terminate the COPY step with a CANCEL reply. Any other reply causes Sterling Connect:Direct to reissue the mount message.

If you are using both the tape pre-mount message and the tape mount message, and want to cancel the request, reply GO to the tape pre-mount (SVST000B) and CANCEL to the tape mount message (SVST000A). If you do not want to terminate the copy step, the mount message disappears when the tape is mounted.

Verifying Volume Requests

For standard label tapes, Sterling Connect:Direct for z/OS verifies the volume serial number for a specific volume request. If you mount the wrong volume, the following message is issued and the volume is dismounted.

```
SVST001I - D cuu,volser --- IS NOT THE REQUESTED VOLUME
```

Mount the correct volume, or reply CANCEL to the reissued SVST000A mount message.

Handling Multivolume Files

The Sterling Connect:Direct for z/OS mount message is issued only for the first volume of a file, when a multivolume file is requested. Subsequent mount requests causes a SYSZTIOT enqueue during end-of-volume processing.

To keep Sterling Connect:Direct from long waits while a second or subsequent volume is mounted, use UNIT=(unit,P) or UNIT=(unit,n) for the UNIT keyword of the COPY statement.

Sterling Connect:Direct for z/OS Messages on 3480 Display

The 3480 tape drive has an 8-character display. Sterling Connect:Direct issues messages to this display concerning tape processing in the following manner:

- When a tape is to be dismounted, the first character position of the display contains a D. Positions 2–7 consist of the tape's volume serial number. Position eight contains an N if the tape is nonlabeled or an S if the tape has standard labels.
- When a tape is to be mounted, the first character position of the display contains an M. Positions 2–7 consist of the tape's volume serial number. Position eight contains an N if the tape is nonlabeled or an S if the tape has standard labels.
- When a tape is loaded, the first character position of the display is blank. Positions 2–7 consist of the tape's volume serial number. Position eight contains an N if the tape is nonlabeled or an S if the tape has standard labels.

Chapter 8. Event Services Support

Sterling Connect:Direct Event Services Support (ESS) implements an asynchronous, event-generation facility in Sterling Connect:Direct. ESS is designed for use by external management and automated operations applications that require real-time notification of Sterling Connect:Direct activities. ESS supports a publish or subscribe protocol with optional guaranteed event delivery and automated recovery.

Customer applications register interest in receiving event data, and specify the types of event data the application receives through the new event services commands. ESS supports a user exit point and an optional API for interface communication with user-written CICS automation applications.

ESS Concepts and Components

ESS provides real-time delivery of Sterling Connect:Direct event records to interested application interfaces. ESS is based on the existing Sterling Connect:Direct statistics facility and is designed to:

- Minimize the server-performance overhead for ESS processing
- Prevent adverse impact on Sterling Connect:Direct server reliability

ESS is a low-level Sterling Connect:Direct server technology that enables you to layer multiple APIs. An end-user application interfaces with the API rather than the low-level ESS core technology. This design enables future extension of ESS to support multiple application interface protocols and publishing of the same event data to several event consumer applications.

System Interfaces

ESS supports the event services exit and the CICS API interface.

An application can access event data through an ESS exit. A sample event exit (DGAXEV01) is in the sample library, and writes the event data to a predefined data set.

A CICS API initiates event processing by signing on to Sterling Connect:Direct through the current CICS API and issuing ESS commands. The CICS API provided with Sterling Connect:Direct writes event data to a CICS Transient Data Queue (TDQ). A sample program, DGAQ249, shows how to read an event record from the TDQ.

System Advantages

Building on the existing statistics facility has the following advantages:

- Event Definition
Because ESS event records are Sterling Connect:Direct statistics records, ESS does not restrict events to abnormal activities. This design enables ESS-enabled applications to initiate procedures based on either successful or unsuccessful Process statements.
- Historical Data Recovery

The Sterling Connect:Direct statistics file functions as the historical repository of ESS event data. ESS supports optional automated recovery of past event data if an event consumer application fails. Upon restart, ESS requests old event records from the statistics file.

The API automatically manages the restart point for an ESS-enabled application. This API tracks the last successfully delivered event record to a designated subscriber. Upon restart, the API resynchronizes event processing by issuing a SELEct STATistics command to retrieve the historical event data and deliver it to the restarted event consumer.

- Event Record Types

The event record types give external applications greater visibility into Sterling Connect:Direct activities and improve the reliability and responsiveness of interface applications in a production environment. ESS supports several Sterling Connect:Direct event record types, including:

- Process Initialization (PI) occurs immediately prior to the execution of the first Process statement in a Process.
- Step Start (CI, JI, TI) events occur immediately prior to the execution of a COPY, RUN JOB, or RUN TASK statement.
- COPY Step I/O Start (CE) occurs just before the first COPY step I/O in a Process.
- Queue Change (QW, QH, QE, QT) events occur whenever a Process moves from one logical queue to another in the TCQ. The sample initialization parameters provided in the base Sterling Connect:Direct install the SDGAPARM data set and specify STAT.EXCLUDE=(QE, QH, QT, QW). This specification prevents Sterling Connect:Direct from producing the queue change records. If you want queue change records, you must set this parameter appropriately.

ESS also supports basic event filtering. When an event consumer application registers interest in receiving events, the application can restrict the types of event data that it wants to receive. These options support the same filtering syntax as the SELEct STATistics command. Following are two possible selections:

- A fault management application can request notification of COPY requests that did not complete normally, QH (Queue Hold) events or both. When such an event occurs, the fault management application can then poll Sterling Connect:Direct through SELEct STATistics or SELEct PROCess to investigate the problem further.
- An application registers interest in all events for a small group of mission-critical Processes.

Event Services Support Architecture

ESS uses three components to provide real-time information about Sterling Connect:Direct activities:

- Client application
- API
- Sterling Connect:Direct server

ESS communicates with client application interfaces through the CICS API or an ESS user exit.

The components interact to accomplish the following tasks:

- Define which events are reported to the client application

- Turn event services requests on and off
- Register event data
- Report event data

The following diagram details ESS with a CICS application using the Sterling Connect:Direct CICS API. The structure consists of the following components:


The client application defines the event data requests and issues commands through a user-written program. The DGAE transaction ID causes DGAQ247 to be driven. This sample program demonstrates the method to issue ESS commands.

- The API receives and passes event data and ESS commands to the Sterling Connect:Direct server, and maintains information for the guaranteed delivery feature.
- The Sterling Connect:Direct server is the Data Transmission Facility (DTF) that processes ESS commands and sends the requested event data to the client application through the API.

```

//JOBNAME JOB (ACTNG), 'PROGRAM', NOTIFY=PSJOB, TIME=(11), COND=(0,NE),
// REGION=10248,MSGCLASS=,CLASS=
//*****
//** THIS JCL CAN BE EDITED TO CREATE A JOB STREAM THAT KIDS
//** ARE INDEPENDENTLY OF THE AS2 PANELS. IT IS SET UP TO
//** PRODUCE MULTIPLE REPORTS. FOLLOW THE INSTRUCTIONS OUTLINED BELOW.
//**
//**
//** 1) MODIFY JOB CARD WITH APPROPRIATE INFORMATION.
//** 2) CHANGE SCD.SCDALINK TO BE THE NAME OF THE C/D LOAD LIBRARY.
//** 3) CHANGE SCD.SCDAPROC TO BE THE NAME OF THE C/D PROCESS LIBRARY.
//** 4) CHANGE ALL OCCURRENCES OF SCD.MSG TO THE NAME OF THE C/D
//** MESSAGE DATA SET.
//** 5) CHANGE SCD IN SIGNON CMD TO YOUR C/D USERID-ADD PWD IF NEC.
//** 6) CHANGE SCD.NETMAP TO YOUR NETWORK MAP DATA SET NAME.
//** 7) CHANGE ALL OCCURRENCES OF UNITNAME TO VALID UNIT.
//** 8) CHANGE SCDPROC TO THE NAME OF SAS CATALOGED PROCEDURE USED AT
//** YOUR INSTALLATION.
//** 9) ROUTE OUTPUT TO A SYSTMT CLASS (LOOK FOR PFD0F001 ID)
//**
//** OR ...
//**
//** 9) CHANGE ALL OUTPUT.DATASET.NAME TO THE NAME OF THE DATA SET YOU
//** HAVE CHOSEN TO ROUTE THE OUTPUT TO. THIS DATA SET SHOULD BE
//** ALLOCATED AS FRA WITH AN LRECL OF 240 AND BLKSIZE OF 3120.
//** THIS DATA SET SHOULD BE EMPTY BEFORE RUNNING THIS JOB.
//** (DO NOT FORGET TO DELETE THE ASTERISK ON THIS LINE IN THE JOB
//** AND PLACE IT ON THE LINE ABOVE BEFORE RUNNING.)
//**
//** A) BECAUSE THE SAS PROGRAMS ARE SET UP TO BE RUN INDIVIDUALLY,
//** YOU MUST EDIT THE MEMBERS 'ACTIVITY' AND 'SECURITY' IN
//** YOUR SCD.SCDMAP DATA SET IN THE FOLLOWING MANNER:
//**
//** CHANGE THE SAS STATEMENT ...
//** PROC PRINTO NEW UNIT=20; TO ...
//**
//** PROC PRINTO UNIT=20;
//**
//** THIS WILL CAUSE THE OUTPUT FROM EACH REPORT TO APPEND TO
//** THE END OF THE OUTPUT FILE RATHER THAN OVERLAY WHAT'S
//** ALREADY THERE.
//**
//** 10) CHANGE SCD.SCDMAP TO THE NAME OF THE DATA SET CONTAINING
//** THE SAS PROGRAMS.
//**
//** NOTE - IF YOU WOULD LIKE TO PUT SPECIFIC BOUNDARIES ON THE TIME
//** SPAN TO BE REPORTED ON, MODIFY THE SAS STATISTICS COMMAND IN
//** THE SYSTMT STREAM OF THE DGAIRATC STEP TO CONTAIN START AND STOP
//** TIMES. AS IS, REPORTING WILL OCCUR ON THE ENTIRE STAT FILE.
//**
//*****
//DGAIRATC EXEC PGM=DGAIRATC, PARM='*TRIM'
//SYSPRINT DD DSN=SCD.SCDALINK, DISP=MER
//DMSGFILE DD DSN=SCD.SCDAPROC, DISP=MER
//DMSGFILE DD DSN=SCD.MSG, DISP=MER
//TMPDSW DD DSN=ACDAP, DISP=(NEW,PASS), DCB=(DCB=PS,
// KRCFB=VE, LRECL=4100, BLKSIZE=4104), SPACE=(4104, (70, 13)),
// UNIT=UNITNAME
//DMSGFILE DD SYSPRINT*
//SYSPRINT DD SYSPRINT*
//SYSTMT DD*
SIGNON USERID=(SUID) NETMAP=SCD.NETMAP TMPDSW=TMPDSW
SEL STAT WHERE () FILE
SIGNOFF
//**
//**
//**/SASTEP EXEC SASPROC,
//** OPTIONS=DDOPE MACRO MACROERR MESSAGE="*"
//**/WSAS DD UNIT=UNITNAME, SPACE=(CYL, (20, 10))
//WMS001 DD DISP=(OLD,DELETE), DSN=ACDAP
//DMSGFILE DD DISP=MER, DSN=SCD.MSG
//SASPROC DD DISP=MER, DSN=SCD.SCDMAP
//PFD0F001 DD SYSPRINT*
//PFD0F001 DD DISP=MER, DSN=OUTPUT.DATASET.NAME
//SYSTMT DD *
//INCLUDE SASPROC(ACTIVITY, SUMMARY, EXCEPT, SECURITY, HPGCOPY, PRCOPY,
// RINACE, RINBASE, RINMT?)
//**

```




ESS Data Flow Using CICS API

Define the event services environment by specifying the types of event data your application receives. These definitions are the event data requests that you issue through the DGAQ247 program or a user-written program.

After you define the event data requests for the client application and activate the request by issuing the EVENT SERVICES START command, ESS processes the event data as follows:

- Upon receiving the EVENT SERVICES START ID parameter, the API (DGAQ012) passes the command to the DTF through a VTAM session.
When a requested event occurs, the DTF sends the event data to the API for distribution to the Transient Data Queue (TDQ).
- The event data is then available to the client application through the DGAQ249 Sample Program. The DGAQ249 program provides a way to read event data from the TDQ and processes the data for use by your application.

The following diagram illustrates the flow of event data from the DTF to the client application:



Deciding What Event Data to Collect

Deciding what event data to collect requires that you understand the types of data the ESS delivers and how you can use this data in your event consumer application. Although it is technically possible to request all event data for all Processes in the system, it is usually unnecessary and impractical to do so. Typically, an event consumer application is interested in a subset of event data.

Note: Statistics records excluded through the API STAT command or a DTF statistics exit, or by coding the DTF STAT.EXCLUDE initialization parameter, are not available to ESS.

Following are commonly requested event data:

- All event data for a Process or group of Processes
Requesting all event data provides the most detailed trace of Process execution. This information is useful when testing an event consumer application. However, it is unnecessary after an application goes into production.
- Major event data for a Process or group of Processes
This request is the most common subset specification. For normal production work, this request gives a sufficient trace of Process execution, and minimizes overhead for ESS processing and event records by your application.
- Subset of event data for a particular Process, set of Processes, or all Processes
For example, an application executes a procedure when a Sterling Connect:Direct Process terminates. In this case, it may be sufficient to register interest in PT (Process Termination) records only. As a second example, a fault reporting application needs CT (Copy Termination) statements that did not complete normally (signalling the failure of a Sterling Connect:Direct file transfer request).

ESS Event Record Examples

The following examples show the ESS event records from a single Copy Process. The examples show the records produced from Process submittal until normal

Process termination. The examples assume that no Sterling Connect:Direct commands affecting the Process [including the SElect PROCess command] are issued between Process submittal and termination.

ESS Event Records Example 1 (No Retries)

In this example, the Process does not undergo a Process retry for any reason. The sequence of ESS event records produced by this Process are listed in the following table:

Record Type	Record Description
PS	Process submit
QE	Process moved to EXEC queue
PI	Process initiation
CI	COPY step statement start
CE	COPY step I/O start
CT	COPY termination
NL	Last statement (null step 1)
PT	Process termination

ESS Event Records Example 2 (One Retry)

This example shows the sequence of ESS records that are produced if the same Process undergoes a single Process retry. Sterling Connect:Direct commands are deliberately issued to suspend the Process and then release it for retry. As a result, the following record sequence includes the various operator commands required. The events are in sequential order.

Record Type	Record Description
PS	Process submit
QE	Process moved to EXEC queue
PI	Process initiation
CI	COPY step statement start
CE	COPY step I/O start
FS	Suspend Process command issued
CT	COPY termination (as a result of requested SUSPEND)
QH	Process moved to HOLD queue
CH	Change Process command issued with RELEASE=Yes
QE	Process moved to EXEC queue
PI	Process initiation
CI	COPY step start
CE	COPY I/O start
CT	COPY termination
NL	Last statement in Process end
PT	Process termination

Using ESS with the CICS API

The CICS API writes event data to the Transient Data Queue (TDQ). Your CICS application must include a program to read these event records from the TDQ and send them for processing..

About this task

To enable a CICS application for ESS:

Procedure

1. Decide what event data the application requires.
2. Verify that the Sterling Connect:Direct CICS API software is installed and working. Refer to the Sterling Connect:Direct installation documentation for information.
3. Create an ESS registration program. Include this program in the startup portion of your application. It must be called whenever your application wants to initiate event record collection. This program must perform the following:
 - Sign on to the Sterling Connect:Direct CICS API.
 - Issue the EVENT SERVICES CREATE command to register interest in receiving event data and to specify event record filter criteria.
 - Specify the ID parameter to identify a subscriber for your application. Specify the WHERE and ORWHERE parameters for filtering criteria.
 - Issue the EVENT SERVICES START command and specify the ID parameter to initiate event reception.
4. Create a customer interface program to read event records from the CICS TDQ and send them for processing. The sample interface program (DGAQ249) demonstrates how to read an event record from the TDQ. The application must issue an EXEC CICS READQ TD QUEUE instruction.
5. Modify the application to process the ESS event records.
6. Embed a call to the EVENT SERVICES STOP ID=subscriber_name parameter in the location to stop collecting event data.

Using ESS with the ESS User Exit

You can execute Event Services commands through any existing Sterling Connect:Direct API such as CICS, ISPF, and the batch interface. However, not all Sterling Connect:Direct APIs can process synchronous event data received from an EVENT SERVICES START command. In some cases, it is preferable not to have the Sterling Connect:Direct API process synchronous event data. The event services exit provides an alternative. Rather than passing synchronous event data back to the API that issued the EVENT SERVICES START (ESS) command, an exit processes the event data.

The ESS exit acts as an extension to the Sterling Connect:Direct server. When a synchronous event occurs, Sterling Connect:Direct calls the event services exit. An event exit control block is passed for each event and contains the following:

- Address of the event record
- Flags indicating first or last call
- Fields for the user to indicate return code and message

DGA\$EVCB, found in \$CD.SDGAMAC, maps the event exit control block. The sample exit, DGAXEV01, is in \$CD.SDGASAMP.

The event services exit is called as a subtask from Sterling Connect:Direct so that the user code waiting for system services does not directly effect Sterling Connect:Direct processing. The sample exit (DGAXEV01) writes each event record to a predefined data set. You must modify DGAXEV01 to specify the name of your event exit data set, and you must define the data set to accommodate records up to 2048 bytes in length.

Using the ESS Exit

About this task

Each record passed to the exit consists of a record header and an event record. DGA\$NHDR, in \$CD.SDGAMAC, maps the record header. Other members in \$CD.SDGAMAC map the event records. See Event Services Record, to determine which member maps a particular event record.

The exit must reside in a load library accessible to the Sterling Connect:Direct server (DTF). This exit accommodates systems where I/O calls must be done below the line.

To use the ESS user exit:

Procedure

1. Create an ESS exit program that can process the requested event records.
2. Decide what event data your application requires.
3. Verify that your software is correctly installed and working.
4. Create an ESS registration program. Include this program in the startup portion of your application. It is called whenever your application initiates event record collection. This program must accomplish the following tasks:
 - Signon to Sterling Connect:Direct through the CICS API, the ISPF IUI, or the batch interface.
 - Issue the EVENT SERVICES CREATE command to register interest in receiving event data and specify event record filter criteria.
 - Specify the EXIT parameter to identify the name of your exit program, and the ID parameter to identify a subscriber name for your application. Specify the WHERE and ORWHERE parameters for your filtering criteria. Refer to EVENT SERVICES CREATE Command Format for more information about event filter criteria.
 - Issue the EVENT SERVICES START command and specify the ID parameter to initiate event reception.

Embed a call to the EVENT SERVICES STOP ID=subscriber_name parameter in your application where you want to stop collecting event data. If the user application does not process records fast enough, the internal queue, which holds asynchronous events, becomes full. When the queue is full, event processing for this request ends, and Sterling Connect:Direct writes a WTOR message. To customize the internal queue size, specify the MAXQCNT parameter.

Issuing Event Services Commands

EVENT SERVICES CREATE Command Format

The EVENT SERVICES CREATE command enables you to create a new request for event data and define which data is sent to your application. The EVENT SERVICES CREATE command uses the following format and parameters:

Command	Parameters
EVENT [SERVICES] CREATE	ID=event-request-name
	WHERE (CCODE PNAME PNUMber STARTT STOPT USER SNODE TYPE FNAME CASE LASTSEQ MAXQCNT EXIT)
	ORWHERE =(CCODE PNAME PNUMber USER SNODE TYPE FNAME)

Required Parameters

The EVENT SERVICES CREATE command has two required parameters.

ID=event-request-name

specifies a logical name for the event services request. This name is a text string of 1–16 characters. You can use any printable characters. You cannot use embedded blanks.

WHERE (CCODE = (condition, completion code) | PNAME = name | (list)

PNUMber = number | (list)

STARTT = ([date | day] [,hh:mm:ssXM])

STOPT = ([date | day] [,hh:mm:ssXM])

USER = name | (list)

SNODE = name | (list)

TYPE = id | (list)

FNAME = dsname | (list)

CASE = YES | NO

LASTSEQ=n

MXQCNT=n

EXIT=exitname)

specifies selection criteria for event records.

You must specify at least one WHERE () subparameter, such as CCODE, PNAME, PNUMBER, or TYPE.

CCODE = (condition, completion code)

specifies selection by completion code.

condition specifies a relationship to the completion code given in the subsequent positional parameter. The options for specifying condition are:

GT greater than LT less than EQ equal to NE not equal to GE greater than or equal to LE less than or equal to

completion specifies a completion code value ranging from 1 to 2,147,483,647 so the RUN TASK can pass all values.

For example, if you specify CCODE = (GT,0), you see event records in which the step completion code is greater than zero, as long as the records also meet other specified criteria.

PNAME = name | (list)

specifies selection by Process name. Specify a list of Processes by enclosing them in parentheses. You can use a wild card character (*) at the end of the name.

For example, if you specify PNAME=TEST*, then all records with TEST in the first four characters of the Process name field are selected. Records having TEST, TEST123, and TESTX all satisfy the selection criterion.

name specifies the name of the Process to select.

(list) specifies a list of Process names to select. Enclose the list in parentheses. Separate Processes in the list with commas.

PNUMBER = number | (list)

specifies selection by Process number. To request a list of Processes, enclose them in parentheses. The range is 1–99999.

number specifies the number of the Process to select.

STARTT = ([date | day] [,hh:mm:ssXM])

specifies selection by start date and time. Specify STARTT as a date and time prior to the current time. If you set this parameter, the event records retrieved from the statistics file begin with the date and time you specified and continue until the current time is reached. At that point, event records are processed as they occur.

Note: If you specify STARTT and LASTSEQ with the EVENT SERVICES START command, those values replace the values specified for these parameters in the EVENT SERVICES CREATE command. When you use the time specification in conjunction with the LASTSEQ parameter, you must include hours, minutes, seconds, and hundredths of seconds in the format hh:mm:ss.th.

date specifies the starting date from which event records are retrieved from the statistics file. You can specify the date in either Gregorian or Julian format.

If you use a Gregorian date format, set the DATEFORM initialization parameter to the appropriate date format. Otherwise, the date format defaults to the platform date format. You do not need to set the DATEFORM parameter for Julian date format.

The following table shows the acceptable date formats:

Format	DATEFORM Parameter	Date Format
Gregorian	DATEFORM=MDY	mmddy or mmddyyy mm/dd/yy or mm/dd/yyyy mm.dd.yy or mm.dd.yyyy
Gregorian	DATEFORM=DMY	ddmmy or ddmmyyy dd/mm/yy or dd/mm/yyyy dd.mm.yy or dd.mm.yyyy
Gregorian	DATEFORM=YMD	yymmdd or yyyymmdd yy/mm/dd or yyyy/mm/dd yy.mm.dd or yyyy.mm.dd

Gregorian	DATEFORM=YDM	yyddmm or yyyyddmm yy/dd/mm or yyyy/dd/mm yy.dd.mm or yyyy.dd.mm
Julian	N/A	yyddd or yyyyddd yy/ddd or yyyy/ddd yy.ddd or yyyy.ddd

Note: If RETAIN=Y, you cannot specify a date in the STARTT parameter of the initialization file.

day specifies the day of the week to select. Valid names include MONday, TUEsday, WEDnesday, THURsday, FRIday, SATurday, and SUNday. You can also specify YESTER to retrieve event records created since yesterday, or TODAY to retrieve event records created today.

hh:mm:ssXM indicates the start time of day in hours (hh), minutes (mm), and seconds (ss) selected. XM indicates AM or PM. You can use the 24-hour clock or the 12-hour clock. If you use the 24-hour clock, valid times are 00:00-24:00. If you use the 12-hour clock, valid times are 00:00-12:00 and you must indicate AM or PM. For example, 01:00 hours on the 24 hour clock is expressed as 1:00AM on the 12 hour clock. If you do not specify AM or PM, Sterling Connect:Direct assumes the 24-hour clock. You do not need to specify minutes and seconds. You can also specify NOON to retrieve event records starting at noon, or MIDNIGHT to retrieve event records starting at midnight. The default for the time is 00:00:00, the beginning of the day.

If you do not specify the STARTT parameter, event processing begins with the current time.

STOPT = ([date | day] [,hh:mm:ssXM])

specifies when interest in event data ends.

date specifies the stop date when event processing ends. You can specify the date in either Gregorian or Julian format.

Refer to the STARTT subparameter for a discussion of Gregorian and Julian date formats.

If you specify only the date, the time defaults to 24:00:00.

day specifies the day of the week to select. Valid values include MONday, TUEsday, WEDnesday, THURsday, FRIday, SATurday, and SUNday. You can also specify TODAY.

hh:mm:ssXM indicates the stop time of day in hours (hh), minutes (mm), and seconds (ss) to select. XM indicates AM or PM. You can use the 24-hour clock or the 12-hour clock. If you use the 24-hour clock, valid times are 00:00-24:00. If you use the 12-hour clock, valid times are 00:00-12:00 and you must indicate AM or PM. For example, 01:00 hours on the 24 hour clock is expressed as 1:00AM on the 12 hour clock. If you do not specify AM or PM, Sterling Connect:Direct assumes the 24-hour clock.

You do not need to specify minutes and seconds. You can also specify NOON to retrieve event records starting at noon, or MIDNIGHT to retrieve event records starting at midnight. The default time is 24:00:00, the end of the day.

If you do not specify the STOPT parameter, you must issue an EVENT SERVICES STOP command to stop event processing.

USER = name | (list)

limits the selected event records to those written for userids with the specified name. You can specify a list of names by enclosing them in parentheses. You can use wild card characters. For example, if you specify USER = SYS\$, then records with SYS\$ in the first four characters of the userid field are selected. Records having SYS\$BOB, SYS\$ADM, and SYS\$0001 all satisfy this selection criterion. Userid names can be up to 64 characters in length and can contain lowercase characters.

name specifies the userid to select.

(list) specifies a list of userids to select. Enclose the list in parentheses. Separate userids in the list with commas.

SNODE = name | (list)

limits the selected event records to those written for Processes where the specified node name acted as SNODE. You can specify a list of names by enclosing them in parentheses. You can use wild card characters. For example, if you specify SNODE=DALLAS*, then all records with DALLAS in the first six characters of the SNODE field are selected. Records having DALLAS.PROD, DALLAS.TEST, and DALLAS all satisfy this selection criterion. SNODE names can contain lowercase characters.

name specifies the SNODE to select.

(list) specifies a list of SNODES to select. Enclose the list in parentheses. Separate SNODES in the list with commas.

TYPE = id | (list)

specifies the event record types to select. Every event record that Sterling Connect:Direct generates has an associated record-type identifier. Each identifier is two characters long and indicates the event or function that generated the record. The identifier also indicates the record format and contents.

id specifies the event record type.

(list) specifies a list of event record types to select. Enclose the list in parentheses. Separate record types in the list with commas.

FNAME=dsname | (list)

limits the selected event records to those that contain the specified filename. The FNAME subparameter is valid for the following record types: Copy Termination (CT), Run Job (RJ), Start Sterling Connect:Direct (SD), and Submit within Process (SW).

name specifies the filename to select.

(list) specifies a list of filenames to select. Enclose the list in parentheses. Separate filenames in the list with commas.

The meaning of the filename within these records is unique for each record type. For example, the Run Job record contains the filename of the submitted JCL. Filenames can be up to 254 characters in length and can contain lowercase characters. Filenames must conform to your platform's naming conventions.

CASE=YES | NO

specifies whether lowercase or mixed-case data is permitted for the USER, SNODE, and FNAME subparameters. The CASE subparameter overrides the global CASE option defined at signon for the SELECT STATISTICS command.

YES changes the data in USER, SNODE, and FNAME to uppercase regardless of the actual data specified.

NO preserves the actual case entered for the USER, SNODE, and FNAME subparameters.

The CASE defaults to the setting defined in the session defaults, if nothing is specified.

LASTSEQ=n

specifies the last sequence number (for Restart capability) associated with the date/time stamp. Use it with the STARTT parameter. This information is provided by CICS when you issue a CREATE EVENT SERVICES REQUEST command for an event services request that finished abnormally.

MAXQCNT=n

specifies the maximum number of elements that can reside in the internal event queue for this request. All events that match the WHERE criteria for this request are placed on an internal queue. If events occur faster than the API can process them, the queue can become full. If the queue becomes full, Sterling Connect:Direct terminates event services requests. You can modify the queue size using MAXQCNT. Each queue element takes approximately 2K in storage. The default is 100.

EXIT=exitname

specifies the name of an EVENT SERVICES OPTION exit. The sample exit DGAXEV01 is provided in the sample library. Event data is processed by an exit rather than the calling API, if EXIT is specified.

Optional Parameters

The following parameters are optional for the EVENT SERVICES CREATE command.

ORWHERE (CCODE = (condition, completion code) | PNAME = name | (list)

PNUMber = number | (list)

USER = name | (list)

SNODE = name | (list)

TYPE = id | (list)

FNAME = dsname | (list)

specifies which statistics records you want to examine.

The subparameters, such as CCODE, PNAME, PNUMBER, and TYPE, are optional, but you must specify at least one.

The parameters for the ORWHERE keyword are defined in the WHERE keyword section.

Sample Command

The following is an example of the EVENT SERVICES CREATE command.

```
EVENT CREATE ID=PROCESS_TERM WHERE(TYPE=PT)
```

EVENT SERVICES START Command Format

The EVENT SERVICES START command enables you to start a specific notification request for event data. This command provides parameters where you can define what data (date, time, and sequence) is sent to your application.

The EVENT SERVICES START command uses the following format and parameters.

Command	Parameters
EVENT [SERVICES] START	ID=event-request-name WHERE=(STARTT LASTSEQ KEEPREC (for CICS only)TRACE) (CICS only)

Required Parameter

The EVENT SERVICES START command has one required parameter.

ID=event-request-name

specifies the logical name of the event services request to start. Specify this name in a CREATE EVENT SERVICES command.

Optional Parameters

The following parameter is optional for the EVENT SERVICES START command.

WHERE(STARTT | LASTSEQ | KEEPREC | TRACE)

sets restriction on event records meeting the following selection criteria.

STARTT=([date | day],[hh:mm:ssXM])

specifies selection by designated starting date and time. STARTT must be a date and time prior to the current time. If you specify this parameter, the event records retrieved from the statistics file begins with the date and time you specified, and continues until the current time is reached. At that point, event records are processed as they occur.

For a complete explanation of the subparameters, refer to EVENT SERVICES CREATE Command Format.

LASTSEQ=n

specifies the last sequence number (for Restart capability) associated with the date/time stamp. Use this parameter with the STARTT parameter. This information is provided by CICS when

you issue a CREATE EVENT SERVICES REQUEST command for an event services request that finished abnormally.

KEEPREC (CICS-only)

specifies that the restart record created by Sterling Connect:Direct is kept, regardless of whether the event request completed abnormally or not. If KEEPREC is not specified, the restart record created by Sterling Connect:Direct is deleted if the event request completes normally.

TRACE (CICS-only)

specifies that every event record placed on the CICS TDQ is also written to the NDMTRACE temporary storage (TS) queue. You can use the NDMTRACE temporary storage queue to verify that EVENT records are flowing to the transient data queue.

Sample Command

Following is an example of the EVENT SERVICES START command.

```
EVENT START ID=PROCESS_TERM
```

EVENT SERVICES STOP Command Format

The EVENT SERVICES STOP command stops event notification for a specific event services request.

The EVENT SERVICES STOP command stops event notification and deletes the event request from the system.

The EVENT SERVICES STOP command uses the following format and parameters.

Command	Parameters
EVENT [SERVICES] STOP	ID=event-request-name
	IMMEDIATE

Required Parameter

The EVENT SERVICES STOP command has one required parameter.

ID=event-request-name

specifies the logical name of the event services request to start. This name must match a name specified in a CREATE EVENT SERVICES command.

Optional Parameter

The EVENT SERVICES STOP command has one optional parameter.

IMMEDIATE

indicates that no more event records can be sent. If you do not specify IMMEDIATE, all records on the internal EVENT queue are sent before the EVENT request is terminated.

EVENT SERVICES DISPLAY Command Format

The EVENT SERVICES DISPLAY command enables you to display event data for a specific event services request. The EVENT SERVICES DISPLAY command uses the following format and parameter.

Command	Parameter
EVENT [SERVICES] DISPLAY	ID=event-request-name

Required Parameters

The EVENT SERVICES DISPLAY command has no required parameters.

Optional Parameter

The EVENT SERVICES DISPLAY command has one optional parameter.

ID=event-request-name

specifies the logical name of the event services request to display. This name must match a name specified in a CREATE EVENT SERVICES command. If you do not specify this parameter, all event services requests are displayed.

CICS ESS Customization

The Sterling Connect:Direct CICS interface enables you to use Sterling Connect:Direct through the Customer Information Control System (CICS) from local and remote sites. The system includes a set of nested menus, prompts for required information, online Help facilities, and monitoring features for current status.

In addition to the Sterling Connect:Direct IUI, a facility is provided that enables you to issue standard Sterling Connect:Direct commands from a CICS application program. You can use this interface for both terminal and non-terminal tasks. Following are two typical uses for this API:

- For terminal tasks, the API enables an installer to provide their own user interface to all or part of Sterling Connect:Direct or work with Sterling Connect:Direct from application programs using the DGAN transaction.
- For non-terminal tasks, the API enables an installer to write background transactions which programmatically issue Sterling Connect:Direct commands. The most typical sequence is SIGNON - SUBMIT - SIGNOFF. In this case, the SIGNON generates a SIGNON TYPE=CICS, and the SIGNOFF results in a cleanup operation of the signon table entry, temporary storage, and so forth. To avoid having to sign on before each command and sign off after each command, the user application can pass a logical task number through the Q012TASK field. If Q012TASK is used, a user program can sign on once and issue multiple commands in pseudo-conversational mode. A signoff is only needed when the user application is terminating.

An example of the use of this facility is provided in member DGAQ247 of the \$CD.SDGASAMP. This program enables you to type Sterling Connect:Direct commands on a screen and view the resulting return code, message number, message text, and Process number assigned to your Sterling Connect:Direct Process. In addition, the CICS application displays the name of the CICS

Temporary Storage (TS) queue where the results of your command are stored, the count of items in the queue, and the maximum record length in the queue.

You must install both Sterling Connect:Direct and the Sterling Connect:Direct CICS interface, and they must be operating for the Sterling Connect:Direct CICS API to function.

The following elements are required to use DGAQ247:

Component	Description
DGAQ247	The program source, written in assembly language
DGAQM98	The BMS map used by DGAQ247
DGAQBMST	A parsing macro used by DGAQ247
DGAQCA12	A command-level COMMAREA passed to the CICS Interface

Following is a sample Sterling Connect:Direct API DRIVER screen. It shows data after the ESS registration program has signed on to the Sterling Connect:Direct CICS API driver and issued an EVENT SERVICES CREATE command.

CONNECT:Direct API DRIVER	
COMMAND	EVENT SERVICES CREATE ID=MES00031 WHERE(MAXQCNT=998 LASTSEQ=1 STARTT=(02.14.2010,04:14:12.45) STOPT=(12.31.2041,24:00:00.00) TYPE=(QE,QW,QH,QT,PI,CE,CT,PT,CI,RJ,RT,JI,TI,SW,DP))
COMMAND RC	0000
COMMAND MSG ID	SOPM0001
COMMAND MSG	An EVENT REQUEST HAS COMPLETED NORMALLY
PROCESS NUMBER	
TD EXIT COUNT	
TS QUEUE NAME	
TS MAX LRECL	
EVENT RESTART DATA	
WHERE(STARTT=(00000,00:00:00.00),LASTSEQ=000)	
PF keys:	3 Exit 5 Signon 6 Command 7 Signoff

The following table describes the Driver fields:

Field	Description
COMMAND	This 3-line field contains your API command.
COMMAND RC	This 4-character field contains the return code from your API Process.
COMMAND MSG ID	This 8-character field contains the identification number of the message associated with your API Process.
COMMAND MSG	This 64-character field contains the text of the message.
PROCESS NUMBER	This 6-character field contains the Process number assigned by the system to your API Process.
TD EXIT COUNT	This 6-character field contains the number of bytes indicating how much data is written by the exit module for your API Process.
TS QUEUE NAME	This 8-character field contains the name of the TS queue used during your API request.
TS MAX LRECL	This 4-character field contains the maximum logical record length in bytes of the TS queue.

Field	Description
EVENT RESTART DATA	This 62-character field contains the DATE/TIME/SEQ of the last event record successfully received. Data is only displayed if an EVENT SERVICES CREATE command is issued and a previous event services request had ended abnormally.

CICS API Option

To use the sample program, you must first change DGAQ247 to issue a valid SIGNON command for your environment (the SIGNON command is defined near the end of the source module). Include a valid USERID, PASSWORD, and NODE. Before executing this program as a transaction, you must be signed on to CICS. Also observe the following items.

- Assemble DGAQM98 and then DGAQ247. Sample JCL is in the \$CD.SDGASAMP. Assemble DGAQM98 and DGAQ247 as follows:
 - Use member DGAXASMB to assemble DGAQM98
 - Use member DGAXASMC to assemble DGAQ247
- Use the Sterling Connect:Direct Administrative (DGAA) transaction to verify that the CICS Interface and the appropriate node are both active.
- Use transaction DGAN to display DGAQM98.

The program checks for the presence of a communications area in the Exec Interface Block (EIB). If none is present, or if you press the Clear key, the DGAQM98 map is sent and a RETURN TRANSID is performed to invoke the transaction again when you press Enter.

- If you pressed the PF3 or PF15 key, the program terminates.
- The DGAQM98 map is received. If you pressed PF5 or PF17, a Sterling Connect:Direct SIGNON request is generated and the results of the command are presented in the map.
- Following a successful signon (that is, the return code on DGAQM98 after the SIGNON is zero), you can type a valid Sterling Connect:Direct command on the line provided in the DGAQM98 map and press PF6 or PF18 to send the command to the Sterling Connect:Direct DTF. Command results are displayed when they are returned from the DTF.
- To signoff from the DTF, press PF7 or PF19.

When you type a command through the DGAQM98 screen, its length is determined and the address of the length and command are placed in the DGAQC12 communications area at label Q012CMDA. Program DGAQ012 is then invoked through an EXEC CICS LINK command. When control returns to DGAQ247, the DGAQC12 communications area contain the results of the command.

Note: The DGAQ247 does not display the results of the issued command stored in CICS temporary storage. Retrieve these records programmatically or view them using the CICS CEBR transaction.

Use the techniques in the DGAQ247 sample program to issue any valid Sterling Connect:Direct command. Results of commands such as SELECT PROCESS and SELECT STATISTICS are written to CICS temporary storage; other commands may produce no output.

Accessing the API Module (DGAQ012) Procedure

Access the API by linking to program DGAQ012 within your CICS program/transaction as follows.

EXEC CICS LINK PROGRAM('DGAQ012') COMMAREA(Q012COMM) + LENGTH(Q012CMLH)
--

The COMMAREA Q012COMM is defined by macro DGAQCA12 in \$CD.SDGASAMP and is also provided in \$CD.SDGASAMP. A COBOL version of this record layout is provided as member DGAQAPIC in the sample library. A brief description of each of the fields follows:

Field	Assembler Directive	Format	Description
Q012CMDA	DS	XL4	Full word containing the address of the command to be issued to Sterling Connect:Direct. The command must be in the following format: CMDLEN DS H Length of CMDTEXT that Sterling Connect:Direct recognizes, not including length of CMDLEN. CMDTEXT DS Cx Command text
Q012RETC	DS	XL4	Return code received after the command is invoked. 0: request completed successfully 1: C:D-CICS interface level error 2: C:D-CICS node level error 3: C:D-CICS signon level error 5: invalid COMMAREA or command passed to CICS API 8 and above: unsuccessful request
Q012TDCT	DS	XL4	TDEXIT ITEM COUNT. The field contains the number of records received from the Sterling Connect:Direct DTF.

Q012CMDA is the only required parameter you must set before the EXEC CICS LINK to DGAQ012. For optimum performance, follow the example of DGAQ247 and initialize all fields before linking to DGAQ012.

Any output generated by issuing the command is returned in a temporary storage queue. Your terminal ID is displayed as the last four characters in the unique TS queue name.

LASTSEQ Parameter

All event records contain a unique timestamp that consists of date, time, and sequence number. Each EVENT SERVICES request is associated with an ID. The Sterling Connect:Direct CICS API creates a restart record for an ID when an EVENT SERVICES CREATE command is processed.

After an event record is successfully delivered to the Transient Data Queue, its timestamp is saved in the restart file. If event services processing ends abnormally, the restart record is retained. The restart record is also retained when you specify KEEP RRREC (keep restart record) in the EVENT START statement.

When an EVENT SERVICES CREATE command is processed, the restart file is searched for a record matching the ID of the CREATE. If a match is found, the date, time, and sequence number of the last successfully delivered event record is returned. When you use the time specification in conjunction with the LASTSEQ parameter, you must include hours, minutes, seconds, and hundredths of seconds in the format hh:mm:ss.th.

Field	Assembler Directive	Format	Description
Q012TDMX	DS	XL2	TDEXIT MAX ITEM SIZE - the maximum record size received from the Sterling Connect:Direct DTF.
Q012PROC	DS	CL6	Process number of the latest submitted Process.
Q012TSKY	DS	CL8	Temporary storage ID - the name of the CICS TS queue that contains the command output.
Q012MSID	DS	CL8	Message ID returned from the Sterling Connect:Direct for z/OS DTF.
Q012MSTX	DS	CL64	Message Text returned from the Sterling Connect:Direct for z/OS DTF.
Q012DTE	DS	PL4	Date of the last event acknowledgment.
Q012TME	DS	XL4	Time of the last event acknowledgment.
Q012SEQ	DS	XL2	Sequence number of the last event acknowledgment.

Note: DGAQ012 requires that it run in CICS key. For the transaction that executes a program linking DGAQ012, set the following parameters in the CEDA definitions (or in the RDO for that program):

- TaskDataLoc:ANY
- TaskDataKey:CICS

If missed event data is required, use this information as the STARTT and LASTSEQ values as in the following example.

Event records beginning after this timestamp are processed.

Event Record from the Transient Data Queue

The sample program DGAQ249 reads an ESS event record from the Transient Data queue. The sample program DGAQ249 is in \$CD.SDGASAMP. Use JCL DGAXASMC in \$CD.SDGASAMP to assemble DGAQ249.

Each record passed to the user application consists of a record header and an event record. DGA\$NHDR, which is in the Sterling Connect:Direct sample library, maps the record header. Members in the sample library also map the event records. Search for Event Services Record Descriptions to determine which member maps a particular event record.

Event Services Record Descriptions

ESS enables you to create ESS-enabled applications. Following is reference information about event record types and attributes that help you create applications. For a list of statistics record types, search for Using Sterling Connect:Direct Exits.

Assembler DSECT members are in the sample library. Access the information by the member names listed in the following table. Use the two-character designations for record types when you browse the Sterling Connect:Direct statistics file.

Event Record Type Attributes

ESS has several statistics record types. This section summarizes the attributes of these record types.

Most record types have the following common attributes:

- Process name
- Process number
- Message ID
- Submitter's symbolic node name
- PNODE name for this Process
- SNODE name for this Process
- THISNODE (This node is P[node] or S[node].)

The following paragraphs detail the attributes of specific record types. For ease of reference, the information is grouped according to event type or enhancement type, and they are presented alphabetically.

Event Record Types:

Record type attributes for event records are described in the following paragraphs. The information is organized alphabetically by record type identifier.

CI (COPY Step Initiation)

This record is created immediately prior to the execution of any tasks associated with a COPY statement. The intent of this record is to capture the timing of such work as data set allocation prior to any I/O occurring. In addition to the common attributes, CI has the following individual attributes:

- COPY step start date/time
- Step name or label
- CI record retry count
- Transfer direction
- Source file name
- Destination file name
- Member name (when applicable)

CE (COPY I/O Start)

This record is created immediately prior to the first block of data transferred in a COPY statement. In addition to the common attributes, CE has the following individual attributes:

- COPY I/O start date/time
- Step name or label

- CE record retry count

EI (Event Request Initiation)

This record is created upon completion of a `EVENT SERVICES START` command.

Note: The common attributes for Process-related records do not apply to this record.

The following attributes apply to this event:

- Date/Time the command completed
- User ID of the user who issued the command
- Event services request ID
- Completion code for the command
- Command parameter string

EL (Event Session Lost)

This record is created when the Sterling Connect:Direct DTF is lost.

ET (Event Request Stop)

This record is created when an `EVENT SERVICES STOP` command completes.

Note: The common attributes for Process-related records do not apply to this record.

The following attributes apply to this event:

- Date/Time the command completed
- User ID of user who issued the command
- Event services request ID
- Completion code for the command

JI (RUN JOB Start)

This record is created immediately before the job specified by the `RUN TASK` statement is submitted. In addition to common attributes, JI has the following individual attributes:

- RUN JOB start date/time
- Step name or label
- Job name
- JI record retry count

QE (Process moved to EXEC queue)

This record is created when a Process is moved to the execution queue. In addition to the common attributes, QE has the following individual attributes:

- Process execution start date/time
- QE record retry count

PI (Process Initiation)

This record is created immediately prior to when the first Process step is executed. In addition to the common attributes, PI has the following individual attributes:

- Queue change date/time
- Execution queue status value
- PI record retry count

QH (Process moved to the HOLD queue)

This record is created when a Process is moved to the Hold queue, through a problem during Process execution or submission, a SUSPEND PROCESS command issued or a session failure. The reason is identified by the Hold queue status value. In addition to the common attributes, QH has the following individual attributes:

- Queue change date/time
- Hold queue status value
- QH record retry count

QT (Process moved to the TIMER queue)

This record is created whenever a Process is moved to the Timer queue, normally through a Process retry. In addition to the common attributes, QT has the following individual attributes:

- Queue change date/time
- Timer queue status value
- QT record retry count

QW (Process moved to the WAIT queue)

This record is created whenever a Process is moved to the Wait queue from the Hold or Timer queues. In addition to the common attributes, QW has the following individual attributes:

- Queue change date/time
- Wait queue status value
- QW record retry count

TI (RUN TASK Initiation)

This record is created immediately prior to the initiation of the task specified by the RUN TASK statement. In addition to the common attributes, TI has the following individual attributes:

- RUN TASK start date/time
- Step name or label
- Program name
- TI record retry count
- Date/time
- Process name and number
- Event name
- Event trigger
- Event type

Event Record Enhancements: An enhancement to existing statistics records is described in the following paragraph.

CT (COPY Termination) Record Enhancements

The existing CT record is enhanced to include the following information:

- Total number of retries for the COPY step
- Total amount of data moved for all attempts of the COPY

- Type keywords specified in a COPY step to retrieve data set defaults for allocating the destination file

Chapter 9. Spool Transfer Facility

Sterling Connect:Direct Spool Transfer is an interface that enables you to transfer Job Entry Subsystem (JES) spool files in the following ways:

- Copy from JES Spool Files
The VPS/CDI option and the VPSSCDI program manage input from JES spool files. Using this feature allows Sterling Connect:Direct to transfer spool from one system to another.
- Copy to JES Print Queues
Sterling Connect:Direct dynamically allocates a print file and writes the input file directly to the JES Spool.
- Copy to JES Reader Queues
Sterling Connect:Direct dynamically allocates an internal reader and writes the input file directly to the JES Reader.

For outbound transfers, this feature requires the following additional products from Levi, Ray & Schoup (LRS):

- VTAM Printer Support (VPS)
- VPS Sterling Connect:Direct Interface (VPS/CDI) Option


Note: To send output to JES2 or JES3 (Reader or a printer queue), you do not need the VTAM Printer Support and VPS Sterling Connect:Direct Interface (VPS/CDI) Option components.

Sterling Connect:Direct Spool Transfer uses standard Sterling Connect:Direct facilities, which provide automation, reliability, management, interoperability, and security.

Spool Transfer Components

The major components of Sterling Connect:Direct Spool Transfer are:

- VTAM Printer Support (VPS) System
- Application Program Interface (API)
- Data Transmission Facility (DTF)
- The following diagram shows the relationship between these components. This chapter summarizes the function of each component.




You implement Sterling Connect:Direct Spool Transfer by changing definitions in the VPS initialization. Please refer to the Levi, Ray & Shoup documentation for their VPS product for correct implementation of VPS.

VTAM Printer Support

Sterling Connect:Direct for z/OS uses VTAM Printer Support (VPS) to retrieve JES spool files for processing. Expansion of the VPS application includes Sterling Connect:Direct support for moving print files from the JES spool to any Sterling Connect:Direct node. The VPS module (VPSSCDI) directs spooled output from JES to the Sterling Connect:Direct API for file transfer.

The following diagram illustrates the flow of the print file through this process.



VPS passes control to the Sterling Connect:Direct API at the following times:

Phase	Description
System Initialization	When a JES spool file is sent through Sterling Connect:Direct, VPS first transfers control to the Sterling Connect:Direct API for printer initialization and the API issues a SIGNON to the local DTF.
Printer Initialization	After signon, VPS copies the print files to a disk file and sends it to the Sterling Connect:Direct API.
SYSOUT Data Set Ready	The Sterling Connect:Direct API constructs a SUBMIT PROCESS command to send printer attributes, data set name, and the submitter's user ID to the local DTF. If the SUBMIT fails because the Process can not be found or the SNODE is unavailable, the print file is returned to the JES print queue according to the values specified in the requeue parameters. If the SUBMIT fails for another reason, VPS deletes the staged data set, drains its DTF WRITER, and leaves the JES spool file in the JES queue for restart. If the SUBMIT is successful, VPS releases ownership of the staged data set to Sterling Connect:Direct, and the JES spool file is PURGED from JES.
Printer Termination	When no more JES files are printing to Sterling Connect:Direct, a printer termination request is sent to Sterling Connect:Direct API.

Phase	Description
System Termination	The Sterling Connect:Direct API then sends a SIGNOFF command to the local DTF.

You can change VPSSCDI to modify Sterling Connect:Direct control blocks prior to calling DGASVPSA.

Sterling Connect:Direct API

The Sterling Connect:Direct API (DGASVPSA) communicates with the Data Transmission Facility through an application interface. DGASVPSA signs on to the local DTF, submits a Process, and signs off of the local DTF.

Module or Command	Description
DGASVPSA	<p>DGASVPSA is part of the VPS interface and is distributed in \$CD.SDGASAMP. This program is in source form. You can assemble and link-edit when you install a new release of Sterling Connect:Direct VPS.</p> <p>It uses the VPS system log for reporting exception conditions and informational messages describing the Processes submitted to the local DTF. This log serves as one central point to determine the status of any print file controlled by VPS.</p> <p>The DGASVPSA program receives control from VPSSCDI and validates the function calls and control block fields passed by VPSSCDI. If a function executes successfully, the program returns a condition code of 0 (zero) to the VPSSCDI.</p> <p>If a noncritical error occurs, DGASVPSA returns a code of 4 to VPSSCDI to indicate that VPS requeues the print file according to VPS printer specifications.</p> <p>If DGASVPSA detects a critical error, it returns a code of 8 or greater, indicating that VPS can EDRAIN the printer.</p> <p>A function call of PRINTER INITIALIZATION causes a SIGNON to be sent to the local DTF as defined in the network map specification for this printer.</p> <p>A function call of DATA SET SYSOUT READY invokes the routines to validate the control blocks and build the Sterling Connect:Direct SUBMIT PROCESS command and send it to the local DTF.</p> <p>A function call of PRINTER TERMINATION sends a SIGNOFF to the local DTF.</p> <p>DGASVPSA uses the Sterling Connect:Direct API interface module (DGADCHLA) to communicate with the Data Transmission Facility.</p>
VPSSCDI	<p>The VPS module VPSSCDI, the interface to Sterling Connect:Direct, is distributed in VPS. This program is in source form and you can reassemble and link-edit it when you install a new release of VPS or Sterling Connect:Direct.</p>

Module or Command	Description
SIGNON	<p>This command uses the network map specification for the specified Sterling Connect:Direct printer.</p> <p>If you do not have a network map override specified in the VPS printer definition table (CDNETMAP), the SIGNON command uses the DMNETMAP DD statement in the VPS startup JCL for the network map.</p>
SIGNON Security	<p>The SIGNON command for DGASVPSA does not pass a user id or password. If you use the Stage 1 security exit, user id associated with the VPS started task is extracted and the user id and a special password (assigned by the Stage 1 exit) is placed in the UICB, a user interface control block used for security.</p> <p>If the Stage 1 processing is successful, the SIGNON command passes to the DTF, where the DTF Stage 2 security is invoked. The Stage 2 exit recognizes the special password, as assigned by the Stage 1 exit. All verification calls to the security system are by user id only.</p> <p>If you send to a secured Sterling Connect:Direct, you can specify user id and password by adding the SNODEID specification to the Process. All Processes submitted by the VPS API have the security access level associated with the VPS job or started task, unless the security is overridden by PNODEID, SNODEID, and/or secure point-of-entry (SPOE) translation.</p>

Process Names

VPS print files are routed through the Sterling Connect:Direct network by specifying the SNODE keyword on the submitted Process. To provide flexibility, you can set up the VPS Sterling Connect:Direct printer either to submit a single Process name regardless of printer class or to submit a Process name with the printer output class appended to the name.

By appending the printer class to the name, one VPS/CDI printer can submit up to 36 different Process names, one for each printer class A–Z or 0–9. You can control the Process name being submitted with the VPS printer name and VPS printer definitions as follows:

- Define the CDSNODE in the VPS Printer Definition Table
- Define the CDPMBR in the VPS Printer Definition Table
- Use a VPS printer name of seven characters or less
- Use a VPS printer name of eight characters

This flexibility enables a VPS printer to submit Processes that send print files to one or more Sterling Connect:Direct SNODEs.

Use the following table to select the best method for your environment.

Where to Code	Keyword	Requirements	Results
Use Default (Do not code)	None	1 to 7-character printer name	Process name is the VPS Printer name with the class appended.
Use Default (Do not code)	None	8-character printer name	Process name is the VPS Printer name.

Where to Code	Keyword	Requirements	Results
VPS Printer Definition Table	CDSNODE	Value for CDSNODE Process name specified in CDPMBR	Process name is the printer name. (Class is not appended.)
VPS Printer Definition Table	CDSNODE CDPMBR	Value for CDSNODE and CDPMBR	Process name is the name specified in CDPMBR. (Class is not appended.)
VPS Printer Definition Table	CDPMBR	8 characters	Process member name remains the same for all print files. (Class is not appended.)
VPS Printer Definition Table	CDPMBR	Up to 7 characters	Process name is the name specified in CDPMBR (Class is appended.)

Note: Sterling Connect:Direct searches the Sterling Connect:Direct Process library, SDGAPROC, for the Process name. You must define the Process names in the Process library.

For example, if you select CDPMBR=CDPROC and the output print class is A, Sterling Connect:Direct searches the Process library for the Process name of CDPROCA. If you select an output print class of C for the same printer, Sterling Connect:Direct searches for the Process name CDPROCC.

However, if you use an eight-character name such as CDPMBR=DGAXPRC1, the Process name for that printer is DGAXPRC1, regardless of the printer class.

Sample Process to Display Attributes in the SUBMIT Statement

The following sample Process is provided in the Install Process Library, SDGAPROC. This example shows all attributes that can pass from DGASVPSA to the local Sterling Connect:Direct DTF in the SUBMIT statement. Any value of X'00' passed from VPS to DGASVPSA is considered a null value, and the SUBMIT command does not pass the corresponding field to the Process. For example, if your printer output DD statement does not code COPIES, then the symbolic &COPIES is not passed in the SUBMIT command.

```

/* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * */
/*
/*      C:D-ZOS JES SPOOL TRANSFER FACILITY SAMPLE PROCESS          */
/*
/*  CHANGE $CD.PROC TO THE Z/OS PROC LIBRARY THAT YOU HAVE        */
/*  INSTALLED THE PROC GENER INTO.  THE CONNECT:DIRECT            */
/*  INSTALLATION LOADED THIS MEMBER INTO YOUR                     */
/*  CONNECT:DIRECT PROCESS LIBRARY.                                */
/*
/*
/* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * */
CDPROCES PROC  SNODE=&SNODE,
               &ADDR1=,      /* ADDRESS LINE 1          */ -
               &ADDR2=,      /* ADDRESS LINE 1          */ -
               &ADDR3=,      /* ADDRESS LINE 1          */ -
               &ADDR4=,      /* ADDRESS LINE 1          */ -
               &BLDG=,       /* BUILDING                 */ -
               &BURST=,      /* BURST=YES OR NO         */ -
               &CHARS=,      /* CHAR ARRANGEMENT TABLE */ -
               &CKPTL=,      /* CKPTLINE                 */ -
               &CKPTP=,      /* CKPTPAGE                 */ -
               &CKPTS=,      /* CKPTSEC                  */ -

```

```

&CLASS=,          /* OUTPUT CLASS          */ -
&CMOD=,          /* COPY MODIFICATION MOD */ -
&CMTTC=,        /* COPY MODULE TABLE REF */ -
&CNTL=,         /* DEFAULT SPACING      */ -
&COMPACT=,      /* COMPACTATION TABLE  */ -
&COPIES=,       /* OUTPUT NUMBER COPIES */ -
&COPYG=,        /* COPY GROUP(S)        */ -
&DATCK=,        /* DATAK                */ -
&DEFAULT=,      /* DEFAULT              */ -
&DEPT=,         /* DEPARTMENT           */ -
&DEST=,         /* OUTPUT DESTINATION   */ -
&FCB=,          /* OUTPUT WTR FCB      */ -
&FLASH=,        /* FLASH FORMS OVERLAY  */ -
&FLSCT=,        /* FLASH FORMS OVERLAY CNT*/ -
&FMDEF=,        /* FORMDEF              */ -
&FORM=,         /* OUTPUT FORM          */ -
&GROUPID=,      /* GROUPID              */ -
&INDEX=,        /* INDEX                */ -
&JACCT=,        /* JOB ACCOUNTING NUMBER */ -
&JESDS=,        /* JESDS                */ -
&JOBID=,        /* JES ASSIGNED JOB ID  */ -
&JOBNM=,        /* JOB NAME              */ -
&JPNAME=,       /* JOB PROGRAMMERS NAME */ -
&JPROC=,        /* JOB PROC NAME        */ -
&JROOM=,        /* JOB PROGRAMMERS ROOM */ -
&JSECL=,        /* SECURITY LABEL        */ -
&LINDEX=,       /* LINDEX               */ -
&LINECT=,       /* LINES PER PAGE       */ -
&NAME=,         /* NAME                 */ -
&NOTIFY1=,      /* 1ST NOTIFY ID       */ -
&NOTIFY2=,      /* 2ND NOTIFY ID       */ -
&NOTIFY3=,      /* 3RD NOTIFY ID       */ -
&NOTIFY4=,      /* 4TH NOTIFY ID       */ -
&OPTCD=,        /* OPTCD=J SPECIFIED   */ -
&PGDEF=,        /* PAGEDEF              */ -
&PIMCT=,        /* PIMSG MSG-COUNT     */ -
&PIMSG=,        /* PIMSG                */ -
&PRMODE=,       /* PRMODE              */ -
&PRTY=,         /* PRTY                 */ -
&ROOM=,         /* ROOM                 */ -
&STEPDD=,       /* STEP DDNAME         */ -
&STEPNM=,       /* STEP NAME            */ -
&SUBNAME=,      /* SUBMITTERS NAME     */ -
&THRES=,        /* THRESHLD            */ -
&TITLE=,        /* TITLE                */ -
&TRC=,          /* TRC                  */ -
&UCS=,          /* OUTPUT WTR UCS      */ -
&UDATA01=,      /* 1ST USERDATA        */ -
&UDATA02=,      /* 2ND USERDATA        */ -
&UDATA03=,      /* 3RD USERDATA        */ -
&UDATA04=,      /* 4TH USERDATA        */ -
&UDATA05=,      /* 5TH USERDATA        */ -
&UDATA06=,      /* 6TH USERDATA        */ -
&UDATA07=,      /* 7TH USERDATA        */ -
&UDATA08=,      /* 8TH USERDATA        */ -
&UDATA09=,      /* 9TH USERDATA        */ -
&UDATA10=,      /* 10TH USERDATA       */ -
&UDATA11=,      /* 11TH USERDATA       */ -
&UDATA12=,      /* 12TH USERDATA       */ -
&UDATA13=,      /* 13TH USERDATA       */ -
&UDATA14=,      /* 14TH USERDATA       */ -
&UDATA15=,      /* 15TH USERDATA       */ -
&UDATA16=,      /* 16TH USERDATA       */ -
&ULIB1=,        /* 1ST USERLIB LIBRARY */ -
&ULIB2=,        /* 2ND USERLIB LIBRARY */ -
&ULIB3=,        /* 3RD USERLIB LIBRARY */ -
&ULIB4=,        /* 4TH USERLIB LIBRARY */ -

```

```

&ULIB5=,          /* 5TH USERLIB LIBRARY */ -
&ULIB6=,          /* 6TH USERLIB LIBRARY */ -
&ULIB7=,          /* 7TH USERLIB LIBRARY */ -
&ULIB8=,          /* 8TH USERLIB LIBRARY */ -
&VPSDSN=,        /* VPS PRINTER STAGED DSN */ -
&WRITER=,        /* OUTPUT WRITER NAME */ -
&WTR=,           /* OUTPUT WTR NAME (OLD) */ -
&OUTDSN=&SUBNAME.&JOBNM.&JOBID.&STEPNM.&STEPDD
/* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * */
/* COPY FILE STAGED BY VPSSCDI */
/* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * */
STEP01 COPY FROM(PNODE -
          DSN=&VPSDSN -
          DISP=SHR ) -
          CKPT=10M -
          COMPRESS EXT -
        TO(SNODE -
          DSN=&OUTDSN -
          DISP=(NEW,CATLG,DELETE) )
/* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * */
/* DELETE FILE STAGED BY VPSSCDI */
/* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * */
STEP02 IF (STEP01 = 0) THEN
STEP03 RUN TASK (PGM=DMRTDYN -
          PARM=(C"ALLOC DSN=&VPSDSN,DISP=(OLD,DELETE)" -
          F'-1' -
          C"UNALLOC DSN=&VPSDSN"))
        EIF
/* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * */
/* EXECUTE PROC GENER TO PRINT THE OUTPUT FILE */
/* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * */
STEP04 RUN TASK (PGM=DMRTSUB -
          PARM=("DSN=$CD.PROC(GENER),DISP=SHR", -
          "ADDR1 &ADDR1", -
          "ADDR2 &ADDR2", -
          "ADDR3 &ADDR3", -
          "ADDR4 &ADDR4", -
          "BLDG &BLDG", -
          "BURST &BURST", -
          "CHARS &CHARS", -
          "CKPTL &CKPTL", -
          "CKPTP &CKPTP", -
          "CKPTS &CKPTS", -
          "CLASS &CLASS", -
          "CMOD &CMOD", -
          "CMTTC &CMTTC", -
          "CNTL &CNTL", -
          "COMPACT &COMPACT", -
          "COPIES &COPIES", -
          "COPYG &COPYG", -
          "DATCK &DATCK", -
          "DEFAULT &DEFAULT", -
          "DEPT &DEPT", -
          "DEST &DEST", -
          "FCB &FCB", -
          "FLASH &FLASH", -
          "FLSCT &FLSCT", -
          "FMDEF &FMDEF", -
          "FORM &FORM", -
          "GROUPID &GROUPID", -
          "INDEX &INDEX", -
          "INPUT &OUTDSN", -
          "JACCT &JACCT", -
          "JESDS &JESDS", -
          "JNOTIFY &JNOTIFY", -
          "JOBID &JOBID", -
          "JOBNM &JOBNM", -

```

```

"JPNAME &JPNAME", -
"JPROC &JPROC", -
"JROOM &JROOM", -
"JSECL &JSECL", -
"LINDEX &LINDEX", -
"LINECT &LINECT", -
"NAME &NAME", -
"NOTIFY1 &NOTIFY1", -
"NOTIFY2 &NOTIFY2", -
"NOTIFY3 &NOTIFY3", -
"NOTIFY4 &NOTIFY4", -
"OPTCD &OPTCD", -
"PGDEF &PGDEF", -
"PIMCT &PIMCT", -
"PIMSG &PIMSG", -
"PRMODE &PRMODE", -
"PRTY &PRTY", -
"ROOM &ROOM", -
"STEPDD &STEPDD", -
"STEPNM &STEPNM", -
"SUBNAME &SUBNAME", -
"THRES &THRES", -
"TITLE &TITLE", -
"TRC &TRC", -
"UCS &UCS", -
"UDATA01 &UDATA01", -
"UDATA02 &UDATA02", -
"UDATA03 &UDATA03", -
"UDATA04 &UDATA04", -
"UDATA05 &UDATA05", -
"UDATA06 &UDATA06", -
"UDATA07 &UDATA07", -
"UDATA08 &UDATA08", -
"UDATA09 &UDATA09", -
"UDATA10 &UDATA10", -
"UDATA11 &UDATA11", -
"UDATA12 &UDATA12", -
"UDATA13 &UDATA13", -
"UDATA14 &UDATA14", -
"UDATA15 &UDATA15", -
"UDATA16 &UDATA16", -
"ULIB1 &ULIB1", -
"ULIB2 &ULIB2", -
"ULIB3 &ULIB3", -
"ULIB4 &ULIB4", -
"ULIB5 &ULIB5", -
"ULIB6 &ULIB6", -
"ULIB7 &ULIB7", -
"ULIB8 &ULIB8", -
"VPSDSN &VPSDSN", -
"WRITER &WRITER", -
"WTR &WTR", -
) SNODE
EXIT

```

DGAPGNER Job

The following sample JCL is provided in the Install Process Library, SDGASAMP. This example is the DGAPGNER job that is submitted by DGADTSUB in STEP 04 of the preceding Process example. Because it runs on the SNODE, it shows how you can print files back into the JES spool at the remote site.

If Sterling Connect:Direct Spool Transfer is enabled at the remote site, use Sterling Connect:Direct to transfer output back into the JES spool. Refer to Output to the JES Reader.

CAUTION:

When you use this JCL to test your own VPS, a print loop can occur if you use the symbolic &DEST on the same VPS system from which you submitted the print job.

```
//&JOBNM      JOB (00000),&PGMR,PRTY=12,TIME=(10),
//REGION=4096K,MSGLEVEL=(1,1),MSGCLASS=X
//*
//STEP01     EXEC PGM=IEBGENER
//SYSPRINT   DD SYSOUT=*
//SYSIN      DD DUMMY
//SYSUT1     DD DSN=&INPUT,
//           DISP=(OLD,DELETE,KEEP)
//SYSUT2     DD SYSOUT=&CLASS,COPIES=&COPIES,DEST=&DEST
//*
//*ADDR1=&ADDR1
//*ADDR2=&ADDR2
//*ADDR3=&ADDR3
//*ADDR4=&ADDR4
//*BLDG=&BLDG
//*BURST=&BURST
//*CHARS=&CHARS
//*CKPTL=&CKPTL
//*CKPTP=&CKPTP
//*CKPTS=&CKPTS
//*CLASS=&CLASS
//*CMOD=&CMOD
//*CMTTC=&CMTTC
//*CNTL=&CNTL
//*COMPACT=&COMPACT
//*COPIES=&COPIES
//*COPYG=&COPYG
//*DATCK=&DATCK
//*DEFAULT=&DEFAULT
//*DEPT=&DEPT
//*DEST=&DEST
//*FCB=&FCB
//*FLASH=&FLASH
//*FLSCT=&FLSCT
//*FMDEF=&FMDEF
//*FORM=&FORM
//*GROUPID=&GROUPID
//*HOLD=&HOLD
//*INDEX=&INDEX
//*INPUT=&INPUT
//*JACCT=&JACCT
//*JESDS=&JESDS
//*JNOTIFY=&JNOTIFY
//*JOBID=&JOBID
//*JOBNM=&JOBNM
//*JPNAME=&JPNAME
//*JPROC=&JPROC
//*JROOM=&JROOM
//*JSECL=&JSECL
//*LINDEX=&LINDEX
//*LINECT=&LINECT
//*NAME=&NAME
//*NOTIFY1=&NOTIFY1
//*NOTIFY2=&NOTIFY2
//*NOTIFY3=&NOTIFY3
//*NOTIFY4=&NOTIFY4
//*OPTCD=&OPTCD
//*PGDEF=&PGDEF
//*PIMCT=&PIMCT
//*PIMSG=&PIMSG
//*PRMODE=&PRMODE
//*PRTY=&PRTY
```

```

//*ROOM=&ROOM
//*STEPDD=&STEPDD
//*STEPNM=&STEPNM
//*SUBNAME=&SUBNAME
//*THRES=&THRES
//*TITLE=&TITLE
//*TRC=&TRC
//*UCS=&UCS
//*UDATA01=&UDATA01
//*UDATA02=&UDATA02
//*UDATA03=&UDATA03
//*UDATA04=&UDATA04
//*UDATA05=&UDATA05
//*UDATA06=&UDATA06
//*UDATA07=&UDATA07
//*UDATA08=&UDATA08
//*UDATA09=&UDATA09
//*UDATA10=&UDATA10
//*UDATA11=&UDATA11
//*UDATA12=&UDATA12
//*UDATA13=&UDATA13
//*UDATA14=&UDATA14
//*UDATA15=&UDATA15
//*UDATA16=&UDATA16
//*ULIB1=&ULIB1
//*ULIB2=&ULIB2
//*ULIB3=&ULIB3
//*ULIB4=&ULIB4
//*ULIB5=&ULIB5
//*ULIB6=&ULIB6
//*ULIB7=&ULIB7
//*ULIB8=&ULIB8
//*VPSDSN=&VPSDSN
//*WRITER=&WRITER
//*WTR=&WTR

```

Symbolic Definitions

This topic identifies the parameters that can be passed to the Process submitted by the Sterling Connect:Direct API.

Job and Jobstep Values

The following table lists the job and jobstep values.

Parameter	Definition
&JACCT	Job accounting number
&JNOTIFY	NOTIFY value
&JOBID	JOB ID assigned by JES
&JOBNM	JOB name
&JPNAME	Name of the programmer
&JPROC	Procedure name
&JROOM	Room number of the programmer
&JSECL	Security label
&STEPDD	DD name of the print file DD statement
&STEPNM	Process step name
&SUBNAME	User ID of the submitter

Parameter	Definition
&VPSDSN	Printer staged data set

Printer File Attributes

Refer to Sample Process for SYSOUT for the available parameters and associated symbolic names for print file attributes passed by the VPSSCDI interface program. Any non-zero attributes for a printer file cause the corresponding symbolic name to be generated on the SUBMIT command created by the Sterling Connect:Direct interface program, DGASVPSA . You can reference these symbolic names in the Sterling Connect:Direct Process you are submitting.

Customizing VPSSCDI

VPSSCDI creates the control blocks that the Sterling Connect:Direct API uses to build the SIGNON, SUBMIT, and SIGNOFF commands. Any customized validation or modification to the Sterling Connect:Direct control blocks is done at this point.

You can change printer values to reflect the destination environment. For example, you can change the destination name to a printer name at your location.

You can perform security or usage validation by validating any fields and either continuing the processing or returning to VPS with the appropriate return code settings.

The VPS return code settings are:

- RC=00 Normal execution continues.
- RC=04 Print file is queued per VPS printer specifications.
- RC=08 The printer is EDRAINed.

Note: Do not change VPS control blocks.

Chapter 10. Transferring Data to the JES Reader or Spool

Sterling Connect:Direct Spool Transfer transfers data from any Sterling Connect:Direct node and routes job control language (JCL) statements to the JES reader or sends files to the JES spool.

By transferring data to the JES reader, any Sterling Connect:Direct node can send z/OS JCL to the JES reader. Unlike the Sterling Connect:Direct RUN JOB, z/OS JCL can be located where the Process is executing, on any media that Sterling Connect:Direct supports.

The RUN JOB Security Exit provides a standard interface for security verification of job streams before they are submitted. For information on the RUN JOB Security Exit, search for Implementing Security.

Sterling Connect:Direct Spool Transfer uses dynamic allocation (SVC 99) to allocate the JES spool file. You can also use the OUTADD and OUTDEL macros to allocate an OUTPUT DD reference statement dynamically.

You can print a Sterling Connect:Direct banner page at the beginning of each print report. For information, search for Sterling Connect:Direct Banners.

Sterling Connect:Direct Spool Transfer supports the checkpoint/restart facility. Sterling Connect:Direct takes a checkpoint at the top of form of the page printed after the checkpoint interval. Top of form is one of the following:

- X'F1' for ASA carriage control
- X'8B' for machine carriage control
- LINECT (line count) if NOCC or the TOF=X'xx' is specified in the Process

Output to the JES Reader

Use Sterling Connect:Direct syntax to transfer data to the JES reader. To initiate this transfer, specify the keyword, `READER`, in the `COPY TO` Process statement for Sterling Connect:Direct nodes where this feature is enabled.

For older releases of Sterling Connect:Direct that do not support the `READER` keyword, use the `SYSOPTS` parameter `OUTPUT=READER`.

Examples of JCL Output

You can adapt the following Process language examples to output JCL into the JES reader. These examples are in the Sample Library, `SDGAPROC`.

Using the `READER` Keyword

The following sample Process (`DGAPRDR2`) uses the `READER` keyword to output JCL into the JES reader.

```

CDTORDR2 PROCESS SNODE=xx.xxx.xxxxx -
STEP01 COPY FROM(PNODE -
          DSN=SAMPLE.JCL.LIB(JCL) -
          DISP=SHR -
          ) -
          TO(SNODE -
          READER -
          ) -
EXIT

```

Using the SYSOPTS

The following sample Process (DGAPRDR1) uses SYSOPTS to output JCL into the JES reader.

```

CDTORDR1 PROCESS SNODE=xx.xxx.xxxxx -
STEP01 COPY FROM(PNODE -
          DSN=SAMPLE.JCL.LIB(JCL) -
          DISP=SHR -
          ) -
          TO(SNODE -
          DSN=NULLFILE -
          DISP=RPL -
          SYSOPTS="OUTPUT=READER" -
          ) -
EXIT

```

Output to JES Spool Files

You can also use Sterling Connect:Direct syntax to direct files transferred through Sterling Connect:Direct directly to the JES2/JES3 spool.

Copying a file into the JES spool is controlled through the SYSOUT=(.....) keyword on the COPY TO Process statement. Keyword and parameter definitions are in COPY TO Syntax to Support Spool Transfer.

You can specify all keywords available on the z/OS JCL SYSOUT DD statement within the Sterling Connect:Direct SYSOUT=(...) Process keyword. The format of all subparameters within the Sterling Connect:Direct SYSOUT=(...) follows the rules in the OS/390 JCL Reference Guide for that keyword.

Note: You cannot use SYSOUT=class because the Sterling Connect:Direct feature requires that you specify all subparameters within parentheses.

Sterling Connect:Direct Banners

You can print a Sterling Connect:Direct banner page at the beginning of each print report. If you selected the checkpoint/restart option for the file transfer, the word RESTARTED is added to the banner page during restart.

Select this option by coding the BANNER=(...) subparameter of the SYSOUT=(...) Process keyword. Banner values are supplied in pairs of literal = value. One banner line is printed for each supplied pair. Keyword and parameter definitions are in Sterling Connect:Direct COPY Process.

If the value contains a character other than 0–9 or A–Z, you must enclose it in quotation marks. For example, PROGRAMMER=John Doe must be specified as PROGRAMMER="John Doe". JOBNAME=OS/400 must be specified JOBNAME="OS/400".

You can use literals of 1–25 characters. Literals longer than 25 characters are truncated. Values can be 1–30 characters. Values longer than 30 characters are truncated. If the literal or value contains a character other than 0–9 or A–Z, you must enclose it in quotation marks.

In the following example, three banner data lines are printed. JUNK is ignored because it is not paired with a value.

```
BANNER=(PROGRAMMER=&JPNAME, JOBNAME=&JOBNM,          -
          SUBMITTER=&SUBNAME, STEPNAME=&STEPNM,       -
          DDNAME=&STEPDD, JUNK)
```

Assuming that the symbolics are set to the values defined previously, the following example is generated.

```
***** C O N N E C T : D I R E C T *****
***** C O N N E C T : D I R E C T *****
***** C O N N E C T : D I R E C T *****
***** C O N N E C T : D I R E C T *****
****  PROGRAMMER          JOHN DOE          ****
****  JOBNAME             JOHN1X           ****
****  SUBMITTER           JOHN1            ****
****  STEPNAME            STEP1            ****
****  DDNAME              SYSUT2           ****
***** C O N N E C T : D I R E C T *****
***** C O N N E C T : D I R E C T *****
***** C O N N E C T : D I R E C T *****
***** C O N N E C T : D I R E C T *****
```

The following example illustrates the banner that prints if the job is restarted.

```
***** C O N N E C T : D I R E C T *****
***** C O N N E C T : D I R E C T *****
***** C O N N E C T : D I R E C T *****
***** C O N N E C T : D I R E C T *****
***** R E S T A R T E D *****
****  PROGRAMMER          JOHN DOE          ****
****  JOBNAME             JOHN1X           ****
****  SUBMITTER           JOHN1            ****
****  STEPNAME            STEP1            ****
****  DDNAME              SYSUT2           ****
***** R E S T A R T E D *****
***** C O N N E C T : D I R E C T *****
***** C O N N E C T : D I R E C T *****
***** C O N N E C T : D I R E C T *****
***** C O N N E C T : D I R E C T *****
```

Sterling Connect:Direct COPY Process

The Sterling Connect:Direct COPY Process controls the printing of the output data set by specifying key values within the new Process keyword SYSOUT=(...) or by using the SYSOPTS=(SYSOUT=(...)) for platforms other than z/OS.

COPY Process Examples

The following sample Process shows the simplest COPY Process. SYSOUT=A is not a valid value in this example. Put all subparameters in parentheses, and set CLASS to the output class assigned to the print file.

```
TESTP  PROCESS  SNODE=  
STEP01  COPY    FROM(DSN=NAME,DISP=SHR)          -  
                                TO(SYSOUT=(CLASS=A))  -  
                                )  
  
      END
```

The next example is an alternative way to write the same Process. In this example, the CLASS= parameter is not required because of the additional parentheses in the first parenthetical group of the SYSOUT keyword. This example corresponds to the syntax of the SYSOUT DD statement.

```
TESTP  PROCESS  SNODE=  
STEP01  COPY    FROM(DSN=NAME,DISP=SHR)          -  
                                TO(SYSOUT=((A,writer-name,form-name),...)) -  
                                )  
  
      END
```

The following example uses the SYSOUT= keyword and its subparameters within the SYSOPTS keyword.

```
TESTP  PROCESS  SNODE=  
STEP01  COPY    FROM(DSN=NAME,DISP=SHR)          -  
                                TO(DSN=NULLFILE      -  
                                SYSOPTS="(SYSOUT=(CLASS=A))" -  
                                )  
  
      END
```

Carriage Control

The input file DCB RECFM specification determines carriage control. If RECFM is VA, VBA, FA, FBA, or UA, ASA carriage control is assigned (ASA is also the default). If RECFM is VM, VBM, FM, FBM, or UM, then machine carriage control is assigned.

You can optionally override the specification by defining the NOCC, LINECT, and TOF parameters in the SYSOUT keyword CC=. Keyword and parameter definitions are in the following section, COPY TO Syntax to Support Spool Transfer.

The following example shows how to override carriage control specifications.

```
TESTP  PROCESS  SNODE=  
STEP01  COPY    FROM(DSN=NAME,DISP=SHR)          -  
                                TO(SYSOUT=(CLASS=A,   -  
                                CC=(NOCC,LINACT=n,TOF=x'F1')) -  
                                )  
  
      END
```

COPY TO Syntax to Support Spool Transfer

All keywords and parameters of the COPY TO statement that support Spool Transfer are defined in this section. The table provided in the Symbolics Definitions section identifies where the parameters of the SYSOUT=(...) keyword are documented.

For detailed information on other keywords and parameters, see the Connect:Direct Process Language help.

Keyword	Description
READER	Specifies the output data set that is directed to the JES reader.
SYSOUT=(...)	Controls the printing of the output data set.
BANNER= ('literal 1' = value1 [, 'literal 2' = value2 [...]])	<p>Specifies the banner values in pairs of literal = value. One banner line is printed for each supplied pair. A literal without a corresponding value is ignored.</p> <p>You can use literals of 1–25 characters. Literals greater than 25 characters are truncated. You can use a value size of 1–30 characters. Values greater than the 30 characters are truncated.</p> <p>If the name or value contains a character other than 0–9 or A–Z, you must enclose it in quotation marks.</p>
CC=(A M NOCC LINECT= TOF=)	<p>Overrides carriage control supplied by the input file DCB RECFM.</p> <p>A (for ASA) is assigned if RECFM is VA, VBA, FA, FBA, or UA. It is also the default if carriage control is not specified.</p> <p>M (for machine) is assigned if RECFM is VM, VBM, FM, FBM, or UM.</p> <p>NOCC identifies the file as having no carriage control. If you specify NOCC, you must also specify LINECT and TOF.</p> <p>LINECT=nnn identifies the number of lines printed per page. The default is <u>55</u>.</p> <p>TOF=X'F1' identifies the hex character that is inserted in the print line at the interval specified in the LINECT parameter. The hex character specified by the TOF parameter indicates to skip to the top of form. The default is X'F1'.</p>
SYSOPTS="..."	<p>OUTPUT=READER specifies that the output data set is directed to the JES reader.</p> <p>SYSOUT=(class=class) (class,writer-name,form-name) specifies that the output data set is directed to the JES spool files on platforms other than z/OS.</p>

Symbolic Definitions for the SYSOUT Keyword

The following table lists the subparameter fields for the SYSOUT keyword, identifies the format for the parameter, and the VPS symbolic name.

The As Documented by column states where to find additional information about the parameters. Spool Transfer indicates that the parameter is documented in this book. References to JCL parameters indicate that additional information is available in the MVS JCL documentation.

Parameter	Format	VPS Symbolic Name	As Documented By
ADDRESS=	('adress line1', address line2', address line3, address line4)	&ADDR1, &ADDR2, &ADDR3, &ADDR4	SYSOUT DD
BANNER=	('literal 1' = value1, 'literal 2' = value2,...)		Spool Transfer
BUILDING=	'building identification'	&BLDG	OUTPUT DD
BURST=	Yes or No	&BURST	OUTPUT DD & SYSOUT DD
CC=	ASA or Machine or NOCC		Spool Transfer
CHARS=	(tablename, tablename...)	&CHARS	OUTPUT DD & SYSOUT DD
CKPTLINE=	nnnnn	&CKPTL	OUTPUT DD
CKPTPAGE=	nnnnn	&CKPTP	OUTPUT DD
CKPTSEC=	nnnnn	&CKPTS	OUTPUT DD
CLASS=	class	&CLASS	OUTPUT DD
COMPACT=	compaction-table- name	&COMPACT	
COMSETUP=	name		OUTPUT DD
CONTROL=	PROGRAM SINGLE DOUBLE TRIPLE	&CNTL	OUTPUT DD
COPIES=	nnn (,(group value, group value,...))	&COPIES ©G	SYSOUT DD OUTPUT DD
DATAACK=	BLOCK UNBLOCK BLKCHAR BLKPDS	&DATCK	OUTPUT DD
DEFAULT=	Yes or No	&DEFAULT	OUTPUT DD
DEPT=	'department identification'	&DEPT	OUTPUT DD
DEST=	destination (nodename, userid)	&DEST	SYSOUT DD OUTPUT DD
DPAGELBL=	Yes or No		OUTPUT DD
FCB=	fcb-name (fcb-name, align verify)	&FCB	SYSOUT DD & OUTPUT DD
FLASH=	(overlay-name, count) (,count)	&FLASH &FLSCT	SYSOUT DD & OUTPUT DD
FORMDEF=	membername	&FMDEF	OUTPUT DD
FORMS=	form-name	&FORM	OUTPUT DD
GROUPID=	output-group	&GROUPID	OUTPUT DD
HOLD=	Yes or No		SYSOUT DD

Parameter	Format	VPS Symbolic Name	As Documented By
INDEX=	nn	&INDEX	OUTPUT DD
JESDS=	ALL JCL LOG MSG	&JESDS	OUTPUT DD
JOBNAME=	job name	&JOBNM	Spool Transfer
LINDEX	nn	&LINDEX	OUTPUT DD
LINECT=	nnn	&LINECT	OUTPUT DD
MODIFY=	module-name (module-name, trc)	&CMOD &CMTTC	SYSOUT DD & OUTPUT DD
NAME=	name of output separator	&NAME	OUTPUT DD
NOTIFY=	node.userid (node.userid, node.userid,...)	&NOTIFY1-4	OUTPUT DD
OPTJ=	Yes or No	&OPTCD	Spool Transfer
OUTBIN=	nnnnn		OUTPUT DD
OUTDISP=	(normal, abnormal)		OUTPUT DD
OUTPUT=	(reference)		SYSOUT DD
PAGEDEF=	membername	&PGDEF	OUTPUT DD
PIMSG=	(yes,msg-count) (no,msg-count)	&PIMSG &PIMCT	OUTPUT DD
PRMODE=	line page process-mode	&PRMODE	OUTPUT DD
PRTY=	nnn	&PRTY	OUTPUT DD
ROOM=	'room identification'	&ROOM	OUTPUT DD
SYSAREA=	Yes No		OUTPUT DD
SYSOUT=	(class) (class, writer-name, form-name)	&CLASS &WRITER &FORM	SYSOUT DD
THRESHLD=	nnnnnnnn	&THRES	OUTPUT DD
TITLE=	'description of output'	&TITLE	OUTPUT DD
TOF=	X'F1'		Spool Transfer
TRC=	Yes No	&TRC	OUTPUT DD
UCS=	character-set-code (character-set-code, fold, verify)	&UCS	OUTPUT DD SYSOUT DD

Parameter	Format	VPS Symbolic Name	As Documented By
USERDATA=	('user data description', 'user data description',...)	&UDATA01-16	OUTPUT DD
USERLIB=	('library name 1', 'library name 2',...)	&ULIB1-8	OUTPUT DD
WRITER=	name	&WRITER	OUTPUT DD

Sample Process for SYSOUT

The following sample Process shows all attributes that you can specify within the SYSOUT=(...) keyword. This sample Process is provided in the Sample Library, SDGAPROC.

```

/* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * */
/*                                                                 */
/*           * * *   S A M P L E   P R O C E S S   * * *           */
/*                                                                 */
/*           C:D-ZOS JES SPOOL TRANSFER FACILITY SAMPLE PROCESS   */
/*           INPUT FROM JES SPOOL TRANSFER FACILITY               */
/*           OUTPUT TO VPS CONTROLLED PRINTER                     */
/*                                                                 */
/* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * */
CDTOJES PROC  SNODE=&SNODE, -
              &ADDR1=,      /* ADDRESS LINE 1          */ -
              &ADDR2=,      /* ADDRESS LINE 1          */ -
              &ADDR3=,      /* ADDRESS LINE 1          */ -
              &ADDR4=,      /* ADDRESS LINE 1          */ -
              &BLDG=,       /* BUILDING                */ -
              &BURST=,      /* BURST=YES OR NO        */ -
              &CHARS=,     /* CHAR ARRANGEMENT TABLE */ -
              &CKPTL=,     /* CKPTLINE                */ -
              &CKPTP=,     /* CKPTPAGE                */ -
              &CKPTS=,     /* CKPTSEC                 */ -
              &CLASS=,     /* OUTPUT CLASS            */ -
              &CMOD=,     /* COPY MODIFICATION MOD   */ -
              &CMTTC=,     /* COPY MODULE TABLE REF  */ -
              &CNTL=,     /* DEFAULT SPACING         */ -
              &COMPACT=,   /* COMPACTATION TABLE     */ -
              &COPIES=,    /* OUTPUT NUMBER COPIES   */ -
              &COPYG=,     /* COPY GROUP(S)           */ -
              &DATCK=,     /* DATAK                   */ -
              &DEFAULT=,   /* DEFAULT                  */ -
              &DEPT=,     /* DEPARTMENT              */ -
              &DEST=,     /* OUTPUT DESTINATION      */ -
              &FCB=,      /* OUTPUT WTR FCB         */ -
              &FLASH=,    /* FLASH FORMS OVERLAY     */ -
              &FLSCT=,    /* FLASH FORMS OVERLAY CNT*/ -
              &FMDEF=,    /* FORMDEF                  */ -
              &FORM=,     /* OUTPUT FORM              */ -
              &GROUPID=,  /* GROUPID                  */ -
              &INDEX=,    /* INDEX                    */ -
              &JACCT=,    /* JOB ACCOUNTING NUMBER   */ -
              &JESDS=,    /* JESDS                    */ -
              &JOBID=,    /* JES ASSIGNED JOB ID    */ -
              &JOBNM=,    /* JOB NAME                 */ -
              &JPNAME=,   /* JOB PROGRAMMERS NAME   */ -
              &JPROC=,    /* JOB PROC NAME           */ -
              &JROOM=,    /* JOB PROGRAMMERS ROOM   */ -
              &JSECL=,    /* SECURITY LABEL           */ -

```



```

&LINDEX=, /* LINDEX */ -
&LINECT=, /* LINES PER PAGE */ -
&NAME=, /* NAME */ -
&NOTIFY1=, /* 1ST NOTIFY ID */ -
&NOTIFY2=, /* 2ND NOTIFY ID */ -
&NOTIFY3=, /* 3RD NOTIFY ID */ -
&NOTIFY4=, /* 4TH NOTIFY ID */ -
&OPTCD=, /* OPTCD=J SPECIFIED */ -
&PGDEF=, /* PAGEDEF */ -
&PIMCT=, /* PIMSG MSG-COUNT */ -
&PIMSG=, /* PIMSG */ -
&PRMODE=, /* PRMODE */ -
&PRTY=, /* PRTY */ -
&ROOM=, /* ROOM */ -
&STEPDD=, /* STEP DDNAME */ -
&STEPNM=, /* STEP NAME */ -
&SUBNAME=, /* SUBMITTERS NAME */ -
&THRES=, /* THRESHLD */ -
&TITLE=, /* TITLE */ -
&TOF=X'F1', /* ASA TOP OF FORM */ -
&TRC=, /* TRC */ -
&UCS=, /* OUTPUT WTR UCS */ -
&UDATA01=, /* 1ST USERDATA */ -
&UDATA02=, /* 2ND USERDATA */ -
&UDATA03=, /* 3RD USERDATA */ -
&UDATA04=, /* 4TH USERDATA */ -
&UDATA05=, /* 5TH USERDATA */ -
&UDATA06=, /* 6TH USERDATA */ -
&UDATA07=, /* 7TH USERDATA */ -
&UDATA08=, /* 8TH USERDATA */ -
&UDATA09=, /* 9TH USERDATA */ -
&UDATA10=, /* 10TH USERDATA */ -
&UDATA11=, /* 11TH USERDATA */ -
&UDATA12=, /* 12TH USERDATA */ -
&UDATA13=, /* 13TH USERDATA */ -
&UDATA14=, /* 14TH USERDATA */ -
&UDATA15=, /* 15TH USERDATA */ -
&UDATA16=, /* 16TH USERDATA */ -
&ULIB1=, /* 1ST USERLIB LIBRARY */ -
&ULIB2=, /* 2ND USERLIB LIBRARY */ -
&ULIB3=, /* 3RD USERLIB LIBRARY */ -
&ULIB4=, /* 4TH USERLIB LIBRARY */ -
&ULIB5=, /* 5TH USERLIB LIBRARY */ -
&ULIB6=, /* 6TH USERLIB LIBRARY */ -
&ULIB7=, /* 7TH USERLIB LIBRARY */ -
&ULIB8=, /* 8TH USERLIB LIBRARY */ -
&VPSDSN=, /* VPS PRINTER STAGED DSN */ -
&WRITER=, /* OUTPUT WRITER NAME */ -
&WTR=, /* OUTPUT WTR NAME (OLD) */ -
/* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * */
/* COPY FILE FROM VPS STAGED DATASET INTO JES SPOOL */
/* DESTINATION HAS BEEN CHANGED TO A VPS CONTROLLED PRINTER. */
/* BANNER PAGE WILL BE PRODUCED. */
/* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * */
STEP01 COPY FROM( PNODE -
DSN=&VPSDSN -
DISP=SHR ) -
CKPT=IM -
COMPRESS EXT -
TO( SNODE -
SYSOUT=(CLASS=&CLASS,COPIES=&COPIES,DEST=&DEST -
BANNER=(PROGRAMMER=&JPNAME,JOBNAME=&JOBNM, -
SUBMITTER=&SUBNAME,STEPNAME=&STEPNM, -
DDNAME=&STEPDD),JOBNAME=&JOBNM) -
)
/* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * */
/* DELETE VPS STAGE INPUT FILE */

```

```
/* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * */
STEP02  IF      (STEP01 = 0) THEN
STEP03  RUN TASK (PGM=DMRTDYN                                -
              PARM=(C"ALLOC DSN=&VPSDSN,DISP=(OLD,DELETE)"  -
              F'-1'                                         -
              C"UNALLOC DSN=&VPSDSN"))
              EIF
              EXIT
```

Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing

IBM Corporation

North Castle Drive

Armonk, NY 10504-1785

U.S.A.

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing

Legal and Intellectual Property Law

IBM Japan Ltd.

19-21, Nihonbashi-Hakozakicho, Chuo-ku

Tokyo 103-8510, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be

incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation

J46A/G4

555 Bailey Avenue

San Jose, CA 95141-1003

U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

All IBM prices shown are IBM's suggested retail prices, are current and are subject to change without notice. Dealer prices may vary.

This information is for planning purposes only. The information herein is subject to change before the products described become available.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work, must include a copyright notice as follows:

© IBM 2014. Portions of this code are derived from IBM Corp. Sample Programs. © Copyright IBM Corp. 2014.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

Trademarks

IBM, the IBM logo, and [ibm.com](http://www.ibm.com)[®] are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at <http://www.ibm.com/legal/copytrade.shtml>.

Adobe, the Adobe logo, PostScript, and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

IT Infrastructure Library is a registered trademark of the Central Computer and Telecommunications Agency which is now part of the Office of Government Commerce.

Intel, Intel logo, Intel Inside, Intel Inside logo, Intel Centrino, Intel Centrino logo, Celeron, Intel Xeon, Intel SpeedStep, Itanium, and Pentium are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

ITIL is a registered trademark, and a registered community trademark of the Office of Government Commerce, and is registered in the U.S. Patent and Trademark Office.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Java™ and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Cell Broadband Engine is a trademark of Sony Computer Entertainment, Inc. in the United States, other countries, or both and is used under license therefrom.

Linear Tape-Open, LTO, the LTO Logo, Ultrium and the Ultrium Logo are trademarks of HP, IBM Corp. and Quantum in the U.S. and other countries.

Connect Control Center®, Connect:Direct®, Connect:Enterprise®, Gentran®, Gentran®:Basic®, Gentran:Control®, Gentran:Director®, Gentran:Plus®, Gentran:Realtime®, Gentran:Server®, Gentran:Viewpoint®, Sterling Commerce™, Sterling Information Broker®, and Sterling Integrator® are trademarks or registered trademarks of Sterling Commerce®, Inc., an IBM Company.

Other company, product, and service names may be trademarks or service marks of others.

Index

Special characters

%INCLUDE 29

A

Activity Reporting System (ARS)
 business solutions 18
 example 3
 field descriptions 3
Activity Reporting System (ARS):in
 conjunction with Sterling
 Connect\.:Direct 17
Activity Reporting System (ARS):tracking
 Sterling Connect\.:Direct activities 18
ALLOC.CODES initialization
 parameter[alloc.codes initialization
 parameter] 52
Application Program Interface (API) 70,
73
ARS Reports
 customizing 31
 methods of requesting 3, 17
 multiple reports
 job stream definitions 28
 sample job stream 27
 sample Process to submit job
 stream 30
 requesting through a Process 17
 requesting through a scheduling
 subsystem 17
 requesting through screens 19
 using 17
ARS screens
 accessing through IUI 19
 Report Options
 example 20
 field descriptions 21
 SAS Requirements
 example 23
 field descriptions 23
 using 19
ARS screens: Sterling Connect\.:Direct
 Requirements:example 22
ARS screens: Sterling Connect\.:Direct
 Requirements:field descriptions 23
Authorization Event record 32
Automatic signon 45

B

Banners
 coding 92

C

Capacity planning 18
Carriage control 93
Change Process Termination record 33

CICS
 API interface
 verify software installation 61
 create ESS registration program 61
CLISTs:setting up for Sterling
 Connect\.:Direct for z/OS 46
COMMAND MSG ID field 71
COMMAND RC field 71
Commands 45, 47, 50
 EVENT SERVICES DISPLAY
 format 70
 parameters 70
 EVENT SERVICES START
 format 68
 EVENT SERVICES STOP
 format 69
 EXEC CICS LINK 72
 submitting 47
COMMAREA 71
Components
 diagram 79
 JES Spool Transfer
 Application Program Interface 79
 Data Transmission Facility 79
 VTAM Printer Support 79
 VTAM printer support 80
Components: Sterling Connect\.:Direct
 API 81
COPY process 93
COPY termination (CT)
 message 49
 record 34

D

Data center management 18
Data recovery 55
Data set access security failures 8
DATA SET NAME CONTAINING SAS
 ROUTINES 23
Dates:how Sterling Connect\.:Direct
 processes 64
Delete Process
 termination record 36
DGA\$NHDR 62
DGADBATC 28
DGAE commands 57
DGAE transaction 70
DGAPGNER JCL 86
DGAPOCES 83
DGAQ247 processing 72
DGAQM98 processing 72
DGASVPSA 81
Display Statistics record 36
DMSGFIL 28
DMPRINT 28
DMPUBLIB 28

E

EIB (Exec interface block) 72
Entry fields
 COMMAND 71
 COMMAND MSG 71
Error messages 49
ESS user exit 61
Event data
 reading 74
Event definition 55
Event enhancements
 COPY termination 77
 event records 77
Event filtering 56, 59
Event record
 type attributes 75
EVENT RESTART DATA 72
EVENT SERVICES CREATE
 format 62
 parameters
 ID 62
 ORWHERE 62
EVENT SERVICES DISPLAY
 ID parameter 70
EVENT SERVICES START
 example 68
 parameters 68
EVENT SERVICES STOP
 parameters 69
Event Services Support (ESS)
 interface 56
 output data format 74
Examples: Sterling Connect\.:Direct for
 z/OS 47
Exception Report
 description 6
 field descriptions 7
 use 17

F

F jobname command 47, 50
Field descriptions
 Non-PDS Copy Report 10
 PDS Copy Report 11
 Run Job Report 13
 Run Task Report 14
 Submit Within a Process Report 15
Flush Process/Suspend Process
 Termination record 37
FT20F001 28
Function Reports
 description 9, 17
 Non-PDS Copy Report 9
 PDS Copy Report 9
 Run Job Report 9
 Run Task Report 9
 Submit Within a Process Report 9

I

Initialization parameters[initialization parameters] 51

J

JES

- overview 79
- print queues 79
- reader 91
- reader queues 79
- spool transfer components 79

Job stream

- definitions 28
- modifying for multiple reports 27
- producing ARS reports 19
- SAS options 28
- submitting 29
- viewing from screen 24

JOBCARD INFO 23, 28

jobname 47, 50

M

MCS.CLIST initialization parameter 45

MESSAGE DATA SET NAME 23

Messages 50, 51, 52, 53

multiple reports

- sample job stream 27

Multiple reports

- job stream definitions 28
- routing to an output data set 30
- sample Process to submit job stream 29

N

NDMX0001 28

Non-PDS Copy Report

- description 9

O

Operations

- input from JES spool files 79
- input to JES print queues 79
- input to JES reader queues 79

Operator interface

- invoking 45
- options 47, 50

Output

- data sets 30
- to the JES reader 91

OUTPUT (SYSOUT) CLASS 24

P

Parameters

- CASE 67
- CCODE 63
- EXIT 67
- FNAME 67
- ID 63
- LASTSEQ 67, 69

Parameters (continued)

- MAXQCNT 67

- ORWHERE 68

- PNAME 64

- PNUMBER 64

- SNODE 66

- STARTT 64

- STOPT 66

- SYSOUT 95

- TYPE 66

- USER 66

- WHERE 63, 68

PDS Copy Report

- description 11

PDS Member Copy record 38

Problem isolation 18

Process names 82

PROCESS NUMBER field 71

Process security failures 8

Process Submit Statistics record 38

Process Termination record 39

PUBLIC PROCESS LIBRARIES 23

R

Record types 75

Run Job Report

- description 12

RUN JOB security exit 91

Run Job Termination record 40

Run Task Report

- description 13

Run Task Termination record 41

S

Sample CLISTs: Sterling Connect\Direct

- for z/OS 45

Sample Process to submit job stream 29

Sample Processes

- CDPROCS 83

- copyfile 94

Samples

- CICS API 55

- ESS event records 59

- ESSEVX01 61

- event exit 55

- EVENT SERVICES CREATE 68

- trace of ESS records 59

SAS

- Informat variables 31, 32

SAS CATALOGED PROCEDURE 23

SASPROGS 28

SASTEP 28

SDGAOPLS sample library:z/OS 45

Security subsystems 9

- CA-ACF2 9

Security Violations Report

- description 8, 17

- example 8

- field descriptions 9

- use 18

SIGNON 82

Signon security failures 8

Signon/Signoff Statistics record 42

START DATE 22

Start Sterling Connect\Direct Command record 42

START TIME 22

STEPLIB 28

STEPLIB DATA SET NAME 23

Sterling Connect\Direct for

- z/OS: Operation error messages 49

Sterling Connect\Direct for

- z/OS: Operator interface 45, 47

Sterling Connect\

- :Direct: commands: issuing 72

Sterling Connect\

- :Direct: commands: issuing from

- CICS 70

Sterling Connect\Direct: Event Services

- Support: advantages 55

Sterling Connect\Direct: Event Services

- Support: concepts 55

Sterling Connect\Direct: Event Services

- Support: interfaces 55

Sterling Connect\Direct: utilization 18

Stop Sterling Connect\Direct Command

- record 43

Submit Within a Process Report

- description 14

Summary Report

- description 4

- example 4

- field descriptions 5

Symbolic definitions

- job and jobstep values 88

- printer file attributes 88

SYSIN 28

SYSOUT 92

SYSPRINT 28

System architecture

- Event Services Support 56

System control

- printer initialization 80

- printer termination 80

- SYSOUT data set ready 80

- system initialization 80

- system termination 81

System Management Facility 17

T

TD EXIT COUNT field 71

TEMPDSN 28

Time Sharing Option 17

Transient data

- data flow diagram 58

- ESS data flow 58

- queue 61, 73

TS MAX LRECL field 71

TS QUEUE NAME field 71

Type attributes

- COPY I/O start 75

- COPY step initiation 75

- event request initiation 76

- event request stop 76

- event session lost 76

- HOLD queue 77

- Process initiation 76

- Process moved to EXEC queue 76

- RUN JOB start 76

- RUN TASK initiation 77

Type attributes (*continued*)

TIMER queue 77

WAIT queue 77

V

VPS

initialization 79

VPSSCDI 79, 80, 81

W

WORK 28

Write to Operator (WTO) Statistics

record 43

WTO (Write to operator)[wto (write to operator)] 51

WTOR (Write to operator with reply)[wtor (write to operator with reply)] 51, 53



Product Number: 5655-X01

Printed in USA