

Sterling B2B Integrator



# Windows Non-Cluster Environment Installation

*Version 5.2.3 - 5.2.5*



Sterling B2B Integrator



# Windows Non-Cluster Environment Installation

*Version 5.2.3 - 5.2.5*

**Note**

Before using this information and the product it supports, read the information in "Notices" on page 87.

**Copyright**

This edition applies to Version 5 Release 2 Modification 3 of Sterling B2B Integrator and to all subsequent releases and modifications until otherwise indicated in new editions.

© **Copyright IBM Corporation 2000, 2015.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

## Windows Non-Cluster Environment

### Installation (V5.2.3 - 5.2.5) . . . . . 1

Installation Overview . . . . .	1
Prerequisite Knowledge for Windows Installation	1
Intended audience . . . . .	1
Assumptions for this guide . . . . .	1
Prepare Your System for Installation . . . . .	1
Before You Begin the Installation in a Windows Environment . . . . .	1
System Verification Tasks for a Windows Environment . . . . .	2
Verification of the system requirements . . . . .	2
Configure the Database . . . . .	3
Supported Database Servers in a Non-Cluster Environment . . . . .	3
Database Information You Need Before You Install Sterling B2B Integrator in a Non-Cluster Environment . . . . .	3
Database sizing and capacity planning. . . . .	3
Database Definition Language (DDL) Statements . . . . .	4
Configure the DB2 Database . . . . .	4
Configure the Oracle Database . . . . .	8
Configure the Microsoft SQL Server Database . . . . .	17
Configure the MySQL Database . . . . .	20
Database Password Management . . . . .	22
Installation Checklist . . . . .	25
Installation Checklist for a Windows Non-Cluster Environment . . . . .	25
License information. . . . .	26
Extracting the core license file . . . . .	26
Port Numbers in a Windows Environment . . . . .	27
Security certificates . . . . .	27
Install the Software . . . . .	27
General Installation/Upgrade Information for a Windows Non-Cluster Environment . . . . .	27
General Installation Manager information . . . . .	29
Installing in a Windows non-cluster environment with the IBM Installation Manager in GUI mode . . . . .	31
Installing in a Windows non-cluster environment with the IBM Installation Manager in text mode . . . . .	36
Silent installations . . . . .	41
Installing version 5.2.x as a fix pack . . . . .	47
Configure the Sterling B2B Integrator Desktop Icon for Windows Server 2008 . . . . .	48
Validate the Installation . . . . .	49
Installation validation checklist . . . . .	49
Starting Sterling B2B Integrator in a Windows noncluster environment . . . . .	49
Accessing Sterling B2B Integrator . . . . .	50
Validating the installation with a sample business process . . . . .	50
Stop Sterling B2B Integrator (Windows) . . . . .	50
Stop Sterling B2B Integrator (Hardstop Windows) . . . . .	50
Post Installation Configuration . . . . .	51

Post Installation Configuration Checklist (Windows). . . . .	51
Download of the Sterling B2B Integrator tools . . . . .	51
Property files configuration in a Windows environment . . . . .	52
System Maintenance . . . . .	52
System Maintenance . . . . .	52
Determine If You Need to Apply a Fix Pack (Windows). . . . .	53
DB Checksum Tool . . . . .	56
Fix Pack Changes Report . . . . .	57
License modifications . . . . .	59
Configure Non-English Environment . . . . .	61
Non-English Environment Checklist . . . . .	61
Language Settings in a Windows Environment . . . . .	61
Install the Language Pack (Windows). . . . .	62
Load the Language Pack Factory Defaults (Windows). . . . .	62
Load the Language Pack Translations (Windows) . . . . .	63
Configure Encodings for Sterling B2B Integrator (Windows). . . . .	63
Configure Locales (Windows) . . . . .	64
Configure Browser Settings for a Foreign Language . . . . .	65
Configure Browser Settings . . . . .	65
Support for foreign languages . . . . .	65
Add a Custom Language Preference Code . . . . .	66
Change Default Browser Font . . . . .	67
Set the Client Character Display . . . . .	68
Clearing Browser and Java Plugin Caches Before Initial Deployment . . . . .	69
General Internet Explorer Browser Settings . . . . .	69
Internet Explorer Security Settings. . . . .	69
Perimeter Server Installation. . . . .	71
Perimeter Server Overview . . . . .	71
Installation Guidelines for Perimeter Servers with Sterling B2B Integrator . . . . .	72
Perimeter Server Installation Methods . . . . .	72
Perimeter Server Information Gathering Checklist . . . . .	72
Perimeter Server Security Vulnerabilities. . . . .	73
Installing a Perimeter Server in a More Secure Network (Windows) . . . . .	73
Installing a perimeter server in a less secure network (Windows) . . . . .	74
Silent Installation Method for an External Perimeter Server. . . . .	76
Install a Fix Pack in a Remote Perimeter Server (Windows). . . . .	77
Grant Permissions for Specific Activities for a Perimeter Server. . . . .	78
Perform DNS Lookup on Remote Perimeter Server . . . . .	79
Start Perimeter Servers (Windows). . . . .	79
Stop Perimeter Servers in (Windows). . . . .	80
User Documentation . . . . .	80
Sterling B2B Integrator user documentation. . . . .	80
Improving your access to online documentation . . . . .	81

Request a Documentation CD . . . . . 81  
Uninstall the Software . . . . . 81  
    Uninstall Sterling B2B Integrator from a  
    Windows Non-Cluster Environment . . . . . 81  
Troubleshooting Tips . . . . . 83  
    Troubleshooting Tips for Windows Environment 83

**Notices . . . . . 87**  
Trademarks . . . . . 89  
Terms and conditions for product documentation. . 90

---

## Windows Non-Cluster Environment Installation (V5.2.3 - 5.2.5)

You may follow different installation and upgrade scenarios when you install and upgrade IBM® Sterling B2B Integrator in a Windows Non-Cluster (single node) environment.

### Installation Scenarios for Version 5.2.3 - 5.2.5.x.

It is important to review the following installation scenarios:

Scenario	Instructions
Version 5.2.0 - 5.2.2 is installed as the base release and it needs to be upgraded to the 5.2.3 level.	Use the <i>Install Version 5.2.x as a Fix Pack</i> instructions provided in <i>Install the Software</i> .
Version 5.2.3 is being installed as the base release.	Review this document and use the installation instructions in <i>Install the Software</i> .
Version 5.2.3 is installed as the base release and it needs to be upgraded to a later 5.2.x level.	Use the <i>Install Version 5.2.x as a Fix Pack</i> instructions provided in <i>Install the Software</i> .

---

## Installation Overview

### Prerequisite Knowledge for Windows Installation

Before you begin the installation, you should be knowledgeable on the following topics:

- Application servers
- Database administration
- System Requirements for this release of Sterling B2B Integrator.

### Intended audience

This document can be used by different members of your organization.

This document is intended for use by:

- System administrators
- Installation engineers
- Database administrators.

### Assumptions for this guide

The procedures in this guide are accurate as of the publication date and are specific to this version of the document.

---

## Prepare Your System for Installation

### Before You Begin the Installation in a Windows Environment

Before you begin the installation, you need to:

- Perform some system verification tasks

- Download the correct version of the JDKs, JCE, and JDBC drivers required. See the *System Requirements* for information on how to download the correct version of each.

## System Verification Tasks for a Windows Environment

Before you begin an installation, you need to:

#	System Verification Items	Your Notes
1	<p>Use the system requirements to verify that your system hardware and software meet the requirements specified for this release.</p> <p>Verify you have the correct:</p> <ul style="list-style-type: none"> <li>• Patches required by Java™ for the operation system</li> <li>• Version of the JDK</li> <li>• Absolute path to JDK and patches</li> </ul>	
2	Verify the file system has adequate free disk space.	
3	<p>Verify that your database has been installed and configured.</p> <p>If you are going to manually apply DDL statements, you need to complete the data base schema work before you begin the installation.</p>	
4	If you are using a non-English environment, confirm that you are using the appropriate character set.	

## Verification of the system requirements

Before you begin the installation, verify that your system meets the hardware and software requirements that are specified for this release.

The hardware requirements that are listed in the *System Requirements* are the minimum requirements. Your system requirements exceed these requirements if you are running other applications on the same machine as Sterling B2B Integrator.

The installation strictly enforces the following system requirements:

- Operating system version must match requirement exactly.
- The minimum patch level for the operating system is enforced, but you can apply higher patch levels.
- JDK version must match requirement exactly.
- The disk space is a minimum for the installation. The system must be separately sized to handle whatever load is going to be put on the system.
- Database version must match exactly.
- JDBC driver version supports exact matches and wildcard matches.

If any of these requirements are not met, the installation fails. If the installation fails, review the installation log for a list of noncompliant items.



---

## Configure the Database

### Supported Database Servers in a Non-Cluster Environment

In a non-clustered environment, the following databases can be configured:

- Oracle®
- DB2
- Microsoft SQL Server - In this document, where ever Microsoft SQL Server (MSSQL) is mentioned, it applies to both 2005 and 2008 depending on which version you have installed. If the information is specific to one version or the other version, the version is specifically stated.
- MySQL

See the *System Requirements* for the supported database version information.

You must install, create, and configure a database so that each Sterling B2B Integrator instance has a dedicated schema and login for the database.

### Database Information You Need Before You Install Sterling B2B Integrator in a Non-Cluster Environment

Before you begin to install Sterling B2B Integrator, you need to install and configure your database. Review and gather the following information. An “x” indicates the information is required.

Information to Gather	Oracle	DB2	Microsoft SQL Server	MySQL	Record Information Here
Database User Name	x	x	x	x	
Database Password	x	x	x	x	
Database Catalog Name	x	x	x	x	
Database Host	x	x	x	x	
Database Port	x	x	x	x	
JDBC Driver #1	x	x	x	x	
Use BLOB data?	x		x		
Enable Multibyte Support?	x	x	x		

### Database sizing and capacity planning

Database sizing is designed to give you estimates of the database growth and to help you plan the disk requirements.

There are many factors to consider when you are estimating the amount of disk space that is required for Sterling B2B Integrator. As a result, trying to consider all growth factors is impractical because the user might not know the answers to many questions that are required to do a detailed forecast. Over the years the cost of disks has dramatically decreased, and the capacity and speed of disks has increased. The method of how information system managers order disk capacity also has changed, from purchasing disk arrays that are dedicated to a particular database server and project, to the concept of SANs (storage area networks).

Sterling B2B Integrator provides a way to estimate your initial disk requirements. Consider the confidence that you have in your data estimates when you are making the final purchase decision and adjust accordingly. After the initial purchase and production deployment, disk growth should be tracked for future purchase forecasts.

You should track your actual database storage usage and the number of database records regularly. Correlating these two metrics enabled you to plan your future disk requirements. Moreover, determining the average amount of space used for each order line or shipment line, enables you to accurately predict your future growth requirements.

## Database Definition Language (DDL) Statements

When you install Sterling B2B Integrator, you can manually apply Database Definition Language (DDL) statements to your database tables instead of requiring the installation process to do it directly.

This feature increases database security by reducing the database permissions of the Sterling B2B Integrator database user. The rights to database objects can be reserved for a secure user like a customer database administrator (DBA). A business can require that only a DBA with the proper permissions can make database changes.

## Configure the DB2 Database

### DB2 database configuration checklist

Before you install Sterling B2B Integrator with the DB2® database, you must configure the database.

Before you begin:

- If you do not have DB2 installed, follow the procedures in the DB2 installation manual.
- The installation script creates tables and indexes. Certain tables require a page size of 32 KB. You must have a temporary table space to accommodate such tables. DB2 automatically places tables and indexes in the available table spaces. You can move the tables to a different table space after the installation is complete.
- If you are reinstalling the software, be aware that data in your existing database is deleted. To preserve the data, either back up the existing database or save it under a different name.
- After you create and configure your database, recycle the database. Then, stop and restart the database to apply the changes.

Use the following checklist to configure DB2 for Sterling B2B Integrator:

Item	DB2 Database Configuration Checklist	Your Notes
1	<p>Create the database.</p> <p>Refer to the DB2 documentation on creating the database, including creating a schema repository, login, and table space.</p> <p>Be sure to install the correct version and patches. See the System Requirements for supported version information.</p>	

Item	DB2 Database Configuration Checklist	Your Notes
2	Install the client components, compilers, and fix pack.	
3	Review the DB2 parameters.	
4	Ensure that the DB2 user privileges are set.	
5	Install the JDBC drivers for DB2.	

## DB2 database user privileges

The DBADM role is required to perform administrative operations in DB2 database.

## DB2 parameters

When you install Sterling B2B Integrator with the DB2 database, you must set certain DB2 parameters. Other DB2 parameter settings are recommended for the efficient performance of Sterling B2B Integrator.

When you install Sterling B2B Integrator with DB2, you must set the DB2 parameters that are listed in the following topics:

- “Mandatory settings for IBM DB2 registry variables”
- “Mandatory settings for DB CFG parameters” on page 6

After you install Sterling B2B Integrator with DB2, you can improve the DB2 database performance by setting the recommended parameters that are listed in the performance documentation for the following items:

- DB2 registry variables
- DBM CFG parameters
- DB CFG parameters
- DB2 9.7
- DB2 for Linux on System z<sup>®</sup> (5.2.4.0 or later)
- DB2 for LUW configuration and monitoring

### Mandatory settings for IBM DB2 registry variables:

Mandatory IBM DB2 registry values are critical for IBM DB2 performance with Sterling B2B Integrator.

Variable	Mandatory value
DB2_SKIPDELETED	<p>ON</p> <p>Allows index-range queries or table-scan queries to skip records that are in an uncommitted delete state. This reduces the amount of lock contention from Read Share and Next Key Share locks from range queries in tables with a high frequency of deletes.</p> <p>When enabled, DB2_SKIPDELETED allows, where possible, table or index access scans to defer or avoid row locking until a data record is known to satisfy predicate evaluation. This allows predicate evaluation to occur on uncommitted data.</p> <p>This variable is applicable only to statements using either Cursor Stability or Read Stability isolation levels. For index scans, the index must be a type-2 index. Deleted rows are skipped unconditionally on table scan access while deleted keys are not skipped for type-2 index scans unless DB2_SKIPDELETED is also set.</p> <p>Recommended value: ON</p>
DB2_SKIPINSERTED	<p>ON</p> <p>Allows SELECTs with Cursor Stability or Read Stability isolation levels to skip uncommitted inserted rows. This reduces record lock contention on tables with heavy insert rates.</p>

### Mandatory settings for DB CFG parameters:

For optimal performance, certain parameters and values are mandatory for DB2 9.x.

Parameter	Mandatory value
Database Code Set	UTF-8

## Installing DB2 client components, compilers, and fix pack

The use of Sterling B2B Integrator with the DB2 database requires the installation of different items for the database.

### About this task

Sterling B2B Integrator uses stored procedures for DB2. For more information about these tasks, see the IBM documentation for DB2.

### Procedure

You must install or set up the following DB2 components to use Sterling B2B Integrator with DB2:

1. Install the Administration client.
2. Install the necessary fix pack after you install the client components and compilers. Otherwise, the clients overwrite the fix pack binary files.
3. Set the path for the compiler by entering the db2set command.

## Installing JDBC drivers for DB2

When you install Sterling B2B Integrator with the DB2 database, you must install a JDBC driver for the database.

### About this task

For DB2, install the appropriate DB2 JDBC Type 4 driver and any correlating patches. For the supported version information, see *System Requirements*.

You can obtain these files from the IBM website. After you obtain this JDBC driver, record the absolute path to its location on your system. You must supply this absolute path during installation.

If the JDBC driver provided by your database vendor is distributed among multiple files, you must place all the files that comprise the JDBC driver into one JAR file. Follow these steps to create one JAR file:

### Procedure

To install a JDBC driver for the DB2 database:

1. Identify all the vendor database JAR files for the JDBC driver.
2. Record the absolute path to the JAR file you created on the Preinstallation Checklist.

The Type 4 driver does not require a separate Java™ listener to be running on the database server. Instead, connect directly to the DB2 port.

## Upgrading DB2 to version 10.1

To upgrade from DB2 9.5 or 9.7 to 10.1, you must make configuration changes. DB2 version 10.1 is only supported on Sterling B2B Integrator 5.2.4.1\_2 or higher.

### Procedure

To upgrade from DB2 9.5 or 9.7 to 10.1:

1. Copy your DB2 9.5 or 9.7 database content to DB2 10.1.  
**Attention:** Back up all files before you change any settings.
2. Back up the database driver in the `/install_dir/dbjar/jdbc/DB2/` directory and replace it with the DB2 10.1 version.
3. Update the following `sandbox.cfg` file fields with your environment-specific parameters:

```
DB_PASS=  
DB_SCHEMA_OWNER=  
DB_DRIVERS_VERSION=  
YANTRA_DB_PORT=  
DB_DATA=  
DB_HOST=  
YANTRA_DB_USER=  
DB_PORT=  
YANTRA_DB_PASS=  
YANTRA_DB_DATA=  
YANTRA_DB_HOST=  
DB_DRIVERS=  
DB_USER=  
  
DB2_PORT=
```

DB2\_USER=  
DB2\_PASS=  
DB2\_DATA=  
DB2\_HOST=

4. Edit the following value in the `activemq.xml` file:  
`activemq.xml: <value>jdbc:db2//DB_HOST:DB_PORT/DB_DATA</value>`
5. Run the `setupfiles` script.
6. Run the `deployer` script.
7. Start Sterling B2B Integrator.

## Configure the Oracle Database

### Oracle database configuration checklist

Before you install Sterling B2B Integrator with the Oracle database, you must configure the database.

#### Before you begin

- If you are reinstalling the software, be aware that data in your existing database is deleted. To prevent this deletion, either back up the existing database or save it under a different name.
- After you create and configure your database, recycle the database. Then, stop and restart to apply the changes.

#### About this task

Use the following checklist to configure Oracle for Sterling B2B Integrator:

Item	Oracle Database Configuration Checklist	Your Notes®
1	Create the database.  Refer to the Oracle documentation on creating the database, including creating a schema repository, login, and table space.  Be sure to install the correct version and patches.  See the <i>System Requirements</i> for the supported version information.	
2	Configure an Oracle Instance.	
3	Configure Oracle Rollback.	
4	Install the Oracle JDBC Driver.	
5	Enable Failover in a Multiple Node Oracle RAC Database Cluster.	

Item	Oracle Database Configuration Checklist	Your Notes®
6	After Sterling B2B Integrator is installed, if you want to encrypt the data traffic, perform one of the following tasks: <ul style="list-style-type: none"> <li>• Configure Sterling B2B Integrator for Data Traffic Encryption</li> <li>• Configure Sterling B2B Integrator for Data Traffic Encryption with SSL</li> </ul>	

## Configuring an Oracle instance

An Oracle database requires certain parameter settings and other configurations.

### Before you begin

- You must have the Oracle database installed. Ensure that you have installed the correct versions and patches. See *System Requirements* for supported version information.
- Ensure that the user responsible for creating and modifying the Oracle database has a specified quota (extent) assigned in the table space, even if the user was assigned an unlimited table space. Otherwise, the installer might display the error ORA-09150: no privileges on tablespace name.

### Procedure

1. Run the create instance procedure. Use AL32UTF8 as the character set.
2. Configure the INIT<INSTANCE\_NAME>.ORA file with the settings in the Performance Management guide.
 

After you install Sterling B2B Integrator with Oracle, you can improve the performance of the database with the settings listed in the Performance Management guide.
3. Identify or create a table space for user tables and indexes.
4. Create a user. Unless stated for a task, the user does not require database administrator (DBA) privileges.
5. Grant permissions to the user. The following permissions are required for the administrative user for creating and modifying the Oracle database:
  - GRANT "CONNECT" TO SI\_USER
  - ALTER USER SI\_USER DEFAULT ROLE "CONNECT"
  - GRANT CREATE SEQUENCE TO SI\_USER
  - GRANT CREATE TABLE TO SI\_USER
  - GRANT CREATE TRIGGER TO SI\_USER
  - GRANT SELECT ON CTXSYS.CTX\_USER\_INDEXES TO SI\_USER
  - GRANT SELECT ON SYS.DBA\_DATA\_FILES TO SI\_USER
  - GRANT SELECT ON SYS.DBA\_FREE\_SPACE TO SI\_USER
  - GRANT SELECT ON SYS.DBA\_USERS TO SI\_USER
  - GRANT SELECT ON SYS.V\_\$PARAMETER TO SI\_USER
  - GRANT SELECT ANY DICTIONARY TO SI\_USER
  - GRANT ALTER SESSION TO SI\_USER
  - GRANT CREATE SESSION TO SI\_USER

6. If you are using Oracle AQ, grant the AQ\_ADMINISTRATOR\_ROLE permission.
7. If you are installing or upgrading to Sterling B2B Integrator version 5.2.4 and plan to use EBICS Client, grant the GRANT CREATE VIEW TO SI\_USER permission.

### Mandatory Oracle init parameters:

The Oracle init parameters have mandatory settings for Sterling B2B Integrator performance with an Oracle database.

Parameter	Mandatory value
cursor_sharing	Exact
Character set	AL32UTF8

### Configuring Oracle rollback

The configuration of rollback in an Oracle database helps you manage database transactions.

#### About this task

You can roll back changes in Oracle by using AUTO UNDO management. IBM recommends that you use this option. This practice avoids any manual monitoring of UNDO segments.

If a server is upgraded from Oracle 8i, set the UNDO\_MANAGEMENT=AUTO parameter in the init<SID>.ora file. Your database administrator needs to determine the UNDO\_RETENTION setting. Ensure that the file system, which has the UNDOTBS1 tablespace, has enough space to use the AUTOGROW setting.

### Installation of the Oracle JDBC driver

Sterling B2B Integrator requires the appropriate JDBC driver for the Oracle database.

The JDBC drivers are thin client-based pure Java JDBC drivers. See *System Requirements* for supported version information. The supported versions of the JDBC driver build the correct Sterling B2B Integrator directory structure.

### Enable Failover in a Multiple Node Oracle RAC Database Cluster

#### About this task

You can enable failover in a multiple node Oracle RAC database cluster in Windows using traditional RAC or RAC with SCAN.

#### Procedure

1. Navigate to `\install_dir\install\properties` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"> <li>• Click <b>Start</b>.</li> <li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li> </ul> <p>The Administrator: Command Prompt dialog box is displayed.</p>



- In the `sandbox.cfg` file, add a new property for `ORACLE_JDBC_URL`, which contains the Oracle RAC connection URL.

Choose one of the following depending on whether you are using traditional RAC or RAC with SCAN. The property value must be one string of text starting with `ORACLE_JDBC_URL=`. Your database administrator (DBA) can modify this URL as needed:

- To configure traditional RAC, use this format:

```
jdbc:oracle:thin:@
  (DESCRIPTION=
    (ADDRESS_LIST=
      (FAILOVER=ON)
      (LOAD_BALANCE=OFF)
      (ADDRESS=(PROTOCOL=TCP)(HOST=myhost1)(PORT=1521))
      (ADDRESS=(PROTOCOL=TCP)(HOST=myhost2)(PORT=1521))
    )
    (CONNECT_DATA = (SERVER = DEDICATED)(SERVICE_NAME=myservicename OR mySID))
  )
```

**Note:** This method uses the default Oracle RAC service provided by Oracle.

- To configure RAC with SCAN, use this format:

```
jdbc:oracle:thin:@host:port/service
```

For example:

```
jdbc:oracle:thin:@RAC-SCAN:1521/ORCL
```

Where:

RAC-SCAN is resolved to an IP address by DNS

1521 = Port number

ORCL = the name of your Oracle RAC service

**Important:** In order to use RAC with SCAN, you must also define a new Oracle RAC service (you cannot use the default service) that defines one node as the preferred node and at least one node as a failover node.

- Navigate to `\install_dir\install\bin` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"> <li>Click <b>Start</b>.</li> <li>Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>. The Administrator: Command Prompt dialog box is displayed.</li> </ul>

- Enter `setupfiles.cmd`.

## Data traffic encryption in the Oracle 11g database

You can encrypt transactions between Sterling B2B Integrator and the Oracle 11g database. Encryption prevents anyone who is outside the system from viewing the data that flows between Sterling B2B Integrator and the database.

The following list describes important aspects of enabling database encryption:

- At installation, encryption is turned off by default. If you want your database transactions to be encrypted, you must enable encryption.
- The encryption can be enabled at any time.

- Encryption applies to all database transactions between Sterling B2B Integrator and the database.

System performance might be impacted when encryption is enabled. The extent of this impact depends on your hardware, database configuration, transaction volume, and the relative amount of processing time that is spent by the system against other activities.

For more information on data traffic configuration, see *SSL With Oracle JDBC Thin Driver*.

### **Before you encrypt data traffic for the Oracle 11g database**

The decision to encrypt data traffic for the Oracle 11g database includes different considerations.

Consider the following items when you configure database traffic encryption:

- Sterling B2B Integrator must be installed in TCP (clear) mode before you can configure encryption.
- Perform these changes to your database before you install Sterling B2B Integrator.
- Configure wallets for encryption-only mode even if the wallet that is used is empty. Enable auto login for all wallets.
- If you want to use SSL for encryption only, it is recommended to follow the instructions in the "CASE #1: USE SSL FOR ENCRYPTION ONLY" section of the Oracle documentation. It is not necessary to configure certificates for the wallet. In this mode, Diffie-Hellman ciphers are used. The server and the client are not authenticated through SSL. You must authenticate by using a user name and a password. However, if you are running Sterling B2B Integrator on an operating system that requires an IBM JDK, you cannot use this mode, as IBM JSSE TrustManager does not permit anonymous ciphers. You must configure wallets with certificates.
- If you want to use SSL for encryption and for server authentication, it is recommended to follow the instructions in the "CASE #2: USE SSL FOR ENCRYPTION AND SERVER AUTHENTICATION" section of the Oracle documentation.
- If you want to use SSL for encryption and for server authentication of both tiers, it is recommended to follow the instructions in the Oracle "CASE #3: USE SSL FOR ENCRYPTION AND AUTHENTICATION OF BOTH TIERS" section of the Oracle documentation, depending on how you intend to configure client or server authentication.
- After you configure your database for data traffic encryption, the database accepts both TCP (clear) and TCPS (encrypted) connections.
- There is a known issue in the Oracle 11g database when the listener is configured only for TCPS. The `lsnrctl` utility that is used to start and stop database listeners attempts to contact the listener, which is enabled first. You should define the address list of the listener to contact either TCP or IPC before it contacts TCPS.

### **Configure Sterling B2B Integrator for Data Traffic Encryption in Oracle (Windows)**

#### **About this task**

Use this procedure if you want to enable encryption only, with anonymous authentication, and not SSL authentication.

If you want to use SSL for encryption only, it is recommended to follow the instructions in the Oracle *CASE #1: USE SSL FOR ENCRYPTION ONLY* section of the Oracle documentation. It is not necessary to configure certificates for the wallet. In this mode, Diffie-Hellman ciphers are used and neither the server nor the client is authenticated through SSL. You must authenticate by using a username and a password. However, if you are running Sterling B2B Integrator on a platform that requires an IBM JDK, you cannot use this mode, as IBM JSSE TrustManager does not permit anonymous ciphers. You must configure wallets with certificates.

This procedure is applicable only if you are running Sterling B2B Integrator on a platform that requires Sun JDK. The IBM JSSE TrustManager does not permit anonymous ciphers.

If your Sterling B2B Integrator is a cluster installation, you will need to perform this procedure on each node, starting with node 1.

### Procedure

1. Install Sterling B2B Integrator in TCP (clear) mode.
2. Stop Sterling B2B Integrator.
3. Navigate to `\install_dir\install\properties` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"> <li>• Click <b>Start</b>.</li> <li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li> </ul> The Administrator: Command Prompt dialog box is displayed.

4. Open the **customer\_overrides.properties** file and add the following additional database connection information:

```
jdbcService.oraclePool.prop_oracle.net.ssl_cipher_suites=
(SSL_DH_anon_WITH_3DES_EDE_CBC_SHA, SSL_DH_anon_WITH_DES_CBC_SHA)
jdbcService.oraclePool.prop_oracle.net.ssl_server_dn_match=false
```

If you have a container configured, ensure that the same database information is added to the **customer\_overrides.properties.in** file. To locate the file, navigate to `\install_dir\install\properties\nodexACy`. Where *x* gives the node number and *y* gives the container number. Perform this step for all the containers configured in the system.

5. Repeat Step 4 for the following Oracle connection pools by changing only the poolname:
  - oraclePool\_local
  - oraclePool\_NoTrans
  - oracleArchivePool
  - oracleUIPool

If you have any other database pools, you will need to add the properties for those pools.

6. Open the **sandbox.cfg** file and change the database connection information as shown:

```
ORACLE_JDBC_URL= jdbc:oracle:thin:@(DESCRIPTION=(ADDRESS=(PROTOCOL=tcps)
(HOST=<DB host>)(PORT=<TCPS port as configured in DB config section above>))
(CONNECT_DATA=(SERVICE_NAME=<service name>)))
```

Make sure you enter the HOST, PORT, and SERVICE\_NAME.

7. Open the **activemqconfig.xml.in** file and modify the database connection information:

- Remove or comment out the following default ActiveMQ database configuration information:

```
<bean id="gis-ds" class="org.apache.commons.dbcp.BasicDataSource"
  destroy-method="close" singleton="true" lazy-init="default"
  autowire="default"
  dependency-check="default" SCIOVERRIDEName="persistence-bean">
<property name="driverClassName">
<value>oracle.jdbc.driver.OracleDriver</value>
</property>
<property name="url">
#:ifdef ORACLE_JDBC_URL
<value>&ORACLE_JDBC_URL;</value>
#:else
<value>jdbc:oracle:thin:@&ORA_HOST;:&ORA_PORT;:&ORA_DATA;</value>
#:endif
</property>
  <property name="username">
<value>&ORA_USER;</value>
</property>
  <property name="password">
<value>&ORA_PASS;</value>
</property>
  <property name="maxActive">
<value>32</value>
</property>
</bean>
```

- Add the following ActiveMQ database configuration information:

```
<bean id="gis-ds"
class="oracle.jdbc.pool.OracleDataSource" destroy-method="close"
singleton="true" lazy-init="default"
autowire="default"
dependency-check="default">
<property name="URL"><value>&ORACLE_JDBC_URL;</value></property>
<property name="user"><value>&ORA_USER;</value></property>
<property name="password"><value>&ORA_PASS;</value></property>
<property name="connectionProperties"><value> oracle.net.ssl_cipher_suites:
(SSL_DH_anon_WITH_3DES_EDE_CBC_SHA, SSL_DH_anon_WITH_DES_CBC_SHA)
oracle.net.ssl_client_authentication: false
oracle.net.ssl_version: 3.0
driverClassName:oracle.jdbc.driver.OracleDriver
maxActive: 32
</value>
</property>
</bean>
```

8. Navigate to `\install_dir\install\bin` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"> <li>Click <b>Start</b>.</li> <li>Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li> </ul> <p>The Administrator: Command Prompt dialog box is displayed.</p>

9. Enter StartWindowsService.cmd.
10. Restart Sterling B2B Integrator. All the database connections from Sterling B2B Integrator are now connected through TCPS (encrypted) mode.

## Configure Sterling B2B Integrator for Data Traffic Encryption in Oracle with SSL Authentication (Windows)

### About this task

Use this procedure to enable encryption and SSL authentication. This procedure is applicable if you are running Sterling B2B Integrator on a platform that requires either Sun JDK or IBM JDK.

The example in this procedure uses 2-way SSL authentication. If you want to use SSL for encryption and for server authentication, it is recommended to follow the instructions in the Oracle *CASE #2: USE SSL FOR ENCRYPTION AND SERVER AUTHENTICATION* section of the Oracle documentation.

You can also configure 1-way SSL authentication. If you want to use SSL for encryption and for server authentication of both tiers, it is recommended to follow the instructions in the Oracle *CASE #3: USE SSL FOR ENCRYPTION AND AUTHENTICATION OF BOTH TIERS* section of the Oracle documentation, depending on how you intend to configure client and/or server authentication. For more information about 1-way SSL authentication, refer to Oracle documentation, which can be accessed from [http://www.oracle.com/technology/tech/java/sqlj\\_jdbc/pdf/wp-oracle-jdbc\\_thin\\_ssl.pdf](http://www.oracle.com/technology/tech/java/sqlj_jdbc/pdf/wp-oracle-jdbc_thin_ssl.pdf).

If your Sterling B2B Integrator is a cluster installation, you will need to perform this procedure on each node, starting with node 1.

### Procedure

1. Install Sterling B2B Integrator in TCP (clear) mode.
2. Stop Sterling B2B Integrator.
3. Navigate to `\install_dir\install\properties` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"> <li>• Click <b>Start</b>.</li> <li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li> </ul> The Administrator: Command Prompt dialog box is displayed.

4. Open the **customer\_overrides.properties** file and add additional database connection information:

```

jdbcService.oraclePool.prop_javax.net.ssl.trustStore=../../path/.../
ClientKeyStore.jks
jdbcService.oraclePool.prop_javax.net.ssl.trustStoreType=JKS
jdbcService.oraclePool.prop_javax.net.ssl.trustStorePassword=
password
jdbcService.oraclePool.prop_oracle.net.ssl_version=3.0
jdbcService.oraclePool.prop_javax.net.ssl.keyStore=../../path/.../
ClientKeyStore.jks
jdbcService.oraclePool.prop_javax.net.ssl.keyStoreType=JKS
jdbcService.oraclePool.prop_javax.net.ssl.keyStorePassword=password

```

5. Repeat step 4 for the following Oracle connection pools by changing only the poolname:

- oraclePool\_local
- oraclePool\_NoTrans
- oracleArchivePool
- oracleUIPool

If you have any other database pools, you will need to add the properties for those pools.

6. Open the **sandbox.cfg** file and change the database connection information to:

```
ORACLE_JDBC_URL= jdbc:oracle:thin:@(DESCRIPTION=(ADDRESS=(PROTOCOL=tcps)
(HOST=<DB host>)(PORT=<TCPS port as configured in DB config section above>))
(CONNECT_DATA=(SERVICE_NAME=<service name>)))
```

7. Navigate to `\install_dir\install\activemq\conf` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"> <li>• Click <b>Start</b>.</li> <li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li> </ul> <p>The Administrator: Command Prompt dialog box is displayed.</p>

8. Open the **activemqconfig.xml.in** file and modify the database connection information:

- Remove or comment out the following default ActiveMQ database configuration information:

```
#:ifdef ORACLE
<bean id="gis-ds" class="org.apache.commons.dbcp.BasicDataSource"
  destroy-method="close" singleton="true" lazy-init="default"
  autowire="default"
  dependency-check="default" SCIOVERRIDEName="persistence-bean">
  <property name="driverClassName">
  <value>oracle.jdbc.driver.OracleDriver</value>
  </property>
  <property name="url">
  #:ifdef ORACLE_JDBC_URL
  <value>&ORACLE_JDBC_URL;</value>
  #:else
  <value>jdbc:oracle:thin:@&ORA_HOST;:&ORA_PORT;:&ORA_DATA;</value>
  #:endif
  </property>
  <property name="username">
  <value>&ORA_USER;</value>
  </property>
  <property name="password"><value>&ORA_PASS;</value>
  </property>
  <property name="maxActive"><value>32</value>
  </property>
</bean>
#:endif
```

- Add the following ActiveMQ database configuration information:

```
<bean id="gis-ds"
class="oracle.jdbc.pool.OracleDataSource" destroy-method="close"
singleton="true" lazy-init="default" autowire="default"
dependency-check="default">
<property name="URL"><value>&ORACLE_JDBC_URL;</value></property>
```

```

<property name="user"><value>&ORA_USER;</value></property>
<property name="password"><value>&ORA_PASS;</value></property>
<property name="connectionProperties"><value>
javax.net.ssl.trustStore: /.../path/.../ClientKeyStore.jks
javax.net.ssl.trustStoreType:JKS
javax.net.ssl.trustStorePassword:password
oracle.net.ssl_version:3.0
javax.net.ssl.keyStore: /.../path/.../ClientKeyStore.jks
javax.net.ssl.keyStoreType:JKS
javax.net.ssl.keyStorePassword: password
driverClassName:oracle.jdbc.driver.OracleDriver
maxActive:32
</value>
</property>
</bean>

```

9. Navigate to `\install_dir\install\bin` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"> <li>• Click <b>Start</b>.</li> <li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>. The Administrator: Command Prompt dialog box is displayed.</li> </ul>

10. Enter `StartWindowsService.cmd`.

11. Restart Sterling B2B Integrator. All the database connections from Sterling B2B Integrator are now connected through TCPS (encrypted) mode.

## Configure the Microsoft SQL Server Database

### Microsoft SQL Server database configuration checklist

Before you install Sterling B2B Integrator with the Microsoft SQL Server database, you must configure the database.

#### Before you begin

- If you are reinstalling the software, be aware that data in your existing database is deleted. To preserve your data, either back up the existing database or save it under a different name.
- After you create and configure your database, recycle the database. Then, stop and restart to apply the changes.

#### About this task

Use the following checklist to configure Microsoft SQL Server for Sterling B2B Integrator:

Item	Microsoft SQL Server Database Configuration Checklist	Your Notes
1	<p>If you do not have Microsoft SQL Server installed, follow the installation procedures in the SQL Server installation manual.</p> <p>Refer to the Microsoft SQL Server documentation on creating the database, including creating a schema repository, login, and table space.</p> <p>Be sure to install the correct version and patches.</p> <p>See <i>System Requirements</i> for supported version information.</p>	
2	(SQL Server 2005 only) "Installing the Microsoft SQL Server 2005 service pack and hot fix" on page 19	
3	"Microsoft SQL Server database parameters"	
4	"Microsoft SQL Server database user privileges"	
5	"Configuring the snapshot feature for Microsoft SQL Server" on page 20	
6		

### Microsoft SQL Server database user privileges

In Microsoft SQL Server, you must grant DBO (Database Owner) permission to the user. The DB\_DDLADMIN role is required for creating objects in the SQL Server database.

### Microsoft SQL Server database parameters

When you install Sterling B2B Integrator with the Microsoft SQL Server database, you must set certain Microsoft SQL Server parameters. Other Microsoft SQL Server parameter settings are recommended for the efficient performance of Sterling B2B Integrator.

When you install Sterling B2B Integrator with Microsoft SQL Server, you must set the Microsoft SQL Server parameters that are listed in "Mandatory settings for Microsoft SQL Server."

After you install Sterling B2B Integrator with Microsoft SQL Server, you can improve the database performance by setting the recommended parameters that are listed in the performance documentation for the following items:

- Instance-specific settings for Microsoft SQL Server
- Database-specific settings for Microsoft SQL Server

#### Mandatory settings for Microsoft SQL Server:

The default collation of Microsoft SQL Server must match the collation for the Sterling B2B Integrator database to prevent collation conversions.



The *tempdb* database that is used by Microsoft SQL Server must be created with the same collation as the default collation of Microsoft SQL Server. The Microsoft SQL Server uses the *tempdb* database for results that are too large to fit in memory.

If the collations of the *tempdb* database and the Sterling B2B Integrator database differ, the database engine must convert from the Sterling B2B Integrator collation to the *tempdb* collation, and then back again before it sends the results to the Sterling B2B Integrator server. These conversions might lead to severe performance issues.

The collation that is required for the Sterling B2B Integrator database is a collation that most closely matches the character set used by Java. By using this collation, you can avoid character data conversions before the data is stored in the database tables. Use the mandatory parameter that is described in the following table when you configure the collation setting:

Parameter	Value
Database Collation	SQL_Latin1_General_CP850_Bin

Additionally, you must perform these tasks:

- Allow Microsoft SQL Server to manage memory dynamically (default).
- Disable any antivirus software that is running on the Microsoft SQL Server data, transaction log, and binary files directory.

## Installing the Microsoft SQL Server 2005 service pack and hot fix

You can update a SQL Server 2005 database with service packs and hot fixes.

### Before you begin

- Ensure that Named Pipes and TCP/IP protocols are enabled in the network utility of the SQL Server database.
- Do not use case-sensitive column names in the database. Case-sensitive names prevent the SQL Server 2005 System Management Console from loading.

### Procedure

To install Microsoft SQL Server 2005, Service Pack 2 and hot fixes:

1. Install the Microsoft SQL Server 2005 base release.
2. Install the Microsoft SQL Server 2005 Service Pack 2. You can download it from <http://www.microsoft.com/en-us/download/details.aspx?id=9969>.
3. Apply the cumulative hot fix package. You can download it from <http://support.microsoft.com/default.aspx?scid=kb;EN-US;933097>.
4. Apply the GDR2 hot fix. You can download it from <http://support.microsoft.com/kb/934459/>.

## Install the JDBC Driver in Microsoft SQL Server 2005

### About this task

Sterling B2B Integrator requires the correct Microsoft SQL Server driver. See *System Requirements* for supported version information.

Go to the Microsoft web site to download the driver and any appropriate patches.

## Procedure

1. Download `sqljdbc_version_language.tar.gz` to a temporary directory.
2. To unpack the zipped tar file, navigate to the directory where you want the driver unpacked and type the following command: `gzip -d sqljdbc_version_language.tar.gz`

3. To unpack the tar file, move to the directory where you want the driver installed and type the following command: `tar -xf sqljdbc_version_language.tar`

After the package unpacks, you can find out more information about using this driver by opening the JDBC Help System in the `\absolutePath\sqljdbc_version\language\help\default.htm` file. This will display the help system in your Web browser.

4. When the Sterling B2B Integrator installation asks for the location of the JDBC drivers, specify the extracted jar file created after unpacking the archive (usually named `sqljdbc.jar`). The JDBC driver version is the same as the version of the drivers downloaded from Microsoft.

## Configuring the snapshot feature for Microsoft SQL Server

The snapshot feature in Microsoft SQL Server allows you to view a read-only copy of the database even when it is locked. Configuring the snapshot feature can also reduce deadlocks.

## Procedure

Enter the following command to enable the snap shot feature:

```
ALTER DATABASE db_name SET READ_COMMITTED_SNAPSHOT ON;
```

## Configure the MySQL Database

### MySQL Database Configuration Checklist

You can use a MySQL database for maintaining information on Sterling B2B Integrator. Only non-clustered installations of Sterling B2B Integrator can use the MySQL database.

MySQL is case-insensitive for searches with string values. For example, the search results will be the same when you search for users 'Admin' and 'admin'. As a result, it impacts searches for maps, business processes, services, mailboxes, user names, and other data stored in the database.

Use the following checklist to configure the MySQL database for Sterling B2B Integrator:

#	MySQL Database Configuration Checklist	Your Notes
1	<p>Install MySQL database.</p> <p>Refer to MySQL documentation for information about installing the MySQL database. Be sure to install correct version and patches.</p> <p>See <i>System Requirements</i> for supported version information.</p>	
2	Set the MySQL Parameters.	

#	MySQL Database Configuration Checklist	Your Notes
3	<p>Create the database.</p> <p>For example, you can run the following command to create the database:</p> <pre>CREATE DATABASE database_name</pre> <p>Refer to MySQL documentation for more information about creating the database.</p>	
4	Create a user account and grant permissions.	
5	Install the JDBC Drivers for MySQL.	

If you need additional MySQL database information, see the documentation provided by the vendor at <http://dev.mysql.com/doc/refman/5.0/en/>.

### Update the MySQL Parameters

Sterling B2B Integrator requires various parameter settings in your MySQL database.

The parameter values recommended are minimum values. You can increase the values based on your requirements or if the database server is used by more than one instance of Sterling B2B Integrator.

It is recommended to configure a data file for auto extension (innodb\_data\_file\_path = ibdata1:400M:autoextend).

Parameter	Value
max_connections	500
max_allowed_packet	100M
default-table-type	INNODB
wait_timeout	31536000
max_write_lock_count	500000
transaction-isolation	READ-COMMITTED
character-set-server	utf8
binlog_format	mixed
table_open_cache	512
key_buffer_size	384M
sort_buffer	512K
connect_timeout	15
innodb_data_file_path	ibdata1:400M:autoextend
innodb_data_home_dir	<i>/install_dir/mysql/var/</i>
innodb_log_group_home_dir	<i>/install_dir/mysql/var/</i>
innodb_flush_log_at_trx_commit	1
innodb_mirrored_log_groups	1
innodb_log_files_in_group	3
innodb_file_io_threads	4
innodb_lock_wait_timeout	600

Parameter	Value
innodb_log_file_size	5M
innodb_log_buffer_size	8M
innodb_buffer_pool_size	128M
innodb_additional_mem_pool_size	32M

Review the `innodb_buffer_pool_size` and the `innodb_additional_mem_pool_size` in the `/install_dir/install/mysql/data my.cnf`. If the values from the previous Sterling B2B Integrator `tuning.properties` are larger than what is in your new `my.ini` file, you need to adjust them accordingly.

## Create User Account and Grant MySQL Database User Privileges

You must grant all privileges on the MySQL database to the Sterling B2B Integrator administrative user.

### About this task

The following example creates and grants all privileges to the user in the MySQL database:

```
GRANT ALL PRIVILEGES ON database_name.* TO user@localhost IDENTIFIED BY 'password'
WITH GRANT OPTION
```

Where:

- `database_name` - refers to the name of the database created.
- `user` - refers to the database user account that will be used by Sterling B2B Integrator.
- `password` - refers to the password associated with the database user account.

Once you have granted all the privileges, you will need to FLUSH the privileges to complete the setup. For example, run this command from the SQL prompt:

```
FLUSH PRIVILEGES;
```

## Install the JDBC Drivers for MySQL

Sterling B2B Integrator requires appropriate JDBC driver for MySQL database. These drivers are platform independent and architecture independent drivers.

### About this task

See *System Requirements* for supported version information.

After obtaining the correct JDBC driver, record the absolute path to its location on your system. You must supply this absolute path when installing Sterling B2B Integrator.

## Database Password Management

### Database passwords

A password is used by the system to connect to its database. The password is stored as clear text in a system property file.

If the security policies at your company require you to encrypt these passwords, you can do so after you install the system. Encrypting these passwords is optional.

## Database passwords encryption methods

Database passwords are encrypted with one of two methods: OBSCURED or ENCRYPTED.

The encryption method is decided by the value of the **encryptionPrefix** property in the `propertyEncryption.properties` or the `propertyEncryption.properties_platform_security_ext` file.

## Decrypt Database Passwords (Windows)

### About this task

To decrypt the database password:

### Procedure

1. Stop Sterling B2B Integrator.
2. Navigate to `\install_dir\install\properties` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"><li>• Click <b>Start</b>.</li><li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>. The Administrator: Command Prompt dialog box is displayed.</li></ul>

3. Open the `sandbox.cfg` file.
4. Copy encrypted password from the `database_PASS` property.  
Use the text that appears after the `database_PASS=` text. For example, if `database_PASS= OBSCURED:123ABCxyz321`, you would copy the text `OBSCURED:123ABCxyz321`. (OBSCURED is the encryption method for the password.)
5. Navigate to `\install_dir\install\bin` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"><li>• Click <b>Start</b>.</li><li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>. The Administrator: Command Prompt dialog box is displayed.</li></ul>

6. Enter `decrypt_string.cmd encrypted_password`.  
For `encrypted_password`, use the text that you copied in Step 4.  
You are prompted for the system passphrase.  
Your decrypted password appears.
7. Navigate to `\install_dir\install\properties` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"> <li>• Click <b>Start</b>.</li> <li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li> </ul> The Administrator: Command Prompt dialog box is displayed.

8. Edit the sandbox.cfg file to replace the encrypted password with the password that was returned in Step 6.
9. You need to decrypt the entries for YANTRA\_DB\_PASS and DB\_PASS. Repeat Steps 4 to 8 to decrypt these entries. You should also decrypt any passwords present in the property files. Encrypted passwords typically reside in the following property files:
  - sandbox.cfg
  - apservsetup
  - jdbc.properties/.in
  - customer\_overrides.properties/.in
10. Navigate to `\install_dir\install\bin` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"> <li>• Click <b>Start</b>.</li> <li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li> </ul> The Administrator: Command Prompt dialog box is displayed.

11. Enter `setupfiles.cmd`.
12. Enter `deployer.cmd`.
13. Enter `startWindowsService.cmd` to start Sterling B2B Integrator.

## Encrypt Database Passwords (Windows)

### About this task

To encrypt the database password:

#### Procedure

1. Stop Sterling B2B Integrator.
2. Navigate to `\install_dir\install\bin` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"> <li>• Click <b>Start</b>.</li> <li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li> </ul> The Administrator: Command Prompt dialog box is displayed.

3. Enter `enccfgs.cmd`.
4. Enter `setupfiles.cmd`.

5. Enter `deployer.cmd`.
6. Enter `startWindowsService.cmd` to start Sterling B2B Integrator.
7. Enter your passphrase.

---

## Installation Checklist

### Installation Checklist for a Windows Non-Cluster Environment

The installation checklist contains the items you need to gather and tasks you need to complete prior to installing Sterling B2B Integrator. The checklist contains:

- Brief descriptions for tasks (detailed procedures are provided after the checklist)
- Information you need to gather to complete the installation

You may want to make a copy of the following checklist and use it to record the information you collect.

#	Installation Checklist for Windows	Your Notes
1	Review your IBM contract to determine what software you have licensed. You need to know this <i>License Information</i> so that you can select the correct components/features to install.	
2	Determine which installation method you are going to use: <ul style="list-style-type: none"> <li>• IBM Installation Manager (Graphical User Interface)</li> <li>• IBM Installation Manager (Text Based)</li> <li>• Silent Installation</li> </ul>	
3	Decide which type of security certificates you will use: <ul style="list-style-type: none"> <li>• The default self-signed SSL (Secure Sockets Layer) certificate that is automatically installed.</li> <li>• A Certificate Authority-related certificate that you install before installing Sterling B2B Integrator.</li> </ul>	
4	If you are using an Oracle, Microsoft SQL Server, or DB2 database, decide if you are going to manually or automatically apply Database Definition Language (DDL) Statements (schema) to the database.	
5	If you are using an Oracle 11.1 database, you must set it up for native compilation by allocating space and by setting the <code>plsql_native_library_dir</code> parameter.	
6	Determine if the database password needs to be encrypted.	
7	Record the Hostname on which you plan to install the software.	
8	Record the Directory Name where you plan to install the software.	
9	Record the Login to host machine.	
10	Record the Password to the host machine.	
11	Record the path to the Installation Manager and the installation package file name.	
12	Record the path to JDK.	

#	Installation Checklist for Windows	Your Notes
12	Record the path to JCE file.	
14	Record the Host IP address.	
15	Record the Initial Port Number.	
16	Record the System passphrase.	
17	Record the Database vendor name.	
18	Record the Database user name.	
19	Record the Database password.	
20	Record the Database (catalog) name.	
21	Record the Database host name.	
22	Record the Path and file name for the JDBC Driver(s).	
23	Determine if your windows environment is: <ul style="list-style-type: none"> <li>• Windows 2003 or earlier</li> <li>• Windows Server 2008</li> </ul>	
24	Ensure you have read and write privileges on the parent installation directory.	

## License information

IBM provides the license files for each feature of Sterling B2B Integrator that you purchased with the software media. You do not have to contact IBM Customer Support to get the license files.

A separate license is required for each Sterling B2B Integrator feature that you purchased. During installation, you must choose the license files according to what you purchased. IBM Customer Support audits the system as soon as your system is in use.

After the installation finishes, if you determine that you need to modify licenses files, see "License modifications" on page 59.

## Extracting the core license file

The Core\_License.xml file is required during the installation or upgrade of Sterling B2B Integrator.

### About this task

To extract the Core\_License.xml file:

### Procedure

1. Download the SI\_5020400.jar file from Passport Advantage® to a temporary location.
2. From a command line, open the directory where the SI\_5020400.jar file is located.
3. Type the following command to extract the contents of the JAR file: `jar -xvf SI_5020400.jar`
4. Type the following command to change directories to the middleware folder: `cd ./middleware`



5. From the middleware directory, extract the Core\_License.xml file by typing the following command: `jar -xvf h_B2BF_4020400.jar`
6. The Core\_License.xml file is in the newly extracted directory: `B2BF/components/b2b_base/files/properties/licensefiles`
7. Copy the Core\_License.xml file to a temporary location where you can point to it during your installation or upgrade.

## Port Numbers in a Windows Environment

During installation or an upgrade, you are prompted to specify the initial port number for Sterling B2B Integrator.

To specify an initial port number, follow these guidelines:

- Sterling B2B Integrator requires a range of 200 consecutive open ports between 1025 and 65535. The port range starts with the initial port number and ends with the number that equals the initial port number plus 200. For example, if you specify 10100, then you need to make sure that 10100 through 10199 are not used by any other applications on your system.

**Note:** Because of RMI, on occasion, a port number outside the range may be assigned.

- The initial port number represents the beginning port number in the range.
- Make sure that port numbers in the port range are not used by any other applications on your system.

During the upgrade, about 50 default ports are pre-assigned for different services. For example, if you do not want xxx32 (10132) to be a default port, you could assign that port to xxx97 or another number within the port range.

After your installation or upgrade, refer to the `\install_dir\install\properties\sandbox.cfg` file for all of the port assignments.

## Security certificates

You can choose between different security certificates before you install Sterling B2B Integrator.

Before you begin the installation, you must decide which of the following security certificates to use:

- The default self-signed SSL (Secure Sockets Layer) certificate that is automatically generated by the installation.
- A Certificate Authority-related certificate that you generate before you install the software.

If you install with the default SSL certificate, but you later want to switch to a CA-related certificate, you can change the certificate with the `sslCert` property in the `noapp.properties_platform_ifcresources_ext.in` file.

---

## Install the Software

### General Installation/Upgrade Information for a Windows Non-Cluster Environment

Review the general installation and upgrade information before you upgrade Sterling B2B Integrator.

**CAUTION:**

Sterling B2B Integrator should be installed behind a company firewall for security purposes. See the *Perimeter Server and Security* topics in the Sterling B2B Integrator documentation library for more information on secure deployment options.

**Installation Scenarios for Version 5.2.3**

It is important to review the following installation scenarios:

Scenario	Instructions
Version 4.x is installed as the base release and it needs to be upgraded to the 5.2.3 level.	Use the <i>Upgrade the Software</i> instructions provided in the <i>Windows Non-Cluster Environment Upgrade</i> guide for version 5.2.3.
Version 5.0 is installed as the base release and it needs to be upgraded to the 5.2.3 level.	Use the <i>Upgrade the Software</i> instructions provided in the <i>Windows Non-Cluster Environment Upgrade</i> guide for version 5.2.3.
Version 5.1 is installed as the base release and it needs to be upgraded to the 5.2.3 level.	Use the <i>Upgrade the Software</i> instructions provided in the <i>Windows Non-Cluster Environment Upgrade</i> guide for version 5.2.3.
Version 5.2.0 is installed as the base release and it needs to be upgraded to the 5.2.3 level.	Use the <i>Install Version 5.2.1 - 5.2.3 as a Fix Pack</i> instructions provided in the <i>Install the Software</i> chapter.
Version 5.2.1 is installed as the base release and it needs to be upgraded to the 5.2.3 level.	Use the <i>Install Version 5.2.1 - 5.2.3 as a Fix Pack</i> instructions provided in the <i>Install the Software</i> chapter.
Version 5.2.2 is installed as the base release and it needs to be upgraded to the 5.2.3 level.	Use the <i>Install Version 5.2.1 - 5.2.3 as a Fix Pack</i> instructions provided in the <i>Install the Software</i> chapter.
Version 5.2.3 is being installed as the base release.	You will need to review this document and use the installation instructions in the <i>Install the Software</i> chapter.

**Installation Methods**

Use one of the following methods to install your system:

- IBM Installation Manager (Graphical User Interface)
- IBM Installation Manager (Text Based)
- Silent Installation

**General Installation Guidelines**

General installation guidelines include the following:

- Do not create the installation directory manually before the start of the installation. If you create the installation directory before you begin, the installation will fail. The directory name provided during the installation process is used to create the new installation directory.
- The name of the directory cannot include spaces and must be less than 30 characters long excluding separators. Using a directory name of more than 30 characters could create an install that is impossible to delete. An example of an installation directory is C:\SI\_52\install.
- The server on which you are installing must have adequate free disk space.

- *install\_dir* refers to the installation directory where the new software will be installed. Do not use any pre-existing directory name or an old version of the Sterling B2B Integrator installation directory. If you do, you could inadvertently overwrite the existing installation. You should create a new installation directory before you begin the installation.
- *parent\_install* is the directory one level above the *install\_dir* directory.
- Ensure that the *parent\_install* directory has the proper read/write permissions.
- If you need to install more than one instance of Sterling B2B Integrator on the same Windows server, you must install the second instance in a different directory.
- If you are installing Sterling B2B Integrator on VMware, provide the IP address of the virtual machine, not the IP address of the VMware host. For example, if 10.251.124.160 is the IP address of the VMware host and 10.251.124.156 is the IP address of the Windows 2003 server it is hosting, you should use 10.251.124.156 as the correct IP address to install Sterling B2B Integrator.
- Sterling B2B Integrator does not support IPv6 installation on Windows. Before applying an IPv6 address, see the *IPv6 Capabilities* section in *System Requirements*.
- The installation creates subsequent ports based on the initial port number. For all of the port assignments, see the `\install_dir\install\properties\sandbox.cfg` file.

## General Installation Manager information

The IBM Installation Manager Software Delivery Platform is an installation management tool that installs and maintains Installation-Manager-based software packages.

Use the Installation Manager to modify feature sets and search for updates of installed software. The Installation Manager ensures that only compatible fixes are applied to a software installation.

**Important:** The on-screen options **Manage Licenses**, **Roll Back**, **Modify**, and **Update** are not functional as part of the Sterling B2B Integrator release 5.2.3. Additionally, the **Uninstall** option only removes Sterling B2B Integrator from the Installation Manager. The uninstall procedure as described in *Uninstall Sterling B2B Integrator from a Windows Non-Cluster Environment* still must be performed to completely uninstall Sterling B2B Integrator.

**Attention:** If you are using Installation Manager to install Sterling B2B Integrator version 5.2.3 and you plan on using the Financial Services License, you need to manually install the license.

The Installation Manager must be installed on each computer on which Sterling B2B Integrator is being installed. If you have an existing version of Installation Manager installed on your computer for use with other IBM applications, it can be used with Sterling B2B Integrator. If you do not have the Installation Manager installed, it is provided as part of the installation media and can be installed as part of the Sterling B2B Integrator installation.

The Installation Manager user interface provides the following features:

- The choice of either entering the paths or selecting the paths and files (**Select File**).
- Internal navigational buttons on every screen in the Installation Manager. You need to click **Next** to move to the next step. The click **Next** step is not represented in each step in the procedure.

**Important:** The **Next** button does not activate until you enter data on a screen. For fields that require validation, you must click out of the field somewhere on the screen to trigger the validation and after validation completes, the button activates.

- For every screen in the text-based installation wizard, you need to press Enter to move to the next step. The press Enter step is not represented in each step in the procedure.
- Numbered options for each step in the Installation Manager's text mode, you need to press Enter to move to the next step.
- The ability to navigate to the different installation configuration pages out of sequence. The following icons indicate the status of a configuration page:

-



- page is completed

-



- current page you are on

-



- required entry

-



- page not completed

**Note:** All the pages must have a



to continue.

## Additional heap memory parameters

The heap memory parameters specify the amount of memory the Installation Manager can use during the installation process. The heap memory pool sizes that are used by the Installation Manager are hardcoded defaults. If these defaults are not sufficient for your environment, you can specify different values by adding parameters to the Installation Manager's `config.ini` file.

**Important:** These additional parameters are needed only if you are experiencing Out Of Memory errors during the installation process.

The following parameters can be added:

- `memoryMin=user.sb.INSTALL_<OS>_INIT_HEAP.<amount_of_memory>`
- `memoryMax=user.sb.INSTALL_<OS>_MAX_HEAP.<amount_of_memory>`

Where `<OS>` is the user's operating system and `<amount_of_memory>` is the specified amount of memory.

Operating System	Parameter	Example Entry
Sun-Solaris	Initial Heap Size <b>INSTALL_SUN_INIT_HEAP</b>	memoryMin=user.sb.INSTALL_SUN_INIT_HEAP.3072m
	Maximum Heap Size <b>INSTALL_SUN_MAX_HEAP</b>	memoryMax=user.sb.INSTALL_SUN_MAX_HEAP.3072m
Linux	Initial Heap Size <b>INSTALL_LINUX_INIT_HEAP</b>	memoryMin=user.sb.INSTALL_LINUX_INIT_HEAP.3072m
	Maximum Heap Size <b>INSTALL_LINUX_MAX_HEAP</b>	memoryMax=user.sb.INSTALL_LINUX_MAX_HEAP.3072m
AIX®	Initial Heap Size <b>INSTALL_AIX_INIT_HEAP</b>	memoryMin=user.sb.INSTALL_AIX_INIT_HEAP.3072m
	Maximum Heap Size <b>INSTALL_AIX_MAX_HEAP</b>	memoryMax=user.sb.INSTALL_AIX_MAX_HEAP.3072m
HP-UX	Initial Heap Size <b>INSTALL_HPUX_INIT_HEAP</b>	memoryMin=user.sb.INSTALL_HPUX_INIT_HEAP.3072m
	Maximum Heap Size <b>INSTALL_HPUX_MAX_HEAP</b>	memoryMax=user.sb.INSTALL_HPUX_MAX_HEAP.3072m
Windows	Initial Heap Size <b>INSTALL_WIN_INIT_HEAP</b>	memoryMin=user.sb.INSTALL_WIN_INIT_HEAP.3072m
	Maximum Heap Size <b>INSTALL_WIN_MAX_HEAP</b>	memoryMax=user.sb.INSTALL_WIN_MAX_HEAP.3072m

## Installing in a Windows non-cluster environment with the IBM Installation Manager in GUI mode

You can install Sterling B2B Integrator in a Windows non-cluster environment with the IBM Installation Manager in a graphical user interface (GUI) mode.

### Before you begin

- Complete the “Installation Checklist for a Windows Non-Cluster Environment” on page 25.
- Access the JAR file for your installation. The JAR file depends on your operating system and current version of Sterling B2B Integrator. Refer to the following websites for the correct JAR file. Consult with your IBM representative to identify the correct JAR file for your installation.
  - Refer to Fix Central to see if you must use an interim fix or fix pack JAR file for the installation.
  - Refer to Passport Advantage to see if you must use an installation JAR file for the installation.
- If you are using the Standards Processing Engine (SPE) application with Sterling B2B Integrator, you must install SPE before you install Sterling B2B Integrator.

- If you are using the EBICS Banking Server application with Sterling B2B Integrator 5.2.5, the data encryption for storage within the installation location is not supported.

## Procedure

1. Close all open Windows programs and any command prompt windows.
2. From the installation media, copy the compressed installation package to a location on your desktop.
3. Decompress the installation package.
4. Open the IMSI (Installation Manager) folder that is in the directory structure that is created when the installation package was decompressed. The directory includes several *IM\_OperatingSystem.zip* files.
5. Decompress the *IM\_Win.zip* file. This action creates a new *IM\_Win* folder.
6. Open the new *IM\_Win* folder.
7. Start the installation:
  - a. Right-click the *userinst.exe* file.
  - b. Click **Run as administrator**.
8. On the Install Packages page of the Installation Manager, click **Next**.
9. Review the license agreement and select the option **I accept the terms in the license agreement**.

If you do not accept the agreement, the installation process does not continue.

10. Select the location for the shared resources directory and click **Next**. This directory is used by the Installation Manager for the Sterling B2B Integrator installation and other installations.

The shared resources directory cannot be a subdirectory of the directory for the installation of Sterling B2B Integrator. The shared resources directory must be empty.

11. Select the directory for the installation of Sterling B2B Integrator and click **Next**.

The installation directory must be empty. During the installation, the installer creates a directory that is named *install* that contains the installation files.

The system confirms that you have enough space on your system to complete the installation.

If you have other products installed that use the Installation Manager, updates for those products might appear in your listing.

12. After you review the disk space information, click **Next**.
13. Type the path to your JDK directory and click **Next**.
14. Select the feature or features to install and click **Next**.

Select only the licenses and features that were defined by your IBM contract. If you are unsure which to select, the installation can proceed without a selection and complete successfully. Startup and operation of the software, however, requires one of the licenses to be selected. See “License modifications” on page 59 to apply licenses after the installation.

**Note:** Sterling File Gateway requires extra installation steps. See Installing Sterling File Gateway (2.2.2 and higher).

- **IBM Sterling B2B Integrator and/or IBM Sterling File Gateway**

**Important:** Sterling File Gateway requires extra installation steps. See Installing Sterling File Gateway (2.2.2 and higher).

- **FIPS Module**
  - **FIPS Compliance Mode (Must enable FIPS Module)**
- (5.2.5 and higher) **NIST 800-131a Compliance Mode**
  - **off** (default value)
  - **transition**
  - **strict**
- **AS2 Edition Module**
- **Financial Services Module**
- **EBICS Banking Server Module**
- (5.2.5 and higher) **SPE Integration Module (Requires pre-install of SPE, WTX optional)**

If you select the SPE option, you are prompted for the following information:

- SPE installation directory
- (Optional) WebSphere® Transformation Extender (WTX) installation directory
- SPE UI port

For more information, see the documentation for the integration of Sterling B2B Integrator and SPE.

15. Type the path to the JCE policy file and click **Next**.
16. Type the path to the installation JAR file and click **Next**.
17. Enter the following server location information and click **Next**:
  - a. Type the explicit IP address or host name for the server or use the default value of localhost.
  - b. Type the initial port number or use the default value of 8080.
18. Enter the system passphrase information and click **Next**:
  - a. Type a passphrase.
  - b. Confirm the passphrase.
19. Type the email information and click **Next**:
  - a. Type the email address to which you want system alert messages sent.
  - b. Type the SMTP mail server (IP address or host name) that you want to use for system alert messages and other administrative notices.
20. Enter the following database information and click **Next**:
  - a. Select the database vendor that you want to use:
    - Oracle
    - (5.2.3 - 5.2.4.2) Microsoft SQL Server 2005
    - (5.2.5 and higher) Microsoft SQL Server 2012
    - DB2
    - MySQL
  - b. Select all of the following options that apply to this installation:

Choices:	Action
(Not for MySQL) <b>This installation is for a cluster node 2 or higher</b>	Do not select this option because this installation is a non-cluster installation.

Choices:	Action
(Not for MySQL) <b>Apply database schema automatically?</b>	<p>The default is to automatically apply the DDL (Data Definition Language) statements that apply the database schema.</p> <p>If you want to manually create the database schema, then clear the <b>Apply database schema automatically</b> check box and continue with the remaining installation steps.</p> <p><b>Important:</b> If you manually apply the schema, the installation stops without error later in the installation process so that you can manually apply the schema.</p>
(Oracle only) <b>What Datatype you would like to use?</b>	<p>Select either the default BLOB (binary large object) columns data type or the Long Raw data type.</p> <p>You can significantly improve performance by enabling the cache on the BLOB data object in Oracle. For more information, see the Sterling B2B Integrator documentation for slow performance in Oracle.</p>

21. Type the following database connection information. Do not click **Next** until you configure the JDBC driver in the next steps.

- User name
- Password (and confirmation)
- Catalog name
- Host
- Port

22. Select a JDBC driver or drivers and click **Next**:

- a. Click **Add** to browse to the file location for the appropriate JDBC driver or drivers:
  - (Oracle, Microsoft SQL Server, and MySQL only) Absolute path and file name for one JDBC driver file.
  - (DB2 only) Absolute paths and file names for two JDBC driver files. Use the Type-4 JDBC driver. This type of driver converts JDBC calls into the network protocol that is used directly by DB2, allowing a direct call from the system to the DB2 server.
- b. Click **Test** to confirm that the driver is supported for the database and Sterling B2B Integrator.

**Tip:** Make sure that you select the driver path in the **Database driver** field before you click **Test**.

The Installation Manager must successfully validate the connection to the database before you can continue with the installation. If there is a validation failure, you can view the system log to determine more information about the failure. Perform the following tasks:

- 1) Identify the location of the user's application directory. Click **Start** > **Run** and enter the command %APPDATA%.
- 2) Open the user's application directory: *local\_path\IBM\Installation Manager\logs*



- 3) Open the `index.xml` file in a browser.
  - 4) Identify the log file that is based on the time stamp of when you started the installation.
  - 5) Click the installation file to view a listing of errors that occurred during that installation.
23. Determine which of the following options apply to this installation. Select the applicable options and click **Next**:
- **Verbose install?**
  - **This installation is an upgrade from a prior version**  
Do not select this option because this installation is a new installation.
24. Determine what performance configurations apply to this installation and click **Next**. Accept the default value or type the appropriate value.
- **Number of Processor Cores**
  - **Physical Memory (MB) allocated to Sterling B2B Integrator**
25. Review the installation package summary information. Click **Install** to apply your installation settings to the installation.
- If you did not select the option to automatically apply the database schema, the installation stops and you must perform these additional steps to complete the installation with manual DDL statements:
- a. Open the installation directory.
  - b. Locate the `InstallSI.log` file and open it with a file editor.
  - c. Search the file for these error messages:
    - `<SI_Install>/repository/scripts/EFrame_IndexAdds.sql` must be applied to the database.
    - `<SI_Install>//repository/scripts/EFrame_Sequence.sql` must be applied to the database.
    - `<SI_Install>//repository/scripts/EFrame_TableChanges.sql` must be applied to the database. Exiting installation..."
- Important:** If you do not find these error messages in the log file, the installation failed because of another reason and you must resolve that error and attempt the installation again. If you find these messages, continue with the remaining steps.
- d. Edit each `.sql` script for the database. These changes might include changing the SQL delimiter or adding table space options.
  - e. Log in to the database as the database schema user.
  - f. Run the following SQL files manually in this order:

**Important:** When you are running the scripts, you must run the SQL scripts in the specified order.

- `EFrame_IndexDrops.sql`
- `EFrame_TableChanges.sql`
- `EFrame_IndexAdds.sql`
- `EFrame_TextIndexAdds.sql`
- `EFrame_Sequence.sql`
- `EFrame_TextIndexModify.sql`
- `EFrame_TextIndexUpdates.sql`
- `EFrame_TextIndexUpgrade.sql`
- `EFrame_Static.sql`

**Important:** ActiveMQ uses dynamically generated table names that are based on the name of the installation node. Table generation is not included in these SQL scripts, but is performed automatically during the initial start of Sterling B2B Integrator or when a new cluster node is added. Table generation might fail if security restrictions reduced the Sterling B2B Integrator database user permissions. To avoid this issue, ensure that the DBADM role permissions are enabled during the initial startup. If further issues arise, contact IBM customer support for guidance.

- g. Exit from the database.
- h. Open the parent directory of the Sterling B2B Integrator installation directory.
- i. Delete (or rename as a backup) the installation directory.
- j. Restart the installation wizard and provide the same installation options that you provided before you cleared the **Apply database schema automatically** check box.

The Installation Progress screen indicates which component of the installation is in process.

A status bar below the **Repository Information** heading displays the progress of the component installation. When the installation completes, a large green circle with a check mark displays with the message The packages are installed. A link is provided to view the installation log file.

26. Click **Finish**. The Installation Manager closes and you are returned to your desktop.

Check the InstallSI.log file to verify that all of the components were installed properly.

If you are installing on Windows 2008, see “Configure the Sterling B2B Integrator Desktop Icon for Windows Server 2008” on page 48.

27. (This step applies only if you are installing Sterling B2B Integrator 5.2.5.0.)

After the Sterling B2B Integrator 5.2.5.0 installation is complete, install Sterling B2B Integrator 5.2.5.0 interim fix 3 (5020500\_3). See “Install an interim fix (Windows)” on page 55 for instructions.

This interim fix (si\_52\_build\_5020500\_interimfix\_3.jar) is included in the Sterling B2B Integrator 5.2.5 installation media released in April 2015, but is not automatically installed. It must be installed separately. In this case, use the included si\_52\_build\_5020500\_interimfix\_3.jar file rather than downloading from Fix Central.

28. Determine whether you need to apply a fix pack or interim fix to the installation. Refer to “Install an interim fix (Windows)” on page 55 for information.

## Installing in a Windows non-cluster environment with the IBM Installation Manager in text mode

You can install Sterling B2B Integrator in a Windows non-cluster environment with the IBM Installation Manager in a text-based mode that uses a command prompt.

### Before you begin

- Complete the “Installation Checklist for a Windows Non-Cluster Environment” on page 25.
- Access the JAR file for your installation. The JAR file depends on your operating system and current version of Sterling B2B Integrator. Refer to the following

websites for the correct JAR file. Consult with your IBM representative to identify the correct JAR file for your installation.

- Refer to Fix Central to see if you must use an interim fix or fix pack JAR file for the installation.
- Refer to Passport Advantage to see if you must use an installation JAR file for the installation.
- If you are using the Standards Processing Engine (SPE) application with Sterling B2B Integrator, you must install SPE before you install Sterling B2B Integrator.
- If you are using the EBICS Banking Server application with Sterling B2B Integrator 5.2.5, the data encryption for storage within the installation location is not supported.

## Procedure

1. Close all open Windows programs and any command prompt windows.
2. From the installation media, copy the compressed installation package to a location on your desktop.
3. Decompress the installation package.
4. Open the IMSI (Installation Manager) folder that is in the directory structure that is created when the installation package is decompressed. The directory includes several *IM\_OperatingSystem.zip* files.
5. Decompress the *IM\_Win.zip* file. This action creates a new *IM\_Win* folder.
6. Open the new *IM\_Win* folder in a command prompt window.
7. Enter the following command to start the installation:  
`installc.exe -c`

**Note:** Extra memory settings can be specified for the Installation Manager by adding the following parameters to the installation command.

- `-DmemoryMax=-Xmx3072m`
- `-DmemoryMin=-Xms1024m`

The Installation Manager (text mode) starts.

An [X] next to an option number indicates that option is selected.

8. Select the package to install. Press Enter to accept the default selection. The appropriate package is selected by default.
9. Review the license agreement. Enter:
  - 1 to view the Sterling B2B Integrator license agreement.
  - A to accept the agreement.
  - D to not accept the agreement.

If you do not accept the agreement, the installation process is canceled.

The screen refreshes with an [X] in front of your selected option. Press Enter to continue.

10. Specify the path to the Sterling B2B Integrator installation directory. This directory is referred to as *install\_dir*. Below the installation directory, the installer creates a directory that is named *install* that contains the installation files. You can modify the default path by entering M and entering the appropriate path. The screen refreshes with an [X] in front of your selected option. Enter N to continue.
11. At the **IBM B2B Sterling Integrator** prompt, press Enter to accept the default value of Sterling Integrator.
12. Enter the full path of your JDK directory.

13. Select the licenses and features to install. Enter [Y]es to select a feature or [N]o to decline a feature when prompted. You are prompted for each of the following licenses:

- **IBM Sterling B2B Integrator and/or IBM Sterling File Gateway**
- **FIPS Module**
  - **FIPS Compliance Mode (Must enable FIPS Module)**
- (5.2.5 and higher) **NIST 800-131a Compliance Mode**

For this feature, you are prompted to enter a number for the option.

  - **off** (default value)
  - **transition**
  - **strict**
- **AS2 Edition Module**
- **Financial Services Module**
- **EBICS Banking Server Module**
- (5.2.5 and higher) **SPE Integration Module (Requires pre-install of SPE, WTX optional)**

If you select the SPE option, you are prompted for the following information:

- SPE installation directory
- (Optional) WebSphere Transformation Extender (WTX) installation directory
- SPE UI port

For more information, see the documentation for the integration of Sterling B2B Integrator and SPE.

**Note:** Select only the licenses/features that are defined by your IBM contract. If you are unsure which to select, the installation can proceed without making a selection and complete successfully. Startup and operation of the software, however, requires one of the licenses to be selected. See *License Modification* to apply licenses post-install.

**Note:** Sterling File Gateway requires extra installation steps. See the *Sterling File Gateway Installation Guide*.

**Note:** If you are upgrading to Sterling B2B Integrator version 5.2.4 from a previous 5.2.x release, you must manually install the EBICS client. For more information about installing the EBICS Client manually, see the EBICS Client User Guide.

14. Enter the full path to your JCE policy file.
15. Select the JAR file to use.
16. Enter an explicit IP address or host name to override the default value of localhost.
17. Enter the initial port number. The default value is 8080.
18. Enter your system passphrase.

The passphrase is not hidden. It appears in dot format on your screen.
19. Enter your system passphrase again to confirm it.
20. Enter the email address to which you want system alert messages and other administrative notices sent.

21. Enter the SMTP mail server host name that you want to use for system alert messages and other administrative notices.
22. Enter the number of the database vendor as listed in the display:
  - [1] DB2
  - [2] Oracle
  - [3] MySQL
  - (5.2.3 - 5.2.4.2) [4] MSSQL2005
  - (5.2.5 and higher) [4] MSSQL2012
23. (Skip for MySQL) Specify whether this installation is for a cluster node 2 or higher. Enter [N]o.
24. (Skip for MySQL) Specify whether you want to apply the database schema automatically:
  - To automatically apply the database schema, enter [Y]es.
  - To manually create the database schema, enter [N]o and continue with the remaining installation steps.

**Note:** After the installation starts, it runs for a short time and stop without error. When the installation stops, you must perform extra steps later in this procedure.

25. Configure your database by entering the following information:
  - User name.
  - Password (and confirmation).  
This password is not hidden. It appears in dot format on your screen.
  - Catalog name.
  - Host name.
  - Host port number.
  - (Oracle, Microsoft SQL Server, and MySQL only) Absolute path and file name for one JDBC driver.
  - (DB2 only) Absolute paths and file names for two JDBC drivers.  
Use the Type-4 JDBC driver. This type of driver converts JDBC calls into the network protocol that is used directly by DB2, allowing a direct call from Sterling B2B Integrator to the DB2 server.
  - (Oracle only) At the **What Data type would you like to use?** prompt, choose a data type for binary data (BLOB or Long Raw).
    - To use caching for BLOB (binary large object) columns, enter BLOB. You can significantly improve performance by enabling the cache on the BLOB data object in Oracle. For more information, see the documentation for slow performance in Oracle.
    - To use the Long Raw data type, enter Long.

The Installation Manager automatically tries to validate the JDBC driver.

The Installation Manager must successfully validate the connection to the database before you can continue with the installation. If there is a validation failure, you can view the system log to determine more information about the failure. Perform the following tasks:

- a. Identify the location of the user's application directory. Select **Start > Run** and enter %APPDATA%.
- b. Open the user's application directory: `local_path\IBM\Installation Manager\logs`
- c. Open the `index.xml` file in a browser.

- d. Identify the log file that is based on the time stamp of when you started your installation.
  - e. Click the installation file to view a listing of errors that occurred during that installation.
26. Specify whether this installation is an upgrade from a prior version. Enter [N]o.
27. Specify whether you want to use the verbose installation option. Enter the appropriate option for this installation:
- [Y]es.
  - [N]o

Confirm your entry by pressing Enter.

28. Type values in the following fields. You must manually type a value, even if you are using the default value.
- **Number of Processor Cores**
  - **Physical Memory (MB) allocated to Sterling B2B Integrator**

After typing in the values, press Enter.

29. Review the information and select your next course of action:
- To generate an installation response file with the settings that you specified in the Installation Manager, enter G.
  - To start the installation, press Enter to select the default value of I.
  - To return to a previous option, enter B.
  - To cancel the installation, enter C.

If you selected I, the installation begins.

If you did not select the option to apply database schema automatically, the installation stops and you must perform extra steps to complete the installation with manual DDL statements:

- a. Open your install directory.
- b. Locate the InstallSI.log file and open it with a file editor.
- c. Search the file for these error messages:
  - `<SI_Install>/repository/scripts/EFrame_IndexAdds.sql` must be applied to the database.
  - `<SI_Install>//repository/scripts/EFrame_Sequence.sql` must be applied to the database.
  - `<SI_Install>//repository/scripts/EFrame_TableChanges.sql` must be applied to the database. Exiting installation..."

**Note:** If you do not find these error messages in the log file, the installation failed because of another reason and you must resolve that error and attempt the installation again. If you did find these messages, continue with the remaining steps.

- d. Edit each .sql script for your database. These changes might include changing the SQL delimiter or adding table space options.
- e. Log in to your database as the DB schema user.
- f. Run the SQL files manually in this order:

**Important:** When you are running the scripts, you must run the SQL scripts in the specified order.

- EFrame\_IndexDrops.sql
- EFrame\_TableChanges.sql

- EFrame\_IndexAdds.sql
- EFrame\_TextIndexAdds.sql
- EFrame\_Sequence.sql
- EFrame\_TextIndexModify.sql
- EFrame\_TextIndexUpdates.sql
- EFrame\_TextIndexUpgrade.sql
- EFrame\_Static.sql

**Important:** ActiveMQ uses dynamically generated table names that are based on the name of the installation node. Table generation is not included in these scripts, but is performed automatically during the initial startup of Sterling B2B Integrator or when a new cluster node is added. Table generation might fail if security restrictions reduced the Sterling B2B Integrator database user permissions. To avoid this issue, ensure that the DBADM role permissions are enabled during the initial startup. If further issues arise, contact IBM customer support.

- g. Exit from the database.
- h. Open the parent directory of the installation directory.
- i. Delete (or Rename as a backup) the Sterling B2B Integrator installation directory.
- j. Restart the installation wizard and provide the same installation options that you provided before you cleared the **Apply database schema automatically** check box.

Installation information can be found in the InstallSI.log file. The installation automatically continues. When the installation is finished, the system displays the following message:

```
The install completed successfully
```

30. Press Enter to select **Finish**.

Check the InstallSI.log file to verify that all of the components were installed properly.

31. (This step applies only if you are installing Sterling B2B Integrator 5.2.5.0.)

After the Sterling B2B Integrator 5.2.5.0 installation is complete, install Sterling B2B Integrator 5.2.5.0 interim fix 3 (5020500\_3). See “Install an interim fix (Windows)” on page 55 for instructions.

This interim fix (si\_52\_build\_5020500\_interimfix\_3.jar) is included in the Sterling B2B Integrator 5.2.5 installation media released in April 2015, but is not automatically installed. It must be installed separately. In this case, use the included si\_52\_build\_5020500\_interimfix\_3.jar file rather than downloading from Fix Central.

32. Determine whether you need to apply a fix pack or interim fix to the installation. Refer to “Install an interim fix (Windows)” on page 55 for information.

## Silent installations

The silent installation method automates part of the installation process and limits your manual interaction with the installation program. This is useful for doing multiple installations.

To use the silent installation method, you will need to first create a silent install file using a text editor.

## Create the Silent Installation File (Windows)

### About this task

The following entries correlate to the prompts seen in the “Install Using a Silent Installation File (Windows)” on page 45 procedure. Create a silent installation file with the following variables:

**Note:** Special characters need to be preceded by a \ (backslash) esc character.

Entry	Description
ACCEPT_LICENSE	(Required) Indicates if the user accepts the license agreement.  Default: YES
JVM_LOC	(Required) Full path to JDK directory.
LICENSE_FILE_PATH	(Required) Full path to Core_License.xml.  The Core_License.xml file is located on the same media as the install wizard jar and the installation jar.  <b>Attention:</b> If you are installing or upgrading Sterling B2B Integrator to version 5.2.4, refer to the section: <i>Extracting the Core License File</i> .
LICENSE_FILE_# (where # is a number between 1 and 99)	(Required) This is required for each license you install. You need a entry for each license file in the silent install file. The LICENSE_FILE numbering (#) does not need to be sequential.  For example:  LICENSE_FILE_1= SI_SFG_License.xml  LICENSE_FILE_2= Fin_Serv_License.xml  LICENSE_FILE_3= SI_SFG_FIPS_License.xml  LICENSE_FILE_4= AS2_License_.xml  LICENSE_FILE_5= EBICS_License_.xml
SI_LICENSE_AVAILABLE	(Optional) Indicates if a license is being passed in and is required for the installation.  Default: YES
JCE_DIST_FILE	(Required) Full path to unlimited strength JCE policy file. If present, this file will overwrite the JCE file in the JDK.
INSTALL_DIR	(Required) Directory that includes the bin subdirectory (where many commands are stored) and the properties subdirectory (where many properties are stored).The INSTALL_DIR property cannot point to a pre-existing directory or the installation will fail.



Entry	Description
INSTALL_IP	<p>(Required) Host name or IP address.</p> <p>Valid values:</p> <ul style="list-style-type: none"> <li>• localhost (default)</li> <li>• Your IP address or host name</li> </ul> <p>If you are installing Sterling B2B Integrator on VMware, provide the IP address of the virtual machine, not the IP address of the VMware host. For example, if 10.251.124.160 is the IP address of the VMware host and 10.251.124.156 is the IP address of the Windows 2003 server it is hosting, you should use 10.251.124.156 as the correct IP address to install Sterling B2B Integrator.</p> <p><b>Note:</b> Sterling B2B Integrator does not support IPv6 installation on Windows. Before applying an IPv6 address, see <i>IPv6 Capabilities</i> section in the <i>System Requirements</i>.</p> <p>You must install using a host name, not an IPv6 address, otherwise the Lightweight JDBC adapter and Graphical Process Modeler (GPM) will not work.</p>
PORT1	<p>(Required) Base port for ASI server. Ports are assigned consecutively from this port.</p> <p>Example: 12345</p> <p>Default: 8080</p>
APSERVER_PASS	<p>(Required) Passphrase used to secure all encrypted data in database.</p>
SI_ADMIN_MAIL_ADDR	<p>(Required) E-mail address for the administrative user.</p> <p>Example: abc@xyz.com</p>
SI_ADMIN_SMTP_HOST	<p>(Required) Valid SMTP host through which the system can e-mail the administrative user.</p> <p>Example: mail.xyz.com</p>
FIPS_MODE	<p>(Optional) Indicates if you are using FIPS (Federal Information Processing Standards) mode.</p> <p>Valid values:</p> <ul style="list-style-type: none"> <li>• true - Enable FIPS mode.</li> <li>• false (default) - Disable FIPS mode.</li> </ul>
DB_VENDOR	<p>(Required) Database vendor.</p> <p>Valid values:</p> <ul style="list-style-type: none"> <li>• Oracle</li> <li>• MSSQL2005 (use this value for Microsoft SQL 2005 and 2008)</li> <li>• DB2</li> <li>• MySQL (default)</li> </ul>
DB_CREATE_SCHEMA	<p>(Required) Indicates if you want the database schema automatically created.</p> <p>Valid values:</p> <ul style="list-style-type: none"> <li>• true (default) - Automatically create the schema.</li> <li>• false - Manually create the schema. This is not a valid choice for MySQL.</li> </ul>

Entry	Description
DEBUG	(Optional) Records events that occur during the installation in InstallSI.log file.  Valid values: <ul style="list-style-type: none"> <li>• true - records events that occur during the installation.</li> <li>• false (default) - does not record the events that occur during installation.</li> </ul>
DB_USER	(Required) Database user name.
DB_PASS	(Required) Database password.
DB_DATA	(Required) Database catalog name.
DB_HOST	(Required) Database host name.  Default: localhost
DB_PORT	(Required) Database port.  Example: 1234
DB_DRIVERS	(Required) Full path to JDBC driver files. If DB_VENDOR is: <ul style="list-style-type: none"> <li>• Oracle, MSSQL, or MySQL, specify one driver.</li> <li>• DB2, specify two drivers.</li> </ul> If you specify more than one driver, use colons (:) to separate the file names.  Examples: <ul style="list-style-type: none"> <li>• <i>JDBC_driver_dir</i>\db2jdbc.jar</li> <li>• <i>JDBC_driver_dir</i>\db2_1_jdbc.jar:<i>JDBC_driver_dir</i>\db2_2_jdbc.jar</li> </ul>
ORACLE_USE_BLOB	(Required if DB_VENDOR=Oracle) Indicates the data type to use for caching. <ul style="list-style-type: none"> <li>• true (default) - BLOB (binary large object)</li> <li>• false - Long Raw</li> </ul>
MSSQL2005	(Required for Microsoft SQL Server 2005) This attribute is case-sensitive. <ul style="list-style-type: none"> <li>• Set this attribute to the default value of true.</li> <li>• (All other servers) Do not include this attribute.</li> </ul>
JDK64BIT	Indicates if a 32-bit or 64-bit JDK is being used. Refer to the <i>System Requirements</i> to determine the type of JDK for your operating system.  Valid values: <ul style="list-style-type: none"> <li>• true (default) - 64-bit</li> <li>• false - 32-bit</li> </ul>
Icons	(Required) Indicates whether to create a desktop icon for accessing Sterling B2B Integrator.  Valid values: <ul style="list-style-type: none"> <li>• true - Create a desktop icon.</li> <li>• false (default) - Do not create a desktop icon.</li> </ul> If you created a desktop icon and use Windows Servers 2008, you will need to perform the <i>Configure the Sterling B2B Integrator Desktop Icon for Windows Server 2008</i> procedure after the installation has been completed.
PROCESSORS	(Optional) Indicates the number of processor cores in the system, where each core is an independent processing engine.

The following entries do not directly correlate to prompts in the installation procedure. Use these entries to customize or document your installation.

Entry	Description
DB_DRIVERS_VERSION	(Optional) Free form version string for JDBC driver. This is informational only.  Example: 8_1_5
LOAD_FACTORY_SETUP	(Optional) Indicates whether factory setup should be loaded during installation. To manually set LOAD_FACTORY_SETUP to false after an installation where LOAD_FACTORY_SETUP=true (the default value), change LOAD_FACTORY_SETUP to false in sandbox.cfg file.  Valid values: <ul style="list-style-type: none"> <li>• true (default).- loads factory setup during installation.</li> <li>• false - does not load factory setup during installation. Run loadDefaults command after installation.</li> </ul>
CONFIG_GS	(Optional) Indicates whether integration with Sterling Gentran:Server <sup>®</sup> should be configured.  Default: No
NO_DBVERIFY	(Optional) Valid values are true or false. When set to true during installation and installservice, dbverify will not be run.  This means that Sterling B2B Integrator will not generate DDL to make the database like the XML entity repository.

### Install Using a Silent Installation File (Windows)

You can install Sterling B2B Integrator in a Windows non-cluster environment using a silent installation file.

#### About this task

Before you begin, you should have already created the silent installation file.

To install Sterling B2B Integrator using a silent installation file:

#### Procedure

1. Close all open Windows programs and any command prompt windows.
2. From the installation media, copy the compressed installation package to a location on your desktop.
3. Uncompress the installation package.
4. Set up your silent installation file and record the file location.
5. Start the installation using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
<ul style="list-style-type: none"> <li>From a command prompt (or from the <b>Run</b> dialog box), enter the following command:  <pre>absolutePath\bin\java -Xmx512m -jar \absolutePath\ SI_&lt;build_number&gt;.jar -f \absolutePath\SilentInstallFile</pre> </li> </ul>	<ul style="list-style-type: none"> <li>Click <b>Start</b>.</li> <li>Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.  The Administrator: Command Prompt dialog box is displayed.</li> <li>Enter the following command:  <pre>absolutePath\bin\java -Xmx512m -jar \absolutePath\ SI_&lt;build_number&gt;.jar -f \absolutePath\SilentInstallFile</pre> </li> </ul>

The installation begins. The program verifies support for your operating system and JDK. You can follow the progress of your installation through the InstallSI.log file. If the installation stops, check the InstallSI.log file for details.

**Note:** Select only the licenses/features that have been defined by your IBM contract. If you are unsure which to select, the installation can proceed without making a selection and will complete successfully. Start up and operation of the software, however, requires one of the licenses to be selected. See *License Modification* to apply licenses post-install.

**Note:** Sterling File Gateway requires additional installation steps. See the *Sterling File Gateway Installation Guide* for more information.

**Note:** If you are upgrading to Sterling B2B Integrator version 5.2.4 from a previous 5.2.x release, you must manually install the EBICS client. For more information about installing the EBICS Client manually, see the EBICS Client User Guide on the Sterling B2B Integrator 5.2 Information Center.

- (Skip this step if you are applying database schema automatically.) If you are going to manually create the database schema, the install starts and runs for a short time and stops without error.

**Note:** After the installation stops, you must perform these additional steps to complete the installation with manual DDL statements:

- Navigate to your install directory.
- Locate the InstallSI.log file and open it with a file editor.
- Search the file for these error messages:
  - <SI\_Install>/repository/scripts/EFrame\_IndexAdds.sql must be applied to the database.
  - <SI\_Install> // repository/scripts/EFrame\_Sequence.sql must be applied to the database.
  - <SI\_Install> // repository/scripts/EFrame\_TableChanges.sql must be applied to the database. Exiting installation..."

**Note:** If you do not find the above error messages in the log file, the installation failed because of another reason and you must resolve that error and attempt the installation again. If you did find these messages, continue with the remaining steps.

- Edit each .sql script and make changes appropriate for your database. This may include changing the SQL delimiter or adding tablespace options.
- Log in to your database as the DB schema user.
- Execute the SQL files manually in this order:

**Note:** When you are executing the scripts, it is important to execute the SQL scripts in the specified order.

- EFrame\_IndexDrops.sql
- EFrame\_TableChanges.sql
- EFrame\_IndexAdds.sql
- EFrame\_TextIndexAdds.sql
- EFrame\_Sequence.sql
- EFrame\_TextIndexModify.sql
- EFrame\_TextIndexUpdates.sql
- EFrame\_TextIndexUpgrade.sql
- EFrame\_Static.sql

**Important:** ActiveMQ uses dynamically generated table names based on the name of the install node. Table generation is not included in the above scripts, but is performed automatically during the initial start of Sterling B2B Integrator or when a new cluster node is added. Table generation may fail if security restrictions have reduced the Sterling B2B Integrator database user permissions. To avoid this issue, ensure that the DBADM role permissions are enabled during the initial startup. If further issues arise, contact IBM customer support for guidance.

- g. Exit from the database.
  - h. Navigate to the parent directory of *install\_dir*.
  - i. Delete (or Rename as a backup) the Sterling Integrator install directory.
  - j. Restart the installation wizard and provide the same installation options you provided before including clearing the **Apply database schema automatically** check box.
7. Check the **InstallSI.log** to verify all the components have installed properly.
  8. (This step applies only if you are installing Sterling B2B Integrator 5.2.5.0.)  
After the Sterling B2B Integrator 5.2.5.0 installation is complete, install Sterling B2B Integrator 5.2.5.0 interim fix 3 (5020500\_3). See “Install an interim fix (Windows)” on page 55 for instructions.  
This interim fix (*si\_52\_build\_5020500\_interimfix\_3.jar*) is included in the Sterling B2B Integrator 5.2.5 installation media released in April 2015, but is not automatically installed. It must be installed separately. In this case, use the included *si\_52\_build\_5020500\_interimfix\_3.jar* file rather than downloading from Fix Central.
  9. Determine whether you need to apply a fix pack or interim fix to the installation. Refer to “Install an interim fix (Windows)” on page 55 for information.
  10. From the installation directory, install windows services by running the command **installWindowsService.cmd**.

## Installing version 5.2.x as a fix pack

### About this task

Use this procedure to upgrade your non-clustered 5.2.x system to a later 5.2.x version

## Procedure

1. Download the fix pack from the installation media.
2. Verify that the database server is up and ready to accept connections.
3. Stop the system.
4. Perform a full backup of the installation directory, including all sub-directories.
5. Perform a backup of the database.
6. If you edited any property files, ensure that the associated `.properties.in` files have the most current changes. Property files will be overwritten with the contents of the associated `.properties.in` files during the fix pack installation.
7. Is the database password encrypted? If Yes, decrypt the password.
8. To install the fix pack:
  - UNIX or Linux - Navigate to the directory where the system is installed and enter: `./InstallService.sh file_name.jar`  
**Attention:** Running **InstallService.sh** removes any previously installed interim fix to prevent conflicts with what is being installed.
  - Windows - From a command prompt or the Run dialog box, enter:  
`C:\install_dir\install\bin\InstallService.cmd <path>file_name.jar`  
**Attention:** Running **InstallService.cmd** removes any previously installed interim fix to prevent conflicts with what is being installed.

If the fix pack attempts to modify the database schema and the modification fails, you will receive an error message about the failure. The message will provide the error message code from the database and the SQL command that failed. The failure information is also logged to the `system.log` file and to the `patch.log` file.
9. Press **Enter** to continue.
10. To accept the license agreement, enter Y.
11. Enter the passphrase.  
Information about the fix pack is displayed. After the fix pack has been applied, the following message is displayed: `Deployment to application server successful`
12. If you decrypted the database password, re-encrypt the password.
13. Start the system.  
If you are using a perimeter server in the DMZ, review the information on applying a fix pack to the perimeter server.

## Configure the Sterling B2B Integrator Desktop Icon for Windows Server 2008

User Access Control (UAC) is a security component in Windows Server 2008. It affects the installation and the daily processing for Sterling B2B Integrator.

### About this task

If you enable the UAC, it affects the installation process and the daily processing for Sterling B2B Integrator. If you disable the UAC, which requires a reboot, the installation process and daily processing for Sterling B2B Integrator remains the same as in previously supported Windows version.

If you installed or upgraded Sterling B2B Integrator on a Windows Server 2008 and you created a desktop icon for Sterling B2B Integrator, you must complete this task in order for the desktop icon to work.

### Procedure

1. Right-click on the Sterling B2B Integrator **desktop icon**.
2. Click **Properties**.
3. In the Shortcut tab, click **Advanced**.
4. Select the check box for **Run as Administrator**.
5. Click **OK** to apply the changes to Advanced Properties.
6. Click **OK**.

---

## Validate the Installation

### Installation validation checklist

As part of the installation, you need to run validation tests to ensure that the software installation was successful.

Complete the following tasks:

#	Validate Installation Checklist	Your Notes
1	Start Sterling B2B Integrator.	
2	Access Sterling B2B Integrator.	
3	Validate the installation.	
4	Stop Sterling B2B Integrator.	

### Starting Sterling B2B Integrator in a Windows noncluster environment

After you run the upgrade software, you can start Sterling B2B Integrator.

#### Before you begin

If you are starting Sterling B2B Integrator after you upgrade the application from version 5.1.0.4 to 5.2.5, change the values of the following properties in the `centralops.properties` file to 600. This action prevents the `StartWindowsService.cmd` command from timing out before Sterling B2B Integrator starts. The `centralops.properties` file is in the `install_dir\install\properties` directory.

- `OpsServer.commandTimeout`
- `PassPhrase.urlTimeout`

#### Procedure

1. Open the `install_dir\install\bin` directory with one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"> <li>• Click <b>Start</b>.</li> <li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li> </ul> The Administrator: Command Prompt dialog box is displayed.

2. Enter `StartWindowsService.cmd`. The final start processes run, concluding with the following messages:  
Open your Web browser to `http://host:port/dashboard`  
where `host:port` is the IP address and port number on your system.
3. Record the URL address so that you can access Sterling B2B Integrator.

## Accessing Sterling B2B Integrator

You can access Sterling B2B Integrator through a web browser.

### Procedure

1. Open a browser window and enter the address that is displayed at the end of the start.
2. On the login page, enter the default user ID and password. The default login is at an administrative level. One of your first tasks as an administrator is to change the administrative password and to register other users with other levels of permission.

## Validating the installation with a sample business process

You can validate the installation by testing a sample business process.

### Procedure

1. From the **Administration Menu**, click **Business Process > Manager**.
2. In the **Process Name** field, type `Validation_Sample_BPML` and click **Go!**
3. Click **execution manager**.
4. Click **execute**.
5. Click **Go!** The Status: Success message is displayed on the upper left side of the page.

## Stop Sterling B2B Integrator (Windows)

You can stop Sterling B2B Integrator in a Windows environment from the **Administration** menu.

### About this task

To stop Sterling B2B Integrator in a Windows environment:

### Procedure

1. From the Administration Menu, select **Operations > System > Troubleshooter**.
2. Click **Stop the System** and wait for shutdown to complete.

## Stop Sterling B2B Integrator (Hardstop Windows)

You can stop Sterling B2B Integrator in a Windows environment.



## About this task

To stop Sterling B2B Integrator in a Windows environment:

### Procedure

1. Navigate to `\install_dir\install\bin` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"><li>• Click <b>Start</b>.</li><li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li></ul> The Administrator: Command Prompt dialog box is displayed.

2. Enter `StopWindowsService.cmd`. You should receive a message that services have been stopped. Services include Noapps, Opsserver, WebDav, and Database-related service.

---

## Post Installation Configuration

### Post Installation Configuration Checklist (Windows)

After you install Sterling B2B Integrator you need to complete some post installation configuration. Complete the items listed in the post installation checklist:

#	Post Installation Configuration Checklist	Your Notes
1	For security purposes, change all default user ID passwords immediately after installation is completed. See the <i>Update My Account Information</i> task in the documentation library.	
2	Download Sterling B2B Integrator Tools.	
3	Determine if you need to modify any Property Files.	

### Download of the Sterling B2B Integrator tools

After you install Sterling B2B Integrator, you can install tools like the Map Editor and the Graphical Process Modeler (GPM).

Sterling B2B Integrator includes tools that run on a desktop or personal computer. After you install Sterling B2B Integrator, you can install the following tools:

- Map Editor and associated standards
- Graphical Process Modeler (GPM)
- Web Template Designer
- (If licensed) MESA Developer Studio plug-ins, including MESA Developer Studio Software Development Kit (SDK) and MESA Developer Studio Skin Editor
- (If licensed) Reporting Services, which require MESA Developer Studio if you want to use the plug-ins to create fact models and custom reports

**Attention:** Conflicting IP addresses can cause problems when you download a desktop tool.

## Property files configuration in a Windows environment

Property files contain properties that control the operation of Sterling B2B Integrator.

For example, the REINIT\_DB property in the sandbox.cfg file controls whether or not a database is initialized when you install Sterling B2B Integrator.

By modifying the values of these properties, you can customize the Sterling B2B Integrator to suit your business and technical needs. Most property files are in the `\install_dir\install\properties` directory.

After installing Sterling B2B Integrator, most property files and scripts do not need any further configuration for basic operation. However, if you want to customize any specific operations, for example setting a different logging level - you will need to edit ( or in some cases, create) certain property or .xml files.

Before changing any property files, refer to the *Working with Property Files* documentation for general information about how to work with Property Files.

Areas where you might need to make specific property files changes after an installation include:

- LDAP user authentication
- Prevention of cross-site script vulnerabilities
- Logging configuration
- Process-specific property file settings

---

## System Maintenance

### System Maintenance

You might need to perform system maintenance such as applying a fix pack, performing a checksum, or modifying the license files occasionally.

From time to time, you may need to perform system maintenance activities. These activities might include any or all of the following:

- Applying a fix pack
- Applying an interim fix
- Performing a checksum
- Generating a fix pack Change Report
- Modifying the license files

### Preserve Custom Changes

You can preserve your custom changes to system resources (like workflow definitions and maps) when you update your system. During updates, the system can identify when you make a custom change versus when the system makes a change through an upgrade or fix pack.

When a fix pack, installation or upgrade is performed, a baseline record of system resources is created. This baseline is not affected by any subsequent customer

changes. When another fix pack is installed, the resources in this baseline are compared to the resources in the existing system. If a baseline and existing resource are not the same, it means that the existing resource was customized and is not overwritten by the fix pack.

During an update, the baseline is updated with new system resource information, but not with the custom changes to resources.

## Determine If You Need to Apply a Fix Pack (Windows)

Fix Packs contain cumulative fixes for a specific version of Sterling B2B Integrator.

### About this task

Fix packs are available on the IBM Fix Central web site. Because each fix pack contains the fixes from previous fix packs, you only need to install the most recent fix pack.

**Note:** During installation, the dbVerify utility compares the list of standard indexes with those present in the database and drops the custom indexes. You should recreate the custom indexes after the installation is complete.

Fix packs are named using the following naming convention:

`si_<release number>_<build number>.jar`

Information about a fix pack is located in a PDF file with a similar name. The naming convention for PDF files is:

`si_<release number>_<build number>.pdf`

Before you install the fix pack, review the following items:

- Preserve your custom changes to system resources.
- The installation may use one or more property override files. These files will be named `propertyFile_patch.properties`. Do not alter these files.
- Property changes made directly in `*.properties` or `*.properties.in` files may be overwritten during the installation. Properties overridden using the `customer_overrides.properties` file are not affected. IBM recommends that you maintain property file changes using (when possible) the `customer_overrides.properties` file. For more information about this file, refer to the property file documentation.
- If you edited any of the `cdinterop` files, you must back them up before applying the fix pack. The `cdinterop` files do not have initialization ( `*.in` ) files. After applying the fix pack, use the backup version of the files in your installation. These files include the following files: `cdinterop-proxy-records.properties`; `cdinterop-spoee-auth.properties`; `cdinterop-spoee-policy.properties`; and `cdinterop-user-records.properties`.
- Information about the installation is automatically logged to `\install_dir\install\logs\InstallService.log`.
- If you need to rollback a fix pack, see the *Fix Pack Change Report*.

### Install a fix pack (Windows)

Fix packs are used to update Sterling B2B Integrator.

## About this task

To install the latest fix pack for Sterling B2B Integrator in a Windows environment:

### Procedure

1. Navigate to the IBM Fix Central web site.
2. Download the most recent fix pack file for your version of Sterling B2B Integrator and record the absolute path to the downloaded file. Do not rename the file. If you use FTP, you must use Binary mode.
3. Verify that the database server is up and ready to accept connections.
4. Log in to the server where Sterling B2B Integrator is installed with the user ID and password that was used for the installation.
5. Stop Sterling B2B Integrator.
6. Perform a full backup of the Sterling B2B Integrator installation directory, including all subdirectories.
7. Perform a backup of the database.
8. If you edited any property files, ensure that the associated properties.in files have the most current changes. Property files will be overwritten with the contents of the associated properties.in files during the fix pack installation.
9. Is the database password encrypted? If Yes, decrypt the password.
10. Close all command prompt windows.
11. To apply the fix pack:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
<p>From a command prompt or the Run dialog box, enter:</p> <pre>C:\install_dir\install\bin\InstallService.cmd &lt;path&gt;\ si_&lt;version&gt;_sp_0_fix pack_ &lt;number&gt;_&lt;app_server&gt;.jar</pre> <p>Where:</p> <ul style="list-style-type: none"> <li>• &lt;path&gt; is fully qualified path to maintenance fix pack file</li> <li>• &lt;version&gt; is Sterling B2B Integrator version</li> <li>• &lt;number&gt; is fix pack number</li> <li>• &lt;app_server&gt; is Application server</li> </ul> <p>Example:</p> <pre>C:\install_dir\install\bin\InstallService.cmd \fix pack\si_22_sp_0_fix pack_1_jboss.jar</pre>	<p>Complete the following steps:</p> <ul style="list-style-type: none"> <li>• Click <b>Start</b>.</li> <li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li> </ul> <p>The Administrator: Command Prompt dialog box is displayed.</p> <ul style="list-style-type: none"> <li>• Enter:</li> </ul> <pre>C:\install_dir\install\bin\ InstallService.cmd &lt;path&gt;\si_&lt;version&gt;_sp_0_fix pack_&lt;number&gt;_&lt;app_server&gt;.jar</pre> <p>Where:</p> <ul style="list-style-type: none"> <li>• &lt;path&gt; is fully qualified path to maintenance fix pack file</li> <li>• &lt;version&gt; is Sterling B2B Integrator version</li> <li>• &lt;number&gt; is fix pack number</li> <li>• &lt;app_server&gt; is Application server</li> </ul> <p>Example:</p> <pre>C:\install_dir\install\bin\InstallService.cmd \fix pack\si_22_sp_0_fix pack_1_jboss.jar</pre>

If the fix pack attempts to modify the database schema and the modification fails, you will receive an error message about the failure. The message will provide the error message code from the database and the SQL command that failed. The failure information is also logged to the system.log file (in the `\install_dir\install` directory) and to the fix pack.log file. The `InstallService.cmd` command stops the WebDAV server used for MESA Developer Studio. To restart the server, refer to the MESA Studio documentation.

**Attention:** Running `InstallService.cmd` removes any previously installed interim fix to prevent conflicts with what is being installed.

12. Press **Enter** to continue.
13. If you want to accept the license agreement, enter `Y`.
14. Enter the passphrase.

Information about the fix pack is displayed. After the fix pack has been applied, the following message is displayed: **Deployment to application server successful**

15. If you decrypted the database password, re-encrypt the password.
16. Start Sterling B2B Integrator.

If you are using a perimeter server in the DMZ, you will to review the information on apply a fix pack to the perimeter server.

## Install an interim fix (Windows)

After you install Sterling B2B Integrator you may need to install an interim fix.

### About this task

An interim fix is one or more fixes applied to an existing fix pack.

Before you can install an interim fix, you must have completed the following:

- Received the file name of the `ccaseid.jar` to install from IBM Customer Support
- Created a full backup of Sterling B2B Integrator
- Created a full backup of your database
- Preserve your custom changes to system resources

### CAUTION:

**If you are installing a customer-specific interim fix, you cannot install a fix pack unless support notifies you that your interim fix is included in that fix pack. Otherwise, you will lose your custom fix.**

To install an interim fix:

### Procedure

1. Log in to the computer that you are installing the interim fix on.
2. If the database password was encrypted, decrypt the password.
3. Navigate to the IBM Fix Central website.
4. Login using your email address and password.
5. Download the `ccaseid.jar` file, where `ccaseid` includes the ID number you received from Customer Support. If you use FTP, you must use Binary mode.
6. Stop Sterling B2B Integrator.
7. Navigate to `\install_dir\install\bin`.
8. To install the interim fix:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
<p>From a command prompt or the Run dialog box, enter:</p> <pre>C:\install_dir\install\bin\ InstallService.cmd absolutePath\ ccaseid.jar</pre>	<p>Complete the following steps:</p> <ul style="list-style-type: none"> <li>• Click <b>Start</b>.</li> <li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li> </ul> <p>The Administrator: Command Prompt dialog box is displayed.</p> <ul style="list-style-type: none"> <li>• Enter:</li> </ul> <pre>C:\install_dir\install\bin\ InstallService.cmd absolutePath\ ccaseid.jar</pre>

You may need to complete this step twice depending on the fix pack. Read the output from the InstallService script carefully to see if you need to complete this step twice.

**Attention:** Running **InstallService.cmd** removes any previously installed interim fix to prevent conflicts with what is being installed.

9. If you decrypted the database password, re-encrypt the password.
10. Start Sterling B2B Integrator.
11. Navigate to `\install_dir\install\bin` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
<p>Open a command prompt window (from the Run dialog box).</p>	<p>Complete the following steps:</p> <ul style="list-style-type: none"> <li>• Click <b>Start</b>.</li> <li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li> </ul> <p>The Administrator: Command Prompt dialog box is displayed.</p>

12. Run the **dump\_info** command to verify that the interim fix was successfully installed.

### Uninstalling an interim fix

Uninstalling an interim fix is a manual process. IBM support must first determine what is included in the interim fix you want to remove, and then manually backout the changes one at a time. The complexity of this process, therefore, can vary greatly.

If you must remove an interim fix, contact IBM support by creating a PMR (Problem Management Record)

## DB Checksum Tool

A checksum is a simple redundancy check used to detect errors in data. The DB Checksum tool, a resource difference tool generates a granular report of the changes in the system that was not permitted to be set as defaults.

The DB Checksum tool generates the difference in resource checksum between the default resource and the latest system resource from the database.

## Perform a Checksum (Windows)

You can run the DB Checksum tool in the Windows environment.

### About this task

To run the DB Checksum tool in the Windows environment:

### Procedure

1. Navigate to `\install_dir\bin` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"><li>• Click <b>Start</b>.</li><li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>. The Administrator: Command Prompt dialog box is displayed.</li></ul>

2. Enter `db_checksum_tool.cmd [-d] [-i [1 | 2 | 3 | 4 | 5]] [-r [wfd | map | schema | sii | template]] [-o <output file>] [-g]`

Where:

-d is the mode to dump the difference of resource checksum between the default resource and latest system resource.

-i is the resource type integer (optional).

1 is WFD.

2 is MAP.

3 is SCHEMA.

4 is SII.

5 is TEMPLATE.

-r is the resource name (optional). For example, wfd, map, schema, sii, or template.

-o is the file name to output all the messages (optional).

-g is the file name that lists all the ignored resources (optional).

-h is the help screen.

The DB Checksum tool performs the relevant checksum operation based on the command options and generates the output message.

## Fix Pack Changes Report

The Fix Pack Changes Report is used to obtain information if you need to roll back a fix pack.

The fix pack report can be found in the installation directory `fix_pack_reports` folder. The report contains the following fix pack information:

- Fix pack ID
- Fix pack changes
- Number of files deleted
- Number of JAR files removed
- Number of JAR files added
- Number of files added

- Number of files changed
- Number of properties added
- Number of business processes added
- Number of service instances added
- Number of service definitions added
- Number of templates added
- Number of reports added
- Number of maps added
- Number of schemas added
- Number of business rules added

For example, the installation directory `fix pack_reports` folder contains the `fix pack_Report.html` file. When you open this file, you can view the fix pack information.

### Example: Fix Pack Changes Report

The Fix Pack Changes Report includes both summary and detailed report information.

The following is an example of a Fix Pack Changes Report:

```
Summary of Changes
Fix Pack ID: Platform_2.0
Fix Pack Changes: 1287
Number of Files Deleted: 0
Number of JARs Removed: 2
Number of JARs Added: 0
Number of Files Added: 3
Number of Files Changed: 3
Number of Properties Added: 4
Number of BPs Added: 4
Number of Service Instances Added: 2
Number of Service Definitions Added: 3
Number of Templates Added: 0
Number of Reports Added: 0
Number of Maps Added: 3
Number of Schemas Added: 3
Number of Business Rules Added: 0
```

---

```
List of JARs Removed:
JAR Removed: /SAMPLE_INSTALL_1/jar/jaf/1_0_2/activation.jar
Time: Wed May 13 15:23:08 EDT 2009
JAR Removed: /SAMPLE_INSTALL_1/jar/commons_logging/1_0_3/commons-logging-api.jar
Time: Wed May 13 15:23:08 EDT 2009
```

---

```
List of Files Added:
File Added: /SAMPLE_INSTALL_1/bin/sql/fix_db2_schema.sql
Time: Wed May 13 15:21:30 EDT 2009
File Added: /SAMPLE_INSTALL_1/bin/sql/fix_db2iseries_schema.sql
Time: Wed May 13 15:21:30 EDT 2009
File Added: /SAMPLE_INSTALL_1/bin/errorQueueManager.sh.in
Time: Wed May 13 15:21:30 EDT 2009
```

---

```
List of Files Changed:
File Changed: /SAMPLE_INSTALL_1/properties/lang/en/Reports_en.properties
File Changed: /SAMPLE_INSTALL_1/properties/lang/es/Reports_es.properties
File Changed: /SAMPLE_INSTALL_1/properties/lang/fr/Reports_fr.properties
```

---

```
List of Properties Added:
Property Added: /SAMPLE_INSTALL_1/properties/filesToRemove.txt
Property Added: /SAMPLE_INSTALL_1/properties/filesToRemove.txt.in
```



Property Added: /SAMPLE\_INSTALL\_1/properties/csr.properties.sample  
Property Added: /SAMPLE\_INSTALL\_1/properties/csr.properties.sample.in

---

List of BPs Added:

BP Added: Schedule\_AssociateBPsToDocs.bpm1 version: 4  
Time: Wed May 13 15:23:07 EDT 2009  
BP Added: Recovery.bpm1 version: 17  
Time: Wed May 13 15:23:07 EDT 2009  
BP Added: Schedule\_AutoTerminateService.bpm1 version: 10  
Time: Wed May 13 15:23:07 EDT 2009  
BP Added: Schedule\_DBMonitorService.bpm1 version: 1  
Time: Wed May 13 15:23:08 EDT 2009

---

List of Service Instances Added:

Service Instance Added: RetentionProcessor version: 2  
Time: Wed May 13 15:23:28 EDT 2009  
Service Instance Added: MESAHttpServerAdapter version: 1  
Time: Wed May 13 15:25:11 EDT 2009

---

List of Service Definitions Added:

Service Definition Added: LockServiceType  
Time: Wed May 13 15:22:58 EDT 2009  
Service Definition Added: XAPIServiceType  
Time: Wed May 13 15:22:59 EDT 2009  
Service Definition Added: CleanLockServiceType  
Time: Wed May 13 15:22:59 EDT 2009

---

List of Templates Added:

Template Added: Normalize  
Time: Wed May 13 15:23:26 EDT 2009  
Template Added: Derive  
Time: Wed May 13 15:23:26 EDT 2009

---

List of Maps Added:

Map Added: IBMPutResponseToXML  
Time: Wed May 13 15:24:05 EDT 2009  
Map Added: http\_headers  
Time: Wed May 13 15:24:36 EDT 2009  
Map Added: OracleHttpHeaders  
Time: Wed May 13 15:24:51 EDT 2009

---

List of Schemas Added:

Schema Added: E5\_V20\_Acknowledge\_Result.dtd from file: E5\_V20\_Acknowledge\_Result  
Time: Wed May 13 15:24:36 EDT 2009  
Schema Added: E5\_V20\_Acknowledge\_Submit.dtd from file: E5\_V20\_Acknowledge\_Submit  
Time: Wed May 13 15:24:36 EDT 2009  
Schema Added: E5\_V20\_APIs\_Result.dtd from file: E5\_V20\_APIs\_Result  
Time: Wed May 13 15:24:36 EDT 2009

## License modifications

After the installation finishes, you can modify the software licenses that you loaded with the **AddLicenseSet** command.

The **AddLicenseSet** command is in the bin directory of your UNIX or Windows installation. After the initial installation, the license files are in the following directories:

- UNIX - */install\_dir/install/properties/licensefiles*
- Windows - *\install\_dir\install\properties\licensefiles*
- iSeries - */install\_dir/properties/licensefiles*

You can add licenses or review the license list from the UI. On the Administration Menu, click **System > B2B Console > Operations > System > Licenses**.

## AddLicenseSet Command Parameters

Use the **AddLicenseSet** command to modify a single license file or the entire license file directory.

To use the **AddLicenseSet** command, you must do the following:

- Open the bin directory
- Include the absolute path to the license file directory or to a license file

The **AddLicenseSet** command has the following parameters:

AddLicenseSet Parameter	Description
<b>-reload</b>	<p>Use this parameter to reload the license files.</p> <p>This parameter deletes all of the license files from the database before the new files are loaded. The old license files are saved to the following locations:</p> <ul style="list-style-type: none"> <li>• UNIX - <i>/install_dir/install/logs/security/old_licenses</i></li> <li>• Windows - <i>\install_dir\install\logs\security\old_licenses</i></li> <li>• iSeries - <i>/install_dir/logs/security/old_licenses</i></li> </ul>
<b>-upgrade</b>	<p>Use this parameter during an upgrade only.</p> <p>This parameter deletes all of the old license files from the database and installs the new license files. The old license files are saved to the following locations:</p> <ul style="list-style-type: none"> <li>• UNIX - <i>/install_dir/install/logs/security/upgrade</i></li> <li>• Windows - <i>\install_dir\install\logs\security\upgrade</i></li> <li>• iSeries - <i>/install_dir/logs/security/old_licenses</i></li> </ul>

The **AddLicenseSet** command will check if Sterling B2B Integrator is running. If it is running, the command will call the Ops server to refresh the license from the database. If you have any problems with your licenses after running the **AddLicenseSet** command, stop and restart Sterling B2B Integrator.

## License Modification: Examples

There are several different ways you can use the **AddLicenseSet** command to modify your licenses.

### UNIX Examples

From the *install\_dir/bin* directory:

Scenario	Command usage (UNIX example)
Reload a single license file	<code>./AddLicenseSet.sh /install_dir/install/properties/licensefiles/SI_SFG_License.xml -reload</code>
Reload all of the license files in the directory	<code>./AddLicenseSet.sh /install_dir/install/properties/licensefiles/ -reload</code>
Upgrade a single license file	<code>./AddLicenseSet.sh /install_dir/install/properties/licensefiles/SI_SFG_License.xml -upgrade</code>
Upgrade all of the license files in the directory	<code>./AddLicenseSet.sh /install_dir/install/properties/licensefiles/ -upgrade</code>

## Windows Examples

From the *install\_dir*\bin directory:

Scenario	Command usage (Windows example)
Reload a single license file	AddLicenseSet.cmd\install_dir\install\properties\licensefiles\SI_SFG_License.xml -reload
Reload all of the license files in the directory	AddLicenseSet.cmd\install_dir\install\properties\licensefiles\ -reload
Upgrade a single license file	AddLicenseSet.cmd\install_dir\install\properties\licensefiles\SI_SFG_License.xml -upgrade
Upgrade all of the license files in the directory	AddLicenseSet.cmd\install_dir\install\properties\licensefiles\ -upgrade

---

## Configure Non-English Environment

### Non-English Environment Checklist

You can install Sterling B2B Integrator in an English or a non-English environment. The base language for the Configurator can be switched only once. Use the following checklist change to a non-english environment:

#	Non-English Environment Checklist	Your Notes
1	Install the Sterling B2B Integrator Language Pack.	
2	Load the Sterling B2B Integrator Language Pack Factory Defaults.	
3	Load the Sterling B2B Integrator Language Pack translators.	
4	Configure Encodings.	
5	Configure Locales.	

### Language Settings in a Windows Environment

Language settings for Java applications involve both character sets and encoding:

- A character set is a set of characters (letters, numbers, and symbols such as #, \$, and &) that are recognized by computer hardware and software.
- An encoding is a representation of data in a particular character set. An encoding set is a group of encodings.

For information about basic and extended encoding sets, see <http://download.oracle.com/javase/1.5.0/docs/guide/intl/encoding.doc.html>

The default encoding set includes:

- UTF-8 (default)
- ISO-8859-1
- ISO-8859-5
- US-ASCII
- ISO\_8859-1
- EUC-JP
- UTF-16

- ISO-2022-JP

Sterling B2B Integrator provides two property files that contain supported encoding sets. These properties files reside in the `\install_dir\install\properties` directory.

- `encodings.properties` – Contains the default encoding set used in the user interface.
- `encodings_large.properties` – Contains all supported encoding sets.

You are not limited to the encodings in the `encoding.properties` file. Sterling B2B Integrator enables you to configure the `encodings.properties` files to expand the number of encodings you can use.

## Install the Language Pack (Windows)

### About this task

Before installing the language pack be sure that you have successfully installed Sterling B2B Integrator.

To install Sterling B2B Integrator language pack:

### Procedure

1. Insert the language CDs into your CD-ROM drive.
2. Navigate to Win Directory using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"> <li>• Click <b>Start</b>.</li> <li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li> </ul> The Administrator: Command Prompt dialog box is displayed.

3. Run the `setup.exe` command.

## Load the Language Pack Factory Defaults (Windows)

### About this task

To load the language-specific factory defaults, use the `loadDefaults.cmd` script available in the `install_dir\install\bin` directory and pass the locale-specific installer file.

For example:

```
loadDefaults.cmd \install_dir\install\database\FactorySetup\install\  
<language>_<country>_locale_installer.xml
```

The default locale that is shipped with the CD is `ja_JP`.

## Load the Language Pack Translations (Windows)

### About this task

Prior to loading the Sterling B2B Integrator Language Pack factory defaults, be sure that you have successfully completed all instructions in the database chapter.

To load the language pack translation with custom localization literals:

### Procedure

1. Navigate to `\install_dir\install\bin` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"><li>• Click <b>Start</b>.</li><li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li></ul> The Administrator: Command Prompt dialog box is displayed.

2. Run the LocalizedStringReconciler tool in the IMPORT mode, enter: `ant.cmd -f localizedstringreconciler.xml import -Dsrc=install_dir\database\FactorySetup\XMLS`  
This tool first inserts the value specified in the `<from_language>_<from_country>_ycplocalizedstrings_<to_language>_<to_country>.properties` file present in the `install_dir\database\FactorySetup\XMLS\<language>_<country>` directory into the database.  
The basefilename refers to the file present in the `\database\FactorySetup\XMLS` directory, for which the translations are to be imported into the database.
3. Verify that your locale settings such as currency, time format, and date are correct.

## Configure Encodings for Sterling B2B Integrator (Windows)

### About this task

To configure your encoding set:

### Procedure

1. Stop Sterling B2B Integrator and wait for shutdown to complete.
2. Navigate to `\install_dir\install\bin` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"><li>• Click <b>Start</b>.</li><li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li></ul> The Administrator: Command Prompt dialog box is displayed.

3. Open the `encodings_large.properties` file.
4. Select the encodings you want to add to the `encodings.properties` file.
5. Open the `encodings.properties.in` file.

6. At the end of the encodings.properties.in file, add the encodings you selected from the encodings\_large.properties file. When adding encodings from one file to the other, first copy the encodings as they appear in the encodings\_large.properties file. After adding the new encodings, ensure that the index numbers are consecutive. If the index numbers are not consecutive, change the index number or numbers as needed. For example, encoding54 cannot follow encoding6. In this example, change encoding54 to encoding7.  
The first name in the definition (before the comma) is the name that will appear in the Sterling B2B Integrator user interface. You can change this name to make it more descriptive. For example: encoding4 = 819,ISO8859\_1 may be changed to encoding4 = WesternEurope,ISO8859\_1. ISO8859\_1 is the Java canonical name and should not be changed.
7. Update the first line in the encodings.properties.in file (numberof). Change *numberof* to the number of encodings added to the file. For example, if the current value is numberof = 6 and you add 5 new encodings, the new value is numberof = 11.  
*numberof* indicates the total number of encodings located in the file. You must update numberof to ensure that the encodings you added will be visible in the user interface.
8. Navigate to `\install_dir\install\bin` using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"> <li>• Click <b>Start</b>.</li> <li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li> </ul> The Administrator: Command Prompt dialog box is displayed.

9. Enter `setupfiles.cmd`.
10. Start Sterling B2B Integrator.

## Configure Locales (Windows)

### About this task

Sterling B2B Integrator runs in any locale that Java supports. If you want to run in a non-default locale, then configure your environment to the specific locale you want to use.

To determine and set your locale in a windows environment:

### Procedure

1. Select **Control Panel > Regional Options > General**.
2. From the Your locale (location) list, select the language and location.
3. Click **Set Default** and select the locale from the Set the appropriate locale list.
4. To configure your operating system as a non-English environment, consult your operating system's documentation.

---

## Configure Browser Settings for a Foreign Language

### Configure Browser Settings

Some browsers and/or operating systems require additional configuration in order to correctly render the Sterling B2B Integrator user interface in certain languages. Use the procedures provided in this section to properly configure a browser to display the Sterling B2B Integrator user interface in the appropriate language.

**Note:** If your browser is unable to display the user interface properly or you see a mixture of English and another language, this is an indication that the browser is configured incorrectly. You may also need to install additional fonts on the Sterling B2B Integrator server.

### Support for foreign languages

The Sterling B2B Integrator 5.2.3 user interface includes support for several foreign languages

**Attention:** Sterling B2B Integrator 5.2.3 product code is designed to work with Latin based English only input. The use of any other type of input might have uncertain results and is not supported as part of the 5.2.3 release.

The Sterling B2B Integrator 5.2.3 user interface includes support for the following foreign languages:

- French
- German
- Italian
- Japanese
- Korean
- Polish
- Portuguese (Brazilian)
- Simplified Chinese
- Traditional Chinese

Four of these languages involve expanded Unicode character sets:

- Japanese
- Korean
- Simplified Chinese
- Traditional Chinese

The implementation of these languages in your environment might require the addition of new Unicode fonts on your server:

If...	then...
Sterling B2B Integrator is on a server that already supports these languages	You do not need to install any additional fonts.
You are installing on a server that is only setup for the Latin alphabet and you have users who need to view the Sterling B2B Integrator user interface in any of the Asian languages	You need to have the fonts for these languages installed.

A way to test the implementation of a language is to create a user with one of the new languages and setup their browser to use that language as it's primary language. Log in to the system and review the user interface. If you see a mixture of English and the new language, your configuration is not correct. You need to verify that the browser is set up correctly and review the fonts that are installed on the server.

The installation of more fonts/languages on the server should be done in coordination with your technical support team. Be sure to include a Unicode Sans Serif font on your server.

**Important:** While multiple foreign languages are supported, a user account should be configured to use one specific language to avoid user interface display issues.

## Add a Custom Language Preference Code

### About this task

In order for your browser to display the Sterling B2B Integrator user interface and address bar text correctly in a foreign language, you must specify the appropriate language preference code for the browser.

Sterling B2B Integrator 5.2.3 supports the following language preference codes:

- de
- en
- en-US
- es
- fr
- it
- ja
- ko
- pt-BR
- zh
- zh-TW

Your browser must be configured to use one of these specific language preference codes to view the Sterling B2B Integrator user interface.

**Note:** Most browsers provide a default listing of language preference codes. However, Sterling B2B Integrator requires the use of the specific codes as listed here. For example, you cannot use the default German (Germany) [de-DE], you must use **[de]**.

You may need to add these supported codes as a custom language preference code in your browser.

**Note:** The instructions for configuring a browser's display will differ for each browser. Refer to your chosen browser's documentation for specific instructions on configuring that browser's display.

The following is an example of how to configure a client machine display for an IE window.



## Procedure

1. Open an IE browser window.
2. Select **Tools > Internet Options**.
3. At the bottom of the window under Appearance, click **Languages**.
4. Click **Add** to display the Add Language window.
5. In the User defined: text box, enter the appropriate language preference code from the list below:
  - de
  - en
  - en-US
  - es
  - fr
  - it
  - ja
  - ko
  - pt-BR
  - zh
  - zh-TW
6. Click **OK**. The added code should display in the Language: listing in the Language Preference window. An example entry would be, **User Defined [de]**.
7. (Optional) Move the added language up to be the first one listed if there are multiple languages listed.
  - a. Select the newly added language.
  - b. Click **Move up**.

The newly added language should now appear first in the Language listing.
8. Click **OK** to save your Language Preference settings.
9. Click **OK** to close the Internet Options window.
10. Close your browser window.
11. Open a new browser window and access the Sterling B2B Integrator user interface to verify your changes have been applied.

## Change Default Browser Font

### About this task

Some languages require the use of special fonts to properly display the Sterling B2B Integrator user interface. The client computer must be configured to display these types of fonts. Each Windows client must be configured appropriately.

**Note:** The instructions for configuring a browser's display will differ for each browser. Refer to your chosen browser's documentation for specific instructions on configuring that browser's display.

The following is an example of how to change the default browser font for an Internet Explorer (IE) window.

To configure a client machines display for IE:

## Procedure

1. Determine which fonts are needed to support your needed language and verify they are installed on the server.

**Note:** The installation of additional fonts/languages on the server should be done in coordination with your technical support team. Be sure to include a Unicode Sans Serif font on your server.

2. Open an IE browser window.
3. Select **Tools > Internet Options**.
4. At the bottom of the window under Appearance, click **Fonts**.
5. From the Language Script drop-down menu, change the Latin based value to the appropriate script for your needed language.

**Note:** If your encoding is not available, you may need to install a new version of Internet Explorer, but make sure you install the appropriate international options.

6. Select a Webpage font and a Plain text font appropriate for the new language. A Plain text font is one in which all the characters take up the same amount of space and is associated with older computer terminals.

**Note:** If no fonts are listed in the menus, then you need to install fonts designed for that encoding.

7. Click **OK** to close the Fonts window.
8. Click **OK** again to close the Internet Options window.
9. Close your browser window.
10. Open a new browser window and access the Sterling B2B Integrator user interface to verify your changes have been applied.

## Set the Client Character Display

### About this task

To use special characters, such as for various languages, the client computer must be configured to display these types of characters. In order for Unicode characters to display correctly in the application, each Windows client must be configured appropriately.

**Note:** The instructions for configuring a browser's display will differ for each browser. Refer to your chosen browser's documentation for specific instructions on configuring that browser's display.

The following is an example of how to configure a client machine display for an Internet Explorer (IE) window.

To configure a client machines display for IE:

### Procedure

1. Open an IE browser window.
2. Select **View > Encoding > Auto-Select**.

## Clearing Browser and Java Plugin Caches Before Initial Deployment

### About this task

Once the Sterling B2B Integrator is ready for deployment, each user must clear the browser and Java Plugin caches on their client machines before launching Sterling B2B Integrator. This requirement applies to all browsers.

To clear the browser and java caches, do the following:

### Procedure

1. From the browser menu bar, select **Settings > Control Panel > Internet Options**.
2. Select the General tab, and in the Temporary Internet Files panel, click **Delete Files**. The Delete Files dialog displays.
3. Check the **Delete All Offline Content** checkbox. Click **OK** until the Internet Properties window closes. The browser cache is cleared.
4. From the Windows start menu, select **Settings > Control Panel > Java**.
5. Select the General tab, and in the Temporary Internet Files panel, click **Settings**. The Temporary Files Settings dialog displays.
6. In the Disk Space panel, click **Delete Files**. The Delete Temporary Files pop-up window displays.
7. Click **OK** until the Java Control Panel window closes.

## General Internet Explorer Browser Settings

When using Sterling B2B Integrator without any customizations, you need to set the General Browser settings for your Internet Explorer in order to obtain the best browser performance.

**Note:** This can impact the display of reports and search listings.

To set your general browser settings:

1. From the Internet Explorer menu, select **Tools > Internet Options**.  
The Internet Options window opens to the General tab.
2. Locate the Browsing history section and click **Settings**.  
The Temporary Internet Files and History Settings window opens.
3. Below Check for newer versions of stored pages: select the **Everytime I visit the webpage** option.
4. Click **OK** to save your changes.
5. Click **OK** to apply the changes.
6. Close the browser window and re-open it.

The browser is now set to check for updates to pages everytime a page is accessed rather than relying upon a cached version.

## Internet Explorer Security Settings

### About this task

When using Sterling B2B Integrator without any customizations, you need to set security settings for your Internet Explorer to obtain the best browser performance.

To configure the Internet Explorer security and privacy settings:

### Procedure

1. From the Internet Explorer menu, select **Tools > Internet Options**.
2. Click the **Security** tab.
3. Select the Web content zone from which Sterling B2B Integrator is accessed.
4. Set the security level to **Medium-low**.
5. Click **Custom Level** and set your security settings according to the following table:

Internet Explorer Security Setting	Sterling B2B Integrator
<b>.NET Framework</b>	
Loose XAML	Enable
XAML browser applications	Enable
XPS documents	Enable
<b>.NET Framework-reliant Components</b>	
Permissions for components with manifests	High Safety
Run components not signed with Authenticode	Enable
Run components signed with Authenticode	Enable
<b>ActiveX Controls and Plugins</b>	
Allow previously unused ActiveX controls to run without prompt	Enable
Allow Scriptlets	Enable
Automatic prompting for ActiveX controls	Enable
Binary and script behaviors	Enabled
Display video and animation on a webpage that does not use external media player	Disable
Download signed ActiveX controls	Prompt
Download unsigned ActiveX controls	Prompt
Initialize and script ActiveX controls not marked as safe for scripting	Prompt
Run ActiveX controls and plugins	Prompt/Enable
Script ActiveX controls marked as safe for scripting	Enable
<b>Downloads</b>	
Automatic prompting for file downloads	Enable
File download	Enable
Font download	Prompt
<b>Enable .NET Framework setup</b>	Enable
<b>Java VM</b>	
Java permissions	Medium safety
<b>Miscellaneous</b>	
Access data sources across domains	Enable
Allow META REFRESH	Enable
Allow scripting of Internet Explorer web browser control	Enable

<b>Internet Explorer Security Setting</b>	<b>Sterling B2B Integrator</b>
Allow script-initiated windows without size or position constraints	Enable
Allow webpages to use restricted protocols for active contents	Prompt
Allow websites to open windows without address or status bars	Enable
Display mixed content	Prompt
Do not prompt for client certificate selection when no certificates or only one certificate exists	Enable
Drag and drop or copy and paste files	Prompt
Include local directory path when uploading files to a server	Enable
Installation of desktop items	Prompt
Launching applications and unsafe files	Prompt
Launching programs and files in an IFRAME	Prompt
Navigate sub-frames across different domains	Enable
Open files based on content, not file extension	Enable
Software channel permissions	Medium safety
Submit non-encrypted form data	Prompt
Use Phishing Filter	Disable
Use Pop-up Blocker	Disable
Userdata persistence	Enable
Websites in less privileged web content zone can navigate into this zone	Prompt
<b>Scripting</b>	
Active scripting	Enable
Allow Programmatic clipboard access	Prompt
Allow status bar updates via script	Enable
Allow websites to prompt for information using scripted windows	Enable
Scripting of Java applets	Enable
<b>User Authentication</b>	
Logon	Prompt for user name and password

6. Click **OK** to save your settings.
7. Click **OK** to save the new settings and **Apply** to implement the settings. The new settings are applied when a new browser window is opened.

---

## Perimeter Server Installation

### Perimeter Server Overview

A perimeter server is an optional software tool for communications management. A perimeter server can be installed in a demilitarized zone (DMZ). A DMZ is a

computer host or small network inserted as a neutral zone between a company's private network and their public network. A perimeter server requires a corresponding perimeter client.

The perimeter server manages the communications flow between outer layers of your network and the TCP-based transport adapters. A perimeter server can solve problems with network congestion, security, and scalability, especially in high-volume, Internet-gateway environments.

## Installation Guidelines for Perimeter Servers with Sterling B2B Integrator

The installation program installs a perimeter client and a local mode server. The local mode server is useful for testing purposes or in environments that do not require a secure solution. However, if you require high-volume, secure connections, you must install a perimeter server in a remote zone, either a more secure or less secure network than your integration server.

Consider the following before you install a perimeter server:

- Licensing for a perimeter server is determined by the licensing restrictions on the corresponding B2B adapters.
- Each perimeter server is limited to two TCP/IP addresses:
  - Internal interface is the TCP/IP address that the perimeter server uses to communicate with Sterling B2B Integrator.
  - External interface is the TCP/IP address that the perimeter server uses to communicate with trading partners. To use additional TCP/IP addresses, install additional perimeter servers.
- You can have multiple perimeter servers installed on the same computer interacting with one instance of Sterling B2B Integrator. To install a perimeter server on a computer with an existing instance, install the new perimeter server in a different installation directory.
- The combination of internal TCP/IP address and port must be unique for all perimeter servers installed on one computer.
  - If a perimeter server is installed using the wildcard address, then all ports must be unique. The assigned ports are not available for use by adapters that use the server or any other perimeter server on that computer.
  - The internal and external interface may use the same TCP/IP address. However, the port used by the perimeter server is not available to the adapters that use the server.

## Perimeter Server Installation Methods

You can install perimeter server either in silent mode or in interactive mode. The default installation mode is silent. In the silent mode, you should specify the details in a silent file, whereas in the interactive mode, you should enter the value each time a prompt appears.

## Perimeter Server Information Gathering Checklist

Before you install the perimeter server, you need to gather the following information and answer the following questions:

Perimeter Server Information Gathering Checklist	Your Notes
Path to java	

Perimeter Server Information Gathering Checklist	Your Notes
Path to the Sterling B2B Integrator installation directory	
Will this perimeter server be installed in a less secure network?	
TCP/IP address or the DNS address that the perimeter server will listen on.	
Listening port for the perimeter server.	
Local port that the perimeter server will use to connect to Sterling B2B Integrator.	
Port number must be higher than 1024.	

## Perimeter Server Security Vulnerabilities

When Sterling B2B Integrator is deployed with a remote perimeter server in a more secure network zone, there is a security vulnerability. An intruder may compromise the host where the proxy resides, and take over the persistent connection to the perimeter server residing in the more secure zone. If this happens, the perimeter server will relay all the intruder's network requests past the firewall into this internal zone.

To prevent an intrusion, limit the activities the remote perimeter server can perform on behalf of the proxy to specifically those activities that the proxy needs to do for its operation.

Control these limitations by using a configuration residing in the secure network zone with the remote perimeter server, inaccessible by the proxy that could become compromised.

## Installing a Perimeter Server in a More Secure Network (Windows)

Install a perimeter server in a more secure network in a Windows environment in interactive mode.

### Before you begin

- Sterling B2B Integrator must be installed.
- Complete the Perimeter Server information gathering checklist.

### Procedure

1. Close all open Windows programs.
2. Copy the .jar installation files from the installation media to a Windows directory. If you are using FTP to copy the file, be sure that your session is set to binary mode. The .jar installation file names are as follows:
  - For 5.2.3 the file is named ps\_4060300.jar
  - For 5.2.4 the file is named ps\_4060400.jar
3. To start the perimeter server installation, use one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
<ul style="list-style-type: none"> <li>From a command prompt (or from the <b>Run</b> dialog box), enter the following command:  <pre>\path_to_java\java -jar \install_dir\install\packages\ ps_filename.jar -interactive</pre> </li> </ul>	<ul style="list-style-type: none"> <li>Click <b>Start</b>.</li> <li>Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>. The Administrator: Command Prompt dialog box is displayed.</li> <li>Enter the following command:  <pre>path_to_java\java -jar install_dir\install\packages\ ps_filename.jar -interactive</pre> </li> </ul>

The installation program verifies the operating system, minimum fix pack level, and the location and version of the JDK.

- Enter the full path name for the Sterling B2B Integrator installation directory and press **Enter**.  
If there is an existing installation in the directory you specify, you can update it using the same settings. Enter yes, and the installation proceeds without more entries.
- Enter yes to confirm that the installation directory is correct.  
The program verifies the amount of available disk space.
- Answer the question:  
Is this server in a less secure network than the integration server?  
**Yes**
- Answer the question: Will this server need to operate on specific network interfaces?
  - Enter yes to select from a list network interfaces available.
  - Enter no.
- Enter the TCP/IP address or DNS name that the integration server listens on for the connection from this perimeter server.
- Enter yes to confirm the TCP/IP address or DNS name.
- Enter the port that the integration server listens on for the connection from this server. The port number must be higher than 1024.
- Enter the local port number that the perimeter server uses for the connection to the integration server.  
The port number must be higher than 1024. Specify a port of zero for the operating system to select any unused port.
- Enter yes to confirm the port number.  
After the installation is complete, the following messages are displayed:  
Installation of Perimeter Service is finished  
To start this Perimeter Server change to the install directory and run the startup script.  
You will also need to configure this server in your integration server (SI) UI.

## Installing a perimeter server in a less secure network (Windows)

### About this task

Install a perimeter server in a Windows environment in interactive mode.



## Procedure

1. Close all open Windows programs.
2. Copy the .jar installation files from the installation media to a Windows directory. If you are using FTP to copy the file, make sure that your session is set to binary mode. The .jar installation file names are as follows:
  - For 5.2.3 the file is named ps\_4060300.jar
  - For 5.2.4 the file is named ps\_4060400.jar
3. To start the perimeter server installation, use one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
<ul style="list-style-type: none"> <li>• From a command prompt (or from the <b>Run</b> dialog box), enter the following command:  <code>\path_to_java\java -jar            \install_dir\install\packages\            ps_filename.jar -interactive</code> </li> </ul>	<ul style="list-style-type: none"> <li>• Click <b>Start</b>.</li> <li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.            The Administrator: Command Prompt dialog box is displayed.</li> <li>• Enter the following command:  <code>\path_to_java\java -jar            \install_dir\install\packages\            ps_filename.jar -interactive</code> </li> </ul>

The installation program verifies the operating system, minimum fix pack level, and the location and version of the JDK.

4. Enter the full path name of the installation directory.
5. If there is an existing installation in the directory you specify, you can update it using the same settings. Answer the question:  
 There is an existing install at that location, update it while keeping existing settings?  
 If **yes**, the installation proceeds without more entries.

**Note:** If you want to change any of the settings, you must use a new directory, or delete the old installation before you reinstall the perimeter server. You cannot overwrite an existing installation, and you cannot use an existing directory that does not contain a valid installation. The existing installation must be Sterling B2B Integrator 5.2 or later.

6. Confirm that the installation directory is correct.  
 The program verifies the amount of available disk space.
7. Answer the question:  
 Is this server in a less secure network than the integration server?  
**Yes**
8. Answer the question:  
 Will this server need to operate on specific network interfaces?  
 If **yes**, the program returns a list of the network interfaces available on your host. Select the interfaces for the server to use.
9. Enter the TCP/IP address or DNS name for the internal interface to use to communicate with the integration server (Sterling B2B Integrator). Press **Enter** to use a wildcard for this address.
10. Verify the TCP/IP address or DNS name for the internal interface.
11. Enter the TCP/IP address or DNS name for the external interface to use to communicate with trading partners. Press **Enter** to use a wildcard for this address.
12. Verify the TCP/IP address or DNS name for the external interface.

13. Enter the port that the perimeter server listens on for the connection from the integration server (Sterling B2B Integrator). The port number must be higher than 1024.
14. Verify the port.  
When the perimeter server is installed, the following message is displayed:  
Installation of Perimeter Service is finished
15. Change to the installation directory.
16. Enter `startupPs.cmd` to start the perimeter server.

## Silent Installation Method for an External Perimeter Server

You can install an external perimeter server using a silent install file. The perimeter server can be installed on the same machine where you have installed Sterling B2B Integrator or on a separate machine. It is recommended to install the perimeter server on an separate machine.

To use the silent installation method, you first create the silent install file and then you use to complete the installation.

### Create the Silent Installation File for an External Perimeter Server About this task

Create a silent installation file with the following variables:

Entry	Description
INSTALL_DIR	(Required) The installation directory that stores perimeter server files and related directories. This directory must exist prior to running the silent install.
REVERSE_CONNECT	(Optional) Determines if the perimeter server is to be installed in a more secure network zone. Valid values: <ul style="list-style-type: none"> <li>• Y - more secure network zone</li> <li>• N - less secure network zone</li> </ul>
PS_PORT	(Required) Determines the perimeter server port to interact with the system.
PS_SECURE_IF	(Required) Determines the TCP/IP address or DNS name for the internal interface to communicate with the integration server (Sterling B2B Integrator). You can use a wildcard (*) for this address.
PS_EXTERNAL_IF	(Required) Determines the TCP/IP address or DNS name for the external interface to communicate with the trading partners. You can use a wildcard (*) for this address.
REMOTE_ADDR	(Optional) Determines the remote perimeter server address. (Not required if REVERSE_CONNECT=N)
REMOTE_PORT	(Optional) Determines the remote perimeter server port. (Not required if REVERSE_CONNECT=N)
MAX_JVM_HEAP	(Required) Determines the maximum Java heap size allocated to the JVM.

### Installing an external perimeter server with a silent installation file (Windows)

Install an external perimeter server with a silent installation file.

## About this task

Before you begin, create the silent installation file.

### Procedure

1. From the installation media, copy `SI.jar` to a Windows directory.
2. Set up your silent installation file and record the file location.
3. To start the perimeter server silent installation, use one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
<ul style="list-style-type: none"><li>• From a command prompt (or from the <b>Run</b> dialog box), enter the following command: <pre>\path_to_java\java -Xmx512m -jar \install_dir\install\packages\ ps_filename.jar -f silent.txt</pre>The .jar installation file names are as follows:<ul style="list-style-type: none"><li>- For 5.2.3 the file is named <code>ps_4060300.jar</code></li><li>- For 5.2.4 the file is named <code>ps_4060400.jar</code></li></ul></li></ul>	<ul style="list-style-type: none"><li>• Click <b>Start</b>.</li><li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>. The Administrator: Command Prompt dialog box is displayed.</li><li>• Enter the following command: <pre>\path_to_java\java -Xmx512m -jar \install_dir\install\packages\ ps_filename.jar -f silent.txt</pre>The .jar installation file names are as follows:<ul style="list-style-type: none"><li>- For 5.2.3 the file is named <code>ps_4060300.jar</code></li><li>- For 5.2.4 the file is named <code>ps_4060400.jar</code></li></ul></li></ul>

The installation program verifies the operating system, minimum fix pack level, and the location and version of the JDK.

The installation starts. You can follow the progress of the installation on screen.

When the installation is finished, the system displays the following message:

Installation has completed successfully.

## Install a Fix Pack in a Remote Perimeter Server (Windows)

### About this task

Remote perimeter servers are not automatically updated by a fix pack. You must reinstall the perimeter server using the new perimeter server installation file supplied with the fix pack.

To update a Remote Perimeter Server:

### Procedure

1. Update your installation with the latest fix pack. Obtain the fix pack from the Support Center web site.
2. Locate your perimeter server file in the `install_dir\install\packages` directory of your installation. For fix packs, obtain the file from the Support Center web site. These files have a name that identifies a version number. For example, `ps_2006.jar`.
3. Copy the file to a directory on the remote server.
4. Stop the perimeter server.
5. Use one of the following methods to install the fix pack:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
<ul style="list-style-type: none"> <li>From a command prompt (or from the <b>Run</b> dialog box), enter the following command:  <pre>\absolutePath\bin\java -jar filename.jar -interactive</pre> </li> </ul> <p>Where the <i>absolutePath</i> is the directory name where the Java version is installed.</p>	<ul style="list-style-type: none"> <li>Click <b>Start</b>.</li> <li>Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>. The Administrator: Command Prompt dialog box is displayed.</li> <li>Enter the following command:  <pre>\absolutePath\bin\java -jar filename.jar -interactive</pre> </li> </ul> <p>Where the <i>absolutePath</i> is the directory name where the Java version is installed.</p>

The program verifies the operating system, required patch level, and the location and version of the JDK.

- Enter the full path to the installation directory. If you do not want to change any settings for your perimeter server, specify the same directory where the remote perimeter server was originally installed.
- Answer the question:  
There is an existing install at that location, update it while keeping existing settings?  
If **yes**, the installation will proceed without additional entries.

**Note:** If you want to change any of the settings, you must use a new directory, or delete the old installation before performing the new installation. You cannot overwrite an existing installation, and you cannot use an existing directory that does not contain a valid installation. The existing installation must be <https://apps.na.collabserv.com/meetings/join?id=4789-1289> 5.2 or later.

When the perimeter server is installed, the following message is displayed:  
Installation of Perimeter Service is finished

- Change to the installation directory.
- Start the perimeter server.

## Grant Permissions for Specific Activities for a Perimeter Server

### About this task

Before you begin:

- Remote perimeter server must be installed for a more secure zone.
- Know what permissions you want to grant
- Understand the content of the restricted.policy file. The first two grant sections in the restricted.policy file are required for correct perimeter server operation. Do not modify these sections.

### Procedure

- Install a remote perimeter server, choosing the option for a more secure network zone.
- At the installation prompt *Is this server in a less secure network than the integration server?*, select **No**, which is the option for a more secure network zone.
- Navigate to the perimeter server installation directory.
- Open the restricted.policy file.

5. Add permission lines for each back-end server that you intend to allow the proxy to access. There are commented out examples for each type of server. The first two grant sections are required for correct perimeter server operation. Do not modify these sections.

For example, you can grant permission to a target FTP Server. In the example, servers are configured to listen on the following ports: 33001 (for FTP), 33002 (for HTTP), and 1364 (for C:D). These port numbers can be edited.

```
// To restrict or permit the required Host/Server to communicate with the
// PS, update the "ftphost/httpthost/snode" with that of the Server IP and
// provide the appropriate PORT number where the Server will listen. //
// For each target FTP Server
// permission java.net.SocketPermission "10.117.15.87:33001", "connect"; //
// Control connection.
// permission java.net.SocketPermission "10.117.15.87:lowPort-highPort",
// "connect"; // Passive data connections.
// 10.117.15.87 indicates IP of the FTP Server for which the permission is
// granted by PS for communicating with client //
// For each target HTTP Server
//
// permission java.net.SocketPermission "10.117.15.87:33002", "connect";
// 10.117.15.87 indicates IP of the HTTP Server for which the permission
// is granted by PS for communicating with client //

// For each target C:D snode
//
// permission java.net.SocketPermission "snode:1364", "connect";
// 10.117.15.87 indicates IP of the Connect Direct Node for which
// the permission is granted by PS for communication //
```

6. In the perimeter server installation directory, there is the perimeter server settings file called `remote_perimeter.properties`. Edit it to change the "restricted" setting to a value of `true` to turn on restrictions.
7. In the future, any attempt by the perimeter server to access disallowed network resources will be rejected and logged in the perimeter server log written to the perimeter server installation directory.

## Perform DNS Lookup on Remote Perimeter Server

### About this task

By default, a perimeter server performs DNS lookup in the main server JVM. If you have limited DNS in your secure area, you can configure the remote perimeter server to look up trading partner addresses in the DMZ.

To enable DNS lookup, add the following property to `customer_overrides.properties`. Set the value to `true`:

Property Name	Description
<code>perimeter.*.forceRemoteDNS=true</code>	Forces resolution of DNS names at remote perimeter server.  Set the value to <code>true</code> to configure remote perimeter servers to look up trading partner addresses.

## Start Perimeter Servers (Windows)

### About this task

To start a perimeter server in Windows:

## Procedure

1. Navigate to the perimeter server installation directory.
2. Navigate to perimeter server installation directory using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"><li>• Click <b>Start</b>.</li><li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li></ul> The Administrator: Command Prompt dialog box is displayed.

3. Enter startupPs.cmd.

## Stop Perimeter Servers in (Windows)

### About this task

To stop a perimeter server in Windows:

## Procedure

1. Navigate to perimeter server installation directory using one of the following methods:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
Open a command prompt window (from the Run dialog box).	Complete the following steps: <ul style="list-style-type: none"><li>• Click <b>Start</b>.</li><li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>.</li></ul> The Administrator: Command Prompt dialog box is displayed.

2. Enter stopPs.cmd.

---


## User Documentation

### Sterling B2B Integrator user documentation

The user documentation is available from an online documentation site on the web.

Providing the documentation in an online environment allows for frequent updates of content that is based on user feedback and usability.

If you need a printed copy of the documentation, you can print topics of information through your Internet browser, or you can download documents in PDF format, after you add it to a collection on IBM Knowledge Center.

To access the documentation site from within Sterling B2B Integrator or one of its tools, select the help  icon. The system must reside on a computer that supports Internet access and an Internet browser.

## Improving your access to online documentation

You can improve your access to online documentation by using several methods.

### About this task

After you access the IBM Knowledge Center, you can perform the following tasks:

- Enter a word or phrase and search the entire library for information.
- Move through a hierarchy of contents pages to identify the topic you want to read or print.
- Print topics by using your browser's Print function.
- Add documents to your collection and download them in PDF format.

## Request a Documentation CD

You can request a CD that contains all the documentation found on the Documentation site. To submit a request, open a support case.

---

## Uninstall the Software

### Uninstall Sterling B2B Integrator from a Windows Non-Cluster Environment

When you uninstall Sterling B2B Integrator, the software is automatically removed from the server.

#### Before you begin

If you have installed Sterling B2B Integrator software using IIM, then perform these steps to unregister Sterling B2B Integrator packages from the IIM registry:

- Launch IIM.
- Click **Uninstall** and select the required Sterling B2B Integrator package (Media, FixPack, or Interim Fix).
- Confirm and click **Uninstall**.

#### About this task

To uninstall Sterling B2B Integrator from a Windows environment:

#### Procedure

1. Stop Sterling B2B Integrator and wait for shutdown to complete. Use one of the following methods to stop the system:

For Windows Server 2003 or earlier	For Windows Server 2008 or later
<p>Complete the following steps:</p> <ul style="list-style-type: none"> <li>• Open a command prompt window (from the Run dialog box).</li> <li>• Navigate to the <code>install_dir\install\bin</code> directory.</li> <li>• Enter <code>StopWindowsService.cmd</code></li> <li>• Enter <code>uninstallWindowsService.cmd</code> to uninstall Sterling B2B Integrator Windows Services.</li> </ul>	<p>Complete the following steps:</p> <ul style="list-style-type: none"> <li>• Click <b>Start</b>.</li> <li>• Right-click <b>Command Prompt</b> and select <b>Run as administrator</b>. The Administrator: Command Prompt dialog box is displayed.</li> <li>• Navigate to the <code>install_dir\install\bin</code> directory.</li> <li>• Enter <code>StopWindowsService.cmd</code></li> <li>• Enter <code>uninstallWindowsService.cmd</code> to uninstall Sterling B2B Integrator Windows Services.</li> </ul>

If you begin removing files before all business processes and the system is stopped, you may be unable to remove the software successfully.

2. Enter `uninstallWindowsService.cmd` to uninstall Sterling B2B Integrator Windows Services.
3. Back up the file system and database.
4. Remove the installation directory by entering the following command in the parent directory of your installation directory: `rd /s /q \\install_dir\install`
5. If you use an Oracle, Microsoft SQL Server, or DB2 database, these remain intact even after you remove Sterling B2B Integrator from the server. If you no longer want to reference the data, contact your database administrator about removing unwanted tables and recovering the database space where Sterling B2B Integrator used to reside.
6. Manually remove the JDK:
  - a. Navigate into the `_uninst` subdirectory of your JDK installation directory
  - b. Enter `uninstall.cmd`
7. After you remove Sterling B2B Integrator from the server, you can remove Eclipse, and any tools that were downloaded to the desktop, including the following:
  - Map Editor and associated standards  
Refer to the *Map Editor Guide* for information about removing the Map Editor.
  - Graphical Process Modeler  
Refer to the *Graphical Process Modeler Guide* for information about removing the Graphical Process Modeler.
  - Web Template Designer  
Refer to the *Web Extensions Guide* for information about removing the Web Template Designer.
  - (If licensed) MESA Developer Studio plug-ins, including:
    - MESA Developer Studio Software Development Kit (SDK)
    - MESA Developer Studio Skin Editor
Refer to the *MESA Developer Studio* guide for information about removing MESA Developer Studio.
  - (If licensed) Reporting Services, which requires MESA Developer Studio if you want to use the plug-ins to create fact models and custom reports.  
Refer to the *MESA Developer Studio* guide for information about removing Reporting Services.



## Troubleshooting Tips

### Troubleshooting Tips for Windows Environment

You might encounter errors or problems that you can troubleshoot in a Windows environment.

Situation	Message or Symptom	Explanation/Resolution
Installing	You encounter errors or problems during installation.	<b>Explanation</b> The installation creates several log files that you can use to diagnose problems like the failure of an installation. <b>Resolution</b> Examine the log files generated during installation: <ul style="list-style-type: none"><li>• ant.install.log (in the <i>install_dir</i> directory)</li><li>• <i>install_dir</i>\PreInstallSI.log</li></ul>
Installing	When you entered an absolute path during installation, a message indicated that the command was not found.	<b>Explanation</b> You entered an incorrect path. Check the information entered. <b>Resolution</b> Enter the correct path.
Installing	IM is installed successfully, but SI Fails to install.	Go to Start Open IM select Help and then Export logs to a file for analysis.
Installing a desktop tool or resource	Cannot download any of the following: <ul style="list-style-type: none"><li>• Map Editor and associated standards</li><li>• Graphical Process Modeler</li><li>• Web Template Designer</li><li>• (If licensed) MESA Developer Studio plug-ins, including:<ul style="list-style-type: none"><li>– MESA Developer Studio Software Development Kit (SDK)</li><li>– MESA Developer Studio Skin Editor</li></ul></li><li>• (If licensed) Reporting Services, which requires MESA Developer Studio if you want to use the plug-ins to create fact models and custom reports.</li></ul>	<b>Explanation</b> When you install Sterling B2B Integrator, system files are created that contain an internal IP address. If you install Sterling B2B Integrator behind a firewall, and your firewall is configured to accept an external IP address from a client computer, you may not be able to download the desktop tools and resources. The firewall will reject the internal IP address from a client residing outside of the firewall. <b>Resolution</b> Modify the system files that contain the invalid IP address. Follow these steps: <ol style="list-style-type: none"><li>1. Navigate to <i>\install_dir\install\bin</i>.</li><li>2. Stop Sterling B2B Integrator.</li><li>3. Enter the following command followed by the external IP address: <code>patchJNLP.cmd external_IP_address</code></li><li>4. Restart Sterling B2B Integrator.</li></ol>

Situation	Message or Symptom	Explanation/Resolution
Cluster Installation or Upgrade	<p>When configuring TCPS the following warning can be found in the activemqbroker.log:</p> <p>sun.security.provider.certpath. SunCertPathBuilderException: unable to find valid certification path to requested target</p>	<p><b>Resolution</b></p> <p>Add the system certificate to the trust store using the KeyTool command.</p>
Cluster Installation or Upgrade	<p>When configuring TCPS the following warning can be found in the activemqbroker.log:</p> <p>Do not mention any SSL cipher in the ActiveMQconfig. xml. oracle.net.ns.NetException: Invalid cipher suites specified.</p>	<p><b>Resolution</b></p> <p>Do not mention any SSL cipher in the ActiveMQconfig.xml.</p>
e-Invoice Upgrade: Oracle Add Constraint Error	<p>When you upgrade Sterling e-Invoicing and are using an Oracle database, if the upgrade fails with the error message name is already used by an existing object, this occurs because the default behavior for the drop constraint command changed in Oracle 10.</p>	<p><b>Explanation</b></p> <p>The index that is used to support the constraint is now only removed if the index was generated by the create constraint command. The indexes for Sterling e-Invoicing are always generated from constraints during an install. If you receive this error during a Sterling e-Invoicing upgrade, it is because of how the database was restored, the version of Oracle you are using, and because the Oracle imp command exported the indexes and constraints separately. There is no way to determine when the imp command will not add a create index command to the export file if it was generated by a constraint – but if it does add the command, the database restore process loses the association of the constraint and its underlying index. The database script that runs during a Sterling e-Invoicing upgrade executes two steps: 1. First, it drops the unique constraint so the next step can redefine it using additional columns. However, the drop constraint command does not remove the underlying index if the association with its index was lost. 2. The next command that redefines this constraint requires a different index definition, but in this scenario the name of the index the constraint wants to use already exists, which causes the name is already used by an existing object error.</p> <p><b>Resolution</b></p> <p>If you receive this error message, the solution for this problem is to drop the index and rerun the Sterling e-Invoicing upgrade. The drop index command you should use is: drop index UNQ_EINV_CANON</p>

Situation	Message or Symptom	Explanation/Resolution
Apply a fix pack or Upgrade	<p>The <code>\install_dir\install\installed_data</code> directory is created (if clustered, on each node) during an upgrade or applying a fix pack.</p> <p>This directory can become very large and take up needed space on the file system.</p>	<p><b>Explanation</b></p> <p>The information in this directory is used during upgrade or applying a fix pack, but is not required afterward. The deployment/cleanup tasks for the upgrade or fix pack do not remove this directory.</p> <p><b>Resolution</b></p> <p>The directory can be manually removed to increase the available space for the file system:</p> <ol style="list-style-type: none"> <li>1. Navigate to <code>\install_dir\install</code></li> <li>2. Enter <code>rd /S installed_data</code></li> <li>3. If prompted to confirm deletion, enter Y for yes.</li> </ol>



---

## Notices

This information was developed for products and services offered in the US. This material might be available from IBM in other languages. However, you may be required to own a copy of the product or product version in that language in order to access it.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

*IBM Director of Licensing  
IBM Corporation  
North Castle Drive, MD-NC119  
Armonk, NY 10504-1785  
US*

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

*Intellectual Property Licensing  
Legal and Intellectual Property Law  
IBM Japan Ltd.  
19-21, Nihonbashi-Hakozakicho, Chuo-ku  
Tokyo 103-8510, Japan*

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those

websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you provide in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

*IBM Director of Licensing  
IBM Corporation  
North Castle Drive, MD-NC119  
Armonk, NY 10504-1785  
US*

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

The performance data and client examples cited are presented for illustrative purposes only. Actual performance results may vary depending on specific configurations and operating conditions.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

Statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

All IBM prices shown are IBM's suggested retail prices, are current and are subject to change without notice. Dealer prices may vary.

This information is for planning purposes only. The information herein is subject to change before the products described become available.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

#### COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to

IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work must include a copyright notice as shown in the next column.

© 2015.

Portions of this code are derived from IBM Corp. Sample Programs.

© Copyright IBM Corp. 2015.

---

## Trademarks

IBM, the IBM logo, and [ibm.com](http://ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the web at "Copyright and trademark information" at [www.ibm.com/legal/copytrade.shtml](http://www.ibm.com/legal/copytrade.shtml).

Adobe, the Adobe logo, PostScript, and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

IT Infrastructure Library is a registered trademark of the Central Computer and Telecommunications Agency which is now part of the Office of Government Commerce.

Intel, Intel logo, Intel Inside, Intel Inside logo, Intel Centrino, Intel Centrino logo, Celeron, Intel Xeon, Intel SpeedStep, Itanium, and Pentium are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

ITIL is a registered trademark, and a registered community trademark of the Office of Government Commerce, and is registered in the U.S. Patent and Trademark Office.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Cell Broadband Engine is a trademark of Sony Computer Entertainment, Inc. in the United States, other countries, or both and is used under license therefrom.

Linear Tape-Open, LTO, the LTO Logo, Ultrium and the Ultrium Logo are trademarks of HP, IBM Corp. and Quantum in the U.S. and other countries.

Connect Control Center<sup>®</sup>, Connect:Direct<sup>®</sup>, Connect:Enterprise<sup>®</sup>, Gentran<sup>®</sup>, Gentran<sup>®</sup>:Basic<sup>®</sup>, Gentran:Control<sup>®</sup>, Gentran:Director<sup>®</sup>, Gentran:Plus<sup>®</sup>, Gentran:Realtime<sup>®</sup>, Gentran:Server<sup>®</sup>, Gentran:Viewpoint<sup>®</sup>, Sterling Commerce<sup>™</sup>, Sterling Information Broker<sup>®</sup>, and Sterling Integrator<sup>®</sup> are trademarks or registered trademarks of Sterling Commerce<sup>®</sup>, Inc., an IBM Company.

Other company, product, and service names may be trademarks or service marks of others.

---

## Terms and conditions for product documentation

Permissions for the use of these publications are granted subject to the following terms and conditions.

### Applicability

These terms and conditions are in addition to any terms of use for the IBM website.

### Personal use

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of IBM.

### Commercial use

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of IBM.

### Rights

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.







Product Number:

Printed in USA