

eNetwork Personal Communications Version 4.3  
for Windows® 95, Windows 98, and Windows NT®  
and Version 4.2 for OS/2



# Emulator Programming



eNetwork Personal Communications Version 4.3  
for Windows® 95, Windows 98, and Windows NT®  
and Version 4.2 for OS/2



# Emulator Programming

**Note**

Before using this information and the product it supports, read the information in "Appendix J. Notices" on page 531.

**First Edition (January 1999)**

This edition applies to Version 4.3 of IBM eNetwork Personal Communications and to all subsequent releases and modifications until otherwise indicated in new editions.

© **Copyright International Business Machines Corporation 1989, 1999. All rights reserved.**

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

---

# Contents

Figures . . . . .	xiii
Tables . . . . .	xv
<b>About This Book</b> . . . . .	xvii
Who Should Read This Book . . . . .	xvii
Highlighting Conventions . . . . .	xvii
Related Publications . . . . .	xviii
Notation . . . . .	xix
<b>Chapter 1. Introduction to Emulator APIs</b> . . . . .	1
Cross Platform Support . . . . .	2
Using API Header Files . . . . .	2
Critical Sections . . . . .	3
Stack Size . . . . .	3
Sample Programs . . . . .	3
<b>Chapter 2. Introduction to IBM Standard EHLLAPI, IBM Enhanced EHLLAPI and WinHLLAPI Programming</b> . . . . .	5
EHLLAPI Overviews . . . . .	5
IBM Standard EHLLAPI . . . . .	5
WinHLLAPI . . . . .	5
WinHLLAPI vs. IBM Standard EHLLAPI . . . . .	5
IBM Enhanced EHLLAPI vs. IBM Standard EHLLAPI . . . . .	6
Languages . . . . .	6
EHLLAPI Call Format . . . . .	6
Data Structures . . . . .	7
Memory Allocation . . . . .	8
EHLLAPI Return Codes . . . . .	8
Compiling and Linking . . . . .	9
Static Link Method . . . . .	10
Dynamic Link Method . . . . .	10
Multi-Threading . . . . .	11
Presentation Spaces . . . . .	11
IBM Enhanced 32-bit Interface Presentation Space IDs. . . . .	11
Types of Presentation Spaces . . . . .	12
Size of Presentation Spaces . . . . .	12
Presentation Space IDs . . . . .	12
Host-Connected Presentation Space . . . . .	12
Presentation Space ID Handling . . . . .	13
Sharing EHLLAPI Presentation Space between Processes . . . . .	14
ASCII Mnemonics . . . . .	17
Debugging . . . . .	19
A Simple EHLLAPI Sample Program . . . . .	20
Standard/Enhanced Interface Considerations . . . . .	21
Host Automation Scenarios . . . . .	22
<b>Chapter 3. EHLLAPI Functions</b> . . . . .	27
Page Layout Conventions . . . . .	27
Prerequisite Calls . . . . .	27
Call Parameters . . . . .	27
Return Parameters . . . . .	27
Notes on Using This Function . . . . .	27

Summary of EHLLAPI Functions . . . . .	28
Allocate Communications Buffer (123) . . . . .	29
Change PS Window Name (106) . . . . .	30
Change Switch List LT Name (105) . . . . .	31
Connect for Structured Fields (120) . . . . .	32
Connect Window Services (101) . . . . .	34
Connect Presentation Space (1) . . . . .	35
Convert Position or Convert RowCol (99) . . . . .	37
Copy Field to String (34) . . . . .	39
Copy OIA (13) . . . . .	44
Copy Presentation Space (5) . . . . .	52
Copy Presentation Space to String (8) . . . . .	57
Copy String to Field (33) . . . . .	62
Copy String to Presentation Space (15) . . . . .	64
Disconnect from Structured Fields (121) . . . . .	67
Disconnect Window Service (102) . . . . .	68
Disconnect Presentation Space (2) . . . . .	68
Find Field Length (32) . . . . .	69
Find Field Position (31) . . . . .	71
Free Communications Buffer (124) . . . . .	72
Get Key (51) . . . . .	73
Get Request Completion (125) . . . . .	76
Lock Presentation Space API (60) . . . . .	78
Lock Window Services API (61) . . . . .	80
Pause (18) . . . . .	81
Post Intercept Status (52) . . . . .	83
Query Close Intercept (42) . . . . .	83
Query Communications Buffer Size (122) . . . . .	84
Query Cursor Location (7) . . . . .	86
Query Field Attribute (14) . . . . .	86
Query Host Update (24) . . . . .	88
Query Window Coordinates (103) . . . . .	89
Query Session Status (22) . . . . .	91
Query Sessions (10) . . . . .	92
Query System (20) . . . . .	94
Read Structured Fields (126) . . . . .	95
Receive File (91) . . . . .	100
Release (12) . . . . .	102
Reserve (11) . . . . .	103
Reset System (21) . . . . .	103
Search Field (30) . . . . .	104
Search Presentation Space (6) . . . . .	106
Send File (90) . . . . .	108
Send Key (3) . . . . .	110
Set Cursor (40) . . . . .	118
Set Session Parameters (9) . . . . .	119
Start Close Intercept (41) . . . . .	127
Start Host Notification (23) . . . . .	129
Start Keystroke Intercept (50) . . . . .	132
Start Playing Macro (110) . . . . .	134
Stop Close Intercept (43) . . . . .	135
Stop Host Notification (25) . . . . .	136
Stop Keystroke Intercept (53) . . . . .	136
Wait (4) . . . . .	137
Window Status (104) . . . . .	138
Write Structured Fields (127) . . . . .	141

<b>Chapter 4. WinHLLAPI Extension Functions</b>	147
Summary of WinHLLAPI Functions	147
WinHLLAPI Asynchronous Functions	147
WinHLLAPIAsync	147
WinHLLAPICancelAsyncRequest	153
Initialization/Termination Functions	154
WinHLLAPI Startup	154
WinHLLAPI Cleanup	155
Blocking Routines	155
WinHLLAPIIsBlocking	155
WinHLLAPISetBlockingHook	156
WinHLLAPIUnhookBlockingHook	156
WinHLLAPICancelBlockingCall	157
<b>Chapter 5. PCSAPI Functions</b>	159
How to Use PCSAPI	159
Page Layout Conventions	159
Function Type	159
Parameter Type and Description	159
Return Code	159
pcsConnect Session	160
pcsDisconnect Session	160
pcsQueryEmulatorStatus	161
pcsQuerySessionList	161
pcsQueryWorkstationProfile	163
pcsSetLinkTimeout	164
pcsStartSession	164
pcsStopSession	165
<b>Chapter 6. DDE Functions for Windows and OS/2</b>	167
DDE Functions in a Windows 32-Bit Environment	167
Personal Communications DDE Data Items	167
DDE Functions	169
Find Field	172
Get Keystrokes	174
Get Mouse Input	175
Get Number of Close Requests	178
Get Operator Information Area	179
Get Partial Presentation Space	180
Get Presentation Space	182
Get Session Status	184
Get System Configuration	186
Get System Formats	187
Get System Status	187
Get System SysItems	188
Get System Topics	189
Get Trim Rectangle	190
Initiate Session Conversation	190
Initiate Structured Field Conversation	191
Initiate System Conversation	192
Put Data to Presentation Space	192
Search for String	193
Send Keystrokes	194
Session Execute Macro	196
Set Cursor Position	203
Set Mouse Intercept Condition	204

Set Presentation Space Service Condition . . . . .	207
Set Session Advise Condition . . . . .	208
Set Structured Field Service Condition . . . . .	209
Start Close Intercept . . . . .	210
Start Keystroke Intercept . . . . .	211
Start Mouse Input Intercept . . . . .	212
Start Read SF . . . . .	215
Start Session Advise . . . . .	217
Stop Close Intercept . . . . .	218
Stop Keystroke Intercept . . . . .	219
Stop Mouse Input Intercept . . . . .	219
Stop Read SF . . . . .	220
Stop Session Advise . . . . .	220
Terminate Session Conversation . . . . .	221
Terminate Structured Field Conversation . . . . .	221
Terminate System Conversation . . . . .	222
Write SF . . . . .	222
DDE Menu Item API in a Windows 32-Bit Environment . . . . .	223
DDE Menu Functions in a Windows 32-Bit Environment . . . . .	225
DDE Functions in an OS/2 Environment . . . . .	244
Personal Communications DDE Data Items (OS/2) . . . . .	244
DDE Functions . . . . .	246
Find Field . . . . .	249
Get Keystrokes . . . . .	251
Get Mouse Input . . . . .	253
Get Number of Close Requests . . . . .	256
Get Operator Information Area . . . . .	257
Get Partial Presentation Space . . . . .	258
Get Presentation Space . . . . .	260
Get Session Status . . . . .	262
Get System Configuration . . . . .	264
Get System Formats . . . . .	265
Get System Status . . . . .	266
Get System SysItems . . . . .	267
Get System Topics . . . . .	268
Get Trim Rectangle . . . . .	269
Initiate Session Conversation . . . . .	270
Initiate Structured Field Conversation . . . . .	271
Initiate System Conversation . . . . .	271
Put Data to Presentation Space . . . . .	272
Search for String . . . . .	273
Send Keystrokes . . . . .	274
Session Execute Macro . . . . .	275
Set Cursor Position . . . . .	282
Set Mouse Intercept Condition . . . . .	283
Set Presentation Space Service Condition . . . . .	286
Set Session Advise Condition . . . . .	287
Set Structured Field Service Condition . . . . .	288
Start Close Intercept . . . . .	289
Start Keystroke Intercept . . . . .	291
Start Mouse Input Intercept . . . . .	292
Start Read SF . . . . .	295
Start Session Advise . . . . .	296
Stop Close Intercept . . . . .	297
Stop Keystroke Intercept . . . . .	298
Stop Mouse Input Intercept . . . . .	299



Stop Read SF . . . . .	300
Stop Session Advise . . . . .	300
Terminate Session Conversation . . . . .	301
Terminate Structured Field Conversation . . . . .	302
Terminate System Conversation . . . . .	302
Write SF . . . . .	302
DDE Menu Item API in OS/2 Environment . . . . .	303
DDE Menu Functions . . . . .	305
<b>Chapter 7. Using DDE Functions with a DDE Client Application . . . . .</b>	<b>325</b>
Using the Personal Communications DDE Interface . . . . .	325
System Conversation . . . . .	326
Session Conversation . . . . .	326
Session Conversation (Hot Link) . . . . .	328
Personal Communications DDE Interface . . . . .	329
DDE Functions for System Conversation . . . . .	330
Get System Configuration . . . . .	330
Get System Formats . . . . .	330
Get System Status . . . . .	330
Get System Systems . . . . .	331
Get System Topics . . . . .	331
Initiate System Conversation . . . . .	332
Terminate System Conversation . . . . .	332
DDE Functions for Session Conversation . . . . .	332
Find Field . . . . .	332
Get Operator Information Area . . . . .	334
Get Partial Presentation Space . . . . .	335
Get Presentation Space . . . . .	335
Get Session Status . . . . .	336
Get Trim Rectangle . . . . .	336
Initiate Session Conversation . . . . .	337
Put Data to Presentation Space . . . . .	337
Search for String . . . . .	338
Session Execute Macro . . . . .	339
Set Cursor Position . . . . .	339
Terminate Session Conversation . . . . .	340
DDE Functions for Session Conversation (Hot Link) . . . . .	340
Initiate Session Conversation . . . . .	340
Start Close Intercept . . . . .	340
Start Keystroke Intercept . . . . .	341
Start Session Advise . . . . .	342
Stop Close Intercept . . . . .	343
Stop Keystroke Intercept . . . . .	343
Stop Session Advise . . . . .	344
Terminate Session Conversation . . . . .	344
Visual Basic Sample Program . . . . .	344
<b>Chapter 8. Server-Requester Programming Interface (SRPI) Support . . . . .</b>	<b>357</b>
How to Use SRPI . . . . .	357
SRPI Compatibility . . . . .	357
Using the Server-Requester Programming Interface . . . . .	358
SEND_REQUEST Parameters . . . . .	360
Supplied Parameters . . . . .	361
Returned Parameters . . . . .	362
How PC/3270 Applications Use SRPI . . . . .	363
Invoking SEND_REQUEST . . . . .	363

Performance Considerations . . . . .	363
Handling the Interrupt (Ctrl+Break) Key . . . . .	364
C Requesters . . . . .	364
C send_request Function. . . . .	364
SRPI Record Definition . . . . .	365
SRPI Return Codes. . . . .	365
<b>Appendix A. Query Reply Data Structures Supported by EHLLAPI . . . . .</b>	<b>367</b>
The DDM Query Reply . . . . .	367
DDM Application Name Self-Defining Parameter . . . . .	368
PCLK protocol controls Self-Defining Parameter . . . . .	368
Base DDM Query Reply Formats . . . . .	368
The IBM Auxiliary Device Query Reply . . . . .	370
Direct Access Self-Defining Parameter . . . . .	371
PCLK Protocol Controls Self-Defining Parameter . . . . .	372
The OEM Auxiliary Device Query Reply . . . . .	372
Direct Access Self-Defining Parameter . . . . .	373
PCLK Protocol Controls Self-Defining Parameter . . . . .	373
The Cooperative Processing Requester Query Reply . . . . .	373
The Product-Defined Query Reply . . . . .	374
Optional Parameters . . . . .	374
Direct Access Self-Defining Parameter . . . . .	375
The Document Interchange Architecture Query Reply . . . . .	376
Direct Access Self-Defining Parameter . . . . .	376
<b>Appendix B. Compatibility with Personal Communications 4.1 for Windows 3.1 . . . . .</b>	<b>379</b>
<b>Appendix C. Compatibility with Communications Manager/2 . . . . .</b>	<b>381</b>
Set Session Parameter (9) . . . . .	381
Set Options. . . . .	381
Return Parameters . . . . .	381
EAB Option. . . . .	381
Copy OIA (13). . . . .	382
Copy String to PS (15). . . . .	382
Storage Manager (17) . . . . .	383
Copy String to Field (33) . . . . .	383
Get Key (51) . . . . .	383
Window Status (104) . . . . .	383
Query Sessions (10) . . . . .	383
Connect for Structured Fields (120) . . . . .	383
Allocate Communications Buffer (123) . . . . .	384
ASCII Mnemonics . . . . .	384
Get Request Completion (125). . . . .	384
<b>Appendix D. DOS-Mode EHLLAPI (Windows 95, Windows 98, and Windows NT) . . . . .</b>	<b>385</b>
Installation . . . . .	385
Compatibility . . . . .	385
<b>Appendix E. DOS-Mode EHLLAPI (OS/2) . . . . .</b>	<b>387</b>
Installation . . . . .	387
Installation of the DOS-Mode EHLLAPI Virtual Device Driver. . . . .	387
Installation of the PC/3270-5250-Windows Interface Module. . . . .	387
How to Use DOS-Mode EHLLAPI Applications . . . . .	387
Compatibility . . . . .	388

<b>Appendix F. SRPI Return Codes</b>	389
Error Handling	389
Transport Layer Errors	389
Application Errors	389
SEND_REQUEST Processing Errors	389
Types of SRPI Return Codes	389
Type 0 Return Code Definitions	390
Type 1 Return Code Definitions	390
Type 2 Return Code Definitions	393
Type 3 Return Code Definitions	393
Class Definitions for Type 2 and Type 3	393
Exception Code Values for Type 2 and Type 3	394
Exception Object Values for Type 2 and Type 3	395
Server Return Codes	395
<b>Appendix G. DDE Functions in a 16-Bit Environment</b>	397
Personal Communications DDE Data Items in a 16-Bit Environment	397
Using System Topic Data Items	398
Using Session Topic Data Items	398
Using LU Topic Data Items (PC/3270 Only)	398
DDE Functions in a 16-Bit Environment	398
Naming Conventions for Parameters	399
Find Field	400
Get Keystrokes	401
Get Mouse Input	402
Get Number of Close Requests	405
Get Operator Information Area	406
Get Partial Presentation Space	406
Get Presentation Space	409
Get Session Status	411
Get System Configuration	412
Get System Formats	413
Get System Status	414
Get System SysItems	415
Get System Topics	416
Get Trim Rectangle	416
Initiate Session Conversation	417
Initiate Structured Field Conversation	418
Initiate System Conversation	418
Put Data to Presentation Space	419
Search for String	420
Send Keystrokes	421
Session Execute Macro	422
Set Cursor Position	428
Set Mouse Intercept Condition	429
Set Presentation Space Service Condition	431
Set Session Advise Condition	433
Set Structured Field Service Condition	434
Start Close Intercept	434
Start Keystroke Intercept	436
Start Mouse Input Intercept	437
Start Read SF	441
Start Session Advise	442
Stop Close Intercept	443
Stop Keystroke Intercept	444
Stop Mouse Input Intercept	444

Stop Read SF . . . . .	445
Stop Session Advise . . . . .	446
Terminate Session Conversation . . . . .	446
Terminate Structured Field Conversation . . . . .	447
Terminate System Conversation . . . . .	447
Write SF . . . . .	448
Summary of DDE Functions in a 16-Bit Environment . . . . .	448
DDE Menu Item API in a 16-Bit Environment . . . . .	453
DDE Menu Client in a 16-Bit Environment . . . . .	453
DDE Menu Server, 32-Bit. . . . .	454
DDE Menu Functions in a 16-bit Environment . . . . .	455
Change Menu Item . . . . .	456
Create Menu Item . . . . .	461
Initiate Menu Conversation . . . . .	462
Start Menu Advise . . . . .	463
Stop Menu Advise . . . . .	464
Terminate Menu Conversation . . . . .	464
<b>Appendix H. REXX EHLLAPI Functions.</b> . . . . .	467
Overview of REXX EHLLAPI Function Calls and Return Values. . . . .	467
Installation . . . . .	467
Conventions . . . . .	467
Summary of Prerequisite Calls for Functions . . . . .	468
Summary of EHLLAPI and REXX EHLLAPI Functions . . . . .	470
Change_Switch_Name. . . . .	472
Change_Window_Name . . . . .	473
Connect . . . . .	474
Connect_PM . . . . .	475
Convert_Pos . . . . .	476
Copy_Field_To_Str . . . . .	477
Copy_OIA . . . . .	478
Copy_PS . . . . .	479
Copy_PS_To_Str. . . . .	480
Copy_Str_To_Field . . . . .	481
Copy_Str_To_PS. . . . .	482
Disconnect . . . . .	483
Disconnect_PM . . . . .	484
Find_Field_Len . . . . .	485
Find_Field_Pos . . . . .	486
Get_Key . . . . .	487
Get_Window_Status . . . . .	488
Intercept_Status . . . . .	489
Lock_PMSVC . . . . .	490
Lock_PS. . . . .	491
Pause. . . . .	492
Query_Close_Intercept . . . . .	493
Query_Cursor_Pos . . . . .	494
Query_Emulator_Status . . . . .	495
Query_Field_Attr . . . . .	496
Query_Host_Update . . . . .	497
Query_Session_List. . . . .	498
Query_Session_Status . . . . .	499
Query_Sessions . . . . .	501
Query_System. . . . .	502
Query_Window_Coord. . . . .	503
Query_Workstation_Profile . . . . .	504

Receive_File . . . . .	505
Release . . . . .	506
Reserve . . . . .	507
Reset_System. . . . .	508
Search_Field . . . . .	509
Search_PS . . . . .	510
Send_File . . . . .	511
Sendkey . . . . .	512
Set_Cursor_Pos . . . . .	513
Set_Session_Parms . . . . .	514
Set_Window_Status. . . . .	515
Start_Close_Intercept . . . . .	516
Start_Communication . . . . .	517
Start_Host_Notify . . . . .	518
Start_Keystroke_Intercept . . . . .	519
Start_Session . . . . .	520
Stop_Close_Intercept . . . . .	521
Stop_Communication . . . . .	522
Stop_Host_Notify. . . . .	523
Stop_Keystroke_Intercept . . . . .	524
Stop_Session . . . . .	525
Wait . . . . .	526
Programming Notes. . . . .	527
Sample Programs . . . . .	527
<b>Appendix I. Trademarks.</b> . . . . .	<b>529</b>
<b>Appendix J. Notices</b> . . . . .	<b>531</b>
<b>Glossary</b> . . . . .	<b>533</b>
<b>Index</b> . . . . .	<b>549</b>
<b>Readers' Comments — We'd Like to Hear from You.</b> . . . . .	<b>557</b>



---

# Figures

1. Keystroke Flow . . . . .	25
2. Host Presentation Space Characters. . . . .	46
3. DDE Menu Server Conversation . . . . .	224
4. DDE Menu Client Conversation . . . . .	225
5. DDE Menu Server Conversation . . . . .	304
6. DDE Menu Client Conversation . . . . .	305
7. Example of PC/3270 SRPI Requester and Server . . . . .	358
8. IBM Workstation Requester and IBM Host Computer Server Relationship	359
9. Example of an SRPI Requester and Server Flow . . . . .	360
10. DDE Menu Server Conversation . . . . .	453
11. DDE Menu Client Conversation . . . . .	455





## Tables

1. Emulator API Support . . . . .	2
2. EHLLAPI Read and Write Sharing Option Combinations . . . . .	15
3. Prerequisite Functions and Associated Dependent Functions . . . . .	16
4. Mnemonics with Uppercase Alphabetic Characters . . . . .	112
5. Mnemonics with Numbers or Lowercase Characters . . . . .	112
6. Mnemonics with @A and @ Uppercase Alphabetic Characters . . . . .	113
7. Mnemonics with @A and @ Lowercase Alphabetic Characters . . . . .	114
8. Mnemonics with @A and @ Alphanumeric (Special) Characters. . . . .	114
9. Mnemonics with @S (Shift) and @ Alphabetic Characters . . . . .	115
10. Mnemonics Using @X and @Alphabetic Lowercase (For DBCS Only) . . . . .	115
11. Mnemonics Using @M, @Q and @Alphabetic Lowercase (For VT Only) . . . . .	115
12. Mnemonics with Special Character Keys . . . . .	118
13. Naming Scheme for Data Items . . . . .	167
14. Applications for Personal Communications . . . . .	167
15. Topics for Personal Communications. . . . .	168
16. SENDKEY Command List. . . . .	198
17. DDE Function Summary in a Windows 32-Bit Environment . . . . .	236
18. Naming Scheme for Data Items (OS/2). . . . .	244
19. Application for Personal Communications . . . . .	245
20. Topics for Personal Communications. . . . .	245
21. SENDKEY Command List. . . . .	278
22. DDE Function Summary in an OS/2 Environment . . . . .	316
23. Naming Scheme for Data Items . . . . .	325
24. Topics for Personal Communications. . . . .	325
25. Parameters Supplied by the SRPI Requester . . . . .	361
26. Parameters Returned to the SRPI Requester . . . . .	362
27. DDM Query Reply Base Format . . . . .	367
28. DDM Application Name Self-Defining Parameter . . . . .	368
29. DDM PCLK Auxiliary Device Self-Defining Parameter . . . . .	368
30. Base DDM Query Reply Format with Name and Direct Access Self-Defining Parameters . . . . .	368
31. Base DDM Query Reply Format with Direct Access and Name Self-Defining Parameters . . . . .	369
32. IBM Auxiliary Device Base Format with Direct Access Self-Defining Parameter . . . . .	370
33. IBM Auxiliary Device Direct Access Self-Defining Parameter . . . . .	371
34. IBM Auxiliary Device PCLK Self-Defining Parameter . . . . .	372
35. OEM Auxiliary Device Base Format with Direct Access Self-Defining Parameter . . . . .	372
36. OEM Auxiliary Device Direct Access Self-Defining Parameter. . . . .	373
37. IBM Auxiliary Device PCLK Self-Defining Parameter . . . . .	373
38. CPR Query Reply Buffer Format . . . . .	373
39. IBM Product-Defined Query Reply Base Format . . . . .	374
40. Valid REFID and SSID Values for the IBM Product-Defined Query Reply . . . . .	375
41. IBM Product-Defined Direct Access Self-Defining Parameter . . . . .	375
42. IBM DIA Base Format . . . . .	376
43. IBM Product-Defined Direct Access Self-Defining Parameter . . . . .	376
44. Type 1 Return Code Definitions and Descriptions . . . . .	390
45. Type 3 Return Code Definitions and Descriptions . . . . .	393
46. Class Definitions for Type 2 and Type 3 . . . . .	394
47. Exception Code Values for Type 2 and Type 3 . . . . .	394
48. Exception Object Values for Type 2 and Type 3. . . . .	395
49. Naming Scheme for Data Items . . . . .	397

50. Applications for Personal Communications . . . . .	397
51. Topics for Personal Communications. . . . .	397
52. SENDKEY Command List. . . . .	424
53. Summary of DDE Functions in a 16-Bit Environment. . . . .	448
54. Prerequisite Calls for Functions . . . . .	468
55. EHLLAPI and REXX EHLLAPI Functions . . . . .	470

---

## About This Book

This book provides necessary programming information for you to use the IBM Personal Communications and the IBM Personal Communications AS/400 for Windows 95, Windows 98, Windows NT, and OS/2, Emulator High-Level Language Application Program Interface (EHLLAPI), Dynamic Data Exchange (DDE), Personal Communications Session API (PCSAPI), and Server-Requester Programming Interface (SRPI). The Host Access Class Library is described in *eNetwork Personal Communications Version 4.3 Host Access Class Library*.

EHLLAPI/DDE/PCSAPI is used with Personal Communications to provide a way for users and programmers to access the host presentation space with a set of functions that can be called from an application program running in a workstation session.

If you want only to get started using Personal Communications or have no interest in using the programming interface, see the *Personal Communications Version 4.3 for Windows 95, Windows 98, and Windows NT Quick Beginnings* or the *Personal Communications Version 4.2 for OS/2 Quick Beginnings*.

In this book, Windows\*\* refers to Windows 95, Windows 98, or Windows NT\*\*. When information is specific to only Windows 95, Windows 98, or Windows NT, this will be indicated in the text.

---

## Who Should Read This Book

This book is intended for programmers who write application programs that use the APIs documented in this book.

A working knowledge of Windows or OS/2 is assumed. For information about Windows and OS/2, refer to the list of publications under "Related Publications" on page xviii .

The programmer must also be familiar with connecting to a host system from a terminal or from a workstation with terminal emulation software.

This book assumes you are familiar with the language and the compiler that you are using. For information on how to write, compile, or link-edit programs, refer to Related Publications for the appropriate references for the specific language you are using.

---

## Highlighting Conventions

Highlighting refers to different type styles used within text to show certain kinds of information. Type styles other than the standard body text font that are used in this manual are shown along with a description of the kind of information that each different type style is used for.

**Type Style**  
ROMAN CAPS

**Emphasized Information**  
ROMAN CAPS are used for commands, keywords, or other information that the programmer is to type in literally. keyword highlighting command highlighting. This type style is not used in lengthy sample program listings.

<b>Type Style</b>	<b>Emphasized Information</b>
<b>Bold</b>	A <b>Bold</b> type style (Initial Caps) is used for EHLLAPI function names. Keep in mind that these names are labels used to refer to the function. They are not used <i>in</i> an application to <i>call</i> an EHLLAPI function; the <i>function number</i> parameter is used to specify which EHLLAPI function is to be performed. See Chapter 3. EHLLAPI Functions.
<i>Italics</i>	When <i>italics</i> or <b><i>bold italics</i></b> appear in text, either a term is being used for the first time or the meaning implied by the word is being stressed.
<b>Bold Monospace</b>	<b>Bold monospace</b> type indicates file and directory names. It is also used for programmable keywords.
<i>Italic Monospace</i>	<i>Italic monospace</i> type indicates variables for placeholders, parameters, and file names. When you enter a command, replace all variables with the appropriate file name, number, or option. On an example display screen, nonitalic regular monospace type indicates a variable quantity other than a default value.
Monospace	Monospace type is used in the following situations: <ul style="list-style-type: none"> <li>• In sample code listings of more than a few lines.</li> <li>• As options for link or compile commands.</li> <li>• For names of session options set by the <b>Set Session Parameters</b> (9) function. See “Set Session Parameters (9)” on page 119 .</li> <li>• For ASCII mnemonics in text.</li> <li>• For displayed information.</li> <li>• For input from either a programmer or an operator.</li> </ul>

---

## Related Publications

Following is a list of related publications:

- *eNetwork Personal Communications Version 4.3 Quick Beginnings*, SC31-8679
- *eNetwork Personal Communications Version 4.3 Reference, Volume I and Volume II* , SC31-8680 and SC31-8682
- *eNetwork Personal Communications Version 4.3 System Management Programming* , SC31-8480
- *eNetwork Personal Communications Version 4.3 Client/Server Programming* , SC31-8479
- *eNetwork Personal Communications Version 4.3 Configuration File Reference* , SC31-8655
- *eNetwork Personal Communications Version 4.3 Host Access Class Library* , SC31-8685
- *eNetwork Personal Communications Version 4.2 for OS/2 Quick Beginnings*, SC31-8258
- *eNetwork Personal Communications Version 4.2 for OS/2 Reference*, SC31-8259
- *IBM 3270 Information Display System Data Stream Programmer's Reference* , GA23-0059
- *IBM 5250 Information Display System Functions Reference Manual* , SA21-9247

---

## Notation

A table at the beginning of each section explains API or DDE functions in Chapter 3. EHLLAPI Functions, Chapter 5. PCSAPI Functions, Chapter 6. DDE Functions for Windows and OS/2, and Appendix G. DDE Functions in a 16-Bit Environment. It shows whether a function is supported for the products that provide the function described in the section. 'Yes' means it is supported for a host type, and 'No' means not supported. For example, the following table indicates that a function is available for 3270 and VT sessions but not for 5250 sessions.

<i>3270</i>	<i>5250</i>	<i>VT</i>
Yes	No	Yes



---

## Chapter 1. Introduction to Emulator APIs

The IBM eNetwork Personal Communications product supplies several application programming interfaces (APIs). Each interface has a specific set of functions and may be used for different purposes. Choose the programming interface that best matches the functional requirements of your application. Some applications may use more than one interface to achieve the desired results. The programming interfaces are:

- **Emulator High Level Language API (EHLLAPI):** This interface provides functions to access emulator "presentation space" data such as characters on the host screen. It also provides functions for sending keystrokes to the host, intercepting user-entered keystrokes, querying the status of the host session, uploading and downloading files, and other functions. This interface is often used for 'automated operator' applications which read host screens and enter keystrokes without direct user intervention. See "Chapter 3. EHLLAPI Functions" on page 27.
  - **IBM Standard HLLAPI Support:** This is a standard programming interface which allows programmatic access to a host emulator session. See "Chapter 2. Introduction to IBM Standard EHLLAPI, IBM Enhanced EHLLAPI and WinHLLAPI Programming" on page 5.
  - **IBM Enhanced HLLAPI Support:** This interface is based on the IBM Standard HLLAPI interface. It provides all of the existing functionality but uses modified data structures. See "Chapter 2. Introduction to IBM Standard EHLLAPI, IBM Enhanced EHLLAPI and WinHLLAPI Programming" on page 5.
  - **Windows High Level Language API (WinHLLAPI):** This interface provides much of the same functionality of IBM Standard EHLLAPI and adds some extensions that take advantage of the Windows environment. See "Chapter 2. Introduction to IBM Standard EHLLAPI, IBM Enhanced EHLLAPI and WinHLLAPI Programming" on page 5.
  - **REXX EHLLAPI:** This allows programmers who are using EHLLAPI to write REXX language application programs.
- **Dynamic Data Exchange (DDE):** This interface is similar to the EHLLAPI interface in that it provides a programmable means to read the host screen, send keystrokes, and perform related functions. It has some additional functions for access to the emulator clipping rectangle, intercepting mouse events, and adding/removing commands on the emulator menu bar. See "Chapter 6. DDE Functions for Windows and OS/2" on page 167.
- **Personal Communications Session API (PCSAPI):** This interface is used to start, stop, and control emulator sessions. See "Chapter 5. PCSAPI Functions" on page 159 .
- **Server-Requestor Programming Interface (SRPI):** This interface is used in cooperation with an IBM Enhanced Connectivity Facility (ECF) application running on a host system. This API provides functions for writing synchronous call-return interfaces to remote server programs. See "Chapter 8. Server-Requestor Programming Interface (SRPI) Support" on page 357.
- **IBM eNetwork Personal Communications Host Access Class Library (ECL):** ECL is a set of objects that allow application programmers and scripting language writers to access host applications easily and quickly. Personal Communications supports three different ECL layers (C++ objects, ActiveAutomation (OLE), and LotusScript Extension (LSX)). Refer to *Personal Communications Version 4.3 Host Access Class Library* for more details.

---

## Cross Platform Support

The emulator programming interfaces are provided across a variety of workstation platforms. On some platforms 16- and 32-bit interfaces may be provided. Note that support for emulator APIs on a particular platform requires a licensed copy of IBM Personal Communications for that platform.

The following table shows the emulator API support on various platforms:

Table 1. Emulator API Support

Supported PCOM Emulator APIs	PCOM DOS	PCOM OS/2	PCOM Windows 3.1	PCOM Windows 95, 98 & NT
IBM Standard EHLLAPI (16-bit)	Yes	Yes	Yes	Yes
IBM Standard EHLLAPI (32-bit)				Yes
IBM Standard EHLLAPI (DOS-mode)*		Yes	Yes	Yes
IBM Enhanced EHLLAPI (DOS-mode)*		Yes		Yes
EHLLAPI (WinOS/2-mode)**		Yes		
WinHLLAPI (16-bit)				Yes
WinHLLAPI (32-bit)				Yes
PCSAPI (16-bit)			Yes	Yes
PCSAPI (32-bit)		Yes		Yes
DDE (16-bit)		Yes	Yes	Yes
DDE (32-bit)		Yes		Yes
DDE (WinOS/2-mode)**		Yes		
SRPI (16-bit)		Yes	Yes	Yes
SRPI (32-bit)		Yes		Yes
Host Access Class Library				Yes
REXX		Yes		Yes

### Notes:

1. \* DOS-mode is support for DOS applications in a DOS-compatibility mode of the operating system; for example the DOS emulation window of OS/2.
2. \*\* WinOS2-mode is support for 16-bit Windows applications in a Win-OS2 session on OS/2 using the Personal Communications for OS/2 product.

---

## Using API Header Files

The application program should include operating system header files before including API header files. For example:

```
#include <windows.h>      // Windows main header
#include "pcsapi.h"      // PComm PCSAPI header
...
```



---

## Critical Sections

Use critical sections (Windows **EnterCriticalSection** function, OS/2 **DosEnterCritSec**) carefully when your program calls emulator APIs. Do not make emulator API calls within a critical section. If one thread of an application establishes a critical section and another thread is within an emulator API call, the call is suspended until you exit from the critical section.

During processing of an API call, all signals (except numeric coprocessor signals) are delayed until the call completes or until the call needs to wait for incoming data. Also, **TerminateProcess** issued from another process is held until the application completes an API call it might be processing.

---

## Stack Size

Emulator APIs use the calling program's stack when they are executed. The operating system, the application, and the API all require stack space for dynamic variables and function parameters. At least 8196 bytes (8K) of stack space should be available at the time of an API call. It is the responsibility of the application program to ensure sufficient stack space is available for the API.

---

## Sample Programs

Several sample programs are provided, each of which illustrates the use of one of the Personal Communications APIs. If you choose to install the sample programs, they will be installed in the default directory: \SAMPLES for Windows, or \SDK\SAMPLES for OS/2.

**Note:** International Business Machines Corporation provides these files "as is," without warranty of any kind, either express or implied, including, but not limited to, the implied warranties of merchantability or fitness for a particular purpose.

The sample program files include source and supporting files for the following Personal Communications Version 4.3 for Windows 95, Windows 98, and Windows NT APIs:

- Emulator High-Level Language Programming Interface (EHLLAPI)
- Dynamic Data Exchange (DDE)
- Server-Requester Programming Interface (SRPI)
- PCSAPI Functions

The following files will be installed in the \SAMPLES directory for Windows, or the \SDK\SAMPLES directory for OS/2:

File Name	Description
DDE_C.H	DDE include file
EHLAPI32.H	IBM standard 32-bit EHLLAPI include file
WHLLAPI.H	WinHLLAPI 16-bit include file
HAPI_C.H	EHLLAPI include file
PCSAPI.H	PCSAPI include file
PCSCALLS.LIB	Import library for standard interface
PCSCAL32.LIB	Import library for enhanced interface
EHLAPI32.LIB	Import library for IBM Standard 32-bit EHLLAPI interface

<b>File Name</b>	<b>Description</b>
<b>WHLLAPI.LIB</b>	Import library for WinHLLAPI 16-bit interface
<b>WHLAPI32.LIB</b>	Import library for WinHLLAPI 32-bit interface
<b>UUC CPRB.H</b>	SRPI include file

The following subdirectories will be created in the \SAMPLES directory for Windows, or \SDK\SAMPLES directory for OS/2:

<b>File Name</b>	<b>Description</b>
<b>DDXFER</b>	Shows how EHLLAPI can be used to create a "Drag and Drop" application; in this case, for file transfer
<b>ECL</b>	HACL sample files
<b>HLLSMP</b>	Shows how to use EHLLAPI to request a keystroke and log on to a VM system
<b>LISTFILE</b>	Illustrates how DDE can make use of the LOAD button to transfer files from the host
<b>PCSMAN</b>	Illustrates the use of PCSAPI to start and stop sessions, query the session status, and query the profile for the session
<b>SPL2FILE</b>	A program that uses DDE to save an AS/400 spool file as an ASCII file on the PC
<b>SRPSMP</b>	Illustrates the use of the Server Requester Programming Interface (SRPI)
<b>VBDDE</b>	VBDDE sample files
<b>VBHLLAPI</b>	VBHLLAPI sample files
<b>VBPCSAPI</b>	VBPCSAPI sample files

---

## Chapter 2. Introduction to IBM Standard EHLLAPI, IBM Enhanced EHLLAPI and WinHLLAPI Programming

This chapter provides information needed to incorporate IBM Standard EHLLAPI (16- and 32-bit), WinHLLAPI (16- and 32-bit), and IBM Enhanced 32-bit EHLLAPI (EHLAPI32) functions into applications written in a high level language. It provides details on call format, memory allocation considerations, initializing the interfaces, and compiling and linking applications. Also included is a short sample EHLLAPI program and the compile/link instructions used to build it. Finally, a set of possible uses for the EHLLAPI interface (scenarios) is described.

An "EHLLAPI application" is any application program which uses the EHLLAPI interface to access the host 3270/5250/VT presentation space. The presentation space includes the visible emulator character data, fields and attribute data, keystroke data, and other information.

---

### EHLLAPI Overviews

Following are overviews for HLLAPI programming interfaces.

#### IBM Standard EHLLAPI

EHLLAPI is a standard programming interface which allows programmatic access to a host emulator session. Functions are provided for reading host screen data (such as the characters and attributes), for sending keystrokes, and performing other emulator-related functions.

The EHLLAPI interface is a single call-point interface. There is a single callable API through which all EHLLAPI functions are requested. On each call to the interface the application provides a function number which identifies the function requested, a pointer to a data buffer, a pointer to the length of the data buffer, and a pointer to a return code (see "EHLLAPI Call Format" on page 6).

#### WinHLLAPI

WinHLLAPI is based on the familiar EHLLAPI.API. It encompasses all of the existing functionality and adds extensions that take advantage of the Windows message driven environment. Users of the IBM Personal Communications EHLLAPI interface will notice no functional difference unless they incorporate the WinHLLAPI extensions.

The WinHLLAPI extension functions and any functions that deviate from the EHLLAPI form are described in "Chapter 4. WinHLLAPI Extension Functions" on page 147 . For information on common functions, refer to "Chapter 3. EHLLAPI Functions" on page 27.

#### WinHLLAPI vs. IBM Standard EHLLAPI

The entry symbol for WinHLLAPI, is appropriately, **WinHLLAPI**. EHLLAPI users wishing to switch to the WinHLLAPI implementation must change from the **hllapi**

standard entry. New users should follow all of the directions in “Chapter 3. EHLLAPI Functions” on page 27, and use the **WinHLLAPI** entry in place of the standard **hllapi** entry.

## IBM Enhanced EHLLAPI vs. IBM Standard EHLLAPI

IBM Enhanced EHLLAPI is based on the familiar EHLLAPI API. It encompasses all of the existing data functionality but takes advantage of the 32-bit environment and uses modified data structures. Standard interface users wishing to switch to IBM Enhanced 32-bit EHLLAPI need to change only the entry symbol from LPWORD to LPINT in the first, third, and fourth parameters. New users should use the procedures in the following sections.

---

## Languages

Any programming language which can invoke an entry point in a DLL with the “Pascal” calling convention can be used to execute EHLLAPI functions. However, the Personal Communications EHLLAPI toolkit provides header files and function prototypes only for the C++ languages. A clear understanding of data structure layout and calling conventions is required to use any other language. The EHLLAPI toolkit supports the following C/C++ compilers:

- IBM Visual Age for C/C++ for (Windows and OS/2)
- Microsoft Visual C/C++ Version 4.0 (Windows)

Most other C/C++ compilers will also work with the toolkit.

EHLLAPI C/C++ applications must include the Personal Communications EHLLAPI header file (HAPI\_C.H). This file defines the layout of data structures and provides a prototype for the EHLLAPI entry point.

**Note:** The data structure layout for 16- and 32-bit applications are not the same (see “Standard/Enhanced Interface Considerations” on page 21).

---

## EHLLAPI Call Format

The EHLLAPI entry point (**hllapi**) is always called with the following four parameters:

1. EHLLAPI Function Number (input)
2. Data Buffer (input/output)
3. Buffer Length (input/output)
4. Presentation Space Position (input); Return Code (output)

The prototype for IBM Standard EHLLAPI is:

```
[long hllapi (LPWORD, LPSTR, LPWORD, LPWORD);
```

The prototype for IBM Enhanced EHLLAPI is:

```
[long hllapi (LPINT, LPSTR, LPINT, LPINT);
```

Each parameter is passed by *reference* not by value. Thus each parameter to the function call must be a *pointer* to the value, not the value itself. For example, the following is a correct example of calling the EHLLAPI Query Session Status function:

```

#include "hapi_c.h"
struct HLDQuerySessionStatus QueryData;
int   Func, Len, Rc;
long  Rc;

memset(QueryData, 0, sizeof(QueryData)); // Init buffer
QueryData.qsst_shortcode = 'A';         // Session to query
Func = HA_QUERY_SESSION_STATUS;        // Function number
Len  = sizeof(QueryData);              // Len of buffer
Rc   = 0;                               // Unused on input

hllapi(&Func, (char *)&QueryData, &Len, &Rc); // Call EHLLAPI
if (Rc != 0) {                             // Check return code
    // ...Error handling
}

```

All the parameters in the **hllapi** call are pointers and the return code of the EHLLAPI function is returned in the value of the 4th parameter, not as the value of the function. For example, the following is **not** correct:

```

if (hllapi(&Func, (char *)&QueryData, &Len, &Rc) != 0) { // WRONG!
    // ...Error handling
}

```

Although the **hllapi** function is defined to return a **long** data type for IBM Standard and Enhanced EHLLAPI, and **void** data type for WinHLLAPI, its value is undefined and should not be used.

The second through fourth parameters of the **hllapi** call can return information to the application. The description of each EHLLAPI function describes what, if any, information is returned in these parameters.

---

## Data Structures

Many EHLLAPI functions use a formatted data structure to pass information to or from the application program. The description of each function shows the layout of the data structure. The data passed to or from the EHLLAPI function must exist in storage exactly as documented, byte for byte. Note that the structure layout is the same for all IBM Standard and WinHLLAPI 16- and 32-bit applications. Data structures for the IBM Enhanced 32-bit applications are packed to a 4-byte alignment.

It is *highly recommended* that the supplied header file and data structure definitions be used to ensure proper data alignment and layout. Although it is technically possible, the following is *not* recommended:

```

char QueryData[20]; // Not recommended
...
Func = HA_QUERY_SESSION_STATUS;
hllapi(&Func, QueryData, &Len, &Rc);
if (QueryData[13] == 'F') {
    // ...this is a 5250 session
}

```

The recommended way to write this function would be:

```

#include "hapi_c.h"
struct HLDQuerySessionStatus QueryData; // Recommended
...
Func = HA_QUERY_SESSION_STATUS;

```

```

hllapi(&Func, (char *)&QueryData, &Len, &Rc);
if (QueryData.qsst_sestype == 'F') {
    // ...this is a 5250 session
}

```

---

## Memory Allocation

EHLLAPI functions do not allocate or free memory. The application program must preallocate buffer space for EHLLAPI functions which require it before calling the **hllapi** entry point. The buffer space may be pre-allocated as a dynamic variable such as:

```
struct HLDQuerySessionStatus QueryBuff;
```

or it may be allocated by a call to a C library or operating system function such as:

```

struct HLDQuerySessionStatus *QueryBuff;
...
QueryBuff = malloc(sizeof(struct HLDQuerySessionStatus));

```

In any case, the application is responsible for allocating sufficient buffer space before calling EHLLAPI functions and for freeing buffers when they are not needed.

---

## EHLLAPI Return Codes

EHLLAPI functions return a completion code or return code in the 4th parameter of the **hllapi** function call (except for the **Convert Position** or **RowCol** (99) function). The return code indicates the success or failure of the requested function.

Unless indicated otherwise in the description of each function, the following table shows the meaning of each return code value. Some functions may have a slightly different interpretation of these return codes; refer to the individual function descriptions for details.

Return Code	Explanation
0	The function successfully executed, or no update since the last call was issued.
1	An incorrect host presentation space ID was specified. The specified session either was not connected, does not exist, or is a logical printer session.
2	A parameter error was encountered, or an incorrect function number was specified. (Refer to the individual function for details.)
4	The execution of the function was inhibited because the target presentation space was busy, in X CLOCK state (X []), or in X SYSTEM state.
5	The execution of the function was inhibited for some reason other than those stated in return code 4.
6	A data error was encountered due to specification of an incorrect parameter (for example, a length error causing truncation).
7	The specified presentation space position was not valid.
8	A functional procedure error was encountered (for example, use of conflicting functions or missing prerequisite functions).
9	A system error was encountered.
10	This function is not available for EHLLAPI.
11	This resource is not available.
12	This session stopped.

Return Code	Explanation
24	The string was not found, or the presentation space is unformatted.
25	Keystrokes were not available on input queue.
26	A host event occurred. See <b>Query Host Update</b> (24) for details.
27	File transfer was ended by a Ctrl+Break command.
28	Field length was 0.
31	Keystroke queue overflow. Keystrokes were lost.
32	An application has already connected to this session for communications.
33	Reserved.
34	The message sent to the host was canceled.
35	The message sent from the host was canceled.
36	Contact with the host was lost.
37	Inbound communication has been disabled.
38	The requested function has not completed its execution.
39	Another DDM session is already connected.
40	The disconnection attempt was successful, but there were asynchronous requests that had not been completed at the time of the disconnection.
41	The buffer you requested is being used by another application.
42	There are no outstanding requests that match.
43	The API was already locked by another EHLLAPI application (on LOCK) or API not locked (on UNLOCK).

## Compiling and Linking

Applications using EHLLAPI functions must include the appropriate header file to obtain the proper function prototypes, constants, and data structure definitions. These header files may be used with any of the supported C/C++ compilers (see “Languages” on page 6). If a different compiler or language is used, then you must provide your own equivalent definitions and structures.

There are two possible ways to link the application program, depending on how the entry point is to be resolved. The simplest way is to statically link the application with the appropriate Personal Communications library. This will resolve the entry point at link time. The operating system will load the correct DLL with the application when it starts. Another way to link to the entry point is to perform dynamic linking. In this case, the application uses operating system calls to load the correct DLL and obtain the entry point address at run time.

The following table shows which header files to use, which .LIB should be used for static linking, and which .DLL should be used for dynamic loading.

Interface	Entry Point	Header File	LIB	DLL
IBM Standard (16-bit)	hllapi	hapi_c.h	PCSCALLS.DLL	PCSHLL.DLL
IBM Standard (32-bit)	hllapi	ehllapi32.h	EHLAPI32.LIB	EHLAPI32.DLL
IBM Enhanced (32-bit)	hllapi	hapi_c.h	PCSCAL32.LIB	PCSHLL32.DLL
WinHLLAPI (16-bit)	winhllapi	whllapi.h	WHLLAPI.LIB	WHLLAPI.DLL
WinHLLAPI (32-bit)	winhllapi	whllapi.h	WHLAPI32.LIB	WHLAPI32.DLL

## Static Link Method

Using the static link method the application can simply call the **hllapi** entry point when needed such as:

```
#include "hapi_c.h"
int HFunc, HLen, HRc;           // Function parameters
char HBuff[1];                // Function parameters
...
HFunc = HA_RESET_SYSTEM;      // Run EHLLAPI function
HLen = 0;
HRc = 0;
hllapi(&HFunc, HBuff, &HLen, &HRc);
if (HRc != 0) {
    // ... EHLLAPI access error
}
```

When the application is linked, the appropriate Personal Communications library files must be linked with the application executable code. For example, the following link command might be used (IBM Visual Age C/C++):

```
ilink /de /noe pcsca132.lib sample.obj
```

When the operating system loads an application constructed in this way, the Personal Communications EHLLAPI module is loaded automatically.

## Dynamic Link Method

Using the dynamic link method the application makes calls to the operating system at run time to load the Personal Communications EHLLAPI module and to locate the **hllapi** entry point within it. This method requires more code in the application but gives the application greater control over error conditions. For example, the application can display a specific error message to the user if the Personal Communications EHLLAPI module cannot be found.

To use dynamic linking, the application needs to load the appropriate Personal Communications module and locate the entry point. It is recommended that the entry point be located by its ordinal number and not by name. The ordinal number is defined in the header file. The following 32-bit Windows code loads the IBM Standard 32-bit EHLLAPI module, locates the **hllapi** entry point, and makes an EHLLAPI function call.

```
#include "hapi_c.h"

HMODULE Hmod;                  // Handle of PCSHLL32.DLL
long (APIENTRY hllapi)(int *, char *, int *, int *); // Function pointer
int HFunc, HLen, HRc;         // Function parameters
char HBuff[1];               // Function parameters

Hmod = LoadLibrary("PCSHLL32.DLL"); // Load EHLLAPI module
if (Hmod == NULL) {
    // ... Error, cannot load EHLLAPI module
}

hllapi = GetProcAddress(Hmod, MAKEINTRESOURCE(ord_hllapi)); // Get EHLLAPI entry point
if (hllapi == NULL) {
    // ... Error, cannot find EHLLAPI entry point
}

HFunc = HA_RESET_SYSTEM;      // Run EHLLAPI function
HLen = 0;
HRc = 0;
```



```

(*hllapi>(&Func, HBuf, &HLen, &HRc);
if (HRc != 0) {
    // ... EHLLAPI access error
}

```

The following is similar code for 32-bit OS/2:

```

#include "hapi_c.h"

HMODULE Hmod; // ACS3EHAP.DLL handle
long (* APIENTRY hllapi)(int *, char *, int *, int *); // Func ptr
int HFunc, HLen, HRc; // Func parms
char HBuf[1]; // Func parms

if (DosLoadModule(NULL, 0, "ACS3EHAP", &Hmod) != 0) { // Load HLLAPI module
    // ...Error, cannot load EHLLAPI module
}

// Get EHLLAPI entry point
if (DosQueryProcAddr(Hmod, ord_hllapi, NULL, (PFN *)&hllapi) != 0) {
    // ...Error, cannot find EHLLAPI entry point
}

HFunc = HA_RESET_SYSTEM; // Run HLLAPI function
HLen = 0;
HRc = 0;
(*hllapi>(&HFunc, HBuf, &HLen, &HRc);
if (HRc != 0) {
    // ... EHLLAPI access error
}

```

## Multi-Threading

IBM Enhanced EHLLAPI (32-bit) and IBM Standard EHLLAPI 16-bit connect on a per process basis. All threads access the same connected host session. The thread that performs the connections must also perform the disconnection.

IBM Standard EHLLAPI (32-bit) and WinHLLAPI connect on a per thread basis. Each thread must maintain its own connections. This allows a multi-threaded process to maintain connections to more than one connected host session at a time. This eliminates the need for multi-process schemes when using a WinHLLAPI program to coordinate data between different hosts. It also puts the burden of connecting and disconnecting as necessary on the individual thread.

---

## Presentation Spaces

Many EHLLAPI functions require a *presentation space ID (PSID)* to indicate which host emulator session is to be used for the function. (This is also referred to as the *short session ID*). A presentation space ID is a single character in the range 'A' to 'Z'. There are a maximum of 26 sessions.

## IBM Enhanced 32-bit Interface Presentation Space IDs

For IBM Enhanced EHLLAPI applications, the session ID is extended with three additional bytes. These extended session bytes must be set to zero for future compatibility. This is most easily accomplished by setting the contents of EHLLAPI buffers to all binary zero before filling them in with the required information. For example, the following might be used to query the status of session 'B':

```

#include "hapi_c.h"
int HFunc, HLen, HRc; // Function parameters
struct HLDPMWindowStatus StatusData; // Function parameters

Func = HA_PM_WINDOW_STATUS;
HLen = sizeof(StatusData);
HRc = 0;

// Set data buffer to zeros and fill in request
memset(&StatusData, 0x00, sizeof(StatusData));
StatusData.cwin_shortname = 'B'; // Short session ID
StatusData.cwin_option = 0x02; // Query command

hllapi(&Func, (char *)&StatusData, &HLen, &HRc);

```

## Types of Presentation Spaces

An emulator session can be configured as a display session or a printer session. EHLLAPI applications cannot connect to printer or router sessions of PC400. The **Query Sessions (10)** function can be used to determine the type of a particular session.

## Size of Presentation Spaces

An emulator display session can be configured for a range of screen sizes from 1920 bytes (24x80 screen size) to 9920 bytes (62x160 screen size). Some EHLLAPI functions such as **Copy PS to String (8)** require the application to allocate enough storage to hold (possibly) the entire presentation space. The size of the presentation space for a given session can be obtained using the **Query Session Status (22)** function.

## Presentation Space IDs

EHLLAPI functions interact with only one presentation space at a time. The presentation space ID (PSID) is used to identify the particular presentation space in which a function is to operate.

For some functions, the PSID is contained in a preceding call to the **Connect Presentation Space (1)** function. For other functions, the PSID is contained in the calling data string parameter.

## Host-Connected Presentation Space

Connection to the host presentation space (or session) is controlled by using the **Connect Presentation Space (1)** and **Disconnect Presentation Space (2)** functions. The status of the connection determines whether some functions can be executed. It also affects how the PSID is defined. The following text explains how to control the status of the connection to the host presentation space:

- At any given time, there can be either no host-connected presentation space, or there can be one and only one host-connected presentation space.
- There is no default host-connected presentation space.
- Following a connect, there is one and only one host-connected presentation space. The host presentation space that is connected is identified in the calling data string parameter of the connect function.
- A subsequent call to connect can be executed with no intervening disconnect. In this case, there is still one and only one host-connected presentation space.

Again, the host presentation space that is connected is identified in the calling data string parameter of the connect function.

- Following a disconnect, there is no host-connected presentation space. This rule applies following multiple consecutive calls to connect or following a single call to connect.
- You cannot connect to a logical printer session.

## Presentation Space ID Handling

The PSID is used to specify the host presentation space (or session) in which you desire a function to operate. The way the PSID is handled is affected by two factors:

1. The method used to specify the PSID:
  - a. As the calling data string parameter of a preceding call to the **Connect Presentation Space (1)** function
  - b. As a character in the calling data string of the function being executed. Handling varies depending on whether the character is:
    - A letter *A* through *Z*
    - A blank or a null
2. The status of the connection to the host presentation space.

The following paragraphs describe how the PSID is handled for the various combinations of these two factors.

### PSID Handling for Functions Requiring Connect

Some functions interact only with the host-connected presentation space. These functions require the **Connect Presentation Space (1)** function as a prerequisite call. The PSID for these functions is determined by the **Connect Presentation Space (1)** and the **Disconnect Presentation Space (2)** functions as follows:

- When there is no host-connected presentation space, these functions do not interact with any presentation space. A return code of 1 is generated.
- When there is one host-connected presentation space, these functions interact with the presentation space specified in the calling data string parameter of the most recent call to the **Connect Presentation Space (1)** function.

### PSID Handling for Functions Not Requiring Connect

Some functions can interact with a host presentation space whether it is connected or not. These functions allow you to specify the PSID in the calling data string parameter. They are as follows:

- **Connect Presentation Space (1)**
- **Convert Position RowCol (99)**
- **Get Key (51)**
- **Post Intercept Status (52)**
- **Query Close Intercept (42)**
- **Query Host Update (24)**
- **Query Session Status (22)**
- **Start Close Intercept (41)**
- **Start Host Notification (23)**
- **Start Keystroke Intercept (50)**

- **Stop Close Intercept** (43)
- **Stop Host Notification** (25)
- **Stop Keystroke Intercept** (53)

All except the first two of these functions allow you to specify the PSID using either:

- A letter A through Z
- A blank or a null

The first two functions require that a letter be used to specify the PSID.

When there is no host-connected presentation space, the following rules apply:

1. The function can interact with any host presentation space if a letter, not a blank or a null, is used to specify the PSID.
2. If a blank or a null is used to specify the PSID, a return code of 1 is generated. The function does not execute.
3. Using a letter to specify the PSID does not establish a host-connected presentation space, except on a connect PS request.

When there is one host-connected presentation space, the following rules apply:

1. The function can interact with any host presentation space if a letter is used to specify the PSID.
2. If a blank or a null is used to specify the PSID, the function operates in the presentation space identified in the most recent call to the **Connect Presentation Space** (1) function.
3. Using a letter to specify the PSID does not change the established PSID of the host-connected presentation space, except on a connect PS request.

The following functions are available for printer sessions:

- **Start Host Notification** (23)
- **Query Host Update** (24)
- **Stop Host Notification** (25)

## Sharing EHLLAPI Presentation Space between Processes

More than one EHLLAPI application can share a presentation space if the applications support sharing (that is, if they were developed to work together or if they exhibit predictable behavior). To determine which applications support sharing, EHLLAPI applications are specified as one of following types:

- Supervisory
- Exclusive write with read privilege allowed
- Exclusive write without read privilege allowed
- Super write
- Read

The type of shared access can be defined by setting the following read and write sharing options for each function in the **Set Session Parameters** (9) function call:

### **SUPER\_WRITE**

The application allows other applications that allow sharing and have write access permissions to concurrently connect to the same presentation space. The

originating application performs supervisory-type functions but does not create errors for other applications that share the presentation space.

### WRITE\_SUPER

The application requires write access and allows only supervisory applications to concurrently connect to its presentation space. This is the default value.

### WRITE\_WRITE

The application requires write access and allows partner or other applications with predictable behavior to share the presentation space.

### WRITE\_READ

The application requires write access and allows other applications that perform read-only functions to share the presentation space. The application is also allowed to copy the presentation space and perform other read-only operations as usual.

### WRITE\_NONE

The application has exclusive use of the presentation space. No other applications are allowed to share the presentation space, including supervisory applications. The application is allowed to copy the presentation space and perform read-only operations as usual.

### READ\_WRITE

The application requires only read access to monitor the presentation space and allows other applications that perform read or write, or both, functions to share the presentation space. The application is also allowed to copy the presentation space and perform other read-only operations as usual.

**Note:** Sharing presentation space is not available between threads in a process.

Table 2. EHLAPI Read and Write Sharing Option Combinations

Calling Application	Super_Write	Write_Super	Write_Write	Write_Read	Write_None	Read_Write
Super_Write	Yes	Yes	Yes	No	No	Yes
Write_Super (default)	Yes	No	No	No	No	No
Write_Write	Yes	No	Yes	No	No	Yes
Write_Read	No	No	No	No	No	Yes
Write_None	No	No	No	No	No	No
Read_Write	Yes	No	Yes	Yes	No	Yes

In addition to specifying compatible read and write access options, applications that are designed to work together but cannot allow others to work in the same presentation space can optionally define a keyword, KEY\$nnnnnnnn, in the **Set Session Parameters** (9) function call. This keyword allows only those applications that use the same keyword to share the presentation space.

**Notes:**

1. The **Start Keystroke Intercept** (50) function is non-shareable. Only one application at a time can trap keystrokes.

2. The **Connect To Presentation Space** (1) and **Start Keystroke Intercept** (50) functions share common subsystem functions. Successful requests by an application to share either of these functions can affect the requests of these two functions by other applications. For example, if application A successfully requests a **Connect To Presentation Space** (1) with Write\_Read access and KEY\$abcdefgh as the keyword, a request by application B to **Connect To Presentation Space** (1) or **Start Keystroke Intercept** (50) is successful only if both applications have set compatible read and write options.

Table 3. Prerequisite Functions and Associated Dependent Functions

Prerequisite Call	Functions	Access
Allocate Communications Buffer (120)	Free Communication Buffer (120)	
Connect Window Service (101)	Change PS Window Name (106) Change Switch List Name (105) Disconnect Window Service (102) Query Window Service (103) Window Status (104)	Write Read Query=Read Set=Write Write
Connect Presentation Space (1)	Copy Field to String (34) Copy OIA (13) Copy Presentation Space (5) Copy Presentation Space to String (8) Copy String to Field (33) Copy String to Presentation Space (15) Disconnect Presentation Space (2) Find Field Length (32) Find Field Position (31) Query Cursor Location (7) Query Field Attribute (14) Release (12) Reserve (11) Search Field (30) Search Presentation Space (6) Send key (3) Set Cursor (40) Start Playing Macro (110) Wait (4)	Read Read Read Read Write Write Read Read Read Read Write Write Read Read Read Read Write Write Read Read Read Write Write Read Read Read Write Write Read
Connect Structured Field (120)	Disconnect Structured Field (121) Get Request Completion (125) Read Structured Field (126) Write Structured Field (127)	
Read Structured Field (126)	Get Request Completion (125)	
Start Close Intercept (41)	Query Close Intercept (42) Stop Close Intercept (43)	
Start Host Notification (23)	Query Host Update (24) Stop Host Notification (25)	
Start Keystroke Intercept (50)	Get Key (51) Post Intercept Status (52) Stop Keystroke Intercept (53)	
Write Structured Field (127)	Get Request Completion (125)	

## Locking Presentation Space

An application, even if specified with shared presentation space, can obtain exclusive control of a presentation space by using the **Lock Presentation Space**

**API** (60) or the **Lock Windows Services API** (61) functions. Requests by the other applications to use a presentation space locked by these functions are queued and processed in first-in-first-out (FIFO) order when the originating application unlocks the presentation space.

If the application that locked the presentation space does not unlock it by using the same call with an **Unlock** option or **Reset System** (21) call, the lock is removed when the application terminates or the session stops.

## ASCII Mnemonics

Keystrokes originating at a host keyboard might have a corresponding ASCII value. The response of the **Get Key** (51) function to a keystroke depends on whether the key is defined and also on whether the key is defined as an ASCII value or an ASCII mnemonic.

The keyboard for one session might not be capable of producing some codes needed by the another session. ASCII mnemonics that represent these codes can be included in the data string parameter of the **Send Key** (3) function.

The capabilities of the **Send Key** (3) function and the **Get Key** (51) function allow sessions to exchange keystrokes that might not be represented by ASCII values or by an available key. A set of mnemonics that can be generated from a keyboard is provided. These mnemonics let you use ASCII characters to represent the special function keys of the workstation keyboard.

Mnemonics for unshifted keys consist of the escape character followed by an abbreviation. This is also true for the shift keys themselves, Upper shift, Alt, and Ctrl. Mnemonics for shifted keys consist of the mnemonic for the shift key followed by the mnemonic for the unshifted key. Hence the mnemonic for a shifted key is a 4-character sequence of escape character, abbreviation, escape character, abbreviation.

The default escape character is @. You can change the value of the escape character to any other character with the ESC=c option of the **Set Session Parameters** (9) function. The following text uses the default escape character, however.

Shift indicators that are not part of the ASCII character set are represented to the host application by 2-byte ASCII mnemonics as follows:

<b>Upper shift</b>	@S
<b>Alt</b>	@A
<b>Ctrl</b>	@r

Mnemonics for these shift indicators are never received separately by an application. Likewise, they are never sent separately by an application. Shift indicator mnemonics are always accompanied by a non-shift-indicator character or mnemonic.

The abbreviations used make the mnemonics for special keys easy to remember. An alphabetic key code has been used for the most common keys. For example, the Clear key is *C*; the Tab key is *T*, and so on. Please note that the uppercase and lowercase alphabetic characters are mnemonic abbreviations for different keys.

The following text describes the use of these functions.



## General

All defined keys are represented by either:

- A 1-byte ASCII value that is part of the 256-element ASCII character set, or
- A 2-, 4-, or 6-byte ASCII mnemonic

To represent a key defined as an ASCII character, a 1-byte ASCII value that corresponds to that character is used.

To represent a key defined as a function, a 2-, 4-, or 6-byte ASCII mnemonic that corresponds to that function is used. For example, to represent the backtab key, @B is used. To represent PF1, @1 is used. To represent Erase Input, @A@F is used. See the following tables:

@B	Left Tab	@0	Home	@j	PF19
@C	Clear	@1	PF1/F1	@k	PF20
@D	Delete	@2	PF2/F2	@l	PF21
@E	Enter	@3	PF3/F3	@m	PF22
@F	Erase EOF	@4	PF4/F4	@n	PF23
@H	Help (PC400)	@5	PF5/F5	@o	PF24
@I	Insert	@6	PF6/F6	@q	End
@J	Jump	@7	PF7/F7	@s	ScrLk
@L	Cursor Left	@8	PF8/F8	@t	Num Lock
@N	New Line	@9	PF9/F9	@u	Page UP (PC400)
@O	Space	@a	PF10/F10	@v	Page Down (PC400)
@P	Print	@b	PF11/F11	@x	PA1
@R	Reset	@c	PF12/F12	@y	PA2
@T	Right Tab	@d	PF13	@z	PA3
@U	Cursor Up	@e	PF14	@@	@ (at) symbol
@V	Cursor Down	@f	PF15	@\$	Alternate Cursor
@X	DBCS	@g	PF16	@<	Backspace
@Y	Caps Lock	@h	PF17		
@Z	Cursor Right	@i	PF18		

**Note:** The @Y, @s and @t mnemonics can be intercepted by the **Get Key** (51) function, but they cannot be sent by the **Send Key** (3) function.

@A@C	Test (PC400)	@A@d	Red (PC/3270)
@A@D	Word Delete	@A@e	Pink (PC/3270)
@A@E	Field Exit	@A@f	Green (PC/3270)
@A@F	Erase Input	@A@g	Yellow (PC/3270)
@A@H	System Request	@A@h	Blue (PC/3270)
@A@I	Insert Toggle	@A@i	Turquoise (PC/3270)
@A@J	Cursor Select	@A@j	White (PC/3270)
@A@L	Cursor Left Fast	@A@l	Reset Host Color (PC/3270)
@A@Q	Attention	@A@t	Print (Personal Computer)
@A@R	Device Cancel	@A@y	Forward Word Tab
@A@T	Print Presentation Space	@A@z	Backward Word Tab
@A@U	Cursor Up Fast	@A@-	Field - (PC400)
@A@V	Cursor Down Fast	@A@+	Field + (PC400)
@A@Z	Cursor Right Fast	@A@<	Record Backspace (PC400)
@A@9	Reverse Video	@S@E	Print Presentation Space on Host (PC400)
@A@b	Underscore (PC/3270)	@S@x	Dup
@A@c	Reset Reverse Video (PC/3270)	@S@y	Field Mark



### Notes:

1. The first @ symbol in the first table represents the escape character. The first and second @ symbol in the second table is the escape character. The @ symbol is the default escape character. You can change the value of the escape character using the ESC=c option of the **Set Session Parameters** (9) function.  
If you change the escape character to #, the literal sequences used to represent the Backtab, Home, and Erase Input keys become #B, #0, and #A#F, respectively.  
Also, the literal sequence used to represent the @ symbol becomes #@.
2. If you send the mnemonic for print screen (that is, either @P or @A@T), place it at the end of the calling data string.
3. If you send the mnemonic for device cancel (that is, @A@R), it is passed through with no error message; however, local copy is not stopped.

### Get Key (51) Function

If the terminal operator types a key defined as an ASCII character, the host application receives a 1-byte ASCII value that corresponds to that character.

If the operator types a key defined as a function, the host application receives a 2-, 4-, or 6-byte ASCII mnemonic that corresponds to that function. For example, if the **Backtab** key is typed, @B is received. If **PF1** is pressed, @1 is received. If **Erase Input** is pressed, @A@F is received.

If the operator types a defined shift key combination, the host application receives the ASCII character, or the 2-, 4-, or 6-byte ASCII mnemonic that corresponds to the defined character or function.

If the operator types an individual key that is not defined, the **Get Key** (51) function returns a return code of 20 and nothing is sent to the host application.

The **Get Key** (51) function precedes all characters and mnemonics sent to the host application as described in the preceding text with two ASCII characters. The first ASCII character is the PSID of the host presentation space to which the keystrokes are sent. The fourth character is an A or M for ASCII, special shift, or mnemonic, respectively. See page 74.

### Send Key (3) Function

To send an ASCII character to another session, include that character in the data string parameter of the **Send Key** (3) function.

To send a function key to another session, include the ASCII mnemonic for that function in the data string parameter of the **Send Key** (3) function.

If the **Send Key** (3) function sends an unrecognized mnemonic to the host session a return code rejecting the key might result.

## Debugging

As an aid in debugging EHLLAPI applications, the Trace Facility of Personal Communications may be used. This facility will produce a log of all EHLLAPI calls, parameters, return values, and return codes. For more information on using the Trace Facility, see the *Personal Communications Quick Beginnings*.

## A Simple EHLLAPI Sample Program

The following sample Windows application will enter the character string "Hello World!" in the first input field of host session 'A'.

```
#include <stdlib.h>
#include <stdio.h>
#include <windows.h>
#include "hapi_c.h"

int main(char **argv, int argc) {
    int HFunc, HLen, HRc;
    char HBuff[1];
    struct HLDConnectPS ConnBuff;
    // Send Key string for HOME+string+ENTER:
    char SendString[] = "@@Hello World!@E";

    HFunc = HA_RESET_SYSTEM;
    HLen = 0;
    HRc = 0;
    hllapi(&HFunc, HBuff, &HLen, &HRc);
    if (HRc != HARC_SUCCESS) {
        printf("Unable to access EHLLAPI.\n");
        return 1;
    }

    HFunc = HA_CONNECT_PS;
    HLen = sizeof(ConnBuff);
    HRc = 0;
    memset(&ConnBuff, 0x00, sizeof(ConnBuff));
    ConnBuff.steps_shortname = 'A';
    hllapi(&HFunc, (char *)&ConnBuff, &HLen, &HRc);
    switch (HRc) {
        case HARC_SUCCESS:
        case HARC_BUSY:
        case HARC_LOCKED: // All these are OK
            break;
        case HARC_INVALID_PS:
            printf("Host session A does not exist.\n");
            return 1;
        case HARC_UNAVAILABLE:
            printf("Host session A is in use by another EHLLAPI application.\n");
            return 1;
        case HARC_SYSTEM_ERROR:
            printf("System error connecting to session A.\n");
            return 1;
        default:
            printf("Error connecting to session A.\n");
            return 1;
    }

    HFunc = HA_SENDKEY;
    HLen = strlen(SendString);
    HRc = 0;
    hllapi(&HFunc, SendString, &HLen, &HRc);
    switch (HRc) {
        case HARC_SUCCESS:
            break;
        case HARC_BUSY:
        case HARC_LOCKED:
            printf("Send failed, host session locked or busy.\n");
            break;
        default:
            printf("Send failed.\n");
            break;
    }
}
```

```

    HFunc = HA_DISCONNECT_PS;
    HLen = 0;
    HRc = 0;
    hllapi(&HFunc, HBuff, &HLen, &HRc);

    printf("EHLLAPI program ended.\n");
    return 0;
}

```

The following MAKEFILE file could be used to build this application with the IBM Visual Age C/C++ for Windows compiler (assuming the source file is named SAMPLE.C):

```

all: sample.exe

hllldir = C:\PCOMWIN\SAMPLES
hlllib = C:\PCOMWIN\SAMPLES

.SUFFIXES: .C .OBJ

.c.obj:
    icc.exe /Ti /Gh /Gm /Gd /C /I $(hllldir) /Tc $*.c

sample.exe: sample.obj
    ilink.exe /de /noe $(hlllib)\pcscal32.lib $**

sample.obj: sample.c

```

The application could be built with the following command:

```
nmake /a all
```

## Standard/Enhanced Interface Considerations

There is no functional difference between the standard and enhanced EHLLAPI interfaces on a given platform. However there are other important differences:

1. The enhanced EHLLAPI interface extends the presentation space ID (PSID) from 1 byte to 4 bytes. Currently the additional bytes are not used, but your application should set them to binary zeros to ensure compatibility with future versions of enhanced EHLLAPI.
2. The position (offset) of data elements in memory buffers passed to and from EHLLAPI functions are different. Data elements in enhanced EHLLAPI are aligned to double-word boundaries. Data elements in standard EHLLAPI are not aligned in any particular way. EHLLAPI applications should not be coded to set or retrieve data in the buffers by offset (byte) values. Instead, the supplied data structures in the HAPI\_C.H file should be used to set and retrieve data elements. This will ensure that data is set and retrieved from the correct position for both 16- and 32-bit programs.

By prefilling EHLLAPI data buffers with binary zeros, and using the data structures supplied in HAPI\_C.H, an application can be compiled for standard or enhanced operation without any source code changes. For example, the following section of code would work for standard EHLLAPI but would fail for enhanced EHLLAPI:

```

#include "hapi_c.h"
...
int Func, Len, Rc;
char Buff[18];
char SessType;

Func = HA_QUERY_SESSION_STATUS; // Function
Len = 18; // Buffer length

```

```

Rc = 0;
Buff[0] = 'A' // Session to query
hllapi(&Func, Buff, &Len, &Rc); // Execute function

SessType = Buff[9]; // Get session type
...

```

The above example would fail if compiled as an enhanced EHLLAPI application because:

- The application does not set the extended session ID bytes to zero.
- The buffer length for this function is 20, not 18.
- The session type indicator is not at offset 9 in the data buffer, it is at offset 12.

The following is the same function written to work correctly if compiled for standard or enhanced operation. Changed lines are indicated with a ">" mark:

```

#include "hapi_c.h"
...
int Func, Len, Rc;
> struct HLDQuerySessionStatus Buff;
char SessType;

Func = HA_QUERY_SESSION_STATUS; // Function
> Len = sizeof(Buff); // Buffer length
Rc = 0;
> memset(&Buff, 0x00, sizeof(Buff)); // Zero buffer
> Buff.qsst_shortcode = 'A'; // Session to query
hllapi(&Func, (char *)&Buff, &Len, &Rc); // Execute function

> SessType = Buff.qsst_sesstype; // Get session type
...

```

## Host Automation Scenarios

The sample scenarios presented here provide conceptual information about activities that can be facilitated by using EHLLAPI. The scenarios deal with the duties your EHLLAPI programmed operator can perform in these areas:

- Host system operation, including:
  - Search function
  - Sending keystrokes
- Distributed processing, including:
  - Data extraction
  - File transfer
- Integrating interfaces

### Scenario 1. A Search Function

There are four phases in a typical host system transaction:

1. Starting the transaction
2. Waiting for the host system to respond
3. Analyzing the response to see if it is the expected response
4. Extracting and using the data from the response

Your programmed operator can use a series of EHLLAPI functions to mimic these actions. After determining the correct starting point for the host system transaction,

the programmed operator can call the **Search Presentation Space** (6) function to determine which keyword messages or prompting messages are on the display screen.

Next, the programmed operator can use the **Send Key** (3) function to type data into a host system session and enter a host system transaction. Then the programmed operator can:

- Use the **Wait** (4) function that waits for the X CLOCK, X [], or X SYSTEM condition to end (or returns a keyboard-locked condition if the terminal has locked up).

If the keyboard is inhibited, your EHLLAPI program can call the **Copy OIA** (13) function to get more information about the error condition.

- Use the **Search Presentation Space** (6) function to look for an expected keyword to validate that the proper response had been received.
- Use the **Copy Presentation Space to String** (8) function (or any of several data access functions) to extract the desired data.

The **Search Presentation Space** (6) function is critical to simulate another task of the terminal operator. Some host systems do not stay locked in X CLOCK, X [], or X SYSTEM mode until they respond; instead, they quickly unlock the keyboard and allow the operator to stack other requests. In this environment, the terminal operator depends on some other visual prompt to know that the data has returned (perhaps a screen title or label). The **Search Presentation Space** (6) function allows your EHLLAPI program to search the presentation space while waiting. Also, while waiting for a response, calling the **Pause** (18) function allows other DOS sessions to share the central processing unit resource. The **Pause** (18) function has an option that allows your EHLLAPI program to wait for a host system update event to occur.

If no host system event occurs after a reasonable time-out period, your EHLLAPI program could call a customized error message such as:

```
No Response From Host.  Retry?
```

In this environment, program revisions become very important considerations, because the “programmed operator” must be reprogrammed for even minor changes in the display messages.

For example, if a terminal operator expects the message:

```
Enter Part Number:
```

as a prompt, he or she will probably be able to respond properly to an application change that produces the message:

```
Enter Component Number:
```

However, because the “programmed operator” is looking for a literal keyword string, subtle changes in message syntax, even as trivial as uppercase versus lowercase, can make the program take a preprogrammed “error” action.

## Scenario 2. Sending Keystrokes

There are several considerations that demand attention in designing programs that send keystrokes to the host system. In some application environments, issuing a command is as simple as typing a string and pressing Enter. Other applications

involve more complex formatted screens in which data can be entered into any one of several fields. In this environment you must understand the keystrokes required to “fill in” the display screen.

The Tab key mnemonic (@T; see page 18 for a full list of mnemonics) can be used to skip between fields. When sending keystrokes to a field using the **Send Key** (3) function, you should be aware of the field lengths and contents. If you fill the fields completely and the next attribute byte is “autoskip”, your cursor will then be moved to the next field. If you then issued a tab, you would skip to yet another field.

Likewise, if your keystrokes do not completely fill the field, there might be data left from prior input. You should use the Erase End of Field (EOF) command to clear this residual data.

### Scenario 3. Distributed Processing

Some applications fall into the category called “collaborative.” These applications provide a single end-user interface, but their processing is performed at two or more different physical locations.

An EHLLAPI application can interact with host system applications by intercepting the communication between the host system and the terminal user. The host system presentation space is the vehicle used to intercept this data. The local application can request to be notified each time the presentation space is updated or whenever an AID key is pressed by the operator.

This workstation application can then cooperate with a host system application in any of the following ways:

- On a field or presentation space basis using either the copy functions that address fields (**Copy String to Field** (33) function or **Copy Field to String** (34) function) or the functions that let you copy from and into presentation spaces (for example, **Copy String to Presentation Space** (15) function or **Copy Presentation Space to String** (8) function).
- On a keystroke basis, using the **Send Key** (3) function.
- On a file basis, for large blocks of data. You can have your application use the EHLLAPI file transfer capability (using **Send File** (90) function or **Receive File** (91) function) to transfer data or functions (such as load modules) and have it processed locally or remotely.

### Scenario 4. File Transfer

In this scenario, assume that you want to automate a file transfer:

- You could begin by using the procedure discussed in the search scenario earlier to log on to a host system session.
- Instead of using one of the copy functions (which are inefficient for copying many screens of data), your EHLLAPI program could call file transfer functions **Send File** (90) and **Receive File** (91) to transfer data.
- Upon successful completion:
  - If the **Send File** (90) function finished executing, your EHLLAPI program could submit a batch job using either a copy function or the **Send Key** (3) function before logging off.
  - If the **Receive File** (91) function finished executing, your EHLLAPI program could start up a local application.

## Scenario 5. Automation

An application can provide all the keystrokes for another application or can intersperse keystrokes to the target destination with those from the keyboard. Sometimes, to do this, the application must “lock out” other sources of keystroke input that might be destined for a target application or presentation space (using the **Reserve** (11) function) and the later “unlock” it (using the **Release** (12) function).

The origin of keystrokes presented to any application is determined by the design of the application. Keystrokes can originate from:

- The keyboard
- Data integrated into the source application
- Secondary storage retrieved through the DOS interface
- The Personal Communications interface

In all cases the keystrokes that are provided to the target application are indistinguishable from the ordinary operator input.

## Scenario 6. Keystroke Filtering

An application that acts as a filter can intercept a keystroke coming from EHLLAPI (either from the keyboard or a source application) that is targeted for another destination. The keystroke can then be:

- Ignored (that is, deleted)
- Redirected to another application
- Validated
- Converted (for example, uppercase to lowercase)
- Enhanced (through keyboard macros)

Figure 1 provides a simplified representation of the keystroke flow and the objects within a keyboard enhancement environment.




Figure 1. Keystroke Flow

## Scenario 7. Keyboard Enhancement

Scenario 8 makes use of filtering to create an **enhancer application program**. An enhancer application program is one that monitors the data coming in from the keyboard and changes it in some specified way. Typically, these application programs use instructions called **keyboard macros**, which tell them what keystrokes to look for and what changes to make. The change might involve suppressing a keystroke (so it appears to the target application as though it was never sent), replacing a keystroke with another, or replacing single keystroke with a series of keystrokes.

To do this using EHLLAPI, you might construct this scenario:

1. Your EHLLAPI application program calls the **Connect Presentation Space** (1) function to connect to the presentation space whose keystrokes are to be filtered.
2. Your EHLLAPI program next calls the **Start Keystroke Intercept** (50) function specifying the L option. This causes all keystrokes to be routed to the filtering application program.
3. The filtering application program can now define a loop in which:
  - a. The **Get Key** (51) function intercepts all keystrokes being sent to the target presentation space.
  - b. The filtering application examines each keystroke and performs a keyboard macro task, such as:
    - Abbreviating program commands so that three- or four-keystroke command can be condensed into a single keystroke
    - Customizing commands so that they are easier to remember or consistent with other software packages
    - Creating **boiler plates** for contracts or frequently used letters
    - Rearranging the keyboard for concurrent applications that use the same keys for differing functions

For example, the filtering application might convert a key combination such as **Alt+Y** into a command to move the cursor to column 35 of the second line in presentation space and write the string "XYZ Tool Corporation, Dallas, Texas".
- c. If a keystroke is rejected, your EHLLAPI program can cause a "beep" to be sounded, using the **Post Intercept Status** (52) function.
4. After your EHLLAPI program exits the filtering loop, **Stop Keystroke Intercept** (53) function to end the filtering process.



---

## Chapter 3. EHLLAPI Functions

This chapter describes each individual Personal Communications EHLLAPI function in detail and explains how to use the EHLLAPI program sampler. The functions are arranged alphabetically by name. The functions are explained for both the standard and enhanced interfaces.

**Note:** Throughout this chapter WinHLLAPI, IBM Standard 32-bit HLLAPI and 16-bit EHLLAPI are referred to as Standard Interface, and IBM Enhanced 32-bit EHLLAPI is referred to as Enhanced Interface.

---

### Page Layout Conventions

All EHLLAPI function calls are presented in the same format so that you can quickly retrieve the information you need. The format is:

- Function Name (Function Number)
- Prerequisite Calls
- Call Parameters
- Return Parameters
- Notes on Using This Function

### Prerequisite Calls

“Prerequisite Calls” lists any calls that must be made prior to calling the function being discussed. If no prerequisite call is required, the word *None* is listed.

### Call Parameters

“Call Parameters” lists the parameters that must be defined in your program to call the discussed EHLLAPI function and explains how those parameters are to be defined. If a parameter is never used by a function, then *NA* (not applicable) is listed. If a parameter can be overridden by certain values of session parameters defined with calls to the **Set Session Parameters** (9) function, such session parameters are named.

### Return Parameters

“Return Parameters” lists the parameters that must be received by your program after a call to the discussed EHLLAPI function and explains how to interpret those parameters.

### Notes on Using This Function

“Notes on Using This Function” lists any session options that affect the function under discussion. It also provides technical information about using the function and application development tips.

## Summary of EHLLAPI Functions

The following table is the summary of the EHLLAPI functions:

No.	Function	3270	5250	VT	Page
1	Connect Presentation Space (1)	Yes	Yes	Yes	35
2	Disconnect Presentation Space (2)	Yes	Yes	Yes	68
3	Send Key (3)	Yes	Yes	Yes	110
4	Wait (4)	Yes	Yes	Yes	137
5	Copy Presentation Space (5)	Yes	Yes	Yes	52
6	Search Presentation Space (6)	Yes	Yes	Yes	106
7	Query Cursor Location (7)	Yes	Yes	Yes	86
8	Copy Presentation Space to String (8)	Yes	Yes	Yes	57
9	Set Session Parameters (9)	Yes	Yes	Yes	119
10	Query Sessions (10)	Yes	Yes	Yes	92
11	Reserve (11)	Yes	Yes	Yes	103
12	Release (12)	Yes	Yes	Yes	102
13	Copy OIA (13)	Yes	Yes	Yes	44
14	Query Field Attribute (14)	Yes	Yes	Yes	86
15	Copy String to Presentation Space (15)	Yes	Yes	Yes	64
18	Pause (18)	Yes	Yes	Yes	81
20	Query System (20)	Yes	Yes	Yes	94
21	Reset System (21)	Yes	Yes	Yes	103
22	Query Session Status (22)	Yes	Yes	Yes	91
23	Start Host Notification (23)	Yes	Yes	Yes	129
24	Query Host Update (24)	Yes	Yes	Yes	88
25	Stop Host Notification (25)	Yes	Yes	Yes	136
30	Search Field (30)	Yes	Yes	Yes	104
31	Find Field Position (31)	Yes	Yes	Yes	71
32	Find Field Length (32)	Yes	Yes	Yes	69
33	Copy String to Field (33)	Yes	Yes	Yes	62
34	Copy Field to String (34)	Yes	Yes	Yes	39
40	Set Cursor (40)	Yes	Yes	Yes	118
41	Start Close Intercept (41)	Yes	Yes	Yes	127
42	Query Close Intercept (42)	Yes	Yes	Yes	83
43	Stop Close Intercept (43)	Yes	Yes	Yes	135
50	Start Keystroke Intercept (50)	Yes	Yes	Yes	132
51	Get Key (51)	Yes	Yes	Yes	73
52	Post Intercept Status (52)	Yes	Yes	Yes	83
53	Stop Keystroke Intercept (53)	Yes	Yes	Yes	136
60	Lock Presentation Space API (60)	Yes	No	No	78
61	Lock Window Services API (61)	Yes	No	No	80
90	Send File (90)	Yes	Yes	No	108
91	Receive File (91)	Yes	Yes	No	100
99	Convert Position or Convert RowCol (99)	Yes	Yes	Yes	37
101	Connect Window Services (101)	Yes	Yes	Yes	34
102	Disconnect Window Service (102)	Yes	Yes	Yes	68
103	Query Window Coordinates (103)	Yes	Yes	Yes	89
104	Window Status (104)	Yes	Yes	Yes	138
105	Change Switch List LT Name (105)	Yes	Yes	Yes	31

No.	Function	3270	5250	VT	Page
106	Change PS Window Name (106)	Yes	Yes	Yes	30
110	Start Playing Macro (110)	Yes	Yes	Yes	134
120	Connect for Structured Fields (120)	Yes	No	No	32
121	Disconnect from Structured Fields (121)	Yes	No	No	67
122	Query Communications Buffer Size (122)	Yes	No	No	84
123	Allocate Communications Buffer (123)	Yes	No	No	29
124	Free Communications Buffer (124)	Yes	No	No	72
125	Get Request Completion (125)	Yes	No	No	76
126	Read Structured Fields (126)	Yes	No	No	95
127	Write Structured Fields (127)	Yes	No	No	141

## Allocate Communications Buffer (123)

3270	5250	VT
Yes	No	No

The **Allocate Communications Buffer** function obtains a buffer from the operating system. A buffer address must be passed on both the **Read Structured Fields** (126) and **Write Structured Fields** (127) functions.

### Prerequisite Calls

None.

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 123	
Data String	See the following table	
Length	Must be 6	Must be 8
PS Position	NA	

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1–2	1–4	32-bit or 16-bit buffer length. (0 < size ≤ (64 KB–256 bytes)=X'FF00')
3–6	5–8	32-bit allocated buffer address (returned)

### Return Parameters

Return Code	Explanation
0	The <b>Allocate Communications Buffer</b> function was successful.
2	An error was made in specifying parameters.
9	A system error occurred.

Return Code	Explanation
11	Resource unavailable (memory unavailable).

### Notes on Using This Function

1. The EHLLAPI obtains a buffer from the operating system memory management and places the buffer address into the return parameter string. The requested buffer size (length) is also passed in the parameter string. The buffer size can be from 1 byte to 64 KB minus 256 bytes (X'FF00' bytes) in length.  
See “**Query Communications Buffer Size (122)**” for information regarding buffer size.
2. Buffers obtained using this function must not be shared among different processes. If this is attempted, the applications will experience unpredictable results.
3. An EHLLAPI application must issue a **Free Communications Buffer (124)** function to free the allocated memory.
4. A maximum of 10 buffers can be allocated to an application. If this limit is reached, a return code for resource unavailable (RC=11) will be returned.
5. The **Reset System (21)** function frees buffers allocated by this function.

## Change PS Window Name (106)

3270	5250	VT
Yes	Yes	Yes

The **Change PS Window Name** function allows the application to specify a new name for the presentation space window or reset the presentation space window to the default name.

### Prerequisite Calls

**Connect Window Services (101).**

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 106	
Data String	See the following table	
Length	Must be specified (See note.)	Must be 68
PS Position	NA	

**Note:** The data string length must be specified (normally 3–63 for PC/3270, 4–63 for PC400, 68 for enhanced interface).

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2–4	Reserved

Byte		Definition
2	5	A change request option value, select one of: <ul style="list-style-type: none"> <li>• X'01' for changing the presentation space window name.</li> <li>• X'02' for resetting the presentation space window name.</li> </ul>
3–63	6–66	An ASCII string of from 1 (for PC/3270) or 2 (for PC400) to 61 bytes including a terminator byte. The ASCII string must end with a NULL character. This string must contain at least one non-NULL character followed by a NULL character.
	67–68	Reserved

### Return Parameters

Return Code	Explanation
0	The <b>Change PS Window Name</b> function was successful.
1	An incorrect host presentation space short session ID was specified, or the host presentation space was not connected.
2	An error was made in specifying parameters.
9	A system error occurred.
12	The session stopped.

### Notes on Using This Function

A string is ended at the first NULL character found. The NULL character overrides the specified string length. If the NULL character is not at the end of the specified length, the last byte at the specified length is replaced by a NULL character, and the remainder of the data string is lost. If the NULL character is found before the specified length, the string is truncated at that point, and the remainder of the data string is lost.

If the application fails to reset the presentation space name before exiting, the exit list processing resets the name.

## Change Switch List LT Name (105)

3270	5250	VT
Yes	Yes	Yes

The **Change Switch List LT Name** function allows the application to change or reset a switch list for a selected logical terminal (LT). The application must specify on the call the name to be inserted in the switch list.

**Note:** This is for compatibility with Communications Manager EHLLAPI, and has the same result as the **Change PS Window Name** (106) function.

### Prerequisite Calls

**Connect Window Services** (101).

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 105	
Data String	See the following table	
Length	Normally 4–63	Must be 68
PS Position	NA	

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2–4	Reserved
2	5	A change request option; select: <ul style="list-style-type: none"> <li>• X'01' for changing a switch list LT name</li> <li>• X'02' for resetting a switch list LT name</li> </ul>
3–63	6–66	An ASCII string of 2 to 61 bytes including a terminator byte. The ASCII string must end with a NULL character. This string must contain at least one non-NULL character followed by a NULL character.
	67–68	Reserved

## Return Parameters

Return Code	Explanation
0	The <b>Change Switch List LT Name</b> function was successful.
1	An incorrect host presentation space short session ID was specified, or the host presentation space was not connected.
2	An error was made in specifying parameters.
9	A system error occurred.
12	The session stopped.

## Notes on Using This Function

A string is ended at the first NULL character found. The NULL character overrides the specified string length. If the NULL character is not at the end of the specified length, the last byte at the specified length is replaced by a NULL character, and the remainder of the data string is lost. If the NULL character is found before the specified length, the string is truncated at that point, and the remainder of the data string is lost.

If the application fails to reset the switch list LT name before exiting, the exit list processing resets the name.

## Connect for Structured Fields (120)

3270	5250	VT
Yes	No	No

The **Connect for Structured Fields** function allows an application to establish a connection to the emulation program to exchange structured field data with a host application. The workstation application must provide the Query Reply data field and must point to it with in the parameter string. The destination/origin ID returned by the emulator will be returned to the application.

## Prerequisite Calls

None.

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 120	
Data String	See the following table	
Length	7 or 11	Must be 16
PS Position	NA	

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2–4	Reserved
2–5	5–8	Address of the Query Reply data buffer
6–7	9–10	Destination/origin unique ID. (16-bit word, returned)
	11–12	Reserved
8–11	13–16	The data in these position is ignored by EHLLAPI. However, no error is caused if the migrating program has data in these positions. This data is accepted to provide compatibility with migrating applications.

## Return Parameters

Return Code	Explanation
0	The <b>Connect for Structured Fields</b> function was successful.
1	A specified host presentation space short session ID was not valid, or the host presentation space was not connected.
2	An error was made in specifying parameters.
9	A system error occurred.
10	The function is not supported by the emulation program.
32	An application has already connected to this session for communications (successful connect).
39	One DDM session is already connected to this session.

## Notes on Using This Function

- EHLLAPI scans the query reply buffers for the destination/origin ID (DOID) self-defining parameter (SDP) to determine the contents of the DOID field of the query reply. If this value is X'0000', the emulator will assign a DOID to the application and EHLLAPI will fill in the DOID field of the query reply with the assigned ID. If the value specified by the application in the DOID field of the query reply is a nonzero value, the emulator will assign the specified value as

the application's DOID, assuming that the ID has not been previously assigned. If the specified DOID is already in use, a return code of 2 will be returned by EHLLAPI.

2. The application should build the Query Reply Data structures in the application's private memory. Refer to Appendix A. Query Reply Data Structures Supported by EHLLAPI, for the detailed formats and usages of the query reply data structures supported by EHLLAPI.
3. Only cursory checking is performed on the Query Reply Data. Only the ID and the length of the structure are checked for validity.
4. Only one DDM base type connect is allowed per host session. If the DDM connection supports the self-defining parameter (SDP) for the destination origin ID (DOID), then multiple connects are allowed.
5. If return code RC=32 or RC=39 is received, an application is already connected to the selected session and use of that presentation space should be approached with caution. Conflicts with SRPI, file transfer, and other EHLLAPI applications might result.

## Connect Window Services (101)

3270	5250	VT
Yes	Yes	Yes

The **Connect Window Services** function allows the application to manage the presentation space windows. Only one EHLLAPI application at a time can be connected to a presentation space for window services.

An EHLLAPI application can connect to more than one presentation space concurrently for window services.

### Prerequisite Calls

None.

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 101	
Data String	1-character short session ID of the host presentation space	
Length	1 is implied	Must be 4
PS Position	NA	

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2-4	Reserved

### Return Parameters

Return Code	Explanation
0	The <b>Connect Window Services</b> function was successful.



Return Code	Explanation
1	An incorrect host presentation space short session ID was specified, or the Sessions Window Services manager was not connected. This return code could also mean that the API Setting for DDE/EHLLAPI is not set on.
9	A system error occurred.
10	The function is not supported by the emulation program.
11	This resource is unavailable. The host presentation space is already being used by another system function.

### Notes on Using This Function

1. An EHLLAPI application can be connected to multiple presentation space windows at the same time. The application can go back and forth between the connected presentation space windows without having to disconnect. For example, if an application is connected to presentation space windows A, B, and C, the application can access all of A, B, and C at the same time, and the other applications cannot access A, B, or C.

A **Connect Window Services** function is sufficient for the process. However, each thread that requests a **Connect Window Services** must have a corresponding **Disconnect Window Services** (102), or one of the threads must issue a **Reset System** (21), which affects all threads and disconnects any remaining connections.

## Connect Presentation Space (1)

3270	5250	VT
Yes	Yes	Yes

The **Connect Presentation Space** function establishes a connection between your EHLLAPI application program and the host presentation space.

### Prerequisite Calls

None.

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 1	
Data String	1-character short name of the host presentation space	
Length	1 is implied	Must be 4
PS Position	NA	

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2-4	Reserved

## Return Parameters

The **Connect Presentation Space** function sets the return code to indicate the status of the attempt and, if successful, the status of the host presentation space.

Return Code	Explanation
0	The <b>Connect Presentation Space</b> function was successful; the host presentation space is unlocked and ready for input.
1	An incorrect host presentation space ID was specified. The specified session either does not exist or is a logical printer session. This return code could also mean that the API Setting for DDE/EHLLAPI is not set on.
4	Successful connection was achieved, but the host presentation space is busy.
5	Successful connection was achieved, but the host presentation space is locked (input inhibited).
9	A system error was encountered.
11	This resource is unavailable. The host presentation space is already being used by another system function.

## Notes on Using This Function

1. The **Connect Presentation Space** function is affected by the CONLOG/CONPHYS session option.
2. An EHLLAPI application cannot be connected to multiple presentation spaces concurrently. Calls requiring the **Connect Presentation Space** function as a prerequisite use the currently connected presentation space. For example, if an application is connected to presentation space A, B, and C in that order, the application must connect to B or A again to issue functions.
3. Each thread that requests a **Connect Presentation Space** must have a corresponding **Disconnect Presentation Space** (2), or one of the threads must issue a **Reset System** (21), which affects all threads and disconnects any remaining connections.
4. More than one EHLLAPI application can share a presentation space, if the applications support sharing (that is, if they were developed to work together and if they exhibit predictable behavior) and have compatible read/write access and keyword options as set in the **Set Sessions Parameters** (9) function. For more information, see "Set Session Parameters (9)" on page 119.
5. Because the **Connect Presentation Space** and **Start Keystroke Intercept** (50) functions share common subsystem functions, successful requests by an application to share either of these functions for the same session can affect the request of these two functions by other applications. For example, if application A successfully requests a **Connect Presentation Space** for a session with Write\_Read access and KEY\$abcdefgh as the keyword, a request by application B to **Connect Presentation Space** for a session and **Start Keystroke Intercept** is successful only if both applications have set compatible read/write options.
6. You cannot connect to a session that is defined as a logical printer session. Refer to *Personal Communications Version 4.3 Reference*.

# Convert Position or Convert RowCol (99)

3270	5250	VT
Yes	Yes	Yes

The **Convert Position** or **Convert RowCol** function converts the host presentation space positional value into the display row and column coordinates or converts the display row and column coordinates into the host presentation space positional value. This function does not change the cursor position.

### Prerequisite Calls

None.

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 99	
Data String	Host presentation space short name <i>and</i> P for the <b>Convert Position</b> function (for example, AP converts the presentation space position of session A); <i>or</i> Host presentation space short name and R for the <b>Convert RowCol</b> function (for example, AR converts the row and column coordinates of session A).	
Length	Row, when R is specified as the second character in the data string parameter. The lower limit for valid input is 1. The upper limit for valid input depends on how your host presentation space is configured. See "Notes on Using This Function" on page 38.  NA when P is specified as the second character in the data string parameter.	
PS Position	Column, when R is specified as the second character in the data string parameter. The lower limit for valid input is 1. The upper limit for valid input ranges from 24 to 43 depending on how your host presentation space is configured. See "Notes on Using This Function" on page 38.  Host presentation space position, when P is specified as the second character in the data string parameter. The lower limit for valid input is 1. The upper limit for valid input ranges from 1920 to 3564 depending on how your host presentation space is configured. See "Notes on Using This Function" on page 38 .	

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2–4	Reserved
2	5	<b>Convert</b> option P or R
	6–8	Reserved

## Return Parameters

This function returns a length and a return code.

### Length:

For the **Convert Position** function (P as the second character in the calling data string), a number between 1 and 43 (for PC/3270) or 27 (for PC400) is returned. This value is the number of the row that contains the PS position contained in the calling PS position parameter. The upper limit can be smaller than 43 (for PC/3270) or 27 (for PC400) depending on how the host presentation space is configured.

For the **Convert RowCol** function (R as the second character in the calling data string), a value of 0 indicates an error in the input value for row (calling length parameter).

### Return Code:

The **Convert Position or RowCol** function is the exception to the rule that the fourth return parameter always contains a return code. For this function, the value returned in the fourth parameter is called a status code. This status code can contain data or a return code. Your application must provide for processing of this status code to prevent unpredictable results or an error.

- If the value of the fourth parameter is 0, 9998, or 9999, it is a return code.
- For the **Convert Position** function (P as the second character of the calling data string), a value in the range of 1–132 is the number of the column that contains the PS position passed in the calling PS Position parameter. The upper limit can be smaller than 132 depending on how the host presentation space is configured.
- For the **Convert RowCol** function (R as the second character of the calling data string), a value in the range of 1–3564 represents the host presentation space position that corresponds to the row and column values passed in the calling length and PS position parameters, respectively. The upper limit can be smaller than 3564 depending on how the host presentation space is configured.

The following status codes are defined:

Status Code	Explanation
0	This is an incorrect PS position or column.
>0	This is the PS position or column.
9998	An incorrect host presentation space ID was specified or a system error occurred.
9999	Character 2 in the data string is not P or R.

## Notes on Using This Function

1. To configure your presentation space, refer to *Personal Communications Version 4.3 Reference*
2. To find out how many rows and columns are in your presentation space, examine the returned data string parameter for the **Query Session Status (22)** function. See “Query Session Status (22)” on page 91.

## Copy Field to String (34)

3270	5250	VT
Yes	Yes	Yes

The **Copy Field to String** function transfers characters from a field in the host-connected presentation space into a string.

The **Copy Field to String** function translates the characters in the host source presentation space into American National Standard Code for Information Interchange (ASCII). Attribute bytes and other characters not represented in ASCII normally are translated into blanks.

### Prerequisite Calls

**Connect Presentation Space** (1).

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 34	
Data String	Preallocated target data string. When the <b>Set Session Parameters</b> (9) function with Extended Attribute Bytes (EAB) option is issued, the length of the data string must be at least twice the length of the field.  <b>DBCS Only:</b> When Extended Attributes Double-byte (EAD) option is specified, the length of the data string must be at least three times the length of the field. When both EAB and EAD options are specified, the length of the data string must be at least four times the length of the field.	
Length	Number of bytes to copy (the length of the data string).	
PS Position	Identifies the target field. This can be the PS position of any byte within the target field. Copy always starts at the beginning of the field.	

### Return Parameters

This function returns a data string and a return code.

#### Data String:

A string containing data from the identified field in the host presentation space. The first byte in the returned data string is the beginning byte of the identified field in the host presentation space. The number of bytes in the returned data string is determined by the smaller of:

- Number of bytes specified in the calling length parameter
- Number of bytes in the identified field in the host presentation space

#### Return Code:

The following codes are defined:

Return Code	Explanation
0	The <b>Copy Field to String</b> function was successful.
1	Your program is not connected to a host session.
2	An error was made in specifying parameters.

Return Code	Explanation
6	The data to be copied and the target field are not the same size. The data is truncated if the string length is smaller than the field copied.
7	The host presentation space position is not valid.
9	A system error was encountered.
24	Unformatted host presentation space.

### Notes on Using This Function

- The field position and length information can be found by using the **Find Field Position** (31) and **Find Field Length** (32) functions. The **Copy Field to String** function can be used with either protected or unprotected fields, but only in a *field-formatted* host presentation space.
- The copy is ended when one of the following conditions is encountered:
  - When the end of the field is reached
  - When the length of the target string is exceeded
- DBCS Only:** If the target string is ended at the higher byte of the DBCS character, the byte is translated into a blank. If the EAD option is set to on, three bytes are returned for each character. If both the EAB and EAD options are set to on, four bytes are returned for each character.

**Note:** When the field wraps at the end of the presentation space, wrapping occurs when the end of the presentation space is reached.

- DBCS Only:** The **Set Session Parameters** (9) function EAD option is used with this function to return a 2-byte EAD. If the EAD option is specified instead of the EAB option, EAD is returned preceding each character. If both the EAB and EAD options are specified, EAD is returned preceding the EAB.
- An EAB can be returned when the **Set Session Parameters** (9) function EAB option is used. EAB is related to each character in the presentation space and is returned preceding each character.
- The **Copy Field to String** function is affected by the ATTRB/NOATTRB/NULLATTRB, the ATTRB/NOATTRB/NULLATTRB, the EAB/NOEAB, the XLATE/NOXLATE, the DISPLAY/NODISPLAY, the DISPLAY/NODISPLAY, the EAD/NOEAD (for DBCS only), and the NOS0/SPACES0/S0 (for DBCS only) session options. Refer to items 5 on page 121 ; 13 and 14 on page 124; 17 on page 125; and 20 and 21 on page 126 for more information.

As previously stated, the return of attributes by the various **Copy** (5, 8, and 34) functions is affected by the **Set Session Parameters** (9) function. The involved set session parameters have the following effect:

#### Set Session Parameter Effect on the COPY Function

##### NOEAB and NOEAD

Attributes are not returned. Only text is copied from the presentation space to the user buffer.

##### EAB and NOXLATE

Attributes are returned as defined in the following tables.

##### EAB and XLATE

The colors used for the presentation space display are returned. Colors can be re-mapped; so the attribute colors are not the ones returned by the **COPY** functions when XLATE and EAB are on at the same time.

**EAD** Double-byte character set attributes are returned as shown in the following tables.

The returned character attributes are defined in the following tables. The attribute bit positions are in IBM format with bit 0 the leftmost bit in the byte.

3270 character attributes are returned from the host to the emulator. The following table applies when EAB and NOXLATE are set.

Bit Position	Meaning
0–1	Character highlighting 00 = Normal 01 = Blink 10 = Reverse video 11 = Underline
2–4	Character color (Color remap can override this color definition.) 000 = Default 001 = Blue 010 = Red 011 = Pink 100 = Green 101 = Turquoise 110 = Yellow 111 = White
5–6	Character attributes 00 = Default value 11 = Double byte character
7	Reserved

5250 character attributes are returned from the host to the emulator. The following table applies when EAB and NOXLATE are set.

Bit Position	Meaning
0	Reverse image 0 = Normal image 1 = Reverse image
1	Underline 0 = No underline 1 = Underline
2	Blink 0 = Not blink 1 = Blink
3	Separator of columns 0 = No separator 1 = Separator
4–7	Reserved

The following table shows Personal Communications character color attributes. The following table applies when EAB and XLATE are set.

Bit Position	Meaning
0-3	Background character colors 0000 = Black 0001 = Blue 0010 = Green 0011 = Cyan 0100 = Red 0101 = Magenta 0110 = Brown (3270), Yellow (5250) 0111 = White
4-7	Foreground character colors 0000 = Black 0001 = Blue 0010 = Green 0011 = Cyan 0100 = Red 0101 = Magenta 0110 = Brown (3270), Yellow (5250) 0111 = White 1000 = Gray 1001 = Light blue 1010 = Light green 1011 = Light cyan 1100 = Light red 1101 = Light magenta 1110 = Yellow 1111 = White (high intensity)

- Double-byte character set attributes (for DBCS only)
  - The first byte

Bit Position	Character Position	Field Attribute Position
0	Double-byte character	Reserved
1	The first byte of the double-byte character	Reserved
2	SO	Reserved



Bit Position	Character Position	Field Attribute Position
3–4	SI (Bit position 3)	5250 DBCS related field When the value of bit position 7 is 0: 00 = Default 01 = DBCS only 10 = Either DBCS or SBCS 11 = Mixture of DBCS and SBCS When the value of bit position 7 is 1: 00 = Reserved 01 = DBCS only without SO/SI 10 = Reserved 11 = Reserved
5	Reserved	SO/SI enable (3270 only)
6	Reserved	Character attributes exist (3270 only)
7	Reserved	5250 DBCS related extended field 0 = Basic double-byte field 1 = Extended double-byte field

– The second byte

Bit Position	Character Position	Field Attribute Position
0	Reserved	Left grid line (3270 only)
1	Reserved	Upper grid line (3270 only)
2	Reserved	Right grid line (3270 only)
3	Reserved	Under grid line (3270 only)
4	Left grid line	Left grid line
5	Upper grid line	Upper grid line
6–7	Reserved	Reserved

For a PS/2 monochrome display, the characters in the application (workstation) session appear as various shades of gray. This is required to give users their re-mapped colors in the EHELLAPI application session so they can “get” what they see in their host application presentation spaces.

- To use this function, preallocate memory to receive the returned data string parameter. The statements required to preallocate this memory vary depending on the language in which your application is written. Refer to “Memory Allocation” on page 8 for more information.

**Note:** 5250 emulation supports a presentation space of 24 rows by 80 columns. In some instances, Communications Manager 5250 emulation displays a 25th row. This occurs when either an error message from the host is displayed or when the operator selects the SysReq key. Personal Communications displays 25th row information on the status bar. By **EXTEND\_PS** option, an EHLLAPI application can use the same interface with Communications Manager EHLLAPI and valid presentation space is extended when this condition occurs.

## Copy OIA (13)

3270	5250	VT
Yes	Yes	Yes

The **Copy OIA** function returns the current operator information area (OIA) data from the host-connected presentation space.

The OIA is located under the bottom dividing line of the screen and is used to display session status information about the connection between the workstation and the host.

### Prerequisite Calls

**Connect Presentation Space (1).**

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 13	
Data String	Preallocated target data string	
Length	103	104
PS Position	NA	

### Return Parameters

This function returns a data string and a return code.

#### Data String:

A 103-byte string for 16-bit and 104-byte string for 32-bit. See "Format of the Returned OIA Data String" on page 45 for more information.

#### Return Code:

The following codes are defined:

Return Code	Explanation
0	OIA data is returned. The target presentation space is unlocked.
1	Your program is not connected to a host session.
2	An error was made in specifying string length. OIA data was not returned.
4	OIA data is returned. The target presentation space is busy.
5	OIA data is returned. The target presentation space is locked. (Input inhibited)
9	An internal system error was encountered. OIA data was not returned.

## Notes on Using This Function

1. The OIA Group consists of the bits that show the status of the connected sessions. The group is categorized by the represented host function. (For example, Group 8 consists of the bits that show all conditions of the input inhibit in the session.) The states of each group are ordered so that the high-order bits represent the indicators of higher priority. That is, bit 7 has priority over bit 0. Therefore, if more than one state is active within a group, the state with the highest priority is the active state within that group.
2. To use this function, preallocate memory to receive the returned data string parameter. The statements required to preallocate this memory vary depending on the language in which your application is written. Refer to “Memory Allocation” on page 8 for more information.

## Format of the Returned OIA Data String

The OIA data string contains the following information:

Byte		Definition
Standard	Enhanced	
1	1	The OIA format byte. The value is 1 (PC/3270), 9 (PC400), or 5 (VT).
2–81	2–81	The OIA image in the host code points.
82–103	82–103	OIA group indicator meanings.
	104	Reserved.

**PC/3270 OIA Group Indicator Meanings and Its Image:** The OIA image group consists of an 80-byte ASCII character string with no attribute bytes that contains the OIA image in host code points. Figure 2 on page 46 shows the hexadecimal codes found in the host presentation space, and the characters they represent. The returned data can be translated into OIA graphics characters. Refer to the *Personal Communications Version 4.3 Quick Beginnings* for information on the OIA indicators.

To translate the returned data into OIA graphics characters, proceed as follows:

1. Print the data returned in bytes 2 through 81 to the screen or to a printer.
2. Using the code page chart applicable to the device on which the output appears, find the hexadecimal value corresponding to each character.
3. Using Figure 2 on page 46, find the OIA graphics character corresponding to each hexadecimal value found in step 2.

**Note:** Group 8 (byte 0) machine, communications, and program check images are followed by a three-digit number related to the type of check.

The online and screen ownership group images are for non-SNA 3274 controller configurations. For SNA, the CD hex value is translated by CD (see Figure 2 on page 46 ). If running on a 3174 controller or SDLC connection, the hex value X'F4' is replaced by X'B2' or X'22'. The highlight indicator is a corresponding image (in the first 80 bytes of the data string) of the “Group 5 (offset 86: Highlight group 1” byte. The highlight indicator is followed by either X'F9' (blink), X'FC' (underscore), X'D2' (reverse video), or X'80' (host default).

The short session ID followed by X'20' is in column 7.

All group images are represented by Main Frame Interactive (MFI) hex code points.

**Note:** The OIA image data string position minus 1 position equals the OIA column.

	0x	1x	2x	3x	4x	5x	6x	7x	8x	9x	Ax	Bx	Cx	Dx	Ex	Fx
x0	NUL	SP	0	&	à	ä	À	Ä	a	q	A	Q	↖	^	P	☒
x1	EM	=	1	—	è	ë	È	Ë	b	r	B	R	—		S	?
x2	FF	'	2	.	ì	ï	Ì	Ï	c	s	C	S	z	☐	→	↩
x3	NL	"	3	,	ò	ö	Ò	Ö	d	t	D	T	_	°	↑	↩
x4	STP	/	4	:	ù	ü	Ù	Ü	e	u	E	U	☺	°	↑	☒
x5	CR	\	5	+	ã	â	Ã	Â	f	v	F	V	☺	+	↓	—
x6			6	—	õ	ê	Õ	Ê	g	w	G	W	☒	☺	☺	—
x7			7	—	ÿ	î	ÿ	Î	h	x	H	X	☒	☺	☺	▶
x8	>	?	8	°	à	ô	À	Ô	i	y	I	Y	←	☺	μ	¿
x9	<	!	9		è	û	E	Û	j	z	J	Z	☺	☺	2	☺
xA	[	\$	β	^	é	á	E	Á	k	æ	K	Æ	☺	☺	3	☺
xB	]	¢	§	~	ì	é	I	É	l	ø	L	Ø	☺	☺	▶	☺
xC	)	£	#	••	Ò	í	O	Í	m	ˆ	M	À	☺	☺	☺	☺
xD	(	¥	@	`	Ù	ó	U	Ó	n	ç	N	Ç	☺	☺	☺	☺
xE	}	Pts	%	'	Ü	Ú	Y	Ú	o	;	O	;	•	+	☺	i
xF	{	☺	—	☺	Ç	ñ	C	Ñ	p	*	P	*	☺	☺	☺	Not Sup-ported

Figure 2. Host Presentation Space Characters

- Group 1 (Offset 82): Online and Screen Ownership

Bit	Meaning
0–1	Reserved
2	SSCP-LU session owns screen
3	LU-LU session owns screen
4	Online and not owned
5	Subsystem ready
6–7	Reserved

- Group 2 (Offset 83): Character Selection

Bit	Meaning
0	Reserved
1	APL
2	Katakana (Japan only)
3	Alphanumeric
4–5	Reserved
6	Hiragana (Japan only)
7	Double-byte character

- Group 3 (Offset 84): Shift State

Bit	Meaning
0	Upper shift
1	Numeric
2	CAPS
3–7	Reserved

- Group 4 (Offset 85): PSS Group 1

Bit	Meaning
0–7	Reserved

- Group 5 (Offset 86): Highlight Group 1

Bit	Meaning
0	Operator selectable
1	Field inherit
2–7	Reserved

- Group 6 (Offset 87): Color Group 1

Bit	Meaning
0	Operator selectable
1	Field inherit
2–7	Reserved

- Group 7 (Offset 88): Insert

Bit	Meaning
0	Insert mode
1–7	Reserved

- Group 8 (Offset 89–93): Input Inhibited (5 bytes)

- Byte 1 (Offset 89)

Bit	Meaning
0	Non-resettable machine check
1	Reserved
2	Machine check
3	Communications check
4	Program check
5–7	Reserved

- Byte 2 (Offset 90)

Bit	Meaning
0	Device busy
1	Terminal wait
2	Minus symbol
3	Minus function
4	Too much entered
5–7	Reserved

– Byte 3 (Offset 91)

Bit	Meaning
0–2	Reserved
3	Incorrect dead key combination, limited key.
4	Wrong place
5–7	Reserved

– Byte 4 (Offset 92)

Bit	Meaning
0–1	Reserved
2	System wait
3–7	Reserved

– Byte 5 (Offset 93)

Bit	Meaning
0–7	Reserved

- Group 9 (Offset 94): PSS Group 2

Bit	Meaning
0–7	Reserved

- Group 10 (Offset 95): Highlight Group 2

Bit	Meaning
0–7	Reserved

- Group 11 (Offset 96): Color Group 2

Bit	Meaning
0–7	Reserved

- Group 12 (Offset 97): Communication Error Reminder

Bit	Meaning
0–6	Communications error
1–7	Reserved

- Group 13 (Offset 98): Printer State

Bit	Meaning
0–7	Reserved

- Group 14 (Offset 99): Graphics

Bit	Meaning
0–7	Reserved

- Group 15 (Offset 100): Reserved
- Group 16 (Offset 101): Automatic Key Play/Record State

Bit	Meaning
0–7	Reserved

- Group 17 (Offset 102): Automatic Key Quit/Stop State

Bit	Meaning
0–7	Reserved

- Group 18 (Offset 103): Expanded State

Bit	Meaning
0–7	Reserved

**PC400 OIA Group Indicator Meanings and Its Image:** Details of the OIA group are listed in the following tables.

- Group 1 (Offset 82): Online and Screen Ownership

Bit	Meaning	Beginning Position of Data String
0–2	Reserved	
3	System available	1
4	Reserved	
5	Subsystem ready	
6–7	Reserved	

- Group 2 (Offset 83): Character Selection

Bit	Meaning	Beginning Position of Data String
0–1	Reserved	
2	Katakana (Japan only)	
3	Alphanumeric	
4–5	Reserved	
6	Hiragana (Japan only)	
7	Double-byte character	

- Group 3 (Offset 84): Shift State

Bit	Meaning	Beginning Position of Data String
0	Reserved	
1	Keyboard shift	39
2	CAPS	
3–6	Reserved	
7	Double-byte character input available	

- Group 4 (Offset 85): PSS Group 1

Bit	Meaning	Beginning Position of Data String
0–7	Reserved	

- Group 5 (Offset 86): Highlight Group 1

Bit	Meaning	Beginning Position of Data String
0–7	Reserved	

- Group 6 (Offset 87): Color Group 1

Bit	Meaning	Beginning Position of Data String
0–7	Reserved	

- Group 7 (Offset 88): Insert

Bit	Meaning	Beginning Position of Data String
0	Insert mode	68
1–7	Reserved	

- Group 8 (Offset 89–93): Input Inhibited (5 bytes)

- Byte 1 (Offset 89)

Bit	Meaning	Beginning Position of Data String
0–7	Reserved	

- Byte 2 (Offset 90)

Bit	Meaning	Beginning Position of Data String
0–7	Reserved	

- Byte 3 (Offset 91)

Bit	Meaning	Beginning Position of Data String
0–4	Reserved	
5	Operator input error	64
6–7	Reserved	

- Byte 4 (Offset 92)

Bit	Meaning	Beginning Position of Data String
0–1	Reserved	
2	System wait	64
3–7	Reserved	

- Byte 5 (Offset 93)

Bit	Meaning	Beginning Position of Data String
0–7	Reserved	

- Group 9 (Offset 94): PSS Group 2

Bit	Meaning	Beginning Position of Data String
0–7	Reserved	

- Group 10 (Offset 95): Highlight Group 2

Bit	Meaning	Beginning Position of Data String
0–7	Reserved	

- Group 11 (Offset 96): Color Group 2

Bit	Meaning	Beginning Position of Data String
0–7	Reserved	



- Group 12 (Offset 97): Communication Error Reminder

Bit	Meaning	Beginning Position of Data String
0	Communications Error	
1–5	Reserved	
7	Message wait	3

- Group 13 (Offset 98): Printer State

Bit	Meaning	Beginning Position of Data String
0–7	Reserved	

- Group 14 (Offset 99): Graphics

Bit	Meaning	Beginning Position of Data String
0–7	Reserved	

- Group 15 (Offset 100): Reserved
- Group 16 (Offset 101): Automatic Key Play/Record State

Bit	Meaning	Beginning Position of Data String
0–7	Reserved	

- Group 17 (Offset 102): Automatic Key Quit/Stop State

Bit	Meaning	Beginning Position of Data String
0–7	Reserved	

- Group 18 (Offset 103): Expanded State

Bit	Meaning	Beginning Position of Data String
0–7	Reserved	

**VT Host OIA Group Indicator Meanings and Its Image:** Details of the VT Host OIA group are listed in the following tables.

- Group 1 (Offset 82): Online and Screen Ownership

Bit	Meaning
5	Subsystem ready

- Group 2 (Offset 83): Character Selection

Bit	Meaning
0	Upper shift
2	CAPS

- Group 7 (Offset 88): Insert

Bit	Meaning
0	Insert mode

Some columns on the OIA line display different messages for VT than those messages displayed for 3270/5250. See the following table for specific details.

Column	Symbol
1-7	VT220 7
	VT220 8
	VT100
	VT52
	VTANSI
9 - 12	LOCK
61 - 64	HOLD

## Copy Presentation Space (5)

3270	5250	VT
Yes	Yes	Yes

The **Copy Presentation Space** function copies the contents of the host-connected presentation space into a data string that you define in your EHLLAPI application program.

The **Copy Presentation Space** function translates the characters in the host source presentation space into ASCII. Attribute bytes and other characters not represented in ASCII normally are translated into blanks. If you do not want the attribute bytes translated into blanks, you can override this translation with the ATTRB option under the **Set Session Parameters** (9) function.

### Prerequisite Calls

**Connect Presentation Space** (1).

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 5	
Data String	Preallocated target string the size of your host presentation space. This can vary depending on how your host presentation space is configured. When the <b>Set Session Parameters</b> (9) function with the EAB option is issued, the length of the data string must be at least twice the length of the presentation space.  <b>DBCS Only:</b> When the EAD option is specified, the length of the data string must be at least three times the length of the presentation space. When both the EAB and EAD options are specified, the length of the data string must be at least four times the length of the presentation space.	
Length	NA (the length of the host presentation space is implied).	
PS Position	NA.	

### Return Parameters

This function returns a data string and a return code.

#### Data String:

Contents of the connected host presentation space.

**Return Code:**

The following codes are defined:

Return Code	Explanation
0	The host presentation space contents were copied to the application program. The target presentation space was active, and the keyboard was unlocked.
1	Your program is not connected to a host session.
4	The host presentation space contents were copied. The connected host presentation space was waiting for host response.
5	The host presentation space was copied. The keyboard was locked.
9	A system error was encountered.

**Notes on Using This Function**

1. An EAB can be returned when the **Set Session Parameters** (9) function EAB option is used. EAB is related to each character in the presentation space and is returned preceding each character.
2. **DBCS Only:** The **Set Session Parameters** (9) function EAD option is used with this function to return a 2-byte EAD. If the EAD option is specified instead of the EAB option, EAD is returned preceding each character. If both the EAB and EAD options are specified, EAD is returned preceding the EAB.  
If the start position of the copy is at the second byte in the double-byte character, or the end position is at the first byte in the double-byte character, the bytes are translated into blanks.
3. The **Copy Presentation Space** function is affected by the following session options:
  - ATTRB/NOATTRB/NULLATTRB,
  - EAB/NOEAB,
  - XLATE/NOXLATE,
  - BLANK/NOBLANK,
  - DISPLAY/NODISPLAY,
  - EAD/NOEAD (for DBCS only)
  - NOS0/SPACES0/S0 (for DBCS only)
  - EXTEND\_PS/NOEXTEND\_PS

Refer to items 5 on page 121; 13, 14, 15 and 17 on page 125; and 20 and 21 on page 126 for more information.

If the target data string provided is not large enough to hold the requested number of bytes, the copy ends successfully (RC=0) when the end of the target data string is reached.

As previously stated, the return of attributes by the various **Copy** (5, 8, and 34) functions is affected by the **Set Session Parameters** (9) function. The involved set session parameters have the following effect:

**Set Session Parameter**  
**Effect on the COPY Function**

**NOEAB and NOEAD**

Attributes are not returned. Only text is copied from the presentation space to the user buffer.

**EAB and NOXLATE**

Attributes are returned as defined in the following tables.

**EAB and XLATE**

The colors used for the presentation space display are returned. Colors can be re-mapped; so the attribute colors are not the ones returned by the **Copy** functions when XLATE and EAB are on at the same time.

**EAD** Double-byte character set attributes are returned as shown in the following tables.

**NOSO/SPACESO/SO**

When NOSO is specified, it works as SPACESO. The size of the presentation space is not changed.

The returned character attributes are defined in the following tables. The attribute bit positions are in IBM format with bit 0 the leftmost bit in the byte.

3270 character attributes are returned from the host to the emulator. The following table applies when EAB and NOXLATE are set.

Bit Position	Meaning
0–1	Character highlighting 00 = Normal 01 = Blink 10 = Reverse video 11 = Underline
2–4	Character color (Color remap can override this color definition.) 000 = Default 001 = Blue 010 = Red 011 = Pink 100 = Green 101 = Turquoise 110 = Yellow 111 = White
5–6	Character attribute 00 = Default value 11 = Double-byte character
7	Reserved

5250 character attributes are returned from the host to the emulator. The following table applies when EAB and NOXLATE are set.

Bit Position	Meaning
0	Reverse image 0 = Normal image 1 = Reverse image
1	Underline 0 = No underline 1 = Underline

Bit Position	Meaning
2	Blink 0 = Not blink 1 = Blink
3	Separator of columns 0 = No separator 1 = Separator
4–7	Reserved

The following table shows Personal Communications character color attributes. The following table applies when EAB and XLATE are set.

Bit Position	Meaning
0–3	Background character colors 0000 = Black 0001 = Blue 0010 = Green 0011 = Cyan 0100 = Red 0101 = Magenta 0110 = Brown (3270), Yellow (5250) 0111 = White
4–7	Foreground character colors 0000 = Black 0001 = Blue 0010 = Green 0011 = Cyan 0100 = Red 0101 = Magenta 0110 = Brown (3270), Yellow (5250) 0111 = White 1000 = Gray 1001 = Light blue 1010 = Light green 1011 = Light cyan 1100 = Light red 1101 = Light magenta 1110 = Yellow 1111 = White (high intensity)

- Double-byte character set attributes (for DBCS only)
  - The first byte

Bit Position	Character Position	Field Attribute Position
0	Double-byte character	Reserved
1	The first byte of the double-byte character	Reserved

Bit Position	Character Position	Field Attribute Position
2	SO	Reserved
3–4	SI (Bit position 3)	5250 DBCS related field - When the value of bit position 7 is 0: 00 = Default 01 = DBCS only 10 = Either DBCS or SBCS 11 = Mixture of DBCS and SBCS - When the value of bit position 7 is 1: 00 = Reserved 01 = DBCS only without SO/SI 10 = Reserved 11 = Reserved
5	Reserved	SO/SI enabled (3270 only)
6	Reserved	Character attributes exist (3270 only)
7	Reserved	5250 DBCS related extended field 0 = Basic double-byte field 1 = Extended double-byte field

– The second byte

Bit Position	Character Position	Field Attribute Position
0	Reserved	Left grid line (3270 only)
1	Reserved	Upper grid line (3270 only)
2	Reserved	Right grid line (3270 only)
3	Reserved	Under grid line (3270 only)
4	Left grid line	Left grid line
5	Upper grid line	Upper grid line
6–7	Reserved	Reserved

For a PS/2 monochrome display, the characters in the application (workstation) session appear as various shades of gray. This is required to give users their re-mapped colors in the EHLLAPI application session so they can “get” what they see in their host application presentation spaces.

If you want to copy only a portion of the host presentation space, use the **Copy Presentation Space to String** (8) function.

To use this function, preallocate memory to receive the returned data string parameter. The statements required to preallocate this memory vary depending on the language in which your application is written. Refer to “Memory Allocation” on page 8 for more information.

**Note:** 5250 emulation supports a presentation space of 24 rows by 80 columns. In some instances, Communications Manager 5250 emulation displays a 25th row. This occurs when either an error message from the host is displayed or when the operator selects the SysReq key. Personal Communications displays 25th row information on row 24, or on the status bar. For information to be displayed on the status bar, the status bar must be

configured. Refer to *Personal Communications Version 4.3 Quick Beginnings* for information on configuring the status bar. By the **EXTEND\_PS** option, an EHLLAPI application can use the same interface with Communications Manager EHLLAPI and valid presentation space is extended when this condition occurs.

## Copy Presentation Space to String (8)

3270	5250	VT
Yes	Yes	Yes

The **Copy Presentation Space to String** function is used to copy all or part of the host-connected presentation space into a data string that you define in your EHLLAPI application program.

The input PS position is the offset into the host presentation space. This offset is based on a layout in which the upper-left corner (row 1/column 1) is location 1 and the bottom-right corner is 3564, which is the maximum screen size for the host presentation space. The value of PS Position + (Length - 1) cannot exceed the configured size of your host presentation space.

The **Copy Presentation Space to String** function translates the characters in the host source presentation space into ASCII. Attribute bytes and other characters not represented in ASCII normally are translated into blanks. If you do not want the attribute bytes translated into blanks, you can override this translation with the ATTRB option under the **Set Session Parameters (9)** function.

### Prerequisite Calls

**Connect Presentation Space (1).**

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 8	
Data String	Preallocated target string the size of your host presentation space. When the <b>Set Session Parameters (9)</b> function with the EAB option is issued, the length of the data string must be at least twice the length of the presentation space.  <b>DBCS Only:</b> When the EAD option is specified, the length of the data string must be at least three times the length of the presentation space. When both the EAB and EAD options are specified, the length of the data string must be at least four times the length of the presentation space.	
Length	Length of the target data string.	
PS Position	Position within the host presentation space of the first byte in your target data string.	

### Return Parameters

This function returns a data string and a return code.

#### Data String:

Contents of the host presentation space.

### Return Code:

The following codes are defined:

Return Code	Explanation
0	The host presentation space contents were copied to the application program. The target presentation space was active, and the keyboard was unlocked.
1	Your program is not connected to a host session.
2	An error was made in specifying string length, or the sum of (Length - 1) + PS position is greater than the size of the connected host presentation space.
4	The host presentation space contents were copied. The host presentation space was waiting for host response.
5	The host presentation space was copied. The keyboard was locked.
7	The host presentation space position is not valid.
9	A system error was encountered.

### Notes on Using This Function

1. An EAB can be returned when the **Set Session Parameters** (9) function EAB option is used. EAB is related to each character in the presentation space and is returned preceding each character.
2. **DBCS Only:** The **Set Session Parameters** (9) function EAD option is used with this function to return a 2-byte EAD. If the EAD option is specified instead of the EAB option, EAD is returned preceding each character. If both the EAB and EAD options are specified, EAD is returned preceding the EAB.

If the start position of the copy is at the second byte in the double-byte character, or the end position is at the first byte in the double-byte character, the bytes are translated into blanks. If the EAD option is set to on, three bytes are returned for each character. If both the EAB and EAD options are set to on, four bytes are returned for each character.

3. The **Copy Presentation Space to String** function is affected by the following options:
  - ATTRB/NOATTRB/NULLATTRB
  - EAB/NOEAB
  - XLATE/NOXLATE
  - BLANK/NOBLANK
  - DISPLAY/NODISPLAY
  - EAD/NOEAD (for DBCS only)
  - NOS0/SPACES0/S0 (for DBCS only)
  - EXTEND\_PS/NOEXTEND\_PS

Refer to items 5 on page 121; 13 and 14 on page 124; 15 on page 124; 17 on page 125 ; and 20 and 21 on page 126

If the target data string provided is not large enough to hold the requested number of bytes, the copy ends successfully (RC=0, 4, or 5) when the end of the target data string is reached.

As previously stated, the return of attributes by the various **Copy** (5, 8, and 34) functions is affected by the **Set Session Parameters** (9) function. The involved set session parameters have the following effect:



**Set Session Parameter  
Effect on the Copy Function**

**NOEAB and NOEAD**

Attributes are not returned. Only text is copied from the presentation space to the user buffer.

**EAB and NOXLATE**

Attributes are returned as defined in the following tables.

**EAB and XLATE**

The colors used for the presentation space display are returned. Colors can be re-mapped, so the attribute colors are not the ones returned by the **Copy** functions when XLATE and EAB are on at the same time.

**EAD** Double-byte character set attributes are returned as shown in the following tables.

The returned character attributes are defined in the following tables. The attribute bit positions are in IBM format with bit 0 the leftmost bit in the byte.

- 3270 character attributes are returned from the host to the emulator. The following table applies when EAB and NOXLATE are set.

Bit Position	Meaning
0–1	Character highlighting 00 = Normal 01 = Blink 10 = Reverse video 11 = Underline
2–4	Character color (Color re-map can override this color definition.) 000 = Default 001 = Blue 010 = Red 011 = Pink 100 = Green 101 = Turquoise 110 = Yellow 111 = White
5–7	Reserved

- 5250 character attributes are returned from the host to the emulator. The following table applies when EAB and NOXLATE are set.

Bit Position	Meaning
0	Reverse image 0 = Normal image 1 = Reverse image
1	Underline 0 = No underline 1 = Underline

Bit Position	Meaning
2	Blink 0 = Not blink 1 = Blink
3	Separator of columns 0 = No separator 1 = Separator
4-7	Reserved

- VT character attributes are returned from the host to the emulator. The following table applies when EAB and NOXLATE are set.

Bit Position	Meaning
0-3	Reserved
4	Bold 1 = On 0 = Off
5	Underscore 1 = On 0 = Off
6	Blink 1 = On 0 = Off
7	Reverse 0 = On 1 = Off

- The following table shows Personal Communications character color attributes. The following table applies when EAB and XLATE are set.

Bit Position	Meaning
0-3	Background character colors 0000 = Black 0001 = Blue 0010 = Green 0011 = Cyan 0100 = Red 0101 = Magenta 0110 = Brown (3270), Yellow (5250) 0111 = White

Bit Position	Meaning
4–7	Foreground character colors 0000 = Black 0001 = Blue 0010 = Green 0011 = Cyan 0100 = Red 0101 = Magenta 0110 = Brown (3270), Yellow (5250) 0111 = White 1000 = Gray 1001 = Light blue 1010 = Light green 1011 = Light cyan 1100 = Light red 1101 = Light magenta 1110 = Yellow 1111 = White (high intensity)

- Double-byte character set attributes
  - The first byte

Bit Position	Character Position	Field Attribute Position
0	Double-byte character	Reserved
1	The first byte of the double-byte character	Reserved
2	SO	Reserved
3–4	SI (Bit position 3)	5250 DBCS related field When the value of bit position 7 is 0: 00 = Default 01 = DBCS only 10 = Either DBCS or SBCS 11 = Mixture of DBCS and SBCS When the value of bit position 7 is 1: 00 = Reserved 01 = DBCS only without SO/SI 10 = Reserved 11 = Reserved
5	Reserved	SO/SI enable (3270 only)
6	Reserved	Character Attributes exist (3270 only)

Bit Position	Character Position	Field Attribute Position
7	Reserved	5250 DBCS related extended field 0 = Basic double-byte field 1 = Extended double-byte field

– The second byte

Bit Position	Character Position	Field Attribute Position
0	Reserved	Left grid line (3270 only)
1	Reserved	Upper grid line (3270 only)
2	Reserved	Right grid line (3270 only)
3	Reserved	Under grid line (3270 only)
4	Left grid line	Left grid line
5	Upper grid line	Upper grid line
6–7	Reserved	Reserved

For a PS/2 monochrome display, the characters in the application (workstation) session appear as various shades of gray. This is required to give users their remapped colors in the EHLLAPI application session so they can “get” what they see in their host application presentation spaces.

- To use this function, preallocate memory to receive the returned data string parameter. The statements required to preallocate this memory vary depending on the language in which your application is written. Refer to “Memory Allocation” on page 8 for more information.

**Note:** 5250 emulation supports a presentation space of 24 rows by 80 columns. In some instances, Communications Manager 5250 emulation displays a 25th row. This occurs when either an error message from the host is displayed or when the operator selects the SysReq key. Personal Communications displays 25th row information on row 24, or on the status bar. For information to be displayed on the status bar, the status bar must be configured. Refer to *Personal Communications Version 4.3 Quick Beginnings* for information on configuring the status bar. By the **EXTEND\_PS** option, an EHLLAPI application can use the same interface with Communications Manager EHLLAPI and valid presentation space is extended when this condition occurs.

## Copy String to Field (33)

3270	5250	VT
Yes	Yes	Yes

The **Copy String to Field** function transfers a string of characters into a specified field in the host-connected presentation space. This function can be used only in a *field-formatted* host presentation space.

## Prerequisite Calls

Connect Presentation Space (1).

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 33	
Data String	String containing the data to be transferred to a target field in the host presentation space.	
Length	Length, in number of bytes, of the source data string. Overridden if in EOT mode.	
PS Position	Identifies the target field. This can be the PS position of any byte within the target field. Copy always starts at the beginning of the field.	

### Return Parameters

Return Code	Explanation
0	The <b>Copy String to Field</b> function was successful.
1	Your program is not connected to a host session.
2	Parameter error or zero length for copy.
5	The target field was protected or inhibited, or incorrect data was sent to the target field (such as a field attribute).
6	Copy was completed, but data is truncated.
7	The host presentation space position is not valid.
9	A system error was encountered.
24	Unformatted host presentation space.

### Notes on Using This Function

1. The **Copy String to Field** function is affected by the following options:

- STRLEN/STREOT
- EOT
- EAB/NOEAB
- XLATE/NOXLATE
- PUTEAB/NOPUTEAB

Refer to items 1 and 2 on page 121; 13 and 14 on page 124; 18 on page 125; and 20 and 21 on page 126 for more information.

2. The string to be transferred is specified with the calling data string parameter. The string ends when one of these three conditions is encountered:

- When an end-of-text (EOT) delimiter is encountered in the string if EOT mode was selected using the **Set Session Parameters** (9) function. (See “Set Session Parameters (9)” on page 119).
- When the number specified in the length is reached if not in EOT mode.
- When an end-of-field is encountered in the field.

**Note:** If the field at the end of the host presentation space wraps, wrapping occurs when the end of the presentation space is reached.

3. The keyboard mnemonics (see **Send Key** (3) function) cannot be sent using the **Copy String to Field** function.
4. The first byte of the data to be transferred is always placed at the beginning of the field that contains the specified PS position.
5. **DBCS Only:** Double-byte characters can be included as a part of the string.

**Note:** PC400 does not add SO and SI to the string. When you write the strings, including double-byte characters at the DBCS mixed field, generate SO and SI and create the area where double-byte characters are written by using the **Send Key** (3) function in advance.

If both single-byte and double-byte characters exist in a string, the data might be truncated because the data length in EBCDIC is longer than in JISCI. In this case, only the first byte or the second byte of the double-byte character is not written.

If the last character in the original string is the first byte of the double-byte character, the character is not written and not counted in the length.

A control character is converted from single-byte character to double-byte character, or from double-byte character to single-byte character depending on the field condition. A pair of NULL+Control Character between SO and SI is treated as a double-byte control character. For example, the following strings are copied into the single-byte character field or the double-byte character field:

String	Meanings	Single-byte character field	Double-byte character field
X'000C'	(NULL)(FF) X'00'X'0C'	(SB NULL)(SB FF) X'00'X'0C'	(DB NULL)(DB FF) X'0000'X'000C'
X'0E000C0F'	(SO)(DB FF)(SI) X'0E'X'000C'X'0F'	-S error	(DB FF) X'000C'

**Note:** SB means single-byte characters and DB means double-byte characters.

**Note:** 5250 emulation supports a presentation space of 24 rows by 80 columns. In some instances, Communications Manager 5250 emulation displays a 25th row. This occurs when either an error message from the host is displayed or when the operator selects the SysReq key. Personal Communications displays 25th row information on row 24, or on the status bar. For information to be displayed on the status bar, the status bar must be configured. Refer to *Personal Communications Version 4.3 Quick Beginnings* for information on configuring the status bar. By the **EXTEND\_PS** option, an EHLLAPI application can use the same interface with Communications Manager EHLLAPI and valid presentation space is extended when this condition occurs.

## Copy String to Presentation Space (15)

3270	5250	VT
Yes	Yes	Yes

The **Copy String to Presentation Space** function copies an ASCII data string directly into the host presentation space at the location specified by the PS position calling parameter.

## Prerequisite Calls

**Connect Presentation Space** (1).

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 15.	
Data String	String of ASCII data to be copied into the host presentation space.	
Length	Length, in number of bytes, of the source data string. Overridden if in EOT mode.	
PS Position	Position in the host presentation space to begin the copy, a value between 1 and the configured size of your host presentation space.	

## Return Parameters

Return Code	Explanation
0	The <b>Copy String to Presentation Space</b> function was successful.
1	Your program is not connected to a host session.
2	Parameter error or zero length for copy.
5	The target presentation space is protected or inhibited, or incorrect data was sent to the target presentation space (such as a field attribute byte).
6	The copy was completed, but the data was truncated.
7	The host presentation space position is not valid.
9	A system error was encountered.

## Notes on Using This Function

1. The **Copy String to Presentation Space** function is affected by the following options:

- STRLEN/STREOT
- EOT
- EAB/NOEAB
- XLATE/NOXLATE
- PUTEAB/NOPUTEAB
- EAD/NOEAD (for DBCS only)
- NOS0/SPACES0/S0 (for DBCS only)
- EXTEND\_PS/NOEXTEND\_PS

Refer to items 1 and 2 on page 121; 13 and 14 on page 124; 18 on page 125; and 20 and 21 on page 126 for more information.

2. The keyboard mnemonics (see **Send Key** (3) function) cannot be sent using the **Copy String to Presentation Space** function.
3. The string ends when an end-of-text (EOT) delimiter is encountered in the string if EOT mode was selected using the **Set Session Parameters** (9) function. (See “Set Session Parameters (9)” on page 119).
4. Although the **Send Key** (3) function accomplishes the same purpose, this function responds with the prompt and enters a command more quickly. Because the **Send Key** (3) function emulates the terminal operator typing the

data from the keyboard, its process speed is slow for an application operating with a lot of data. This function provides a faster input path to the host.

5. The original data (the copied string) cannot exceed the size of the presentation space.
6. **DBCS Only:** Double-byte characters can be included as a part of the string.

**Note:** PC400 does not add SO and SI to the string. When you write the strings, including double-byte characters at the DBCS mixed field, generate SO and SI and create the area where double-byte characters are written by using the **Send Key** (3) function in advance.

If both single-byte and double-byte characters exist in a string, the data might be truncated because the data length in EBCDIC is longer than in JISCI. If only the first byte or the second byte of the double-byte character must be written into the string, a blank is written.

If the last character in the original string is the first byte of the double-byte character, the character is not written and not counted in the length.

If the character to be written into the last character of the target presentation space is SO/SI or the first byte of the double-byte character, the character is not written and truncated, and not counted in the length.

A control character is converted from single-byte character to double-byte character, or from double-byte character to single-byte character depending on the field condition. A pair of NULL+Control Character between SO and SI is treated as a double-byte control character. For example, the following strings are copied into the single-byte character field or the double-byte character field:

String	Meanings	Single-byte character field	Double-byte character field
X'000C'	(NULL)(FF) X'00'X'0C'	(SB NULL)(SB FF) X'00'X'0C'	(DB NULL)(DB FF) X'0000'X'000C'
X'0E000C0F'	(SO)(DB FF)(SI) X'0E'X'000C'X'0F'	-S error	(DB FF) X'000C'

**Note:** SB means single-byte characters and DB means double-byte characters.

**Note:** 5250 emulation supports a presentation space of 24 rows by 80 columns. In some instances, Communications Manager 5250 emulation displays a 25th row. This occurs when either an error message from the host is displayed or when the operator selects the SysReq key. Personal Communications for Windows 95, Windows 98, and Windows NT always displays the same information on the 24th row. By the **EXTEND\_PS** option, an EHLLAPI application can use the same interface with Communications Manager EHLLAPI and valid presentation space is extended when this condition occurs.

7. This function call may cause a cursor movement to an unexpected position with some host applications. A SendKey function may be a better choice for filling a field than this function.

**Note:** This only occurs with VT sessions or connections to an ASCII host.



# Disconnect from Structured Fields (121)

3270	5250	VT
Yes	No	No

The **Disconnect from Structured Fields** function drops the connection between the emulation program and the EHLLAPI application. The EHLLAPI application must disconnect from the emulation program before exiting from the system. The EHLLAPI application should issue this function request if a previous **Connect for Structured Fields** was issued.

The **Reset System (21)** function will also disconnect any outstanding SF connections.

## Prerequisite Calls

**Connect for Structured Fields (120)**.

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 121	
Data String	See the following table	
Length	Must be 3	Must be 8
PS Position	NA	

## Data String Contents

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID).
	2-4	Reserved.
2-3	5-6	Destination/origin unique ID returned by the Connect for structured field (120) functions.
	7-8	Reserved.

## Return Parameters

Return Code	Explanation
0	The <b>Disconnect from Structured Fields</b> function was successful.
1	A specified host presentation space short session ID was not valid or was not connected.
2	An error was made in specifying parameters.
9	A system error occurred.
40	Disconnected with asynchronous requests pending.

## Notes on Using This Function

1. When a **Disconnect from Structured Fields** function is called, any outstanding asynchronous **Read Structured Fields (126)** or **Write Structured Fields (127)** function requests are returned if the application issues the **Get Request Completion (125)** function call. Use the asynchronous form of this function when cleaning up after issuing a Disconnect call.

- The **Reset System** (21) function will also free any outstanding asynchronous requests (requests that have not been retrieved by the application using the **Get Request Completion** (125) function).

## Disconnect Window Service (102)

3270	5250	VT
Yes	Yes	Yes

The **Disconnect Window Service** function disconnects the window services connection between the EHLLAPI program and the specified host presentation space window.

### Prerequisite Calls

**Connect Window Services** (101).

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 102	
Data String	See the following table	
Length	1	4
PS Position	NA	

### Data String Contents

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2-4	Reserved

### Return Parameters

Return Code	Explanation
0	The <b>Disconnect Window Service</b> function was successful.
1	Your program is not connected for Window Services.
9	A system error occurred.

### Notes on Using This Function

After the **Disconnect Window Service** function has been called, your application no longer manages the presentation space window.

Before exiting the application, you should request a **Disconnect Window Service** function for all presentation spaces that have been connected for Presentation Manager services. If the application exits with an outstanding connection for window services, the subsystem cancels the outstanding connection.

## Disconnect Presentation Space (2)

3270	5250	VT
Yes	Yes	Yes

The **Disconnect Presentation Space** function drops the connection between your EHLLAPI application program and the host presentation space. Also, if a host presentation space is reserved using the **Reserve** (11) function, it is released upon execution of the **Disconnect Presentation Space** function.

## Prerequisite Calls

**Connect Presentation Space** (1).

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 2	
Data String	NA	
Length	NA	
PS Position	NA	

## Return Parameters

Return Code	Explanation
0	The <b>Disconnect Presentation Space</b> function was successful.
1	Your program was not currently connected to the host presentation space.
9	A system error was encountered.

## Notes on Using This Function

1. After the **Disconnect Presentation Space** function is called, functions that interact with the host-connected presentation space are no longer valid (for example, the **Send Key** (3), **Wait** (4), **Reserve** (11) and **Release** (12) functions).
2. Your EHLLAPI application should disconnect from the host presentation space before exiting.
3. The **Disconnect Presentation Space** function does not reset the session parameters to the defaults. Your EHLLAPI application must call the **Reset System** (21) function to accomplish this.

## Find Field Length (32)

3270	5250	VT
Yes	Yes	Yes

The **Find Field Length** function returns the length of a target field in the connected presentation space. This function can be used to find either protected or unprotected fields, but only in a *field-formatted* host presentation space.

This function returns the number of characters contained in the field identified using the call PS position parameter. This includes all characters from the beginning of the target field up to the character preceding the next attribute byte.

## Prerequisite Calls

**Connect Presentation Space** (1).

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 32	
Data String	See the following table	
Length	NA	NA
PS Position	See note below	

**Note: PS Position:** Identifies the field within the host presentation space at which to start the **Find**. It can be the PS position of any byte within the field in which you desire the **Find** to start.

The calling 2-character data string can contain:

Code	Explanation
bb or Tb	This field
Pb	The previous field, either protected or unprotected.
Nb	The next field, either protected or unprotected
NP	The next protected field
NU	The next unprotected field
PP	The previous protected field
PU	The previous unprotected field

**Note:** The b symbol represents a required blank.

## Return Parameters

This function returns a length and a return code.

### Length:

The following lengths are valid:

Length	Explanation
= 0	When return code = 28, field length is 0. When return code = 24, host presentation space is not field formatted.
> 0	Required field length in the host presentation space.

### Return Code:

The following codes are defined:

Return Code	Explanation
0	The <b>Find Field Length</b> function was successful.
1	Your program is not connected to a host session.
2	A parameter error was encountered.
7	The host presentation space position is not valid.
9	A system error was encountered.
24	No such field was found.
28	Field length of 0 bytes.

## Notes on Using This Function

Except when bb or Tb is used as the calling data string, if the field found is the same as the field from which the **Find** started, a return code of 24 is returned.

## Find Field Position (31)

3270	5250	VT
Yes	Yes	Yes

The **Find Field Position** function returns the beginning position of a target field in the host-connected presentation space. This function can be used to find either protected or unprotected fields but only in a *field-formatted* host presentation space.

## Prerequisite Calls

**Connect Presentation Space** (1).

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 31	
Data String	See the following table	
Length	NA	NA
PS Position	See note below	

**Note: PS Position:** Identifies the field within the host presentation space at which to start the **Find**. It can be the PS position of any byte within the field in which you want the **Find** to start.

The calling 2-character data string can contain:

Code	Explanation
bb or Tb	This field
Pb	The previous field, either protected or unprotected
Nb	The next field, either protected or unprotected
NP	The next protected field
NU	The next unprotected field
PP	The previous protected field
PU	The previous unprotected field

**Note:** The b symbol represents a required blank.

## Return Parameters

This function returns a length and a return code.

### Length:

The following lengths are valid:

Length	Explanation
= 0	When return code = 28, field length is 0. When return code = 24, host presentation space is not field formatted.

Length	Explanation
> 0	Relative position of the requested field from the origin of the host presentation space. This position is defined to be the first position after the attribute byte.

#### Return Code:

The following codes are defined:

Return Code	Explanation
0	The <b>Find Field Position</b> function was successful.
1	Your program is not connected to a host session.
2	A parameter error was encountered.
7	The host presentation space position is not valid.
9	A system error was encountered.
24	No such field was found.
28	Field length of 0 bytes.

#### Notes on Using This Function

Except when **bb** or **Tb** is used as the calling data string, if the field found is the same as the field from which the **Find** started, a return code of 24 is returned.

## Free Communications Buffer (124)

3270	5250	VT
Yes	No	No

The **Free Communications Buffer** function returns to management memory a buffer that is no longer required by the application. The application should free the buffer prior to exiting the system.

#### Prerequisite Calls

**Allocate Communications Buffer** (123).

#### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 124	
Data String	See the following table	
Length	Must be 6	Must be 8
PS Position	NA	

#### Data String Contents

Byte		Definition
Standard	Enhanced	
1–2	1–4	Must be 0
3–6	5–8	The address of the buffer

## Return Parameters

Return Code	Explanation
0	The <b>Free Communications Buffer</b> function was successful.
2	An error was made in specifying parameters.
9	A system error occurred.
41	The buffer is in use.

## Notes on Using This Function

1. If the application attempts to free an “in use” buffer, the free request will be denied and a return code of 41 will be returned.
2. An application should request the **Free Communications Buffer** (124) function before exiting for all communication buffers that have been allocated using the **Allocate Communications Buffer** (123) function.
3. The **Reset System** (21) function will free buffers allocated by the **Allocate Communications Buffer** (123) function.

## Get Key (51)

3270	5250	VT
Yes	Yes	Yes

The **Get Key** function lets your EHLAPI application program retrieve a keystroke from a session specified by the **Start Keystroke Intercept** (50) function and either process, accept, or reject that keystroke. By placing this function in a loop, you can use it to intercept a string.

## Prerequisite Calls

**Start Keystroke Intercept** (50).

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 51	
Data String	See the following table	
Length	8	12
PS Position	NA	

## Data String Contents

Byte		Definition
Standard	Enhanced	
1	1	One of the following values: <ul style="list-style-type: none"> <li>• A 1-character presentation space short name (PSID)</li> <li>• A blank or null indicating a function call for the host-connected presentation</li> </ul>
	2–4	Reserved
2–8	5–11	Blanks that hold space for the symbolic representation of the requested data
	12	Reserved

## Return Parameters

This function returns a data string and a return code.

### Data String:

See the following table:

Byte		Definition
Standard	Enhanced	
1	1	One of the following values: <ul style="list-style-type: none"> <li>• A 1-character presentation space short name (PSID)</li> <li>• A blank or null indicating a function call for the host-connected presentation</li> </ul>
	2–4	Reserved
2	5	An option code character, one of the following characters: <ul style="list-style-type: none"> <li>• A for ASCII returned</li> <li>• M for keystroke mnemonic</li> <li>• S for special mnemonic</li> </ul>
3–8	6–11	These 6 bytes of the preallocated buffer space are used internally to enqueue and dequeue keystrokes. Possible combinations include: <ul style="list-style-type: none"> <li>• Byte 3 contains an ASCII character and byte 4 contains X'00'</li> <li>• Bytes 3 and 4 contains a double-byte character</li> <li>• Bytes 3 contains the escape character (either @ or another character specified using the ESC=c option of function 9) and byte 4 contains a 1-byte abbreviation for a function. (See "ASCII Mnemonics" on page 17)</li> <li>• Bytes 5 through 8 might be similar to bytes 3 and 4 if the returned ASCII mnemonic is longer than 2 bytes (for example, if the ASCII mnemonic represents Attn @A@Q, byte 5 contains @ and byte 6 contains Q). If not used, bytes 5 through 8 are set to zero (X'00').</li> </ul>

For clarification, some examples of returned data strings are provided below:

**Note:** The @ symbol is the default escape character. The value of the escape character can be set to any keystroke represented in ASCII by using the ESC=c option of the **Set Session Parameters** (9) function. If the escape character has been changed to another character using this option, the @ symbol in the following examples is replaced by the other character.

### 16-Bit Interface

**EAt** E is the presentation space short name. The keystrokes are returned as ASCII (A), and the returned key is the lowercase letter t. (Bytes 4–8 = X'00').

**EM@2** E is the presentation space short name. The keystrokes are returned as mnemonics, and the returned key is PF2 (Bytes 5–8 = X'00').



## 32-Bit Interface

**EbbbAt** E is the presentation space short name. The keystrokes are returned as ASCII (A), and the returned key is the lowercase letter t. (Bytes 7–11 = X'00').

**EbbbM@2**

E is the presentation space short name. The keystrokes are returned as mnemonics, and the returned key is PF2 (Bytes 8–11 = X'00').

**Return Code:**

The following codes are valid:

Return Code	Explanation
0	The <b>Get Key</b> function was successful.
1	An incorrect presentation space was specified.
5	You specified the AID only option under the <b>Start Keystroke Intercept</b> (50) function, and non-AID keys are inhibited by this session type when EHLLAPI tries to write incorrect keys to the presentation space.
8	No prior <b>Start Keystroke Intercept</b> (50) function was called for this presentation space.
9	A system error was encountered.
20	An undefined key combination was typed.
25	The requested keystrokes are not available on the input queue.
31	Keystroke queue overflowed and keystrokes were lost.

### Notes on Using This Function

1. If a return code of 31 occurs for the **Get Key** function, either:
  - Increase the value of the calling length parameter for the **Start Keystroke Intercept** (50) function, or
  - Execute the **Get Key** function more frequently.

An intercepted keystroke occupies 3 bytes in the buffer. The next intercepted keystroke is placed in the adjacent three bytes. When the **Get Key** function retrieves a keystroke (first in first out, FIFO), the three bytes that it occupied are made available for another keystroke. By increasing the size of the buffer or the rate at which keystrokes are retrieved from the buffer, you can eliminate buffer overflow.

For the PC/3270, another way to eliminate return code 31 is to operate the PC/3270 emulator in the resume mode.

2. You can use the **Send Key** (3) function to pass both original keystrokes and any others that your EHLLAPI application might need to the host-connected presentation space.
3. Keystrokes arrive asynchronously and are enqueued in the keystroke queue that you have provided in your EHLLAPI application program using the **Start Keystroke Intercept** (50) function.
4. The **Get Key** function behaves like a read. When keystrokes are available, they are read into the data area that you have provided in your application.
5. In the case of field support for a session, the application might be interested only in AID keys, for example the Enter key. If so, the **Start Keystroke Intercept** (50) function option code should be set to D (meaning for AID Keys only).

6. To use this function, preallocate memory to receive the returned data string parameter. The statements required to preallocate this memory vary depending on the language in which your application is written. Refer to “Memory Allocation” on page 8 for more information.

## Get Request Completion (125)

3270	5250	VT
Yes	No	No

The **Get Request Completion** function allows an application to determine the status of a previous asynchronous function request issued to the EHLLAPI and to obtain the function parameter list before using the data string again. This function is valid only if the user specified asynchronous (“A”) completion on a previous function call such as **Read Structured Fields** (126) or **Write Structured Fields** (127).

Each asynchronous request requiring the **Get Request Completion** function will return a unique ID from the asynchronous request. The application must save this ID. This ID is the identification used by the **Get Request Completion** function to identify the desired request. The user has three request options using this function:

1. The application can query or wait for a specific asynchronous function request by supplying the request ID of that function and a nonblank session short name.
2. The application can query or wait for the first completed asynchronous function request for a specified session by supplying a request ID of X'0000' and a nonblank session short name.

### Prerequisite Calls

**Connect Structured Fields** (120) and **Allocate Communications Buffer** (123) and either **Read Structured Fields** (126) or **Write Structured Fields** (127).

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 125	
Data String	See the following table	
Length	Must be 14	Must be 24
PS Position	NA	

### Data String Contents

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2–4	Reserved
2	5	N or W N=NOWAIT is required W=WAIT is required
	6–8	Reserved
3–4	9–10	Function request ID.
5–6	11–12	Reserved
7–10	13–16	Reserved
11–12	17–20	Reserved

Byte		Definition
13–14	21–24	Reserved

The **Get Request Completion** function behaves differently depending upon the second character of the parameter string, which is one of the following characters:

- N**     Nowait option: If a specific request ID was supplied and the function has completed, control will be returned to the application with a return code of zero and a completed data string as defined below. If a request ID of zero was supplied and any eligible asynchronous function has completed, control will be returned to the application with a return code of zero and a completed data string as defined below.
- W**     Wait option: If a specific request ID was supplied and the function has not completed, the call will wait until the function has completed before returning to the application. If the supplied request ID was zero and no eligible asynchronous function has completed, the call will wait until a function completes before returning to the calling application. On return, the return code value will be zero and the data string will be completed as defined below.

## Return Parameters

Byte		Definition
Standard	Enhanced	
5–6	11–12	Function number of the completed asynchronous function (126 or 127). (returned)
7–10	13–16	Address of the data string of the completed asynchronous function call. (The application must not reuse the data string until the request has completed). (returned)
11–12	17–20	Length of the data string of the completed asynchronous function call. (returned)
13–14	21–24	Return code of the completed asynchronous function call. (returned)

Return Code	Explanation
0	The <b>Get Request Completion</b> function was successful.
2	An error was made in specifying parameters.
9	A system error was encountered.
38	Requested function was not complete.
42	No matching request was found.

There are some differences between return codes 38 and 42:

1. Return code 38
  - a. If a specific request ID and session were requested, both the session and ID were found but the request is pending (not in a completed state).
  - b. If a zero request ID and a specific session were requested, the specified session has pending requests, but they are not satisfied (complete).
  - c. If a zero request ID and a blank session were requested, pending requests were found but none were satisfied (complete).
2. Return code 42

- a. If a specific request ID and session were requested, the specific request ID was not found in either a pending or a completed state.
- b. If a zero request ID and a specific session were requested, the specific session contains no pending or completed requests.
- c. If a zero request ID and a blank session were requested, no pending or completed requests were found.

### Notes on Using This Function

1. This function is valid only if the user specified asynchronous completion (“A” for “Asynchronous”) on a previous function call such as **Read Structured Fields** or **Write Structured Fields**.
2. If the return code is a 0, the application should check the returned data string for information pertaining to the completion of the requested asynchronous function.

## Lock Presentation Space API (60)

3270	5250	VT
Yes	No	No

The **Lock Presentation Space API** function allows the application to obtain or release exclusive control of the presentation space window over other Windows 32-bit and OS/2 applications. While locked, no other application can connect to the presentation space window.

Successful processing of this function with the Lock causes EHLLAPI presentation space window functions requested from other EHLLAPI applications to be queued until the requesting application unlocks the presentation space. Requests from the locking application are processed normally.

### Prerequisite Calls

#### Connect to Presentation Space (1)

#### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 60	
Data String	See the following table	
Length	Must be 3	Must be 8
PS Position	NA	

#### Data String Contents

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID).
	2–4	Reserved.
2	5	One of the following characters: • L to lock the API. • U to unlock the API.

Byte		Definition
3	6	One of the following characters: • R to return if the presentation space is already locked by an application. • Q to queue the Lock request if the presentation space is already locked by an application.
	7–8	Reserved.

## Return Parameters

Return Code	Explanation
0	The <b>Lock Presentation Space API</b> function was successful.
1	An incorrect host presentation space short session ID was specified or was not connected.
2	An error was made in specifying parameters.
9	A system error was encountered.
43	The API was already locked by another EHLLAPI application (on LOCK) or API not locked (on UNLOCK).

## Notes on Using This Function

The following EHLLAPI functions are queued when a lock is in effect:

- **Send Key** (3)
- **Copy Presentation Space** (5)
- **Search Presentation Space** (6)
- **Copy Presentation Space to String** (8)
- **Release** (11)
- **Reserve** (12)
- **Query Field Attribute** (14)
- **Copy String to Presentation Space** (15)
- **Search Field** (30)
- **Find Field Position** (31)
- **Find Field Length** (32)
- **Copy String to Field** (33)
- **Copy Field to String** (34)
- **Set Cursor** (40)
- **Send File** (90)
- **Receive File** (91)
- **Connect to Presentation Space** (1) with the CONPHYS parameter set in a previous **Set Sessions Parameter** (9) function call.

These queued requests are not serviced until the lock is removed. When the lock is removed, the queued requests are processed in first-in-first-out (FIFO) order. EHLLAPI functions not listed are run as if there was no lock. The requesting application unlocks the presentation space window by one of the following methods:

- Disconnecting from the presentation space while still owning the Lock.
- Issuing the **Reset System** (21) function while still owning the Lock.
- Stopping the application while still owning the Lock.
- Stopping the session.
- Successfully issuing the **Lock Presentation Space API** with the Unlock option.

Before exiting the application, you should unlock any presentation space windows that have been locked with the **Lock Presentation Space API** function. If the application exits with outstanding locks, or a **Reset System (21)**, or **Disconnect Presentation Space (2)** function is issued, the locks are released.

It is recommended that applications lock the presentation space only for short periods of time and only when exclusive use of the presentation space is required.

## Lock Window Services API (61)

3270	5250	VT
Yes	No	No

The **Lock Window Services API** function allows the application to obtain or release exclusive control of the presentation space window over other Windows 32-bit and OS/2 applications. While locked, no other application can connect to the presentation space window.

Successful processing of this function with the Lock causes EHLLAPI presentation space window functions requested from other EHLLAPI applications to be queued until the requesting application unlocks the presentation space. Requests from the locking application are processed normally.

### Prerequisite Calls

**Connect Window Services (101)**

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 61	
Data String	See the following table.	
Length	Must be 3	Must be 8
PS Position	NA	

### Data String Contents

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID).
	2-4	Reserved.
2	5	One of the following characters: • L to lock the API. • U to unlock the API.
3	6	One of the following characters: • R to return if the presentation space is already locked by an application. • Q to queue the Lock request if the presentation space is already locked by an application.
5-6	11-12	Function number of the completed asynchronous function (126 or 127). (returned)
	7-8	Reserved.

## Return Parameters

Return Code	Explanation
0	The <b>Lock Window Services API</b> function was successful.
1	An incorrect host presentation space short session ID was specified or was not connected.
2	An error was made in specifying parameters.
9	A system error was encountered.
38	Requested function was not complete.
43	The API was already locked by another EHLLAPI application (on LOCK) or API not locked (on UNLOCK).

## Notes on Using This Function

The following EHLLAPI functions are queued when a lock is in effect:

- **Window Status** (104)
- **Change Switch List Name** (105)
- **Change PS Window Name** (106)

These queued requests are not serviced until the lock is removed. When the lock is removed, the queued requests are processed in first-in-first-out (FIFO) order.

The requesting application unlocks the presentation space window by one of the following methods:

- Successfully issuing the **Lock Window Services API** with the UNLOCK option.
- Disconnecting from the presentation space while still owning the Lock.
- Issuing the **Reset System** (21) function while still owning the Lock.
- Stopping the application while still owning the Lock.
- Stopping the session.

Before exiting the application, you should Unlock any presentation space windows that have been locked with the **Lock Window Services API** function. If the application exits with outstanding locks, the subsystem releases the locks.

It is recommended that applications lock the presentation space only for short periods of time and only when exclusive use of the presentation space is required.

## Pause (18)

3270	5250	VT
Yes	Yes	Yes

The **Pause** function waits for a specified amount of time. It should be used in place of *timing loops* to wait for an event to occur. A **Pause** function can be ended by a host event if a prior **Start Host Notification** (23) function has been called and the IPAUSE option is selected.

## Prerequisite Calls

None.

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 18	
Data String	NA	
Length	Contains the pause duration in half-second increments	
PS Position	NA	

## Return Parameters

Return Code	Definition
0	The wait duration has expired.
9	An internal system error was encountered. The time results are unpredictable.
26	The host session presentation space or OIA has been updated. Use the <b>Query Host Update</b> (24) function to get more information.

## Notes on Using This Function

1. Selecting the FPAUSE or IPAUSE option using the **Set Session Parameters** (9) function affects the length of the pause you get when you call this function. See item 6 on page 121 for more information.
2. The value entered in the calling length parameter is the maximum number of half-second intervals that the **Pause** function waits. For a pause of 20 seconds, a hex value of 0028 (decimal 40) must be passed in the calling length parameter.
3. If you use the IPAUSE option, once a pause has been satisfied by a host event, you should call the **Query Host Update** (24) function to clear the queue prior to the next **Pause** function. The **Pause** function will continue to be satisfied with the pending event until the **Query Host Update** (24) function is completed.
4. A practical maximum value for the **Pause** function is 2400. You should not use the **Pause** function for these kinds of tasks:
  - Delay for very long durations (of several hours, for example).
  - Delay for more than a moderate length of time (20 minutes) before checking the system time-of-day clock and proceeding with your EHLLAPI program execution.
  - With applications requiring a high-resolution timer because the time interval created by a **Pause** function is approximate.
  - Set the time interval to zero in a loop.
5. IPAUSE set and the interruptible pause allow an EHLLAPI application to determine whether the specified host presentation space (PS) or operator information area (OIA) is updated. The following three functions are used:
  - **Start Host Notification** (23)
  - **Query Host Update** (24)
  - **Stop Host Notification** (25)

By using IPAUSE when the **Start** function is called, you can make an application wait until the host presentation space or OIA (or both) receives an update. When the receive is completed and the application can issue the **Query** function to determine the changes, **Pause** terminates. Then the application issues the **Search Presentation Space** (6) to check whether the expected update occurred.



## Post Intercept Status (52)

3270	5250	VT
Yes	Yes	Yes

The **Post Intercept Status** function informs the Personal Communications emulator that a keystroke obtained through the **Get Key** (51) function was accepted or rejected. When the application rejects a keystroke, the **Post Intercept Status** function issues a beep.

### Prerequisite Calls

**Start Keystroke Intercept** (50).

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 52	
Data String	See the following table	
Length	Must be 2	Must be 8
PS Position	NA	

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1	1	One of the following values: <ul style="list-style-type: none"> <li>The 1-letter short name of the presentation space.</li> <li>A blank or null indicating a function call for the host-connected presentation space.</li> </ul>
	2–4	Reserved
2	5	One of the following characters: <ul style="list-style-type: none"> <li>A for accepted keystroke.</li> <li>R for rejected keystroke.</li> </ul>
	6–8	Reserved.

### Return Parameters

Return Code	Explanation
0	The <b>Post Intercept Status</b> function was successful.
1	An incorrect presentation space was specified.
2	An incorrect session option was specified.
8	No prior <b>Start Keystroke Intercept</b> (50) function was called for this presentation space ID.
9	A system error was encountered.

## Query Close Intercept (42)

3270	5250	VT
Yes	Yes	Yes

The **Query Close Intercept** function allows the application to determine if the close option was selected.

## Prerequisite Calls

**Start Close Intercept (41).**

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 42	
Data String	1-character short session ID of the host presentation space	
Length	Must be 1	Must be 4
PS Position	NA	

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2-4	Reserved

## Return Parameters

Return Code	Explanation
0	A close intercept event did not occur.
1	The presentation source was not valid.
2	An error was made in specifying parameters.
8	No prior <b>Start Close Intercept (41)</b> function was called for this host presentation space.
9	A system error occurred.
12	The session stopped.
26	A close intercept occurred since the last query close intercept call.

## Query Communications Buffer Size (122)

<i>3270</i>	<i>5250</i>	<i>VT</i>
Yes	No	No

The **Query Communications Buffer Size** function allows an application to determine both the maximum and the optimum buffer sizes supported by the emulation program.

## Prerequisite Calls

None.

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 122	
Data String	See the following table	

	Standard Interface	Enhanced Interface
Length	Must be 9	Must be 20
PS Position	NA	

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2–4	Reserved
2–3	5–8	16- or 32-bit field for the optimum supported inbound buffer size (Returned value)
4–5	9–12	16- or 32-bit field for the maximum supported inbound buffer size (Returned value)
6–7	13–16	16- or 32-bit field for the optimum supported outbound buffer size (Returned value)
8–9	17–20	16- or 32-bit field for the maximum supported outbound buffer size (Returned value)

## Return Parameters

Return Code	Explanation
0	The <b>Query Communications Buffer Size</b> function was successful.
1	A specified host presentation space short session ID was not valid or was not connected.
2	An error was made in specifying parameters.
9	A system error occurred.
10	The function was not supported by the emulation program.

## Notes on Using This Function

1. There is no way to require the user to use this function. It is not a required function so that the application can be tailored to run on any system.
2. The buffer sizes returned represent the record sizes that are actually transmitted across the medium. For a DDM connection, the 8-byte header supplied in the **Read** and **Write Structured Fields** data buffer is stripped off and 1 byte containing the structured field AID value is prefixed. The application should compare the size of the actual data in the data buffer (which does not include the 8-byte header) with the buffer sizes returned by the **Query Communications Buffer Size** minus 1 byte. For destination/origin connections, the 8-byte header supplied in the **Read** and **Write Structured Fields** data buffer is stripped off and 9 bytes are then prefixed to the data. The application should compare the size of the actual data in the data buffer (which does not include the 8-byte header) with the buffer size returned by the **Query Communications Buffer Size** minus 9 bytes.
3. The maximum buffer sizes returned represent the maximum number of bytes supported by the workstation hardware and by the emulator. The maximum buffer size can be used only if the host is also configured to accept at least these maximum sizes.
4. The optimum buffer sizes returned represent the optimum number of bytes supported by the both the workstation hardware and the emulator. Some network configurations might set transmission limits smaller than these values.

In these cases, the data transfer buffer size override value in the emulator configuration profile will be used for structured field support. The **Query Communications Buffer Size** will reflect any buffer size override values entered in the emulator configuration profile.

## Query Cursor Location (7)

3270	5250	VT
Yes	Yes	Yes

The **Query Cursor Location** function indicates the position of the cursor in the host-connected presentation space by returning the cursor position.

### Prerequisite Calls

**Connect Presentation Space (1).**

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 7	
Data String	NA	
Length	NA	
PS Position	NA	

### Return Parameters

This function returns a length and a return code.

#### Length:

Host presentation space position of the cursor.

#### Return Code:

The following codes are defined:

Return Code	Explanation
0	The <b>Query Cursor Location</b> function was successful.
1	Your program is not currently connected to a host session.
9	A system error was encountered.

## Query Field Attribute (14)

3270	5250	VT
Yes	Yes	Yes

The **Query Field Attribute** function returns the attribute byte of the field containing the input host presentation space position. This information is returned in the returned length parameter.

For the PC/3270, note also that:

- The returned length parameter is set to 0 if the screen is unformatted.
- Attribute bytes are equal to or greater than hex C0.

## Prerequisite Calls

Connect Presentation Space (1).

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 14.	
Data String	NA.	
Length	NA.	
PS Position	Identifies the target. This can be the PS position of any byte within the target field.	

## Return Parameters

This function returns a length and a return code.

### Length:

The attribute value if the screen is formatted, or 0 if the screen is unformatted.

### Return Code:

The following codes are defined:

Return Code	Explanation
0	The <b>Query Field Attribute</b> was successful.
1	Your program is not currently connected to a host session.
7	The host presentation space position is not valid.
9	A system error was encountered.
24	Attribute byte not found or unformatted host presentation space.

## Notes on Using This Function

The returned field attributes are defined in the following tables. The bit positions are in IBM format with bit 0 as the leftmost bit in the byte.

- 3270 field attribute:

Bit Position	Meaning
0–1	Both = 1, field attribute byte
2	Unprotected/protected 0 = Unprotected data field 1 = Protected field
3	A/N 0 = Alphanumeric data 1 = Numeric data only
4–5	I/SPD 00 = Normal intensity, pen not detectable 01 = Normal intensity, pen detectable 10 = High intensity, pen detectable 11 = Nondisplay, pen not detectable
6	Reserved

Bit Position	Meaning
7	MDT 0 = Field has not been modified 1 = Field has been modified

- 5250 field attributes:

Bit Position	Meaning
0	Field attribute flag 0 = Nonfield attribute flag 1 = Field attribute flag
1	Visibility 0 = Nondisplay 1 = Display
2	Unprotected/protected 0 = Unprotected data field 1 = Protected field
3	Intensity 0 = Normal intensity 1 = High intensity
4–6	Field type 000 = Alphanumeric data: All characters are available 001 = Alphabet only: Uppercase and lowercase, comma, period, hyphen, blank, or Dup key are available 010 = Numeric shift: Automatic shift for number 011 = Numeric data only: 0–9, comma, period, plus, minus, blank, or Dup key are available 101 = Numeric data only: 0–9, or Dup key are available 110 = Magnetic stripe reading device data only 111 = Signed-numeric data: 0–9, plus, minus, or Dup key are available
7	MDT 0 = Field has not been modified 1 = Field has been modified

## Query Host Update (24)

3270	5250	VT
Yes	Yes	Yes

The **Query Host Update** function lets the programmed operator determine if the host has updated the host presentation space or OIA because:

- The **Start Host Notification** (23) function was called (on first call to the **Query Host Update** function only)
- The previous call to the **Query Host Update** function (for all calls to the **Query Host Update** function except the first).

### Prerequisite Calls

**Start Host Notification** (23).

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 24	
Data String	1-character short name of the host presentation space, or a blank or null indicating request for updates to host-connected presentation space	
Length	1 is implied	4 is implied
PS Position	NA	

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2–4	Reserved

## Return Parameters

Return Code	Definition
0	No updates have been made since the last call.
1	An incorrect host presentation space was specified.
8	No prior <b>Start Host Notification</b> (23) function was called for the host presentation space ID.
9	A system error was encountered.
21	The OIA was updated.
22	The presentation space was updated.
23	Both the OIA and the host presentation space were updated.
44	Printing has completed in the printer session.

## Notes on Using This Function

The target presentation space must be specified in the data string, even though a connection to the host presentation space is not necessary to check for updates.

## Query Window Coordinates (103)

3270	5250	VT
Yes	Yes	Yes

The **Query Window Coordinates** function requests the coordinates for the window of a presentation space. The window coordinates are returned in pels.

**Note:** (0,0) indicates the top-left of the window.

## Prerequisite Calls

**Connect Window Services** (101).

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 103	
Data String	1-character short session ID of the host presentation space	
Length	17 is implied	20 is implied
PS Position	NA	

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1	1	One of the following values: <ul style="list-style-type: none"> <li>A 1-character presentation space short name (PSID)</li> <li>A blank or null indicating a function call for the current connection presentation space</li> </ul>
	2–4	Reserved
2–17	5–20	Reserved

## Return Parameters

This function returns a data string and a return code.

Byte		Definition
Standard	Enhanced	
1	1	One of the following values: <ul style="list-style-type: none"> <li>A 1-character presentation space short session ID</li> <li>A blank or null indicating a function call for the current connection presentation space</li> </ul>
	2–4	Reserved
2–17	5–20	Four 32-bit unsigned integers that return:
2–5	5–8	XLeft Long integer in pels of the left X coordinate of the rectangular window relative to the desktop window
6–9	9–12	YBottom Long integer in pels of the bottom Y coordinate of the rectangular window relative to the desktop window
10–13	13–15	XRight Long integer in pels of the right X coordinate of the rectangular window relative to the desktop window
14–17	16–20	YTop Long integer in pels of the top Y coordinate of the rectangular window relative to the desktop window

### Return Code:

The following codes are defined:

Return Code	Explanation
0	The <b>Query Window Coordinates</b> function was successful.
1	Your program was not currently connected to the host session.
9	A system error occurred.
12	The session stopped.



## Query Session Status (22)

3270	5250	VT
Yes	Yes	Yes

The **Query Session Status** function is used to obtain session-specific information.

### Prerequisite Calls

None.

### Call Parameters

	16-bit	32-bit
Function Number	Must be 22.	
Data String	An 18/20-byte string consisting of a 1-byte short name of the target presentation space plus 17 bytes for returned data. Position 1 can be filled with: <ol style="list-style-type: none"> <li>1. A blank or a null to indicate a request for the host_connected presentation space.</li> <li>2. An * (asterisk) to indicate a request for the keyboard-owner presentation space.</li> </ol>	
Length	Must be 18	Must be 20
PS Position	NA	

### Return Parameters

This function returns a data string and a return code.

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2–4	Reserved
2–9	5–12	Session long name (same as short name)
10	13	<b>Session Type</b> <b>D</b> 3270 display <b>E</b> 3270 printer <b>F</b> 5250 display <b>G</b> 5250 printer <b>H</b> ASCII VT

Byte		Definition
11	14	Session characteristics expressed by a binary number including the following session-characteristics bits  <b>Bit 0</b> EAB 0: Session has the basic attribute. 1: Session has the extended attribute  <b>Bit 1</b> PSS 0: Session does not support the programmed symbols 1: Session supports the programmed symbols  <b>Bits 2–7</b> Reserved
12–13	15–16	Number of rows in the host presentation space, expressed as a binary number
14–15	17–18	Number of columns in the host presentation space, expressed as a binary number
16–17	19–20	Host code page expressed as a binary number
18		Reserved

**Return Code:**

The following codes are defined:

Return Code	Explanation
0	The <b>Query Session Status</b> function was successful.
1	An incorrect host presentation space was specified.
2	An incorrect string length was made.
9	A system error was encountered.

**Notes on Using This Function**

1. To use this function, preallocate memory to receive the returned data string parameter. The statements required to preallocate this memory vary depending on the language in which your application is written. See “Memory Allocation” on page 8 for more information.

**Query Sessions (10)**

3270	5250	VT
Yes	Yes	Yes

The **Query Sessions** function returns a 16-byte (12-byte for standard interface) data string describing each host session.

**Prerequisite Calls**

None.

**Call Parameters**

Function	Description	
	Standard Interface	Enhanced Interface
Function Number	Must be 10	
Data String	Preallocated string of 16nbytes long (12nfor 16-bit) (n =number of sessions) or more	

Function	Description	
Length	12nbytes	16nbytes
PS Position	NA	

**Note:** When the length is not matched to the number of sessions, the return code is 2.

## Return Parameters

This function returns a data string, a length, and a return code.

### Data String:

The returned data string is  $16n$  bytes long ( $12n$  for standard interface), where  $n$  is the number of host sessions. The descriptors are concatenated into the data string and each session type, and presentation space size of a host session.

The format of each 16-byte (12-byte for standard interface) session descriptor is as follows:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2–4	Reserved
2–9	5–12	Session long name (same as short name)
10	13	Connection type H=host
	14	Reserved
11–12	15–16	Host presentation space size (this is a binary number and is not in display format). If the session type is a print session, the value is 0.

### Length:

The number of host sessions started.

### Return Code:

The following codes are defined:

Return Code	Explanation
0	The <b>Query Sessions</b> function was successful.
2	An incorrect string length was made.
9	A system error was encountered.

## Notes on Using This Function

1. If an application program receives RC=2 or RC=0, the number of the active sessions is returned in the length field. The application program can recognize the minimum string length by this number.
2. The **Query Sessions** function is affected by the CFGSIZE/NOCFGZISE session option (see item 16 on page 124 for more information) and by the EXTEND\_PS/NOEXTEND\_PS option (see item 22 on page 126 for more information).

**Notes:**

1. When NOCFGSIZE is set in **Set Session Parameters(9)** for a 5250 session, the value of presentation space size returned in byte position 11 and 12 from **Query Sessions(10)** will be changed in accordance with the selection of EXTEND\_PS or NOEXTEND\_PS.
2. When EXTEND\_PS is set in **Set Session Parameters(9)**, presentation space size returned from **Query Sessions(10)** will include the size of the message line, if it exists.
3. When NOEXTEND\_PS is set, the value will not change regardless of the existence of a message line. In the case of 25 row, 80 column presentation space, the value can be 1920 or 2000.

**Query System (20)**

<i>3270</i>	<i>5250</i>	<i>VT</i>
Yes	Yes	Yes

The **Query System** function can be used by an EHLLAPI application program to determine the level of Personal Communications support and other system-related values. This function returns a string that contains the appropriate system data. Most of this information is for use by a service coordinator when you call the IBM Support Center after receiving a return code 9 (a system error was encountered).

The bytes in this returned string are defined below under "Return Parameters."

**Prerequisite Calls**

None.

**Call Parameters**

	<b>Standard Interface</b>	<b>Enhanced Interface</b>
Function Number	Must be 20	
Data String	Preallocated string of 35 bytes	36 bytes
Length	Must be 35	Must be 36
PS Position	NA	

**Return Parameters**

This function returns a data string and a return code.

**Data String:**

A data string of 35 bytes (for 16-bit) or 36 bytes (for 32-bit) is returned. The bytes are defined as follows:

<b>Byte</b>		<b>Definition</b>
Standard	Enhanced	
1	1	EHLLAPI version number
2-3	2-3	EHLLAPI level number
4-9	4-9	Reserved
10-12	10-12	Reserved
13	13	Hardware base, U=Unable to determine

Byte		Definition
14	14	Program type, where P=IBM Personal Communications
15–16	15–16	Reserved
17–18	17–18	PCOMM version/level as a 2-byte ASCII value
19	19	Reserved
20–23	20–23	Reserved
24–27	24–27	Reserved
28–29	28–29	Reserved
	30	Reserved
30–31	31–32	NLS type expressed as a 2-byte binary number
32	33	1-byte printable ASCII code representing type of monitor being used as follows: <ul style="list-style-type: none"> <li>• A=Personal System/2 Monochrome</li> <li>• B=Personal System/2 Monochrome Model 30</li> <li>• C=CGA</li> <li>• E=EGA</li> <li>• G=MCGA</li> <li>• H=XGA</li> <li>• M=Monochrome</li> <li>• V=VGA</li> <li>• U=Unknown</li> </ul>
33–35	34–36	Reserved

## Return Code

The following codes are defined:

Return Code	Explanation
0	The <b>Query System</b> function was successful; data string has been returned.
1	EHLAPI is not loaded. (PC/3270 only)
2	An incorrect string length was specified. (PC/3270 only)
9	A system error was encountered.

## Notes on Using This Function

To use this function, preallocate memory to receive the returned data string parameter. See “Memory Allocation” on page 8 for more information.

## Read Structured Fields (126)

<i>3270</i>	<i>5250</i>	<i>VT</i>
Yes	No	No

The **Read Structured Fields** function allows an application to read structured field data from the host application. If the call specifies “S” (for Synchronous), the application does not receive control until the **Read Structured Fields** is completed. If the call specifies “A” (for Asynchronous), the application receives control immediately after the call. If the call specifies “M” (for Asynchronous, message

mode), the application receives control immediately after the call. The application can wait for the message. In any case (“S”, “A”, or “M”), the application provides the buffer address in which the data from the host is to be placed.

For a successful asynchronous completion of this function, the following statements apply:

The return code field in the parameter list might not contain the results of the requested I/O. If the return code is not 0, the request failed. The application must take the appropriate action based on the return code.

If the return code for this request is 0, the application must use the request ID returned with this function call to issue the **Get Request Completion** function call to determine the completion results of the function associated with the request ID. The **Get Request Completion** function call returns the following information:

1. Function request ID
2. Address of the data string from the asynchronous request
3. Length of the data string
4. Return code of the completed function

## Prerequisite Calls

**Connect for Structured Fields** (120) and **Allocate Communication Buffer** (123).

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 126	
Data String	See the following table	
Length	8, 10 or 14	20
PS Postion	NA	

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID).
	2–4	Reserved.
2	5	S or A or M  <b>S =</b> Synchronous. Control is not returned to the application until the read is satisfied.  <b>A =</b> Asynchronous. Control is returned immediately to the application, can wait for the event object.  <b>M =</b> Asynchronous. Control is returned immediately to the application, can wait for the message.
	6	Reserved.
3–4	7–8	2-byte destination/origin ID.
5–8	9–12	4-byte address of the buffer into which the data is to be read. The buffer must be obtained using the <b>Allocate Communications Buffer</b> (123) function.

Byte		Definition
9–10	13–16	Reserved.
11–12	17–20	When “M” is specified in position 2 the window handle of the window that receives the message should be set. The message is a return value of RegisterWindowMessage (“PCSHLL”)(not equal 0).
13–14		The data in these positions is ignored by EHLLAPI. However, no error is caused if the migrating program has data in these positions. This data is accepted to provide compatibility with migrating applications.

## Return Parameters

This function returns a data string and a return code.

### Data String:

If “A” (asynchronous) is specified in position 5, (2 for standard interface) and the function is completed successfully, the following data string is returned:

Byte		Definition
Standard	Enhanced	
9–10	13–14	2-byte function request ID. It is used by the <b>Get Request Completion</b> (125) function to determine the completion of this function call.
	15–16	Reserved.
	17–20	4-byte value in which the event object address is returned by EHLLAPI. The application can wait for this event object. When the event object is cleared, the application must issue the <b>Get Request Completion</b> (125) function call (32-bit only).

**Note:** An event object address is returned for each successful asynchronous request. The event object should not be used again. A new event object is returned for each request and is valid for only the duration of that request.

### Data String:

If “M” (asynchronous message mode) is specified in position 5 (2 for 16-bit applications) and the function is completed successfully, the following data string is returned:

Byte		Definition
9–10	13–14	A 2-byte function request ID. It is used by the <b>Get Request Completion (125)</b> function to determine the completion of this function call.
	15–16	Reserved.
11–12	17–18	Task ID of asynchronous message mode.
	19–20	Reserved.

**Note:** If the function is completed successfully, an application window receives a message. The message is a return value of RegisterWindowMessage (“PCSHLL”). wParam parameter contains Task ID returned by the function call. HIWORD of lParam parameter contains Return Code 0, which shows the function was successful, and LOWORD of lParam parameter contains function number 126.

**Return Code:**

The following codes are defined:

Return Code	Explanation
0	The <b>Read Structured Fields</b> function was successful.
1	A specified host presentation space short session ID was not valid or was not connected.
2	An error was made in specifying parameters.
9	A system error occurred.
11	Resource unavailable (memory unavailable).
35	Request rejected. An outbound transmission from the host was canceled.
36	Request rejected. Lost contact with the host.
37	The function was successful, but the host is inbound disabled.

**Notes on Using This Function**

1. Return code 35 will be returned when the first **Read Structured Fields** or **Write Structured Fields** is requested after an outbound transmission from the host is canceled. Corrective action is the responsibility of the application.
2. Return code 36 requires that the application disconnect from the emulation program and then reconnect to reestablish communication with the host. Corrective action is the responsibility of the application.
3. Return code 37 will be returned if the host is inbound disabled. The **Read Structured Fields** function was successfully requested.
4. The EHLLAPI allows for a maximum of 20 asynchronous requests per application to be outstanding. A return code for unavailable resources (RC=11) is returned if more than 20 asynchronous requests are attempted.
5. If you are using an IBM Global Network connection, the maximum number of asynchronous requests is 10.

The structured field data contains the application structured fields received from the host. Structured field headers are removed by the EHLLAPI before the structured field data reaches the application.

The structured field data format is as follows:

Offset	Length	Contents
0	1 word	X'0000'.
2	1 word	m (message length: The number of bytes of data in the message, the number does not include the buffer header prefix, which contains 8 bytes). This value is returned by EHLLAPI.
4	1 word	n (buffer size: the supplied length of the data buffer that does include the 8-byte message header). This value must be set by the application.
6	1 word	X'C000'.
8	8 bytes	Length of the first (or only) structured field message.
10	1 byte	First nonlength byte of the structured field message.
		⋮



Offset	Length	Contents
m+7	1 byte	Last byte in the structured field message.

Bytes 0 through 7 are the buffer header. These first 8 bytes are used by the emulation program. The user section of the buffer begins with offset 8. Bytes 8 and 9 contain the number of bytes in the first structured field (a structured field message can contain multiple structured fields), including 2 bytes for bytes 8 and 9. Bytes 8 through  $m+7$  are used for the structured field message received from the host (which could contain multiple structured fields).

The using application must furnish the complete buffer with the word at offset 0 set to zero. The buffer length must be in the word at offset 4. The word at offset 6 must be X'C000'. The emulation program will place the data message beginning at offset 8 and place the length of the message in the word at offset 2. The buffer length is not disturbed by EHLLAPI.

**Synchronous Requests:** When **Read Structured Fields** is requested synchronously (the S option in the data string), control is returned to the application only after the request is satisfied. The application can assume:

- The return code is correct.
- The data in the communications buffer (read buffer) is correct.
- The host is no longer processing the **Read Structured Fields** request.

**Asynchronous Requests:** When **Read Structured Fields** is requested asynchronously (the A option in the data string), the application *cannot* assume:

- The return code is correct.
- The data in the communications buffer (read buffer) is correct.
- The host is no longer processing the **Read Structured Fields** request.

When requested asynchronously, EHLLAPI returns the following values:

- A 16-bit Request ID in positions 13–14 (9–10 for standard interface) of the data string
- The address of a event object in positions 17—20 of the data string

These are used to complete the asynchronous **Read Structured Fields** call.

The following steps must be completed to determine the outcome of an asynchronous **Read Structured Fields** function call:

- If the EHLLAPI return code is not zero, the request failed. No asynchronous request has been made. The application must take appropriate actions before attempting the call again.
- If the return code is zero, the application should wait until the event object is in the signaled state by using the **Get Request Completion** (125) function or **Wait For SingleObject**. The event object should not be reused. The event object is valid only for the duration of the **Read Structured Fields** function call through the completion of the **Get Request Completion** (125) function call.
- Once the event object is in the signaled state, use the returned 16-bit Request ID as the Request ID parameter in a call to the **Get Request Completion** (125) function. The data string returned from the **Get Request Completion** (125) function call contains the final return code of the **Read Structured Fields** function call.

When **Read Structured Fields** is requested asynchronously (the M option in the data string), the application *cannot* assume:

- The return code is correct.
- The data in the communications buffer (read buffer) is correct.
- The host is no longer processing the **Read Structured Fields** request.

When requested asynchronously with the M option, EHLLAPI returns the following values:

- A 16-bit Request ID in positions 13–14 (9–10 for standard interface) of the data string
- Task ID of asynchronous message mode in positions 17–18 (11–12 for standard interface) of the data string.

These are used to complete the asynchronous **Read Structured Fields** call.

## Receive File (91)

3270	5250	VT
Yes	Yes	No

The **Receive File** function is used to transfer a file from the host session to the workstation session. It is used the same way as the RECEIVE command is used in the PC/3270. The **Receive File** function can be called by an EHLLAPI application program.

### Prerequisite Calls

None.

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 91.	
Data String	Refer to the examples.	
Length	Length, in number of bytes, of the data string. Overridden if in EOT mode.	

Following are examples of the data strings for SBSC:

#### 3270 Session

- To receive the file from the VM/CMS host system:  
*pc\_filename [id:]fn ft [fm] [(option)]*
- To receive the file from the MVS/TSO host system:  
*pc\_filename[id:]dataset [(member)] [/password] [option]*
- To receive the file from the CICS host system:  
*pc\_filename [id:]host\_filename [(option)]*

#### 5250 Session

- To receive the file from the AS/400 host system:  
*pc\_filename [id:]library file member [option]*

Following are examples of the data strings for DBCS:

### 3270 Session

- To receive the file from the VM/CMS host system:  
`pc_filename [id:]fn ft [fm] [(option)]`
- To receive the file from the MVS/TSO host system:  
`pc_filename [id:]dataset [(member)] [/password]  
[(option)]`
- To receive the file from the CICS host system:  
`pc_filename [id:]host_filename [(option)]`

### 5250 Session

- To receive the file from the AS/400 host system:  
`pc_filename [id:]library file member [option]`

**Note:** Parameters within [ ] are optional. Available options are listed below.

Host System	Common Options
VM/CMS	ASCII, JISCI, CRLF, APPEND, TIME n, CLEAR, NOCLEAR, PROGRESS, QUIET
MVS/TSO	ASCII, JISCI, CRLF, APPEND, TIME (n), CLEAR, NOCLEAR, PROGRESS, QUIET, AVBLOCK TRACKS CYLINDERS
CICS	ASCII, JISCI, CRLF, NOCRLF, BINARY, TIME n, CLEAR, NOCLEAR, PROGRESS, QUIET
OS/400	ASCII, JISCI, CRLF, APPEND, TIME n, CLEAR, NOCLEAR, PROGRESS, QUIET

**Note:** JISCI is valid in a DBCS session for Japan only and ASCII is valid for all other SBCS and DBCS sessions.

Other options specified will be passed to the host transfer program. The file transfer program on the host side either uses them, ignores them, or returns an error. Consult the host transfer program documentation to see a complete list of the options supported.

### Return Parameters

Return Code	Explanation
2	Parameter error or you have specified a length that is too long (more than 255 bytes) for the EHLAPI buffer. The file transfer was unsuccessful.
3	File transfer complete.
4	File transfer complete with segmented records.
9	A system error was encountered.
27	File transfer terminated because of either a Cancel button or the timeout set by the <b>Set Session Parameter</b> (9) function.
101	File transfer was successful (transfer to/from CICS).

If you receive return code 2 or 9, there is a problem with the system or with the way you specified your data string.

Other return codes can also be received, which relate to message numbers generated by the host transfer program. For transfers to a CICS host transfer program, subtract 100 from the return code to give you the numeric portion of the message. For example, a return code of 101 would mean that the message number INW0001 was issued by the host. For other host transfer programs, just use the

return code as the numerical part of the message. For example, a return of 34 would mean that message TRANS34 was issued by the host transfer program. The documentation for your host transfer program should give more information about the meanings of the specific messages.

Operating system error codes reported by EHLLAPI are greater than 300. To determine the error code, subtract 300 and refer to the operating system documentation for return codes.

### Notes on Using This Function

1. Four sets of parameters under the **Set Session Parameters** (9) function are related to this function. They are the STRLEN/STREOT, EOT=c, QUIET/NOQUIET and the TIMEOUT=c/TIMEOUT=0 session options. See items 1 and 2 on page 121 and items 7 and 8 on page 122 for more information.
2. If no path is specified when the **Receive File** function is executed, the received file is stored in the current subdirectory, which is the directory in which your application is running.

## Release (12)

3270	5250	VT
Yes	Yes	Yes

The **Release** function unlocks the keyboard that is associated with the host presentation space reserved using the **Reserve** (11) function.

### Prerequisite Calls

**Connect Presentation Space** (1).

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 12	
Data String	NA	
Length	NA	
PS Position	NA	

### Return Parameters

Return Code	Explanation
0	The <b>Release</b> function was successful.
1	Your program is not connected to a host session.
9	A system error was encountered.

### Notes on Using This Function

If you do not **Release** a host presentation space reserved by using the **Reserve** (11) function, you are locked out of that session until you call the **Reset System** (21) function, you call the **Disconnect Presentation Space** (2) function, or you terminate the EHLLAPI application program.

## Reserve (11)

3270	5250	VT
Yes	Yes	Yes

The **Reserve** function locks the keyboard that is associated with the host-connected presentation space to block input from the terminal operator.

The reserved host presentation space remains locked until one of the following occurs:

- **Connect** (1) function is executed to a new session.
- **Disconnect Presentation Space** (2) function is executed.
- **Release** (12) function is executed.
- **Reset System** (21) function is executed.
- **Start Keystroke Intercept** (50) function is executed.
- EHELLAPI application program is terminated.

### Prerequisite Calls

**Connect Presentation Space** (1).

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 11	
Data String	NA	
Length	NA	
PS Postion	NA	

### Return Parameters

Return Code	Explanation
0	The <b>Reserve</b> function was successful.
1	Your program is not connected to a host session.
5	Presentation space cannot be used.
9	A system error was encountered.

### Notes on Using This Function

1. If your EHELLAPI application program is sending a series of transactions to the host, you might need to prevent the user from gaining access to that session until your application processing is complete.
2. The keyboard input that a user makes while the keyboard is locked by this function is enqueued and processed after the session is terminated.
3. This function locks both the mouse and the keyboard input. The application program must unlock the presentation space to enable either the mouse or the keyboard input.

## Reset System (21)

3270	5250	VT
Yes	Yes	Yes

The **Reset System** function reinitializes EHLLAPI to its starting state. The session parameter options are reset to their defaults. Event notification is stopped. The reserved host session is released. The host presentation space is disconnected. Keystroke intercept is disabled.

You can use the **Reset System** function during initialization or at program termination to reset the system to a known initial condition.

### Prerequisite Calls

None.

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 21	
Data String	NA	
Length	NA	
PS Postion	NA	

### Return Parameters

Return Code	Definition
0	The <b>Reset System</b> function was successful.
1	EHLLAPI is not loaded.
9	A system error was encountered.

### Notes on Using this Function

For the PC/3270, this function can be used to check whether EHLLAPI is loaded. Place a call to this function at the start of your application and check for a return code of 1.

## Search Field (30)

3270	5250	VT
Yes	Yes	Yes

The **Search Field** function examines a field within the connected host presentation space for the occurrence of a specified string. If the target string is found, this function returns the decimal position of the string numbered from the beginning of the host presentation space. (For example, in a 24-row by 80-column presentation space, the row 1, column 1 position is numbered 1 and the row 5, column 1 position is numbered 321.)

This function can be used to search either protected or unprotected fields, but only in a *field-formatted* host presentation space.

**Note:** If the field at the end of the host presentation space wraps, wrapping occurs when the end of the presentation space is reached.

### Prerequisite Calls

**Connect Presentation Space (1).**

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 30.	
Data String	Target string for search.	
Length	Length of the target data string. Overridden in EOT mode.	
PS Position	Identifies the target field. For SRCHALL, this can be the PS position of any byte within the target field. For SRCHFROM, it is the beginning point of the search for SRCHFRWD or the ending point of the search for SRCHBKWD. See note 3.	

## Return Parameters

This function returns a length and a return code.

### Length:

The following codes are defined:

Length	Explanation
= 0	The string was not found.
> 0	The string was found at the indicated host presentation space position.

### Return Code:

The following codes are defined:

Return Code	Explanation
0	The <b>Search Field</b> function was successful.
1	Your program is not connected to a host session.
2	Parameter error. Either the string length was zero, or EOT mode was specified but no EOT character was found in calling data string.
7	The host presentation space position is not valid.
9	A system error was encountered.
24	The search string was not found, or the host presentation space was unformatted.

## Notes on Using This Function

- Four sets of parameters under the **Set Session Parameters** (9) function are related to this function. They are the SRCHALL/SRCHFROM, STRLEN/STREOT, SRCHFRWD/SRCHBKWD, and the EOT=c session options. See items 1 on page 120 through 4 on page 121 for more information.
- You can use the **Set Session Parameters** (9) function to determine whether your searches proceed forward (SRCHFRWD) or backward (SRCHBKWD) in a field.
- The **Search Field** function normally checks the entire field (SRCHALL default mode). However, you can use the function 9 to specify SRCHFROM. In this mode, the calling PS position parameter does more than identify the target field. It also provides a beginning or ending point for the search.
  - If the SRCHFRWD option is in effect, the search for the designated string begins at the specified PS position and proceeds toward the end of the field.
  - If the SRCHBKWD option is in effect, the search for the designated string begins at the end of the field and proceeds backward toward the specified PS

position. If the target string is not found, the search ends at the PS position specified in the calling PS position parameter.

4. **DBCS Only:** If the start position of the specified search function is the second byte in a double-byte character, the search is started from the next character for SRCHFRWD and from the character for SRCHBKWD. If the last character of the specified string is the first byte of a double-byte character, the character is not searched for.

The search ignores a pair of SO and SI in the presentation space. When you search a double-byte control character, put SO (X'0E') before the character and SI (X'0F') after it. For example, X'0E000C0F' in the data string is treated as a double-byte character FF (X'000C').

**Note:** 5250 emulation supports a presentation space of 24 rows by 80 columns. In some instances, Communications Manager 5250 emulation displays a 25th row. This occurs when either an error message from the host is displayed or when the operator selects the SysReq key. Personal Communications displays 25th row information on row 24, or on the status bar. For information to be displayed on the status bar, the status bar must be configured. Refer to *Personal Communications Version 4.3 Quick Beginnings* for information on configuring the status bar. By the **EXTEND\_PS** option, an EHLLAPI application can use the same interface with Communications Manager EHLLAPI and valid presentation space is extended when this condition occurs.

## Search Presentation Space (6)

3270	5250	VT
Yes	Yes	Yes

The **Search Presentation Space** function lets your EHLLAPI program examine the host presentation space for the occurrence of a specified string.

### Prerequisite Calls

**Connect Presentation Space** (1).

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 6.	
Data String	Target string for search.	
Length	Length of the target data string. Overridden in EOT mode.	
PS Position	Position within the host presentation space where the search is to begin (SRCHFRWD option) or to end (SRCHBKWD option). Overridden in SRCHALL (default) mode.	

### Return Parameters

This function returns a length and a return code.

#### Length:

The following codes are defined:

Length	Explanation
= 0	The string was not found.



Length	Explanation
> 0	The string was found at the indicated host presentation space position.

#### Return Code:

The following codes are defined:

Return Code	Explanation
0	The <b>Search Presentation Space</b> function was successful.
1	Your program is not connected to a host session.
2	An error was made in specifying parameters.
7	The host presentation space position is not valid.
9	A system error was encountered.
24	The search string was not found.

### Notes on Using This Function

- Four sets of parameters under the **Set Session Parameters** (9) function are related to this function. They are the SRCHALL/SRCHFROM, STRLEN/STREOT, SRCHFRWD/SRCHBKWD, and the EOT=c session options. See items 1 on page 120 through 4 on page 121 through for more information.
- You can use the **Set Session Parameters** (9) function to specify SRCHBKWD. When this option is in effect, the search operation locates the *last* occurrence of the string.
- The **Search Presentation Space** function normally checks the entire host presentation space. However, you can use the **Set Session Parameters** (9) function to specify SRCHFROM. In this mode, the calling PS position parameter specifies a beginning or ending point for the search.
  - If the SRCHFRWD option is in effect, the search for the designated string begins at the specified PS position and proceeds toward the end of the host presentation space.
  - If the SRCHBKWD option is in effect, the search for the designated string begins at the end of the PS and proceeds backward toward the specified PS position. If the target string is not found, the search ends at the PS position specified in the calling PS position parameter.
- The SRCHFROM option is also useful if you are looking for a keyword that might occur more than once in the host presentation space.
- The **Search Presentation Space** function is useful in determining when the host presentation space is available. If your EHLLAPI application is expecting a specific prompt or message before sending data, the **Search Presentation Space** function allows you to check for a prompt message before continuing.
- DBCS Only:** If the start position of the specified search function is the second byte in a double-byte character, the search is started from the next character for SRCHFRWD and from the character for SRCHBKWD. If the last character of the specified string is the first byte of a double-byte character, the character is not searched for.

The search ignores a pair of SO and SI in the presentation space. When you search a double-byte control character, put SO (X'0E') before the character and SI (X'0F') after it. For example, X'0E000C0F' in the data string is treated as a double-byte character FF (X'000C').

**Note:** 5250 emulation supports a presentation space of 24 rows by 80 columns. In some instances, Communications Manager 5250 emulation displays a 25th

row. This occurs when either an error message from the host is displayed or when the operator selects the SysReq key. Personal Communications displays 25th row information on row 24, or on the status bar. For information to be displayed on the status bar, the status bar must be configured. Refer to *Personal Communications Version 4.3 Quick Beginnings* for information on configuring the status bar. By the **EXTEND\_PS** option, an EHLLAPI application can use the same interface with Communications Manager EHLLAPI and valid presentation space is extended when this condition occurs.

## Send File (90)

3270	5250	VT
Yes	Yes	No

The **Send File** function is used to transfer a file from the workstation session where EHLLAPI is running to a host session.

### Prerequisite Calls

None.

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 90.	
Data String	Refer to the examples.	
Length	Length of the target data string. Overridden in EOT mode.	
PS Postion	Must be 0.	

Following are examples of the data strings for SBCS

#### 3270 Session

- To send the file to the VM/CMS host system:  
*pc\_filename [id:]fn ft [fm] [(option)]*
- To send the file to the MVS/TSO host system:  
*pc\_filename [id:]dataset [(member)] [/password] [option]*
- To send the file to the CICS host system:  
*pc\_filename [id:]host\_filename [(option)]*

#### 5250 Session

- To send the file to the AS/400 host system:  
*pc\_filename [id:]library file member [option]*

Following are examples of the data strings for DBCS:

#### 3270 Session

- To send the file to the VM/CMS host system:  
*pc\_filename [id:]fn ft [fm] [(option)]*
- To send the file to the MVS/TSO host system:  
*pc\_filename [id:]dataset [(member)] [/password] [(option)]*

- To send the file to the CICS host system:

`pc_filename [id:]host_filename [(option)]`

### 5250 Session

- To send the file to the AS/400 host system:

`pc_filename [id:]library file member [(option)]`

**Note:** Parameters within [ ] are optional. Available options are listed below. For more information of the options, refer to *Personal Communications Version 4.2 for Windows and OS/2*.

Host System	Common Options
VM/CMS	ASCII, JISCII, CRLF, APPEND, LRECL n, RECFM v f, TIME n, CLEAR, NOCLEAR, PROGRESS, QUIET
MVS/TSO	ASCII, JISCII, CRLF, APPEND, LRECL (n), RECFM (v f u), TIME (n), CLEAR, NOCLEAR, PROGRESS, QUIET, BLKSIZE (n), SPACE (n[,m]), AVBLOCK TRACKS CYLINDERS
CICS	ASCII, JISCII, CRLF, BINARY, TIME n, CLEAR, NOCLEAR, PROGRESS, QUIET
OS/400	ASCII, JISCII, CRLF, APPEND, SRC, LRECL n, TIME n, CLEAR, NOCLEAR, PROGRESS, QUIET

**Note:**

JISCII is valid in a DBCS session for Japan only and ASCII is valid for all other SBCS and DBCS sessions.

**Note:** Time, if specified, overrides the value in Set Session parameters.

**Note:**

Other options specified will be passed to the host transfer program. The file transfer program on the host side either uses them, ignores them, or returns an error. Consult the host transfer program documentation to see a complete list of the options supported.

### Return Parameters

Return Code	Explanation
2	Parameter error or you have specified a length that is too long (more than 255 bytes) for the EHLAPI buffer. The file transfer was unsuccessful.
3	File transfer complete.
4	File transfer complete with segmented records.
5	Workstation file name is not valid or not found. File transfer was canceled.
9	A system error was encountered.
27	File transfer terminated because of either a Cancel button or the timeout set by the <b>Set Session Parameter</b> (9) function.
101	File transfer was successful (transfer to/from CICS).

If you receive return code 2 or 9, there is a problem with the system or with the way you specified your data string.

Other return codes can also be received which relate to message numbers generated by the host transfer program. For transfers to a CICS host transfer program, subtract 100 from the return code to give you the numeric portion of the

message. For example, a return code of 101 would mean that the message number INW0001 was issued by the host. For other host transfer programs, just use the return code as the numerical part of the message. For example, a return of 34 would mean that message TRANS34 was issued by the host transfer program. The documentation for your host transfer program should give more information about the meanings of the specific messages.

Operating system error codes reported by EHLLAPI are greater than 300. To determine the error code, subtract 300 and refer to the operating system documentation for return codes.

### Notes on Using This Function

- Four sets of parameters under the **Set Session Parameters** (9) function are related to this function. They are the QUIET/NOQUIET, STRLEN/STREOT, TIMEOUT=c/TIMEOUT=0, and the EOT=c session options. See items 1 and 2 on page 121 plus items 7 and 8 on page 122 for more information.

## Send Key (3)

3270	5250	VT
Yes	Yes	Yes

The **Send Key** function is used to send either a keystroke or a string of keystrokes to the host presentation space.

You define the string of keystrokes to be sent with the calling data string parameter. The keystrokes appear to the target session as though they were entered by the terminal operator. You can also send all attention identifier (AID) keys such as Enter and so on. All host fields that are input protected or are numeric only must be treated accordingly.

### Prerequisite Calls

**Connect Presentation Space** (1).

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 3.	
Data String	A string of keystrokes, maximum 255. Uppercase and lowercase ASCII characters are represented literally. Function keys and shifted function keys are represented by mnemonics. See "Keyboard Mnemonics" on page 112.	
Length	Length of the source data string. Overridden if in EOT mode.	
PS Position	NA.	

### Return Parameters

Return Code	Explanation
0	The keystrokes were sent; status is normal.
1	Your program is not connected to a host session.
2	An incorrect parameter was passed to EHLLAPI.
4	The host session was busy; all of the keystrokes could not be sent.

Return Code	Explanation
5	Input to the target session was inhibited or rejected; all of the keystrokes could not be sent.
9	A system error was encountered.

### Notes on Using This Function

1. The parameters under the **Set Session Parameters** (9) function are related to this function. They are the **AUTORESET/NORESET**, **STRLEN/STREOT**, **EOT=c**, **ESC=c**, and **RETRY/NORETRY** session options. See items 1 and 2 on page 121, 9 and 10 on page 123, and 19 on page 125 for more information.
2. Keystrokes cannot be sent to the host session when the keyboard is locked or busy. You can check this condition with the **Wait** (4) function.
3. If the host is busy, input might be rejected.
4. The length of the data string must be explicitly defined by the default length parameter, but it can be defined implicitly by the **EOT=c** option of the **Set Session Parameters** (9) function.

When explicitly defining length (see item 1), the value for the length parameter passed by the application must be calculated. For this calculation, allow 2 bytes for compound keystrokes such as @E and allow 4 bytes for compound keystrokes such as @A@C.

5. To send special control keys, a compound character coding scheme is used. In this coding scheme, one keystroke is represented by a sequence of two to four ASCII characters. The first and third character are always the escape character. The second and fourth character are always a keycode.

To send the sequence LOGON ABCDE followed by the Enter key, you would code the string LOGON ABCDE@E. A complete list of these keycodes is represented in "Keyboard Mnemonics" on page 112.

This compound coding technique allows an ASCII string representation of all necessary keystroke codes without requiring the use of complex hexadecimal key codes.

The default escape character is @. The value of the escape character can be changed to any other character with the **ESC=c** option of the **Set Session Parameters** (9) function.

6. Users needing higher levels of performance should use the **Copy String to Field** (33) or **Copy String to Presentation Space** (15) function rather than send keystrokes with the **Send Key** (3) function. But remember, only the **Send Key** (3) function can send the special control keys.
7. Refer to **Set Session Parameters** (9) session option 10 on page 123 (**NORESET** option) to improve the performance of this function.  
Unless **NORESET** is required, the reset mnemonic is added to the keystroke strings as a prefix. Therefore, all resettable status except input inhibit are reset. The **NORESET** option is not the same as the **Reset System** (21) function.
8. The keystroke strings, including the AID key, are sent to the host via multiple paths. Each path sends the strings before the first AID key (or including the AID key). EHLLAPI adjusts the string length and the start position of each path. For a host application program, any keystroke might be lost by the AID key process. Therefore, you should not send a keystroke list that includes plural AID keys.
9. During the @P (Print) or @A@T (Print Presentation Space) process, all requests that update the presentation space are rejected. If the presentation space is

busy or the interruption request occurs during the print request, the mnemonic @A@R (Device Reset – Cancel to print the Presentation Space) cancels the request and resets the status.

## Keyboard Mnemonics

The keyboard mnemonics provide the ASCII characters representing the special function keys of the keyboard in the workstation. The abbreviation codes make the mnemonics for special keys easy to remember. An alphabetic key code is used for the most common keys. For example, the **Clear** key is *C*, and the **Tab** key is *T*.

Table 4. Mnemonics with Uppercase Alphabetic Characters

Mnemonic	Meaning	3270	5250	VT
@B	Left Tab	Yes	Yes	No
@C	Clear	Yes	Yes	No
@D	Delete	Yes	Yes	No
@E	Enter	Yes	Yes	No
@F	Erase EOF	Yes	Yes	No
@H	Help	No	Yes	No
@I	Insert	Yes	Yes	No
@J	Jump (Set Focus)	Yes	Yes	No
@L	Cursor Left	Yes	Yes	Yes
@N	New Line	Yes	Yes	Yes
@O	Space	Yes	Yes	Yes
@P	Print	Yes	Yes	Yes
@R	Reset	Yes	Yes	No
@T	Right Tab	Yes	Yes	Yes
@U	Cursor Up	Yes	Yes	Yes
@V	Cursor Down	Yes	Yes	Yes
@X* <b>Note:</b> Not in Windows 3.1	DBCS (Reserved)	Yes	Yes	No
@Y	Caps Lock (No action)	Yes	Yes	No
@Z	Cursor Right	Yes	Yes	Yes

The following table shows the mnemonics using a number or lowercase alphabetic characters.

Table 5. Mnemonics with Numbers or Lowercase Characters

Mnemonic	Meaning	3270	5250	VT
@0	Home	Yes	Yes	No
@1	PF1/F1	Yes	Yes	No
@2	PF2/F2	Yes	Yes	No
@3	PF3/F3	Yes	Yes	No
@4	PF4/F4	Yes	Yes	No
@5	PF5/F5	Yes	Yes	No

Table 5. Mnemonics with Numbers or Lowercase Characters (continued)

Mnemonic	Meaning	3270	5250	VT
@6	PF6/F6	Yes	Yes	Yes
@7	PF7/F7	Yes	Yes	Yes
@8	PF8/F8	Yes	Yes	Yes
@9	PF9/F9	Yes	Yes	Yes
@a	PF10/F10	Yes	Yes	Yes
@b	PF11/F11	Yes	Yes	Yes
@c	PF12/F12	Yes	Yes	Yes
@d	PF13	Yes	Yes	Yes
@e	PF14	Yes	Yes	Yes
@f	PF15	Yes	Yes	Yes
@g	PF16	Yes	Yes	Yes
@h	PF17	Yes	Yes	Yes
@i	PF18	Yes	Yes	Yes
@j	PF19	Yes	Yes	Yes
@k	PF20	Yes	Yes	Yes
@l	PF21	Yes	Yes	No
@m	PF22	Yes	Yes	No
@n	PF23	Yes	Yes	No
@o	PF24	Yes	Yes	No
@q	End	Yes	Yes	No
@s	ScrLk (No action)	Yes	Yes	Yes
@t	Num Lock (No action)	Yes	Yes	Yes
@u	Page Up	No	Yes	No
@v	Page Down	No	Yes	No
@x	PA1	Yes	Yes	No
@y	PA2	Yes	Yes	No
@z	PA3	Yes	Yes	No

The following table shows the mnemonics using the combination @A and @alphabetic uppercase (A–Z) key.

Table 6. Mnemonics with @A and @ Uppercase Alphabetic Characters

Mnemonic	Meaning	3270	5250	VT
@A@C	Test	No	Yes	No
@A@D	Word Delete	Yes	Yes	No
@A@E	Field Exit	Yes	Yes	No
@A@F	Erase Input	Yes	Yes	No
@A@H	System Request	Yes	Yes	No
@A@I	Insert Toggle	Yes	Yes	No
@A@J	Cursor Select	Yes	Yes	No

Table 6. Mnemonics with @A and @ Uppercase Alphabetic Characters (continued)

Mnemonic	Meaning	3270	5250	VT
@A@L	Cursor Left Fast	Yes	Yes	No
@A@Q	Attention	Yes	Yes	No
@A@R	Device Cancel (Cancels Print Presentation Space)	Yes	Yes	No
@A@T	Print Presentation Space	Yes	Yes	Yes
@A@U	Cursor Up Fast	Yes	Yes	No
@A@V	Cursor Down Fast	Yes	Yes	No
@A@Z	Cursor Right Fast	Yes	Yes	No

The following table shows the mnemonics using the combination @A and @number or @A and @alphabetic lowercase (a-z) key.

Table 7. Mnemonics with @A and @ Lowercase Alphabetic Characters

Mnemonic	Meaning	3270	5250	VT
@A@9	Reverse Video	Yes	Yes	No
@A@b	Underscore	Yes	No	No
@A@c	Reset Reverse Video	Yes	No	No
@A@d	Red	Yes	No	No
@A@e	Pink	Yes	No	No
@A@f	Green	Yes	No	No
@A@g	Yellow	Yes	No	No
@A@h	Blue	Yes	No	No
@A@i	Turquoise	Yes	No	No
@A@j	White	Yes	No	No
@A@l	Reset Host Colors	Yes	No	No
@A@t	Print (Personal Computer)	Yes	Yes	No
@A@y	Forward Word Tab	Yes	Yes	No
@A@z	Backward Word Tab	Yes	Yes	No

The following table shows the mnemonics using the combination @A and @special character.

Table 8. Mnemonics with @A and @ Alphanumeric (Special) Characters

Mnemonic	Meaning	3270	5250	VT
@A@-	Field -	No	Yes	No
@A@+	Field +	No	Yes	No



Table 8. Mnemonics with @A and @ Alphanumeric (Special) Characters (continued)

Mnemonic	Meaning	3270	5250	VT
@A@<	Record Backspace	No	Yes	No

The following table shows the mnemonics using the combination @S and @alphabetic lowercase.

Table 9. Mnemonics with @S (Shift) and @ Alphabetic Characters

Mnemonic	Meaning	3270	5250	VT
@S@E	Print Presentation Space on Host	No	Yes	No
@S@x	Dup	Yes	Yes	No
@S@y	Field Mark	Yes	Yes	No

**DBCS Only:** The following table shows the mnemonics using the combination @X and @number or @alphabetic lowercase (a–z).

Table 10. Mnemonics Using @X and @Alphabetic Lowercase (For DBCS Only)

Mnemonic	Meaning	3270	5250	VT
@X@1	Display SO/SI	Yes	Yes	No
@X@5	Generate SO/SI	No	Yes	No
@X@6	Display Attribute	No	Yes	No
@X@7	Forward Character	No	Yes	No
@X@c	Split vertical bar ( )	No	Yes	No

**VT Only:** The following table shows the mnemonics using the combination @M and @number or @alphabetic lowercase (a-z)

Table 11. Mnemonics Using @M, @Q and @Alphabetic Lowercase (For VT Only)

Mnemonic	Meaning	3270	5250	VT
@M@0	VT Numeric Pad 0	No	No	Yes
@M@1	VT Numeric Pad 1	No	No	Yes
@M@2	VT Numeric Pad 2	No	No	Yes
@M@3	VT Numeric Pad 3	No	No	Yes
@M@4	VT Numeric Pad 4	No	No	Yes
@M@5	VT Numeric Pad 5	No	No	Yes
@M@6	VT Numeric Pad 6	No	No	Yes
@M@7	VT Numeric Pad 7	No	No	Yes

Table 11. Mnemonics Using @M, @Q and @Alphabetic Lowercase (For VT Only) (continued)

Mnemonic	Meaning	3270	5250	VT
@M@8	VT Numeric Pad 8	No	No	Yes
@M@9	VT Numeric Pad 9	No	No	Yes
@M@-	VT Numeric Pad -	No	No	Yes
@M@,	VT Numeric Pad ,	No	No	Yes
@M@.	VT Numeric Pad .	No	No	Yes
@M@e	VT Numeric Pad Enter	No	No	Yes
@M@f	VT Edit Find	No	No	Yes
@M@i	VT Edit Insert	No	No	Yes
@M@r	VT Edit Remove	No	No	Yes
@M@s	VT Edit Select	No	No	Yes
@M@p	VT Edit Previous Screen	No	No	Yes
@M@n	VT Edit Next Screen	No	No	Yes
@M@a	VT PF1	No	No	Yes
@M@b	VT PF2	No	No	Yes
@M@c	VT PF3	No	No	Yes
@M@d	VT PF4	No	No	Yes
@M@h	VT HOld Screen	No	No	Yes
@M@(space)	Control Code NUL	No	No	Yes
@M@A	Control Code SOH	No	No	Yes
@M@B	Control Code STX	No	No	Yes
@M@C	Control Code ETX	No	No	Yes
@M@D	Control Code EOT	No	No	Yes
@M@E	Control Code ENQ	No	No	Yes
@M@F	Control Code ACK	No	No	Yes
@M@G	Control Code BEL	No	No	Yes
@M@H	Control Code BS	No	No	Yes
@M@I	Control Code HT	No	No	Yes
@M@J	Control Code LF	No	No	Yes

Table 11. Mnemonics Using @M, @Q and @Alphabetic Lowercase (For VT Only) (continued)

Mnemonic	Meaning	3270	5250	VT
@M@K	Control Code VT	No	No	Yes
@M@L	Control Code FF	No	No	Yes
@M@M	Control Code CR	No	No	Yes
@M@N	Control Code SO	No	No	Yes
@M@O	Control Code SI	No	No	Yes
@M@P	Control Code DLE	No	No	Yes
@M@Q	Control Code DC1	No	No	Yes
@M@R	Control Code DC2	No	No	Yes
@M@S	Control Code DC3	No	No	Yes
@M@T	Control Code DC4	No	No	Yes
@M@U	Control Code NAK	No	No	Yes
@M@V	Control Code SYN	No	No	Yes
@M@W	Control Code ETB	No	No	Yes
@M@X	Control Code CAN	No	No	Yes
@M@Y	Control Code EM	No	No	Yes
@M@Z	Control Code SUB	No	No	Yes
@M@u	Control Code ESC	No	No	Yes
@M@v	Control Code FS	No	No	Yes
@M@w	Control Code GS	No	No	Yes
@M@x	Control Code RS	No	No	Yes
@M@y	Control Code US	No	No	Yes
@M@z	Control Code DEL	No	No	Yes
@Q@A	VT User Defined Key 6	No	No	Yes
@Q@B	VT User Defined Key 7	No	No	Yes
@Q@C	VT User Defined Key 8	No	No	Yes
@Q@D	VT User Defined Key 9	No	No	Yes
@Q@E	VT User Defined Key 10	No	No	Yes

Table 11. Mnemonics Using @M, @Q and @Alphabetic Lowercase (For VT Only) (continued)

Mnemonic	Meaning	3270	5250	VT
@Q@F	VT User Defined Key 11	No	No	Yes
@Q@G	VT User Defined Key 12	No	No	Yes
@Q@H	VT User Defined Key 13	No	No	Yes
@Q@I	VT User Defined Key 14	No	No	Yes
@Q@J	VT User Defined Key 15	No	No	Yes
@Q@K	VT User Defined Key 16	No	No	Yes
@Q@L	VT User Defined Key 17	No	No	Yes
@Q@M	VT User Defined Key 18	No	No	Yes
@Q@N	VT User Defined Key 19	No	No	Yes
@Q@O	VT User Defined Key 20	No	No	Yes
@Q@a	VT Backtab	No	No	Yes
@Q@r	VT Clear Page	No	No	Yes
@Q@s	VT Edit	No	No	Yes

The following character keys are interpreted as they are.

a-z	!	'	,	<	}
A-Z	\$	(	.	>	[
0-9	%	)	/	=	]
~	&	*	:	?	
#	"	+	;	{	

The following table shows the mnemonics using a special character.

Table 12. Mnemonics with Special Character Keys

Mnemonic	Meaning	3270	5250	VT
@@	@	Yes	Yes	Yes
@\$	Alternate Cursor (The Presentation Manager Interface only)	Yes	Yes	Yes
@<	Backspace	Yes	Yes	Yes

## Set Cursor (40)

3270	5250	VT
Yes	Yes	Yes

The **Set Cursor** function is used to set the position of the cursor within the host presentation space. Before using the **Set Cursor** function, a workstation application must be connected to the host presentation space.

## Prerequisite Calls

**Connect Presentation Space** (1).

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 40	
Data String	NA	
Length	NA	
PS Position	Desired cursor position in the connected host presentation space	

## Return Parameters

Return Code	Explanation
0	Cursor was successfully located at the specified position.
1	Your program is not connected to a host session.
4	The session is busy.
7	A cursor location less than 1 or greater than the size of the connected host presentation space was specified.
9	A system error occurred.

## Notes on Using This Function

**DBCS Only:** If the specified cursor is the second byte of the double-byte character, the cursor moves to the first byte of the character and an error code is not returned.

## Set Session Parameters (9)

<i>3270</i>	<i>5250</i>	<i>VT</i>
Yes	Yes	Yes

The **Set Session Parameters** function lets you change certain default session options in EHLLAPI for all sessions. When EHLLAPI is loaded, the default settings for session options are as indicated by the underscored entries in the tables that appear beginning on page “Session Options” on page 120.. Any, some, or all of these settings can be changed by including the desired option in the calling data string as explained below. Specified settings remain in effect until:

- Changed by a subsequent **Set Session Parameters** (9) function that specifies a new value.
- The **Reset System** (21) function is executed.
- The EHLLAPI application program is terminated.

The following table lists those EHLLAPI functions that are affected by session options. Functions not listed in the table are not affected by any of the session options. Session options that affect each function are indicated by corresponding entries in the “See Items” column. These entries are indexed to the list that follows “Call Parameters” on page 120.

Function Number	Function Name	See Items
1	Connect Presentation Space	11, 23, 24
3	Send Key	1, 2, 9, 10, 19
4	Wait	12
5	Copy Presentation Space	5, 13, 14, 15, 17, 20, 21, 22
6	Search Presentation Space	1, 2, 3, 4
8	Copy Presentation Space to String	5, 13, 14, 15, 17, 20, 21, 22
10	Query Sessions	16, 22
15	Copy String to Presentation Space	1, 2, 13, 14, 18, 20, 21, 22
18	Pause	6
30	Search Field	1, 2, 3, 4, 22
33	Copy String to Field	1, 2, 13, 14, 18, 20, 21, 22
34	Copy Field to String	5, 13, 14, 17, 20, 21, 22
51	Get Key	9, 12
90	Send File	1, 2, 7, 8
91	Receive File	1, 2, 7, 8
101	Connect Window Services	23, 24

**Note:** Items 20 and 21 in this table are for DBCS only

## Prerequisite Calls

None.

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 9.	
Data String	String containing the desired values of those session options that are to be changed. The data string can contain any of the values in the tables of "Session Options". The values should be placed on the data string line, separated by commas or blanks. The sets of parameters are explained in terms of the functions they affect.	
Length	Explicit length of the source data string (the STREOT option is not allowed).	
PS Postion	NA.	

## Session Options

The following tables show the session options. The default is underlined.

- The values in the following table determine how the data string length is defined for functions **Send Key** (3), **Search Presentation Space** (6), **Copy String to Presentation Space** (15), **Search Field** (30), **Copy String to Field** (33), **Send File** (90), and **Receive File** (91).

Value	Explanation
<u>STRLEN</u>	An explicit length is passed for all strings.

Value	Explanation
STREOT	Lengths are not explicitly coded. Calling (source) data strings are terminated with an EOT character.

2. The statement in the following table is used to specify the character that is used as the end-of-text (EOT) delimiter in the calling (source) data string for EHLAPI functions **Send Key** (3), **Search Presentation Space** (6), **Copy String to Presentation Space** (15), **Search Field** (30), **Copy String to Field** (33), **Send File** (90), and **Receive File** (91).

Value	Explanation
EOT=c	Allows you to specify the EOT character for string terminators (in STREOT mode). Binary zero is the default. Do not leave a blank after the equal sign.

To be valid, c must be entered as a 1-byte string literal character with no preceding blanks. The EOT character specified by this statement is used to determine the length of a calling data string only when the STREOT option (see item 1) is in effect.

3. The values in the following table affect the **Search Presentation Space** (6) and **Search Field** (30) search functions.

Value	Explanation
SRCHALL	The <b>Search Presentation Space</b> (6) function and <b>Search Field</b> (30) function scan the entire host presentation space or field.
SRCHFROM	The <b>Search Presentation Space</b> (6) function and <b>Search Field</b> (30) function start from a specified PS position (for SRCHFRWD) or end at a specified PS position (for SRCHBKWD).

4. The values in the following table affect the **Search Presentation Space** (6) and **Search Field** (30) search functions. They determine the direction for the search.

Value	Explanation
SRCHFRWD	The <b>Search Presentation Space</b> (6) function and <b>Search Field</b> (30) function perform in an ascending direction.
SRCHBKWD	The <b>Search Presentation Space</b> (6) function and <b>Search Field</b> (30) function perform in a descending direction. A search is satisfied if the first character of the requested string starts within the bounds specified for the search.

5. The values in the following table determine how attribute bytes are treated for functions **Copy Presentation Space** (5), **Copy Presentation Space to String** (8), and **Copy Field to String** (34).

Value	Explanation
NOATTRB	Convert all unknown values to blanks.
ATTRB	Pass back all codes that do not have an ASCII equivalent as their original values.
NULLATTRB	Convert all field attributes to null characters.

6. The values in the following table affect the **Pause** (18) function.

Value	Explanation
FPAUSE	A full-duration pause lasts for however long you specified in the <b>Pause</b> (18) function.

Value	Explanation
IPAUSE	Interruptible pause. After the <b>Start Host Notification</b> (23) function is executed, a host event satisfies a pause.

7. The values in the following table determine whether messages generated by file transfer functions **Send File** (90) and **Receive File** (91) are displayed.

Value	Explanation
NOQUIET	SEND and RECEIVE messages are displayed.
QUIET	SEND and RECEIVE messages are not displayed.

8. The statements in the following table determine how long Personal Communications EHLLAPI waits before it automatically issues a Cancel during execution of file transfer functions **Send File** (90) and **Receive File** (91). To be valid, c must be an Arabic number 0–9 or a capital letter J–N and must not be preceded by a blank.

Value	Explanation																														
TIMEOUT=0	A Cancel is automatically issued following a 20-second (approximate) delay.																														
TIMEOUT=c	<p>A Cancel is automatically issued following a specified delay. A 1-character indicator from the table below tells Personal Communications how many 30-second cycles it should accept before issuing a Cancel itself.</p> <table border="1"> <thead> <tr> <th>Character</th> <th>Value (in minutes)</th> </tr> </thead> <tbody> <tr><td>1</td><td>0.5</td></tr> <tr><td>2</td><td>1.0</td></tr> <tr><td>3</td><td>1.5</td></tr> <tr><td>4</td><td>2.0</td></tr> <tr><td>5</td><td>2.5</td></tr> <tr><td>6</td><td>3.0</td></tr> <tr><td>7</td><td>3.5</td></tr> <tr><td>8</td><td>4.0</td></tr> <tr><td>9</td><td>4.5</td></tr> <tr><td>J</td><td>5.0</td></tr> <tr><td>K</td><td>5.5</td></tr> <tr><td>L</td><td>6.0</td></tr> <tr><td>M</td><td>6.5</td></tr> <tr><td>N</td><td>7.0</td></tr> </tbody> </table>	Character	Value (in minutes)	1	0.5	2	1.0	3	1.5	4	2.0	5	2.5	6	3.0	7	3.5	8	4.0	9	4.5	J	5.0	K	5.5	L	6.0	M	6.5	N	7.0
Character	Value (in minutes)																														
1	0.5																														
2	1.0																														
3	1.5																														
4	2.0																														
5	2.5																														
6	3.0																														
7	3.5																														
8	4.0																														
9	4.5																														
J	5.0																														
K	5.5																														
L	6.0																														
M	6.5																														
N	7.0																														

9. The statement in the following table is used to define the escape character for keystroke mnemonics. This session option affects functions **Send Key** (3) and **Get Key** (51). The value of c must be entered as a 1-byte literal character string with no preceding blanks.

Value	Explanation
ESC=c	Specifies the escape character for keystroke mnemonics (@ is the default). Do not leave a blank after the equal sign. A blank is not a valid escape character.



10. The values in the following table determine whether EHLLAPI automatically precedes strings sent using the **Send Key** (3) function with a reset.

Value	Explanation
<u>AUTORESET</u>	EHLLAPI attempts to reset all inhibited conditions by prefixing all strings of keys sent using the <b>Send Key</b> (3) function with a reset.
NORESET	Do not AUTORESET.

11. The values in the following table affect the manner in which the **Connect Presentation Space** (1) command function.

Value	Explanation
<u>CONLOG</u>	Establishes a logical connection between the workstation session and a host session. During Connect, does not jump to the requested presentation space.
CONPHYS	Establishes a physical connection between the workstation session and a host session. During Connect, jumps to the requested presentation space.

12. The values in the following table affect the **Wait** (4) function and **Get Key** (51) function. For each value, there are two different effects, one for each function.

Value	Explanation
<u>TWAIT</u>	For the <b>Wait</b> (4) function, waits up to a minute before timing out on XCLOCK (X []) or XSYSTEM.  For the <b>Get Key</b> (51) function, does not return control to your EHLLAPI application program until it has intercepted a key (normal or AID key based on the option specified under the <b>Start Keystroke Intercept</b> (50) function).
LWAIT	For the <b>Wait</b> (4) function, waits until XCLOCK (X [])/XSYSTEM clears. This option is not recommended, because control does not return to your application until the host is available.  For the <b>Get Key</b> (51) function, does not return control to your EHLLAPI application program until it has intercepted a key (normal or AID key based on the option specified under the <b>Start Keystroke Intercept</b> (50) function).
NWAIT	For the <b>Wait</b> (4) function, checks status and returns immediately (no wait).  For the <b>Get Key</b> (51) function, returns return code 25 (keystrokes not available) in the fourth parameter if nothing is queued matching the option specified under the <b>Start Keystroke Intercept</b> (50) function.

**Note:** Use of NWAIT is recommended.

13. The values in the following table affect **Copy Presentation Space** (5), **Copy Presentation Space to String** (8), **Copy String to Presentation Space** (15), **Copy String to Field** (33), and **Copy Field to String** (34). Extended attribute bytes (EAB) include extended character attributes and extended field attributes.

Value	Explanation
<u>NOEAB</u>	Pass data only, no EABs.

Value	Explanation
EAB	<p>Pass the presentation space data with extended attribute bytes. For each character that appears on the screen, 2 bytes of data are passed. Therefore, a buffer twice the size of the presentation space must be preallocated; for example <math>2 \times 1920 = 3840</math> for a 24-row by 80-column presentation space.</p> <p>Extended attributes for a string of characters may be reported as attributes of the field byte, rather than as attributes of each individual character in the field. In this case, to tell if a particular character or set of characters on a screen is underscored, do a CopyPStoString specifying the position of the field attribute byte (the byte before the field that is displayed on the screen) to get the EAB information that applies to all of the characters in that field.</p>

**Note:** When using **EHLLAPI Copy PS to String**, text is copied which should be invisible to the operator. Use the EHLLAPI SetSession Parameters functions to set the **Nodisplay** option to determine if there is hidden data. This causes EHLLAPI to return non-display fields as nulls. Another common procedure for hiding data is to set the foreground and background colors the same (BLACK, for instance) so the text is displayed, but not visible to the human operator. The only way for your application to detect this is to use the **EAB** and **XLATE** session parameters and then copying the PS. The foreground/background color of each position is returned and you can determine which characters are invisible.

14. The values in the following table affect **Copy Presentation Space (5)**, **Copy Presentation Space to String (8)**, **Copy String to Presentation Space (15)**, **Copy String to Field (33)**, and **Copy Field to String (34)**.

Value	Explanation
<u>NOXLATE</u>	EABs are not translated.
YesLATE	EABs are translated to the PC color graphics adapter (CGA) format.

15. The values in the following table affect **Copy Presentation Space (5)** and **Copy Presentation Space to String (8)** if NOATTRB and NOEAB are specified.

Value	Explanation
<u>BLANK</u>	Convert all unknown values to X'20'.
NOBLANK	Convert all unknown values to X'00'.

The default value is BLANK. If you want to change the default value to NOBLANK, add the following statement in the PCSWIN.INI file (drive:\directory-name\PRIVATE\PCSWIN.INI; drive and directory-name are the drive and the directory where Personal Communications was installed.):

```
[API]
NullToBlank=NO
```

16. The values in the following table affect the presentation space size that is returned by the **Query Sessions (10)**.

Value	Explanation
<u>CFGSIZE</u>	Returns the configured size of the connected presentation space. This option ignores any override of the configured size by the host.
NOCFGSIZE	Returns the current size of the connected presentation space.

17. The values in the following table affect **Copy Presentation Space (5)**, **Copy Presentation Space to String (8)**, and **Copy Field to String (34)**.

Value	Explanation
<u>DISPLAY</u>	Copy nondisplay fields in the presentation space to the target buffer area in the same manner as display fields. Current applications function normally.
NODISPLAY	Do not copy nondisplay fields in the presentation space to the target buffer area. Copy the nondisplay fields to the target buffer as a string of null characters. This allows applications to display the copied buffers in the presentation widow without displaying confidential information, such as passwords.

18. The values in the following table affect **Copy String to Presentation Space (15)** and **Copy String to Field (33)**.

Value	Explanation
<u>NOPUTEAB</u>	EAB (or EAD for DBCS) is not contained in the data string of <b>Copy String to Presentation Space</b> or <b>Copy String to Field</b> .
PUTEAB	EAB is contained with character data in the data string of <b>Copy String to Presentation Space</b> or <b>Copy String to Field</b> .

This option is used for the compatibility with Communications Manager/2. For Communications Manager/2, the data string, which is specified in **Copy String to Presentation Space** or **Copy String to Field**, must be contain EAB (or EAD) with character data when EAB (or EAD) is valid in **Set Session Parameters**. Whereas, for the previous Personal Communications, the data string specified in these functions must consist of character data only even if EAB (or EAD) is valid. But Personal Communications for Windows 95, Windows 98, and Windows NT allows that the data string contains EAB (or EAD) by setting PUTEAB to provide the compatibility with Communications Manager/2.

19. The values in the following table affect the **Send Key (3)** function. Keystrokes are not processed if the keyboard is blocked or in use. The options determine whether the function tries to resend the keystrokes until a 4-minute timeout occurs or if the function returns immediately after determining the keyboard is blocked or in use.

Value	Explanation
<u>RETRY</u>	Continues to attempt to send keystrokes until they are sent or until a 4-minute timeout occurs.
NORETRY	Returns immediately after determining the keyboard is blocked or in use.

20. **DBCS Only:** The values in the following table affect **Copy Presentation Space (5)**, **Copy Presentation Space to String (8)**, **Copy String to Presentation Space (15)**, **Copy String to Field (33)**, and **Copy Field to String (34)**.

Value	Explanation
<u>NOEAD</u>	DBCS attribute characters are not passed.
EAD	Pass the presentation space data and two attribute characters for the double-byte character set (DBCS). (Users receive 2 bytes for each character other than the data. Therefore, a buffer twice the size of the presentation space must be preallocated.)

21. **DBCS Only:** The values in the following table affect **Copy Presentation Space (5)**, **Copy Presentation Space to String (8)**, **Copy String to Presentation Space (15)**, **Copy String to Field (33)**, and **Copy Field to String (34)**.

Value	Explanation
<u>NOSO</u>	Pass the presentation space data except Shift-in (SI) and Shift-out (SO) control characters.
SO	Pass the presentation space data including translated SI control character to X'0E' and SO control character to X'0F'. The allocated buffer size depends on the length of the stored data.
SPACESO	Pass the presentation space data including translated SI and SO control characters to X'20' (blank). The allocated buffer size depends on the length of the stored data.

22. The values in the following table affect **Copy Presentation Space (5)**, **Copy Presentation Space to String (8)**, **Copy String to Presentation Space (15)**, **Copy String to Field (33)**, **Copy Field to String (34)**, **Search Field (30)**, and **Query Sessions (10)**

Value	Explanation
EXTEND_PS	5250 emulation supports a presentation space of 24 rows by 80 columns. In some instances, Communications Manager 5250 emulation displays a 25th row. This occurs when either an error message from the host is displayed or when the operator selects the SysReq key. Personal Communications displays 25th row information on row 24, but EHLAPI normally sees the 'real' 24th row. By <b>EXTEND_PS</b> option, an EHLAPI application can use the same interface with Communications Manager EHLAPI and valid presentation space is extended when this condition occurs.
<u>NOEXTEND_PS</u>	The presentation space is not extended when the above condition occurs. This is the default value.

23. The values in the following table affect the **Connect Presentation Space (1)** and **Connect Window Services (101)** functions. The options specify whether an application can or will share the presentation space to which it is connected with another application. Only one of the following values can be specified with each **Set Session Parameter** call.

Value	Explanation
SUPER_WRITE	The application allows other applications that allow sharing and have write access permissions to concurrently connect to the same presentation space. The originating application performs supervisory-type functions but does not create errors for other applications that share the presentation space.
WRITE_SUPER	The application requires write access and allows only supervisory application to concurrently connect to its presentation space. This is the default value.
WRITE_WRITE	The application requires write access and allows partner or other applications with predictable behavior to share the presentation space.
WRITE_READ	The application requires write access and allows other applications that perform read-only functions to share the presentation space. The application is also allowed to copy the presentation space and perform other read-only operations as usual.

Value	Explanation
WRITE_NONE	The application has exclusive use of the presentation space. No other applications are allowed to share the presentation space, including supervisory applications. The application is allowed to copy the presentation space and perform read-only operations as usual.
READ_WRITE	The application requires only read access to monitor the presentation space and allows other applications that perform read or write, or both, functions to share the presentation space. The application is also allowed to copy the presentation space and perform other read-only operations as usual.

24. The values in the following table allow applications that have presentation space sharing requirements to limit the sharing to a partner application (an application that was developed to work with it).

Value	Explanation
NOKEY	Allows the application to be compatible with existing applications that do not specify the <b>KEY</b> parameter.
KEY\$nnnnnnnn	Uses a keyword to restrict sharing access to the presentation space that it supports. The keyword must be exactly 8 bytes in length.

## Return Parameters

This function returns a length and a return code.

### Length:

Number of valid session parameters that are set.

### Return Code:

The following codes are defined:

Return Code	Explanation
0	The session parameters have been set.
2	One or more parameters were not valid.
9	A system error was encountered.

## Start Close Intercept (41)

3270	5250	VT
Yes	Yes	Yes

The **Start Close Intercept** function allows the application to intercept close requests generated when a user selects the close option from the emulator session window. This function intercepts the close request and discards it until a **Stop Close Intercept** (43) function is requested.

After using this function, your application program can use the **Query Close Intercept** (42) function to determine when a close request has occurred.

## Prerequisite Calls

None.

## Call Parameters

Byte	Definition	
	Standard Interface	Enhanced Interface
Function Number	Must be 41	
Data String	See the following table	
Length	5 or 6	Must be 12
PS Position	NA	

The data string contains the following items.

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID).
	2–4	Reserved.
4–5		The data in these positions is ignored by EHLLAPI. However, no error is caused if the migrating program has data in these positions. This data is accepted to provide compatibility with migrating applications.
6	5	Specify "M" to request asynchronous message mode (Windows only).
	6–8	Reserved.
2–3	9–12	When 'M' is specified in position 5 (6 for 16-bit), the window handle of the window that receives the message should be set. The message is a return value of RegisterWindowMessage ("PCSHLL") (not equal 0).

## Return Parameters

This function returns a data string and a return code.

### Data String:

If asynchronous message mode is not specified in position 5 (6 for standard interface) and the function is completed successfully, the following data string is returned.

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID).
	2–8	Reserved.
	9–12	4 byte value in which the event object (Windows) or semaphore (OS/2) address is returned by EHLLAPI. The application can wait for this event object. (32-bit only).

### Data String:

If "M" (asynchronous message mode) is specified in position 5 (6 for standard interface) and the function is completed successfully, the following data string is returned.

Byte		Definition
Standard	Enhanced	

Byte		Definition
1	1	A 1-character presentation space short name (PSID)
	2–8	Reserved
2–3	9–10	Task ID of asynchronous message mode

**Note:** If a user selects the close option, an application window receives a message. The message is a return value of `RegisterWindowMessage("PCSHLL")`. The `wParam` parameter will contain the Task ID returned by this function call. The `HIWORD` of the `lParam` parameter will contain the Return Code 26, which shows a close intercept occurred, and the `LOWORD` of the `lParam` parameter will contain the function number 41.

**Return Code:**

The following codes are defined:

Return Code	Explanation
0	The <b>Start Close Intercept</b> function was successful.
1	An incorrect host presentation space was specified.
2	A parameter error occurred.
9	A system error occurred.
10	The function is not supported by the emulation program.

**Notes on Using This Function**

1. The returned event object or semaphore is in a non-signaled state when the start request function returns. The event object is in the signaled state each time a close request occurs. To receive notification of multiple close request events, put the event object into the signaled state each time using **SetEvent** or the **Query Close Intercept** (42) function (Windows) or **DosResetEventSem(OS/2)**.
2. After using this function, your application program can use the **Query Close Intercept** (42) function to determine when a close request has occurred. The application can wait on the returned event object to determine when the event has occurred.
3. This is not an exclusive call. Multiple applications can request this function for the same short session ID.
4. If there are no applications intercepting close requests for a session, any subsequent close requests selected by the user from the emulator operations dialog result in a normal stop requested for that session.

**Start Host Notification (23)**

3270	5250	VT
Yes	Yes	Yes

The **Start Host Notification** function begins the process by which your EHELLAPI application program determines if the host presentation space or OIA have been updated.

After using this function, your application program can use the **Query Host Update** (24) function to determine when a host event has occurred.

## Prerequisite Calls

None.

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 23	
Data String	Preallocated string, see the following table	
Length	6 or 7 implied	16
PS Position	NA	

The calling data string contains these elements:

Byte		Definition
Standard	Enhanced	
1	1	One of the following values: <ul style="list-style-type: none"> <li>A 1-character presentation space short name (PSID)</li> <li>A blank or null indicating a request for the host-connected host presentation space</li> </ul>
	2–4	Reserved.
2	5	One of the following values: <ul style="list-style-type: none"> <li>The character B asking for notification of both host presentation space and OIA updates.</li> <li>The character O asking for notification of only OIA updates.</li> <li>The character P asking for notification of only host presentation space updates.</li> <li>The character A requesting the asynchronous mode of the notification. When A is specified, position 9–12 returns the address of an event object (Windows) or the address of a semaphore (OS/2). The event selection character B, O, or P must be placed in position 13.</li> <li>The character M requesting the asynchronous message mode of the notification. When M is specified, the event selection character B, O, or P must be placed in position 13 (7 for 16-bit).</li> <li>“M” is not supported on OS/2.</li> <li>“E” The character E asking for notification of completion during a printer session.</li> </ul>
	6–8	Reserved.
3–4	9–12	When “M” is specified in position 5 (2 for 16-bit), the window handle of the window that receives the message should be set. The message is a return value of RegisterWindowMessage (“PCSHLL”) (not equal 0).



Byte		Definition
7	13	One of the following values if position 5 (2 for 16-bit) is A or M: <ul style="list-style-type: none"> <li>The character B asking for notification of both host presentation space and OIA updates</li> <li>The character O asking for notification of only OIA updates</li> <li>The character P asking for notification of only host presentation update.</li> </ul>
	14–16	Reserved.

## Return Parameters

This function returns a data string and a return code.

### Data String:

If “A” (asynchronous mode of notification) is specified in position 5 and the function is completed successfully, the following data string is returned:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID).
	2–8	Reserved.
	9–12	4-byte value in which the event object (Windows) or semaphore (OS/2) address is returned by EHELLAPI. The application can wait for this event object. (32-bit only). For 16-bit OS/2 this is a 16-bit semaphore.

### Data String:

If “M” (asynchronous message mode) is specified in position 5 (2 for standard interface) and the function is completed successfully, the following data string is returned:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2–8	Reserved
3–4	9–10	Task ID of asynchronous message mode

**Note:** If OIA or presentation space is updated, an application window receives a message. The message is a return value of RegisterWindowMessage (“PCSHLL”). The wParam parameter contains the Task ID returned by the function call. HIWORD of lParam contains Return Code 21 (shows the OIA is updated), 22 (shows the host presentation space is updated), or 23 (shows both the OIA and the host presentation space are updated), and LOWORD of lParam parameter contains function number 23.

### Return Code:

The following codes are defined:

Return Code	Definition
0	The <b>Start Host Notification</b> function was successful.
1	An incorrect host presentation space was specified.
2	An error was made in designating parameters.

Return Code	Definition
9	A system error was encountered.

### Notes on Using This Function

1. An application program can issue this function for multiple host sessions. The **Pause** (18) function can notify the application when one or more host sessions (PS, OIA, or both of them) are updated. The **Query Host Update** (24) function can be used to determine whether a PS, OIA, or both of them have been updated.
2. If the application chooses the asynchronous option, it can wait for the returned event object or semaphore to determine when a host event has occurred.
3. The event object or semaphore is initially in a non-signaled state and is signaled each time an appropriate event occurs. To receive notification for multiple events, the application must put the event object into the non-signaled state each time it has been signaled using either the **ResetEvent** or the **Query Host Update** (24) function (Windows) or **DosResetEventSem** (OS/2).
4. An application cannot request Start Host Notification more than once with the same options.
5. This is not an exclusive call. Multiple applications can request this function for the same short session ID.

### Start Keystroke Intercept (50)

3270	5250	VT
Yes	Yes	Yes

The **Start Keystroke Intercept** function allows a workstation application to filter any keystrokes sent to a session by a terminal operator. After a call to this function, keystrokes are intercepted and saved until the keystroke queue overflows or until the **Stop Keystroke Intercept** (53) function or **Reset System** (21) function is called. The intercepted keystrokes can be:

- Received through the **Get Key** (51) function and sent to the same or another session with the **Send Key** (3) function
- Accepted or rejected through the **Post Intercept Status** (52) function
- Replaced by other keystrokes with the **Send Key** (3) function
- Used to trigger other processes

### Prerequisite Calls

None.

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 50	
Data String	See the following table	
Length	Keystroke buffer size EHLLAPI allocates 32 bytes minimum for this buffer.	
PS Position	NA	

The calling data string contains:

Byte		Definition
Standard	Enhanced	
1	1	One of the following values: <ul style="list-style-type: none"> <li>• A specific host presentation space short name (PSID)</li> <li>• A blank or null indicating a request for the host-connected host presentation space</li> </ul>
	2–4	Reserved.
2	5	An <b>option code</b> character: <ul style="list-style-type: none"> <li>• D for AID keystrokes only.</li> <li>• L for all keystrokes.</li> <li>• M for requesting the asynchronous message mode of the notification (Windows only).</li> </ul> When M is specified, a code character “D”, or “L” must be placed in position 13 (7 for 16-bit).
	6–8	Reserved.
3–4	9–12	When “M” is specified in position 5 (2 for 16-bit), the window handle of the window that receives the message should be set. The message is a return value of RegisterWindowMessage (“PCSHLL”) (not equal 0).
7	13	One of the following values if position 5 (2 for 16-bit) is M: <ul style="list-style-type: none"> <li>• D for AID keystrokes only.</li> <li>• L for all keystrokes.</li> </ul>
	14–16	Reserved.

#### Data String:

If “M” (asynchronous message mode) is specified in position 5 (2 for standard interface) and the function is completed successfully, the following data string is returned:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2–8	Reserved
3–4	9–10	Task ID of asynchronous message mode

**Note:** If a user sends keystrokes to a session, an application window receives a message. The message is a return value of RegisterWindowMessage (“PCSHLL”). The wParam parameter contains the Task ID returned by the function call. HIWORD of lParam parameter contains return code 0, which shows that the function was successful, and LOWORD of lParam parameter contains function number 50.

#### Return Parameters

Return Code	Explanation
0	The <b>Start Keystroke Intercept</b> function was successful.
1	An incorrect presentation space was specified.
2	An incorrect option was specified.

Return Code	Explanation
4	The execution of the function was inhibited because the target presentation space was busy.
9	A system error was encountered. Release is being used.

### Notes on Using This Function

- If a return code of 31 occurs for the **Get Key (51)** function, either:
  - Increase the value of the calling length parameter for this function, or
  - Execute the **Get Key (51)** function more frequently.

An intercepted keystroke occupies 3 bytes in the buffer. The next intercepted keystroke is placed in the adjacent 3 bytes. When the **Get Key (51)** function retrieves a keystroke (first-in first-out, or FIFO), the 3 bytes that it occupied are made available for another keystroke. By increasing the size of the buffer or the rate at which keystrokes are retrieved from the buffer, you can eliminate buffer overflow.

In the PC/3270, another way to eliminate return code 31 is to operate the PC/3270 emulator in the resume mode.

- If option code *D* is provided, EHLLAPI writes intercepted non-AID keys to the presentation space to which they were originally intended, and returns only AID keys to the application.
- Call the **Stop Keystroke Intercept (53)** function before exiting your EHLLAPI application. Otherwise, keystroke interception remains enabled with unpredictable results.

## Start Playing Macro (110)

3270	5250	VT
Yes	Yes	Yes

The **Start Playing Macro** function invokes a macro. The macro will be executed in the connected session.

**Note:** This macro must exist in the PCOMM PRIVATE directory and no extension should be specified in the function call for the macro name.

### Prerequisite Calls

**Connect Presentation Space (1).**

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 110	
Data String	See the following table	
Length	Length of macro name, plus 3	
PS Position	NA	

Byte	Definition
Standard	Enhanced
1-2	Reserved

Byte	Definition
3-n	Null terminated macro name

### Return Parameters

Return Code	Explanation
0	The <b>Start Playing Macro</b> function was successful.
1	The programs is not connected to a host session.
2	An error was made in specifying parameters.
9	A system error was encountered.

## Stop Close Intercept (43)

3270	5250	VT
Yes	Yes	Yes

The **Stop Close Intercept** function allows the application to turn off the **Start Close Intercept** (41) function. After the application has issued the **Stop Close Intercept** function, subsequent close requests result in a normal stop sent to the logical terminal session.

### Prerequisite Calls

**Start Close Intercept** (41).

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 43	
Data String	1-character short session ID of the host presentation space	
Length	NA	Must be 4
PS Position	NA	

The calling data string can contain:

Byte	Definition	
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2-4	Reserved

### Return Parameters

Return Code	Explanation
0	The <b>Stop Close Intercept</b> function was successful.
1	An incorrect host presentation space was specified.
2	An error was made in specifying parameters.
8	No previous <b>Start Close Intercept</b> (41) function was issued.
9	A system error occurred.
12	The session stopped.

## Stop Host Notification (25)

3270	5250	VT
Yes	Yes	Yes

The **Stop Host Notification** function disables the capability of the **Query Host Update** (24) function to determine if the host presentation space or OIA has been updated. This function also stops host events from affecting the **Pause** (18) function.

### Prerequisite Calls

**Start Host Notification** (23).

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 121.	
Data String	See the following note.	
Length	1 is implied.	Must be 4.
PS Position	NA.	

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2-4	Reserved

**Note:** 1-character short name of the target presentation space ID, or a blank or a null to indicate a request for the host-connected presentation space.

### Return Parameters

Return Code	Definition
0	The <b>Stop Host Notification</b> function was successful.
1	An incorrect host presentation space was specified.
8	No previous <b>Start Host Notification</b> (23) function was issued.
9	A system error was encountered.

## Stop Keystroke Intercept (53)

3270	5250	VT
Yes	Yes	Yes

The **Stop Keystroke Intercept** function ends your application program's ability to intercept keystrokes.

### Prerequisite Calls

**Start Keystroke Intercept** (50).

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 53	
Data String	Short name of the target presentation space (PSID)	
Length	1 is implied	Must be 4
PS Position	NA	

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2-4	Reserved

## Return Parameters

Return Code	Explanation
0	The <b>Stop Keystroke Intercept</b> function was successful.
1	An incorrect presentation space was specified.
8	No prior <b>Start Keystroke Intercept</b> (50) function was called for this presentation space.
9	A system error was encountered.

## Wait (4)

3270	5250	VT
Yes	Yes	Yes

The **Wait** function checks the status of the host-connected presentation space. If the session is waiting for a host response (indicated by XCLOCK (X []) or XSYSTEM), the **Wait** function causes EHLLAPI to wait up to 1 minute to see if the condition clears.

## Prerequisite Calls

**Connect Presentation Space** (1).

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 4	
Data String	NA	
Length	NA	
PS Position	NA	

## Return Parameters

Return Code	Definition
0	The keyboard is unlocked and ready for input.
1	Your application program is not connected to a valid session.

Return Code	Definition
4	Timeout while still in XCLOCK (X []) or XSYSTEM.
5	The keyboard is locked.
9	A system error was encountered.

### Notes on Using This Function

1. The **Wait** function is used to give host requests like those made by the **Send Key** (3) function the time required to be completed. Using the **Set Session Parameters** (9) function, you can request the TWAIT, LWAIT, or the NWAIT option. See item 12 on page 123.
2. You can use this function to see if the host OIA is inhibited.
3. The **Wait** function is satisfied by the host unlocking the keyboard. Therefore, a return code of 0 does not necessarily mean that the transaction has been completed. To verify completion of the transaction, you should use the **Search Field** (30) function or **Search Presentation Space** (6) function combined with the **Wait** function to look for expected keyword prompts.

## Window Status (104)

3270	5250	VT
Yes	Yes	Yes

The **Window Status** function allows the application to query or change a window's presentation space size, location, or visible state.

### Prerequisite Calls

**Connect Window Services** (101).

### Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 104	
Data String	See the following table	
Length	16 or 20	24 or 28
PS Position	NA	

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID)
	2-4	Reserved
2	5	A request option value, select one of the following values: <ul style="list-style-type: none"> <li>• X'01' for set status</li> <li>• <b>Note:</b> When the session is embedded In-Place in a compound OLE document, the set form of this function (byte 5 = X'01') always returns 0 but has no effect.</li> <li>• X'02' for query for status</li> <li>• X'03' for query for extended status</li> </ul>
	6	Reserved



If the request option value is X'01' (set status):

Byte		Definition
Standard	Enhanced	
3–4	7–8	<p>A 16- or 32-bit word containing the status set bits if the request option is 1 (set status). The following codes are valid return values if the request option is set status:</p> <p><b>X'0001'</b> Change the window size. (Not valid with minimize, maximize, restore, or move.)</p> <p><b>X'0002'</b> Move the window. (Not valid with minimize, maximize, size, or restore.)</p> <p><b>X'0004'</b> ZORDER window replacement.</p> <p><b>X'0008'</b> Set the window to visible.</p> <p><b>X'0010'</b> Set the window to invisible.</p> <p><b>X'0080'</b> Activate the window. (Sets focus to window and places it in the foreground unless ZORDER is specified. In this case, the ZORDER placement is used.)</p> <p><b>X'0100'</b> Deactivate the window. (Deactivates the window and makes the window the bottom window unless ZORDER is also specified. In this case, the ZORDER placement is used.)</p> <p><b>X'0400'</b> Set the window to minimized. (Not valid with maximize, restore, size, or move.)</p> <p><b>X'0800'</b> Set the window to maximized. (Not valid with minimize, restore, size, or move.)</p> <p><b>X'1000'</b> Restore the window. (Not valid with minimize, maximize, size, or move.)</p>
5–6	9–12	A 16- or 32-bit word containing the X window position coordinate. (Ignored if the move option is not set.)
7–8	13–16	A 16- or 32-bit word containing the Y window position coordinate. (Ignored if the move option is not set.)
9–10	17–20	A 16- or 32-bit word containing the X window size in device units. (Ignored if the size option is not set.)
11–12	21–24	A 16- or 32-bit word containing the Y window size in device units. (Ignored if the size option is not set.)
13–16	25–28	<p>A 16- or 32-bit word containing a window handle for relative window placement. These two words are only for the set option. (Ignored if the ZORDER option is not set.)</p> <p>Valid values are as follows:</p> <p>X'00000003' Place in front of all sibling windows.</p> <p>X'00000004' Place behind all sibling windows.</p>

If the request option value is X'02' (query for status):

Byte		Definition
Standard	Enhanced	

Byte		Definition
3-4	7-8	<p>A 16- or 32-bit word containing X'0000' if the request option is 2 (query for status). The following codes are possible return values if the request option is query for status. More than one state is possible.</p> <p><b>X'0008'</b> The window is visible.</p> <p><b>X'0010'</b> The window is invisible.</p> <p><b>X'0080'</b> The window is activated.</p> <p><b>X'0100'</b> The window is deactivated.</p> <p><b>X'0400'</b> The window is minimized.</p> <p><b>X'0800'</b> The window is maximized.</p>
5-6	9-12	A 16- or 32-bit word containing the X window position coordinate. (Ignored if the move option is not set.)
7-8	13-16	A 16- or 32-bit word containing the Y window position coordinate. (Ignored if the move option is not set.)
9-10	17-20	A 16- or 32-bit word containing the X window size in device units. (Ignored if the size option is not set.)
11-12	21-24	A 16- or 32-bit word containing the Y window size in device units. (Ignored if the size option is not set.)
13-16	25-28	<p>A 16- or 32-bit word containing a window handle for relative window placement. These two words are only for the set option. (Ignored if the ZORDER option is not set.)</p> <p>Valid values are as follows:</p> <p>X'00000003' Place in front of all sibling windows.</p> <p>X'00000004' Place behind all sibling windows.</p>

If the request option value is X'03' (query for extended status):

Byte		Definition
Standard	Enhanced	
3-4	7-8	<p>A 16- or 32-bit word containing X'0000' if the request option is 3 (query for extended status). The following codes are possible return values if the request option is query for extended status. More than one state is possible.</p> <p><b>X'0008'</b> The window is visible.</p> <p><b>X'0010'</b> The window is invisible.</p> <p><b>X'0080'</b> The window is activated.</p> <p><b>X'0100'</b> The window is deactivated.</p> <p><b>X'0400'</b> The window is minimized.</p> <p><b>X'0800'</b> The window is maximized.</p>
5-6	9-10	A 16- or 32-bit word containing the current font size in the X-dimension. The value is in screen pels.
7-8	11-12	A 16- or 32-bit word containing the current font size in the Y-dimension. The value is in screen pels.
9-12	13-16	Reserved. This value is always zero.

Byte		Definition
13–14	17–18	A 16- or 32-bit word containing the row number of the first visible character of the presentation space. This value is usually one, unless the Fixed Size font option is in effect, and the window has been resized such that some of the presentation space is hidden.
15–16	19–20	A 16- or 32-bit word containing the column number of the first visible character of the presentation space.
17–20	21–24	A 16- or 32-bit word containing the presentation space window handle of the session.

### Return Parameters

Return Code	Explanation
0	The <b>Window Status</b> function was successful.
1	The presentation space was not valid or not connected.
2	An incorrect option was specified.
9	A system error occurred.
12	The session stopped.

### Notes on Using This Function

The logical terminal (LT) windows use character cells. When resizing the LT windows, the LT rounds the number to prevent character cell truncation. The requested size and position might be slightly different from what was requested. Follow the set option with a query option to determine the final Presentation Manager window position and size. All x and y coordinate positions and sizes are in pels.

## Write Structured Fields (127)

<i>3270</i>	<i>5250</i>	<i>VT</i>
Yes	No	No

The **Write Structured Fields** function allows an application to write structured field data to the host application. If the call specifies “S” (for Synchronous), the application does not receive control until the **Write Structured Fields** function is completed. If the call specifies “A” (for Asynchronous), the application receives control immediately after the call. If the call specifies “M”, the application receives control immediately after the call. The application may wait for the message. In any case (S, A or M), the application provides the buffer address in which data to the host is to be placed.

For a successful asynchronous completion of this function, the following statements apply:

The return code field in the parameter list might not contain the results of the requested I/O. If the return code is not 0, then the request failed. The application must take the appropriate action based on the return code.

If the return code for this request is 0, the application must use the request ID returned with this function call to issue the **Get Request Completion** function call to determine the completion results of the function associated with the request ID. The **Get Request Completion** function call returns the following information:

1. Function request ID
2. Address of the data string from the asynchronous request
3. Length of the data string
4. Return code of the completed function

## Prerequisite Calls

**Connect for Structured Fields (120) Allocate Communication Buffer (123).**

## Call Parameters

	Standard Interface	Enhanced Interface
Function Number	Must be 127	
Data String	See the following table	
Length	8, 10, or 14	Must be 20
PS Position	NA	

The calling data string can contain:

Byte		Definition
Standard	Enhanced	
1	1	A 1-character presentation space short name (PSID).
	2–4	Reserved.
2	5	S or A or M  <b>S =</b> Synchronous. Control is not returned to the application until the read is satisfied.  <b>A =</b> Asynchronous. Control is returned immediately to the application, can wait for the event object.  <b>M =</b> Asynchronous. Control is returned immediately to the application, can wait for the message.
	6	Reserved.
3–4	7–8	2-byte destination/origin ID.
5–8	9–12	4-byte address of the buffer from which the data is to be written. The buffer must be obtained using the <b>Allocate Communications Buffer (123)</b> function.
9–10	13–16	Reserved.
11–12	17–20	When “M” is specified in position 5 (2 for 16-bit), the window handle of the window that receives the message should be set. The message is a return value of RegisterWindowMessage (“PCSHLL”) (not equal 0).
13–14		The data in these positions is ignored by EHLLAPI. However, no error is caused if the migrating program has data in these positions. This data is accepted to provide compatibility with migrating applications.

## Return Parameters

This function returns a data string and a return code.

**Data String:**

If “A” (asynchronous) is specified in position 5 (2 for standard interface) and the function is completed successfully, the following data string is returned:

Byte		Definition
9–10	13–14	2-byte Function Request ID. It is used by the <b>Get Request Completion</b> (125) function to determine the completion of this function call.
	15–16	Reserved.
	17–20	4-byte value in which the event object address is returned by EHELLAPI. The application can wait for this event object. When the event object is cleared, the application must issue the <b>Get Request Completion</b> (125) function call to get results of the <b>Write Structured Fields</b> request. (32-bit only).

**Note:** An event object is returned for each successful asynchronous request. The event object should not be used again. A new event object is returned for each request and is valid for only the duration of that request.

**Data String:**

If “M” (asynchronous message mode) is specified in position 5 (2 for standard interface) and the function is completed successfully, the following data string is returned:

Byte		Definition
9–10	13–14	2-byte Function Request ID. It is used by the <b>Get Request Completion</b> (125) function to determine the completion of this function call.
	15–16	Reserved.
11–12	17–18	Task ID of asynchronous message mode.
	19–20	Reserved.

**Note:** If the function is completed successfully, an application window receive a message. The message is a return value of RegisterWindowMessage (“PCSHLL”). The wParam parameter contains the Task ID returned by the function call. HIWORD of lParam parameter contains return code 0, which shows the function was successful, and LOWORD of lParam parameter contains function number 127.

**Return Code:**

The following codes are defined:

Return Code	Explanation
0	The <b>Write Structured Fields</b> function was successful.
1	A specified host presentation space short session ID was not valid or was not connected.
2	An error was made in specifying parameters.
9	A system error occurred.
11	Resource unavailable (memory unavailable).
34	The message sent inbound to the host was canceled.
35	An outbound transmission from the host was canceled.
36	Request rejected. Lost contact with the host.
37	Failed. The host is inbound disabled.

## Notes on Using This Function

1. Return code 35 will be returned when the first **Read Structured Fields** or **Write Structured Fields** is requested after an outbound transmission from the host is canceled. Corrective action is the responsibility of the application.
2. Return code 36 requires that the application disconnect from the emulation program and then reconnect to reestablish communications with the host. Corrective action is the responsibility of the application.
3. Return code 37 will be returned if the host is inbound disabled.
4. The EHLLAPI allows for a maximum of 20 asynchronous requests per application to be outstanding. A return code for unavailable resources (RC=11) is returned if more than 20 asynchronous requests are attempted.
5. If you are using IBM Global Network connections, the maximum number of asynchronous requests is 10.

The structured field data format is as follows:

Offset	Length	Contents
0	1 word	X'0000'
2	1 word	m (message length: the number of bytes of data in the message, the number does not include the buffer header prefix, which contains 8 bytes). This value must be set by the application.
4	1 word	X'0000'
6	1 word	X'0000'
8	8 bytes	Length of the first (or only) structured field message.
10	1 byte	First nonlength byte of the structured field message.
		:
		:
m+7	1 byte	Last byte in the structured field message.

Bytes 0 through 7 are the buffer header. These first 8 bytes are used by the emulation program. The user section of the buffer begins with offset 8. Bytes 8 and 9 contain the number of bytes in the first structured field (a structured field message can contain multiple structured fields) including 2 bytes for bytes 8 and 9. Bytes 8 through  $m+7$  are used for the structured field message sent to the host.

**Synchronous Requests:** When **Write Structured Fields** is requested synchronously (the S option in the data string), control is returned to the application only after the request is satisfied. The application can assume:

- The return code is correct.
- The data in the communications buffer (read buffer) is correct.
- The host is no longer processing the **Write Structured Fields** request.

**Asynchronous Requests:** When **Write Structured Fields** is requested asynchronously (the A option in the data string), the application *cannot* assume:

- The return code is correct.
- The data in the communications buffer (write buffer) is correct.
- The host is no longer processing the **Write Structured Fields** request.

When requested asynchronously, EHLLAPI returns the following values:

- A 16-bit Request ID in positions 13–14 (9–10 for standard interface) of the data string
- The address of a event object in positions 17–20 of the data string.

These are used to complete the asynchronous **Write Structured Fields** call.

The following steps must be completed to determine the outcome of an asynchronous **Write Structured Fields** function call:

- If the EHLLAPI return code is not zero, the request failed. No asynchronous request has been made. The application must take appropriate actions before attempting the call again.
- If the return code is zero, the application should wait until the event object is in the signaled state by using the **Get Request Completion** (125) function. The event object **Get Request Completion** (125) function) and should not be reused. The event object is valid only for the duration of the **Write Structured Fields** function call through the completion of the **Get Request Completion** (125) function call.
- Once the event object is in the signaled state use the returned 16-bit Request ID as the Request ID parameter in a call to the **Get Request Completion** (125) function. The data string returned from the **Get Request Completion** (125) function call contains the final return code of the **Write Structured Fields** function call.

**Asynchronous Requests:** When **Write Structured Fields** is requested asynchronously (the M option in the data string), the application cannot assume:

- The return code is correct
- The data in the communications buffer (write buffer) is correct
- The host is no longer processing the **Write Structured Fields** request

When requested asynchronously with the M option, EHLLAPI returns the following values:

- A 16-bit request ID in positions 13–14 (9–10 for standard interface) of the data string
- Task ID of asynchronous message mode in position 17–18 (11–12 for standard interface)

These are used to complete the asynchronous **Write Structured Fields** call.





---

## Chapter 4. WinHLLAPI Extension Functions

The following sections describe the extension functions provided when using WinHLLAPI programming support.

---

### Summary of WinHLLAPI Functions

The following table is the summary of the WinHLLAPI functions:

No.	Function	3270	5250	VT	Page
4	Wait (4)	Yes	Yes	Yes	148
23	Start Host Notification (23)	Yes	Yes	Yes	148
41	Start Close Intercept (41)	Yes	Yes	Yes	149
50	Start Keystroke Intercept (50)	Yes	Yes	Yes	150
90	Send File (90)	Yes	Yes	Yes	151
91	Receive File (91)	Yes	Yes	Yes	152

---

### WinHLLAPI Asynchronous Functions

The following sections describe the WinHLLAPI asynchronous functions.

#### WinHLLAPIAsync

This entry point is used for six WinHLLAPI functions that often take a long time to complete. With WinHLLAPIAsync, the function will be launched asynchronously and will not interfere with the continued progression of the calling application. These functions are: **Wait** (04), **Start Host Notify** (23), **Start Close Intercept** (41), **Start Keystroke Intercept** (50), **Send File** (90), and **Receive File** (91), and are described in "Chapter 4. WinHLLAPI Extension Functions".

HANDLE WinHLLAPIAsync (HWINDOW hWnd, LPWORD *lpnFunction*, LPBYTE *lpData*, LPWORD *lpnLength*, LPWORD *lpnRetC*)\*

The parameter list is the same as WinHLLAPI except a window handle is required before the function number. Since the function operates asynchronously, its completion is signaled by a registered message. The window handle is required as the target of the message.

There are two messages that must be registered by the WinHLLAPI application through calls to **RegisterWindowsMessage()** with the strings **WinHLLAPIAsync** (for all functions except 90 and 91) and **WinHLLAPIAsyncFileTransfer** (for functions 90 and 91). The standard format is as follows:

**WPARAM**

contains the Task Handle returned by the original function call.

**LPARAM**

the high word contains the error code and the low word contains the original function number.

## Wait (4)

This function determines whether the Host session is in an inhibited state. If, for some reason, the session is in an inhibited state, this function will signal your application with a message when either the inhibited state expires or your wait period has expired. The amount of time to wait is set with the **Set Session Parameters (9)** function.

**Prerequisite Functions:** Connect Presentation Space (1)

**WinHLLAPIAsync**(*hWnd, lpwFunction, lpbyString, lpwLength, lpwReturnCode*)

**Call Parameters:**

Parameter	Description
<i>Data String</i>	NA
<i>Data Length</i>	NA
<i>PS Position</i>	NA

**Return Codes:**

Code	Description
WHLLOK	The PS is uninhibited and ready for input.
WHLLNOTCONNECTED	Your WinHLLAPI application is not connected to a valid host session.
WHLLPSBUSY	Function timed out while still inhibited.
WHLLNHIBITED	The PS is inhibited.
SHLLSYSERROR	The function failed due to a system error.
WHLLCANCEL	The asynchronous function was cancelled.

**Remarks:** Asynchronous Wait is used to notify the calling application when the inhibited state of the PS is expired. When inhibited state has expired, this version of **Wait** will post a **WinHLLAPIAsync** message to the window specified by the *hWnd*. The session options **TWAIT**, **LWAIT**, and **NWAIT** affect the length of time that this function will wait. See **Set Session Parameters (9)** for details on these session options.

**Note:** If **NWAIT** is specified in the session parameters and the application registers using revision 1.1 of the WinHLLAPI implementation, the **WinHLLAPIAsync** call will work the same as the **WinHLLAPI** call and not send a message. If revision 1.0 is being used then **Wait** will return a message immediately with the inhibited status of the PS.

## Start Host Notification (23)

This function enables you to notify your WinHLLAPI application of changes in the Host Session Presentation Space (PS) or Operation Information Area (OIA).

**Prerequisite Functions:** None.

**WinHLLAPIAsync** (*hWnd, lpwFunction, lpbyString, lpwLength, lpwReturnCode*)

### Call Parameters:

Parameter	Description
<i>Data String</i>	A 7-byte string in the following format:  <b>Byte 1</b> Short name session ID of the desired Host session, or space or null for the current Host session.  <b>Byte 2</b> Notification mode. "P" for presentation space update only, "O" for OIA update only, "B" for both presentation space and OIA updates. When calling WinHLLAPIAsync, this position can be "A".  <b>Byte 3-6</b> Not used. Provided for compatibility with older applications.  <b>Byte 7</b> Reserved or replaced with one of the following if using WinHLLAPIAsync and "A" in byte 2: "P" for presentation space update only, "O" for OIA update only; and "B" for both presentation space and OIA updates.
<i>Data Length</i>	Length of Host event buffer (256 recommended).
<i>PS Position</i>	NA

### Return Parameters:

Parameter	Description
<i>Data String</i>	Same as <i>Data String</i> on the call.

### Return Codes:

Code	Description
WHLLOK	Host notification enabled.
WHLLNOTCONNECTED	The specified Host session is invalid.
WHLLPARAMETERERROR	One of more parameters are invalid.
WHLLSYSERROR	The function failed due to a system error.
WHLLCANCEL	The asynchronous function was cancelled.

**Remarks:** Once enabled, Host notification is enabled until you call **Stop Host Notification (25)** or **WinHLLAPICancelAsyncRequest()**. The function initiates host notification and immediately returns control to your Windows HLLAPI application. This frees your application to perform other tasks while waiting for host updates. When an update occurs, the function will notify the window specified by *hWnd* with the registered message **WinHLLAPIAsync**.

### Start Close Intercept (41)

This function intercepts user requests to close Personal Communications.

**Prerequisite Functions:** None.

**WinHLLAPIAsync** (*hWnd*, *lpwFunction*, *lpbyString*, *lpwLength*, *lpwReturnCode*)

**Call Parameters:**

Parameter	Description
<i>Data String</i>	A 5-byte string for returned semaphore address. The first byte is the session short name of the session to query, or space or null for the current session.
<i>Data Length</i>	Must be specified.
<i>PS Position</i>	NA

**Return Parameters:**

Parameter	Description
<i>Data String</i>	A 5-byte string with the following format:  <b>Byte 1</b> Session short name, or space or null for the current session  <b>Bytes 2-5</b> Semaphore address.

**Return Code:**

Code	Description
WHLLOK	The function was successful.
WHLLNOTCONNECTED	An invalid presentation space was specified.
WHLLPARAMETERERROR	An invalid option was specified.
WHLLSYSERROR	The function failed due to a system error.
WHLLCANCEL	The asynchronous function was cancelled.

**Remarks:** Once enabled, Host notification remains enabled until you call **Stop Close Intercept (43)** or **WinHLLAPICancelAsyncRequest ()**. Initially, the semaphore is set. After using this function, close requests from the user are discarded and the semaphore is cleared.

The function initiates close intercept and immediately returns control to your Windows HLLAPI application. This frees your application to perform other tasks while waiting for close requests. When a close request occurs, the function will notify the window specified by *hWnd* with the registered message **WinHLLAPIAsync**.

**Start Keystroke Intercept (50)**

This function intercepts keystrokes sent to a session by the user.

**Prerequisite Functions:** None.

**WinHLLAPIAsync** (*hWnd, lpwFunction, lpbyString, lpwLength, lpwReturnCode*)

**Call Parameters:**

Parameter	Description
-----------	-------------

<i>Data String</i>	A 6-byte string in the following format:  <b>Byte 1</b> Session short name, or space or null for the current Host session.  <b>Byte 2</b> Keystroke intercept code. "D" causes only AID keystrokes to be intercepted; "L" causes all keystrokes to be intercepted.  <b>Bytes 3-6</b> Reserved
<i>Data Length</i>	Variable (256 is recommended)
<i>PS Position</i>	NA

**Return Code:**

Code	Description
WHLLOK	Keystroke intercept has been initiated.
WHLLNOTCONNECTED	The Host session presentation space is invalid.
WHLLPARAMETERERROR	One or more parameters are invalid.
WHLLPSBUSY	Session is busy.
WHLLSYSERROR	Function failed due to a system error.
WHLLCANCEL	Asynchronous function was cancelled.

**Remarks:** The function initiates keystroke intercept and immediately returns control to your Windows HLLAPI application. This frees your application to perform other tasks while waiting for keystrokes. Once initiated, the function will post a **WinHLLAPIAsync** message to the window specified by *hWnd* whenever the user sends a key to the PS. After notification, the intercepted keystrokes can be handled in any way that is allowed by a normal ELLAPI application. Take note that the keystroke buffer is of limited size so each keystroke should be handled and removed from the buffer.

## Send File (90)

This function transfers a file from the PC to the Host.

**Prerequisite Functions:** None.

**WinHLLAPIAsync** (*hWnd*, *lpwFunction*, *lpbyString*, *lpwLength*, *lpwReturnCode*)

**Call Parameters:**

Parameter	Description
<i>Data String</i>	SEND command parameters.
<i>Data Length</i>	Length of <i>Data String</i> . NA if session option EOT is specified.
<i>PS Position</i>	NA

**Return Codes:**

Code	Description
WHLLOK	File transfer started successfully.

WHLLPARAMETERERROR	Parameter error or <i>Data Length</i> is zero or greater than 255.
WHLLFTXCOMPLETE	File transfer complete.
WHLLFTXSEGMENTED	Transfer is complete with segmented records.
WHLLSYSERROR	The function failed due to a system error.
WHLLTRANSABORTED	File transfer aborted, either due to the user clicking the cancel button or because the timeout period has elapsed.
WHLLFILENOTFOUND	PC file not found.
WHLLFTXCOMPLETECICS	File transfer was successful (transfer to CICS).
WHLLACCESSDENIED	Access denied to PC file.
WHLLMEMORY	Insufficient memory.
WHLLINVALIDENVIRONMENT	Invalid environment.

**Remarks:** Only one file transfer operation is supported per connected Host session.

The function initiates the file transfer and immediately returns control to your Windows HLLAPI application. This frees your application to perform other tasks while the file transfer is occurring. Once initiated the function will regularly post **WinHLLAPIAsyncFileTransfer** messages to the window specified by *hWnd*. These messages will notify the WinHLLAPI application of the status of the transfer and send a final message when the transfer is complete.

*where::*

**wParm**

Is the status indicator: the high byte contains the Session ID, the low byte contains the status. If the low byte is zero, the file transfer is still in progress. If the low byte is one, the file transfer has completed.

**IParm** If the low byte of *wParm* is zero (in progress), *IParm* is the number of bytes transferred. If the low byte *wParm* is one (completed), *IParm* is the completion code.

**Receive File (91)**

This function transfers a file from the PC to the Host.

**Prerequisite Functions:** None.

**WinHLLAPIAsync** (*hWnd, lpwFunction, lpbyString, lpwLength, lpwReturnCode*)

**Call Parameters:**

Parameter	Description
<i>Data String</i>	RECEIVE command parameters.
<i>Data Length</i>	Length of <i>Data String</i> . NA if session option EOT is specified.
<i>PS Position</i>	NA

### Return Codes:

Code	Description
WHLLLOK	File transfer started successfully.
WHLLPARAMETERERROR	Parameter error or <i>Data Length</i> is zero or greater than 255.
WHLLFTXCOMPLETE	File transfer complete.
WHLLFTXSEGMENTED	Transfer is complete with segmented records.
WHLLSYSERROR	The function failed due to a system error.
WHLLTRANSABORTED	File transfer aborted, either due to the user clicking the cancel button or because the timeout period has elapsed.
WHLLFILENOTFOUND	PC file not found.
WHLLFTXCOMPLETECICS	File transfer was successful (transfer to CICS).
WHLLACCESSDENIED	Access denied to PC file.
WHLLMEMORY	Insufficient memory.
WHLLINVALIDENVIRONMENT	Invalid environment.

**Remarks:** Only one file transfer operation is supported per connected Host session.

The function initiates the file transfer and immediately returns control to your Windows HLLAPI application. This frees your application to perform other tasks while the file transfer is occurring. Once initiated the function will regularly post **WinHLLAPIAsyncFileTransfer** messages to the window specified by *hWnd*. These messages will notify the WinHLLAPI application of the status of the transfer and send a final message when the transfer is complete.

*where::*

#### **wParm**

Is the status indicator: the high byte contains the Session ID, the low byte contains the status. If the low byte is zero, the file transfer is still in progress. If the low byte is one, the file transfer has completed.

**IParm** If the low byte of *wParm* is zero (in progress), *IParm* is the number of bytes transferred. If the low byte *wParm* is one (completed), *IParm* is the completion code.

## WinHLLAPICancelAsyncRequest

This function cancels an outstanding asynchronous function launched by a call to **WinHLLAPIAsync()**.

### Syntax

**int WinHLLAPICancelAsyncRequest** (HANDLE *hAsyncTask*, WORD *wFunction*)

## Parameters

### **hAsyncTask**

The handle returned by WinHLLAPIAsync() when the function was initiated.

### **wFunction**

The function number of the asynchronous task to cancel. Because this parameter is required for revision 1.1 but not in 1.0, it is optional.

With this function, any asynchronous task previously initiated by a call to WinHLLAPIAsync() may be canceled while still outstanding.

## Returns

The return value indicates if the specified function was, in fact, canceled. If the function was canceled then the return value is WHLLOK (0). If the outstanding asynchronous function was not cancelled, one of the following codes will be returned.

### **WHLINVALID**

hAsyncTask is not a valid task handle.

### **WHLALREADY**

The asynchronous task specified by hAsyncTask has already completed.

---

## Initialization/Termination Functions

The following section describes the initialization and termination functions of WinHLLAPI programming support.

### WinHLLAPI Startup

This function is used to register the application with the WinHLLAPI implementation and should be called before any other call to the WinHLLAPI implementation. This implementation supports Versions 1.0 and 1.1 of the WinHLLAPI specification. The WinHLLAPI application should negotiate version compatibility with this function.

### Syntax

```
int WinHLLAPIStartup(WORD wVersionRequired, LPWHLAPIDATA lpData)
```

### Parameters

#### **wVersionRequired**

This is the version required by the WinHLLAPI application. The low byte contains the major version number and the high byte contains the minor version (or revision) number.

#### **lpData**

This is a pointer to a WHLLAPIDATA structure which will receive the implementations version number and a string describing the WinHLLAPI implementation provider. The WHLLAPIDATA structure is defined as:

```
#define WHLLDESCRIPTION_LEN 127
typedef struct tagWHLAPIDATA
{
    WORD wVersion;
    Char szDescription[WHLLDESCRIPTION_LEN + 1];
}WHLAPIDATA, * PWHLAPIDATA, FAR *LPWHLAPIDATA;
```



## Returns

The return value indicates success or failure of registering the WinHLLAPI application with the implementation. If registration was successful, the return value is WHLLOK (zero). Otherwise, it is one of the following:

### WHLLSYSNOTREADY

Indicates that the underlying network subsystem is unavailable.

### WHLLVERNOTSUPPORTED

Indicates that the version requested is not provided by this implementation. This implementation supports Versions 1.0 and 1.1 only.

## WinHLLAPI Cleanup

The WinHLLAPI specification recommends that this function be used by the WinHLLAPI application to de-register from the WinHLLAPI implementation.

## Syntax

**BOOL WinHLLAPICleanup()**

## Returns

Returns TRUE if the de-registration was successful. Otherwise, it returns FALSE.

---

## Blocking Routines

The following sections describe the blocking routines supported by WinHLLAPI programming.

**Note:** Although blocking routines are supported for WinHLLAPI compliance, use of them is not recommended. Use of the WinHLLAPIAsync functions are the recommended method for asynchronous processing.

## WinHLLAPIIsBlocking

This function tells the calling WinHLLAPI application thread whether it is in the process of executing a blocking call. A blocking call is any synchronous function that takes a long time to execute and does not return until complete. There are five blocking calls in this implementation of WinHLLAPI. The blocking calls are: **Get Key (51)**, **Wait (4)**, **Pause (18)**, **Send File (90)**, and **Receive File (91)**.

## Syntax

**BOOL WinHLLAPIIsBlocking()**

## Returns

If the WinHLLAPI application thread is in the middle of a blocking call, the function returns TRUE, otherwise, it returns FALSE.

## Remarks

Because the default blocking-hook allows messages to be processed during blocking calls, it is possible to call the blocking call again.

## WinHLLAPISetBlockingHook

This function sets an application-defined procedure to be executed while waiting for the completion of a blocking call. A blocking call is any synchronous function that takes a long time to execute and does not return until complete. There are five blocking calls in this implementation of WinHLLAPI. The blocking calls are: **Get Key (51)**, **Wait (4)**, **Pause (18)**, **Send File (90)**, and **Receive File (91)**.

### Syntax

**FARPROC** WinHLLAPISetBlockingHook(*FARPROC lpfnBlockingHook*)

### Parameters

#### **lpfnBlockingHook**

This is a pointer to the new blocking procedure.

### Description

The WinHLLAPI implementation has a default blocking procedure that consists of nothing more than a message handler. This default mechanism is shown in the following example:

```
BOOL DefaultBlockingHook
{
    MSG msg;

    if (PeekMessage (&msg, NULL, 0, 0, xFPM_NOREMOVE))
    {
        if(msg.message == WM_QUIT)
        {
            return FALSE;
        }
        PeekMessage (&msg, NULL, 0, 0, PM_REMOVE);
        TranslateMessage (&msg);
        DispatchMessage (&msg);
    }
    return TRUE;
}
```

The blocking hook is implemented on a per-thread basis. A blocking hook set by this function will stay in effect for the thread until it is replaced by another call to **WinHLLAPISetBlockingHook()** or until the default is restored by a call to **WinHLLAPIUnhookBlockingHook()**.

The Blocking function must return **FALSE** if it receives a **WM\_QUIT** message so WinHLLAPI can return control to the application to process the message and terminate gracefully. Otherwise, the function should return **TRUE**.

### Returns

This function returns a pointer to the blocking function being replaced.

## WinHLLAPIUnhookBlockingHook

This function restores the default blocking-hook for the calling thread.

### Syntax

**BOOL** WinHLLAPIUnhookBlockingHook()

## Returns

This function returns TRUE if the default blocking mechanism was successfully restored, otherwise it returns FALSE.

## WinHLLAPICancelBlockingCall

This function cancels an executing blocking call in the *current thread*. A blocking call is any synchronous function that takes a long time to execute and does not return until complete. There are five blocking calls in this implementation of WinHLLAPI. The blocking calls are **Get Key** (51), **Wait** (4), **Pause** (18), **Send File** (90), and **Receive File** (91). If one of these is blocking calls are cancelled, the cancelled function will return WHLLCANCEL.

## Syntax

**int WinHLLAPICancelAsyncRequest()**

## Returns

The return value indicates if the specified function was, in fact, canceled. If the function was canceled, then the return value is WHLLOK (0). If the outstanding blocking function was cancelled then the following code will be returned.

### **WHLLINVALID**

Indicates that there is no blocking call currently executing.



---

## Chapter 5. PCSAPI Functions

Personal Communications provides an API set, which is defined here and called *PCSAPI*. Whereas EHLLAPI is used to manage the interaction between a workstation application program and host systems after the session is established, the PCSAPI can be used to control the Personal Communications session itself.

This chapter describes each individual PCSAPI function in detail. The functions are arranged alphabetically by name.

---

### How to Use PCSAPI

You can write application programs using the PCSAPI in C or C++. To develop a PCSAPI application:

1. Prepare source code and add the appropriate PCSAPI calls.
2. Include the header file **PCSAPI.H** in the application program.
3. Compile the source code.
4. Link the resultant **.OBJ** files with the appropriate object file or libraries.

You must also link it with the PCSAPI import library, **PCSCALLS.LIB** for 16-bit and **PCSCAL32.LIB** for 32-bit.

---

### Page Layout Conventions

All PCSAPI function calls are presented in the same format so that you can quickly retrieve the information you need. The format is:

Function Name  
Function Type  
Parameter Type and Description  
Return Code

#### Function Type

“Function Type” shows the type of the function in the following format:

**TYPE** **FunctionName**(*TYPE Parameter1, ...*)

#### Parameter Type and Description

“Parameter Type and Description” lists the type and describes each of the parameters to be specified in the PCSAPI function call.

#### Return Code

“Return Code” lists the codes that must be received by your program after a call to the PCSAPI function.

## pcsConnect Session

3270	5250	VT
Yes	Yes	Yes

The **pcsConnectSession** function starts the communications with a host session specified by the short session ID. This function is valid for both 3270 and 5250 sessions. The session must already be started. This call is equivalent to the Communications-Connect pull-down menu item on the emulator window.

### Function Type

**BOOL** WINAPI **pcsConnectSession**(*char cShortSessionID*)

### Parameter Type and Description

**char cShortID**

Presentation space short session ID.

### Return Code

Return Code	Meaning
TRUE	Function ended successfully.
FALSE	It means one of the following things: <ul style="list-style-type: none"><li>• The session has not started.</li><li>• An incorrect session ID was specified.</li><li>• Call failed.</li></ul>

## pcsDisconnect Session

3270	5250	VT
Yes	Yes	Yes

The **pcsDisconnectSession** function stops the communications link with a host session specified by the short session ID. This function is valid for both 3270 and 5250 sessions. This only disconnects the link, it does not stop the session. This call is equivalent to the Communications-Disconnect pull-down menu item on the emulator window.

### Function Type

**BOOL** WINAPI **pcsDisconnectSession**(*char cShortSessionID*)

### Parameter Type and Description

**char cShortID**

Presentation space short session ID.

### Return Code

Return Code	Meaning
TRUE	Function ended successfully.

Return Code	Meaning
FALSE	It means one of the following things: <ul style="list-style-type: none"> <li>• The session has not started.</li> <li>• An incorrect session ID was specified.</li> <li>• Call failed.</li> </ul>

## pcsQueryEmulatorStatus

3270	5250	VT
Yes	Yes	Yes

The **pcsQueryEmulatorStatus** function returns the status of the host session specified by the short session ID.

### Function Type

**ULONG** WINAPI **pcsQueryEmulatorStatus**(*char cShortSessionID*)

### Parameter Type and Description

**char cShortSessionID**

Presentation space short session ID.

### Return Code

The return code value should be processed bit-significantly, that is, by either one of the following values or an ORed value out of the following values:

Return Code	Value	Meaning
PCS_SESSION_STARTED	0x00000001	Specified session has started. When this bit is off, the specified session has not started or an incorrect session ID was specified.
PCS_SESSION_ONLINE	0x00000002	Specified session is online (connected). When this bit is off, the specified session is offline (disconnected).
PCS_SESSION_API_ENABLED	0x00000004	API (EHLLAPI, DDE) is enabled on the specified session. If this bit is off, API is disabled on this session.

## pcsQuerySessionList

3270	5250	VT
Yes	Yes	Yes

The **pcsQuerySessionList** function returns a list of all the current host sessions. The application must supply an array of SESSINFO structures as defined in the

PCSAPI.H file, and a count of the number of elements in the array. This function fills in the structures with information about each session and returns the number of sessions found.

If the array has fewer elements than there are host sessions, then only the supplied elements of the array are filled in. The function always returns the actual number of sessions, even if the array is too small.

An application can call this function with zero array elements to determine how many sessions exist. A second call can then be made to obtain the session information.

## Function Type

**ULONG WINAPI pcsQuerySessionList(ULONG Count, SESSINFO \*SessionList)**

## Parameter Type and Description

### ULONG Count

Number of elements in the SessionList array.

### SESSINFO \*SessionList

Pointer to an array of SESSINFO structures as defined in PCSAPI.H.

## Return Parameters

### Return Code

Total number of PComm sessions. This may be greater than or less than the Count parameter.

### SessionList

The array of SESSINFO structures is filled with information about the host sessions. Sessions may be placed in the list in any order. Each SESSINFO structure contains the following fields (defined in PCSAPI32.H)

**Name** A union of "char" and "ULONG" which contains the session ID ('A' — 'Z'). In the current implementation of PComm, only the lower byte ("char") is used, the other bytes are returned as zero.

### Status

A combination of bit flags which indicate the current status of the session. The flags (PCS\_SESSION\_\*) are defined in the following table.

The status value should be processed bit-significantly, that is, by either one of the following values or an ORed value out of the following values:

Return Code	Meaning
PCS_SESSION_STARTED	The session is running. If this flag is not set, all others are undefined.
PCS_SESSION_ONLINE	The session has established a communications link to the host (e.g. the session is "connected").
PCS_SESSION_API_ENABLED	The session is enabled for programming APIs. If this flag is not set, the EHLAPI and Host Access Class Library APIs cannot be used on this session.



## Example

```
ULONG      NumSessions, i; // Session counters
SESSINFO  *SessList;      // Array of session information structures
// Find out number of sessions that exist
NumSessions = pcsQuerySessionList (0,NULL);
if (NumSessions == 0) {
    printf("There are no sessions.");
    exit;
}

// Allocate array large enough for all sessions
SessList = (SESSINFO *)malloc(NumSessions * sizeof(SESSINFO));
memset(SessList, 0x00, NumSessions * sizeof(SESSINFO));

// Now read actual session info
pcsQuerySessionList(NumSessions, SessList);

for (i=0; i<NumSessions; i++) {
    if ((SessList[i].Status & PCS_SESSION_STARTED) &&
        (SessList[i].Status & PCS_SESSION_ONLINE)) {

        printf("Session %c is started and connected.",
            SessList[i].Name.ShortName);
    }
}

exit;
```

## pcsQueryWorkstationProfile

3270	5250	VT
Yes	Yes	Yes

The **pcsQueryWorkstationProfile** function returns the workstation profile name that has been used to invoke the host session. To specify the host session, the short session ID must be used. The workstation profile name is copied to the work buffer supplied by the application.

### Function Type

**BOOL** WINAPI **pcsQueryWorkstationProfile**(*char cShortSessionID, PSZ lpBuffer*)

### Parameter Type and Description

#### **char cShortSessionID**

Presentation space short session ID.

#### **PSZ lpBuffer**

Work buffer to copy a null-terminated workstation profile name. The buffer must be large enough to contain a fully qualified file name.

### Return Code

Return Code	Meaning
TRUE	Function ended successfully.
FALSE	It means one of the following things: <ul style="list-style-type: none"><li>• The session has not started.</li><li>• An incorrect session ID was specified.</li></ul>

## pcsSetLinkTimeout

3270	5250	VT
Yes	Yes	Yes

The **pcsSetLinkTimeout** function sets the idle timeout of a Telnet link which is SSCP owned. This function has no effect on non-TN connections or connections which are not in SSCP owned state. If the timeout value is set to zero the link will not timeout. Otherwise the link will timeout (disconnect) after being idle in SSCP-owned state for the number of minutes specified.

### Function Prototype

**ULONG WINAPI pcsSetLinkTimeout**(*char cShortSessionID, USHORT Timeout*)

### Parameter Type and Description

**char cShortSessionID**

Presentation space short session ID.

**USHORT Timeout**

Timeout value in minutes. A value of zero disables timeout.

### Return Code

Return Code	Meaning
PCS_SUCCESSFUL	The function ended successfully.
PCS_SYSTEM_ERROR	A system error occurred.

## pcsStartSession

3270	5250	VT
Yes	Yes	Yes

The **pcsStartSession** function starts a host session by using a specified workstation profile. A short session ID can also be specified.

### Function Type

**ULONG WINAPI pcsStartSession**(*PSZ lpProfile, char cShortSessionID, USHORT fuCmdShow*)

### Parameter Type and Description

**PSZ lpProfile**

Path and completefilename of the profile to load. Path is optional but completefilename must be specified, (.ws is not assumed).

**char cShortSessionID**

Presentation space short session ID. Space or NULL indicates the next available session ID.

**USHORT fuCmdShow**

Specifies how the window is to be displayed. One of the following values from PCSAPI.H:

- PCS\_HIDE
- PCS\_SHOW
- PCS\_MINIMIZE

- PCS\_MAXIMIZE

## Return Code

Return Code	Value	Meaning
PCS_SUCCESSFUL	0	The function ended successfully.
PCS_INVALID_ID	1	An incorrect session ID was specified.
PCS_USED_ID	2	The specified short session ID is already used.
PCS_INVALID_PROFILE	3	An error was made in specifying the workstation profile, or the window parameter was not valid.
PCS_SYSTEM_ERROR	9	A system error occurred.

## pcsStopSession

3270	5250	VT
Yes	Yes	Yes

The **pcsStopSession** function stops a host session specified by the short session ID.

## Function Type

**BOOL** WINAPI **pcsStopSession**(*char cShortSessionID*, *USHORT fuSaveProfile*)

## Parameter Type and Description

### char cShortSessionID

Presentation space short session ID.

### USHORT fuSaveProfile

This parameter can be one of the following values:

fuSaveProfile	Value	Meaning
PCS_SAVE_AS_PROFILE	0	Save the profile as specified in the current profile.
PCS_SAVE_ON_EXIT	1	Save the profile on exit.
PCS_NOSAVE_ON_EXIT	2	Do not save the profile on exit.

## Return Code

Return Code	Meaning
TRUE	The function ended successfully.
FALSE	It means one of the following things: <ul style="list-style-type: none"> <li>• The session has not started.</li> <li>• An incorrect session ID was specified.</li> </ul>



---

## Chapter 6. DDE Functions for Windows and OS/2

Presented in this chapter is information for DDE functions as used in a Windows environment as well as the OS/2 environment.

---

### DDE Functions in a Windows 32-Bit Environment

Personal Communications for Windows and OS/2 provides a 32-bit dynamic data exchange (DDE) interface that allows applications to exchange data. The exchange of data between two Windows applications can be thought of as a conversation between a client and a server. The *client* initiates DDE conversations. The *server* in turn responds to the client. Personal Communications is a DDE server for the open sessions that Personal Communications is managing. For more information about DDE, refer to *Microsoft Windows Software Development Kit Guide to Programming*.

**Note:** If you use DDE functions with Visual Basic, see “Chapter 7. Using DDE Functions with a DDE Client Application” on page 325.

Personal Communications for Windows and OS/2 also supports 16-bit DDE applications. See “Appendix G. DDE Functions in a 16-Bit Environment” on page 397 .

### Personal Communications DDE Data Items

Microsoft Windows DDE uses a three-level naming scheme to identify data items: application, topic, and item. Table 13 on page 167 describes these levels.

Table 13. Naming Scheme for Data Items

Level	Description	Example
Application	A Windows task or a particular task of an application. In this book, the application is Personal Communications.	IBM327032
Topic	A specific part of an application.	SessionA
Item	A data object that can be passed in a data exchange. An item is an application-defined data item that conforms to one of the Windows clipboard formats or to a private, application-defined, clipboard format. For more information regarding Windows clipboard formats, refer to <i>Microsoft Windows Software Development Kit Guide to Programming</i>	PS (presentation space)

Personal Communications for Windows and OS/2 supports the following applications as Win32 DDE server.

Table 14. Applications for Personal Communications

**Application**  
IBM327032  
IBM525032

The following table lists the topics you can use.

Table 15. Topics for Personal Communications

**Topics**

- System
- SessionA, SessionB, ..., SessionZ
- LUA\_xxxx, LUB\_xxxx, ..., LUZ\_xxxx

In DDE, *atoms* identify application names, topic names, and data items. Atoms represent a character string that is reduced to a unique integer value. The character string is added to an atom table, which can be referred to for the value of the string associated with an atom. Atoms are created with the GlobalAddAtom function call. Refer to *Microsoft Windows Software Development Kit Guide to Programming* for more information about how to create and use atoms.

**Using System Topic Data Items**

Applications that provide a DDE interface should also provide a special topic SYSTEM. This topic provides a context for items of information that might be of general interest to an application. The SYSTEM topic for Personal Communications contains these associated data items:

<b>Item</b>	<b>Function</b>
<b>Formats</b>	Returns the list of clipboard formats (numbers) that Personal Communications is capable of rendering.
<b>Status</b>	Returns information about the status of each Personal Communications session.
<b>SysCon</b>	Returns the level of Personal Communications support and other system related values.
<b>Systems</b>	Returns the list of data items that are available when connected to the Personal Communications system topic.
<b>Topics</b>	Returns the list of Personal Communications topics that are available.

**Using Session Topic Data Items**

For each Session topic, the following data items are supported:

<b>Item</b>	<b>Function</b>
<b>CLOSE</b>	Retrieves the window close requests.
<b>CONV</b>	Requests Code Conversion from ASCII to EBCDIC and EBCDIC to ASCII.
<b>EPS</b>	Retrieves the session presentation space with additional data.
<b>EPSCOND</b>	Retrieves the presentation space service condition.
<b>FIELD</b>	Retrieves the field in the presentation space of the session.
<b>KEYS</b>	Retrieves the keystrokes.
<b>MOUSE</b>	Retrieves the mouse input.
<b>OIA</b>	Retrieves the operator information area status line.
<b>PS</b>	Retrieves the session presentation space.
<b>PSCOND</b>	Retrieves the session advise condition.
<b>SSTAT</b>	Retrieves the session status.
<b>STRING</b>	Retrieves the ASCII string data.
<b>TRIMRECT</b>	Retrieves the session presentation space within the current trim rectangle.

## Using LU Topic Data Items (3270 Only)

For each LU topic, the following data items are supported:

Item	Function
SF	Retrieves the destination/origin structured field data.
SFCOND	Retrieves the query reply data.

## DDE Functions

The following table lists the DDE functions that are available for use with Personal Communications, and the page number in this section where more details can be found.

**Note:** Code conversion is now supported in the Windows 32-bit environment. See "Code Conversion" on page 170 for further information.

Function	3270	5250	VT	Page
Find Field	Yes	Yes	Yes	172
Get Keystrokes	Yes	Yes	Yes	174
Get Mouse Input	Yes	Yes	Yes	175
Get Number of Close Requests	Yes	Yes	Yes	178
Get Operator Information Area	Yes	Yes	Yes	179
Get Partial Presentation Space	Yes	Yes	Yes	180
Get Presentation Space	Yes	Yes	Yes	182
Get Session Status	Yes	Yes	Yes	184
Get System Configuration	Yes	Yes	Yes	186
Get System Formats	Yes	Yes	Yes	187
Get System Status	Yes	Yes	Yes	187
Get System SysItems	Yes	Yes	Yes	188
Get System Topics	Yes	Yes	Yes	189
Get Trim Rectangle	Yes	Yes	Yes	190
Initiate Session Conversation	Yes	Yes	Yes	190
Initiate Structured Field Conversation	Yes	No	No	191
Initiate System Conversation	Yes	Yes	Yes	192
Put Data to Presentation Space	Yes	Yes	Yes	192
Search for String	Yes	Yes	Yes	193
Send Keystrokes	Yes	Yes	Yes	194
Session Execute Macro	Yes	Yes	Yes	196
Set Cursor Position	Yes	Yes	Yes	203
Set Mouse Intercept Condition	Yes	Yes	Yes	204
Set Presentation Space Service Condition	Yes	Yes	Yes	207
Set Session Advise Condition	Yes	Yes	Yes	208
Set Structured Field Service Condition	Yes	No	No	209
Start Close Intercept	Yes	Yes	Yes	210
Start Keystroke Intercept	Yes	Yes	Yes	211
Start Mouse Input Intercept	Yes	Yes	Yes	212
Start Read SF	Yes	No	No	215
Start Session Advise	Yes	Yes	Yes	217
Stop Close Intercept	Yes	Yes	Yes	218
Stop Keystroke Intercept	Yes	Yes	Yes	219
Stop Mouse Input Intercept	Yes	Yes	Yes	219
Stop Read SF	Yes	No	No	220
Stop Session Advise	Yes	Yes	Yes	220
Terminate Session Conversation	Yes	Yes	Yes	221
Terminate Structured Field Conversation	Yes	No	No	221

Function	3270	5250	VT	Page
Terminate System Conversation	Yes	Yes	Yes	222
Write SF	Yes	No	No	222

Refer to “Summary of DDE Functions in a Windows 32-Bit Environment” on page 236 for a summary of the DDE functions.

## Naming Conventions for Parameters

Most DDE parameter names have local variables. These variables have a prefix that indicates the general type of the parameter, followed by one or more words that describe the content of the parameter. Prefixes presented in this book are:

- a** Atom
- c** Character (a 1-byte value)
- f** Bit flags packed into a 16-bit integer
- h** 16-bit handle
- p** Short (16-bit) pointer
- lp** Long (32-bit) pointer
- w** Short (16-bit) unsigned integer
- u** Unsigned integer
- sz** Null-terminated character string

## Code Conversion

3270	5250	VT
X	X	X

The **Code Conversion** function allows a client application to convert ASCII to EBCDIC or EBCDIC to ASCII. This function is only available to 32-bit applications.

### Send the message as follows::

```
PostMessage (hServerWnd,
            WM_DDE_POKE,
            hClientWnd,
            PackDDEIParam (WM_DDE_POKE, hData, aCONV));
```

where:

#### *hDATA:*

```
typedef struct tagWCDDDE_CONV
{
    BYTE          ddepoke[(sizeof(DDEPOKE)-1)];
    char          szSourceName[256]; // name of memory-mapped file
    char          szTargetName[256]; // name of memory-mapped file
    BYTE          ConvType;          // Conversion method
    WORD          uSourceLength;     // Length of source buffer
    WORD          uTargetLength;     // Length of target buffer
}WCDDDE_CONV;

typedef union tagDDE_CONV
{
    DDEPOKE      DDEpoke;
```



```

        WCDDE_CONV      DDEConv;
    }DDE_CONV;

typedef DDE_CONV FAR *LPDDE_CONV;

```

**Conversion Types:**

```

        ConvType = 0x01   ASCII to EBCDIC
        ConvType = 0x02   EBCDIC to ASCII

```

**Note:** The string to be converted must be stored in a memory block that is accessible across processes. In win32, this can only be accomplished by use of memory-mapped files. The global memory is created and named in the client application and the names are sent to PComm through the DDE message. The steps required to implement this are demonstrated in the following example:

```

//Steps for a Source Buffer (done in client application)
HANDLE hMapFile;
LPVOID lpMapAddress;
ATOM  aCONV;

hMapFile = CreateFileMapping((HANDLE)0xFFFFFFFF, // not a real file
        NULL, // Default security.
        PAGE_READWRITE, // Read/write
        (DWORD)0, // Ignored
        (DWORD)nStringLength, // Length of string
        (LPCTSTR)szSourceName); // Name of
// mapping object.

If (hMapFile == NULL)
{
    MessageBox ("Could not create file-mapping Source object.");
    return;
}
// Now treat buffer like local memory
strcpy((LPSTR)lpMapAddress, szConversionString);

// Repeat steps for a Target Buffer
.....
// Set up ATOM information

aCONV = GlobalAddAtom("CONV"); // MUST be this string

// Post DDE Message Now ....

// When done with memory blocks, clean up
if (!UnmapViewOfFile(lpMapAddress))
{
    MessageBox ("Could not unmap view of Target.");
}

CloseHandle(hMapFile);

// CODE ENDS

```

**Personal Communications Response:** The function responds with a WM\_DDE\_ACK message for DDE\_POKE. A result value is returned in the high-order byte of the fsStatus word. The following return codes are valid:

Return Code	Explanation
0x0000	Normal End

0x0200	An incorrect conversion type or incorrect parameter was specified
0x0600	An incorrect format was specified
0x0900	A system error occurred
0x1000	The destination buffer was exceeded
0x1100	An internal translation error occurred

## Find Field

<i>3270</i>	<i>5250</i>	<i>VT</i>
Yes	Yes	Yes

The **Find Field** function returns information about the specified field to the client. It can be used in two ways.

Send the message as follows:

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELPARAM(cfFormat, aFIELD) );
```

where:

### **cfFormat**

Identifies the format for the field information. This value can be CF\_DSPTEXT or CF\_TEXT.

### **aFIELD**

Is the atom that specifies the **Find Field** function. The string identified by the atom can have different values depending on the value of **cfFormat**.

## CF\_DSPTEXT

If **CF\_DSPTEXT** is specified for **cfFormat** then **aFIELD** must be an atom that represents the string, FIELD. The PS position must be specified in a previous call to the **Set Presentation Space Service Condition** function. This version will return information only about the field which contains that position. The information will be returned in a WM\_DDE\_DATA(hData, aFIELD) message where:

**hData** Represents

```
typedef struct tagFINDFIELD
{
    unsigned char
    data[sizeof(DDEDATA)-1];
    unsigned short uFieldStart; //Field start position
    unsigned short uFieldLength; //Field Length
    unsigned char cAttribute; //Attribute character value
    unsigned char ubReserved; //reserved, no information for client
} FINDFIELD;

typedef union tagDDE_FINDFIELD
{
    DDEDATA DDEdata;
    FINDFIELD DDEfield;
} DDE_FINDFIELD, *lpDDE_FINDFIELD;
```

## CF\_TEXT

If **CF\_TEXT** is specified for **cfFormat** then **aFIELD** must be an atom that represents the string, FIELD (pos, "XX") where\_

**pos** Is the PS position

**XX** Is a code representing which field relative to **pos** for which information will be returned. These codes are described below:

Type	Meaning
bb or Tb	The field containing <b>pos</b> .
Pb	The field previous to <b>pos</b> , either protected or unprotected.
PP	The previous protected field to <b>pos</b> .
PU	The previous unprotected field to <b>pos</b> .
Nb	The next field after <b>pos</b> , either protected or unprotected.
NP	The next protected field after <b>pos</b> .
NU	The next unprotected field after <b>pos</b> .

**Note:** The **b** symbol represents a required blank.

These codes must appear in quotes as demonstrated above. The information will be returned in a WM\_DDE\_DATA(hData, aFIELD) message where:

**hData** Represents

```
typedef struct tagFINDFIELD_CF_TEXT
{
    uchar data[sizeof(DDEDATA)-1];
    uchar Fielddata[80];
} FINDFIELD_CF_TEXT;

typedef FINDFIELD_CF_TEXT FAR *LPFINDFIELD_CF_TEXT;

typedef union tagDDE_FIELD
{
    DDEDATA DDEdata;
    FINDFIELD DDEFindField;
    FINDFIELD_CF_TEXT DDEFindField_cftext;
} DDE_FIELD;

typedef DDE_FIELD FAR *LPDDE_FIELD;
```

## Personal Communications Response

If the function is successful, it will respond with a WM\_DDE\_DATA message with information as described above. If it fails, it will return with a WM\_DDE\_ACK(wStatus, aFIELD). A result value is returned in the low-order byte of the wStatus word. The following return codes are valid:

Return Code	Explanation
0x0001	PS position is not valid.
0x0002	PS is unformatted.
0x0006	The specified format is not valid.
0x0009	A system error occurred.

## Structure of the Field Information

The field information will be returned in the **Fielddata** member of the **FINDFIELD\_CF\_TEXT** structure as a string in the following format:

<b>3270: "Formatted\t%01d\t%01d\t%01d\t%01d\t%04d\t%04d"</b>		
FA bit 2	Unprotected / Protected	0 or 1
FA bit 3	Alphanumeric / Numeric	0 or 1
FA bit 4–5	Intensity / High / Normal	1, 2 or 3
FA bit 7	Unmodified / Modified	0 or 1
Start Pos	Field Start Position (excluding FA)	
Length	Field Length (excluding FA)	
<b>5250: "Formatted\t%01d\t%01d\t%01d\t%01d\t%01d\t%01d\t%04d\t%04d"</b>		
FA bit 0	Field Attribute Flag	0 or 1
FA bit 1	Invisible / Visible	0 or 1
FA bit 2	Unprotected / Protected	0 or 1
FA bit 3	Intensity Low/High	0 or 1
FA bit 4–6	Field Type 0 = Alphanumeric 1 = Alphabetic 2 = Numeric Shift 3 = Numeric 4 = Default 5 = Digits only 6 = Mag-Stripe Reader Data 7 = Signed Numeric	0 — 7
FA bit 7	Unmodified / Modified	0 or 1
Start Pos	Field Start Position (excluding FA)	
Length	Field Length (excluding FA)	

**Note:** FA = Field Attribute

## Get Keystrokes

<i>3270</i>	<i>5250</i>	<i>VT</i>
<i>Yes</i>	<i>Yes</i>	<i>Yes</i>

The **Get Keystrokes** function returns to the client the keystrokes that are intercepted by the **Start Keystroke Intercept** function. The client sends the following message to receive the keystroke information.

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELPARAM(cfFormat, aKEYS) );
```

where:

**cfFormat**

Identifies the format for the keystroke information. This must be CF\_DSPTXT.

**aKEYS**

Identifies a keystroke data item.

**Personal Communications Response**

Personal Communications either returns the keystrokes in a DDE data message, or responds with one of these ACK messages containing status information:

- WM\_DDE\_DATA(hData, aKEYS)
- WM\_DDE\_ACK(wStatus, aKEYS)

If Personal Communications cannot return the keystroke information, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
2	No keystroke was intercepted.
6	The specified format is not valid.
9	A system error occurred.

**Structure of the Keystroke Information**

Personal Communications returns the keystroke information in the following structure:

```
typedef struct tagKEYSTROKE
{
    unsigned char  data[(sizeof(DDEDATA)-1)];
    unsigned short uTextType; /* Type of keystrokes
    unsigned char  szKeyData_1; /* Keystrokes
} KEYSTROKE;

typedef union tagDDE_GETKEYSTROKE
{
    DDEDATA      DDEdata;
    KEYSTROKE    DDEkey;
} DDE_GETKEYSTROKE, *lpDDE_GETKEYSTROKE;
```

The format for the keystrokes parameters is the same as for the **Session Execute Macro** function SENDKEY command.

The following key text types are supported:

```
PCS_PURETEXT    0      /* Pure text, no HLLAPI commands
PCS_HLLAPITEXT  1      /* Text, including HLLAPI tokens
```

**Get Mouse Input**

3270	5250	VT
Yes	Yes	Yes

The **Get Mouse Input** function returns the latest mouse input intercepted by the **Start Mouse Input Intercept** function to the client.

**Note:** The client must call the **Start Mouse Input Intercept** function before using this function.

The client sends the following command to receive the mouse input information.

```
PostMessage( hServerWnd,
            WM_DDE_REQUEST,
            hClientWnd,
            MAKELPARAM(cfFormat, aMOUSE) );
```

where:

**cfFormat**

Identifies the format for the presentation space. Valid values are CF\_TEXT or CF\_DSPTEXT. The structure of the mouse input data, in these two formats, is shown below.

**aMOUSE**

Identifies the mouse input as the item.

**Personal Communications Response**

Personal Communications either returns the mouse input data in a DDE data message, or responds with one of these ACK messages:

- WM\_DDE\_DATA(hData, aMOUSE)
- WM\_DDE\_ACK(wStatus, aMOUSE)

If Personal Communications cannot return the mouse input information, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
2	No mouse input information was intercepted.
6	The specified format is not valid.
9	A system error occurred.

**Structure of the Mouse Input Information**

If the format is CF\_TEXT, Personal Communications returns the mouse input information in the following format:

```
typedef struct tagMOUSE_CF_TEXT
{
    unsigned char data[(sizeof(DDEDATA)-1)];
    unsigned char PSPos[4]; /* PS Offset - Mouse position
    unsigned char Tab1[1]; /* Tab character
    unsigned char PSRowPos[4]; /* ROW number of Mouse position
    unsigned char Tab2[1]; /* Tab character
    unsigned char PSColPos[4]; /* Col number of Mouse position
    unsigned char Tab3[1]; /* Tab character
    unsigned char PSSize[4]; /* Size of Presentation Space
    unsigned char Tab4[1]; /* Tab character
    unsigned char PSRows[4]; /* Row number of PS
    unsigned char Tab5[1]; /* Tab character
    unsigned char PSCols[4]; /* Column number of PS
    unsigned char Tab6[1]; /* Tab character
    unsigned char Button[1]; /* Type of clicked mouse button
    unsigned char Tab7[1]; /* Tab character
    unsigned char Click[1]; /* Type of clicking
    unsigned char Tab8[1]; /* Tab character
    unsigned char zClickString[1];/* Retrieved string
} MOUSE_CF_TEXT;

typedef union tagDDE_MOUSE_CF_TEXT
{
```

```

DDEDATA      DDEdata;
MOUSE_CF_TEXT DDEmouse;
} DDE_MOUSE_CF_TEXT, *1pDDE_MOUSE_CF_TEXT;

```

The following table shows the values in the parameters:

Parameter Name	Meaning	Value
PSPos	PS offset of the position where the mouse was clicked	0 ... (PSSize - 1)
PSRowPos	Row number of the position where the mouse was clicked	0 ... (PSRows - 1)
PSColPos	Column number of the position where the mouse was clicked	0 ... (PSCols - 1)
PSSize	Size of the presentation space	
PSRows	Number of rows of presentation space	
PSCols	Number of columns of presentation space	
ButtonType	Type of the clicked mouse button	<b>L</b> Left button <b>M</b> Middle button <b>R</b> Right button
ClickType	Type of clicking	<b>S</b> Single click <b>D</b> Double click
ClickString	Retrieved string to which the mouse pointed	A character string terminated with a '\0'
Tab1-8	A tab character for delimiter	'\t'

If the format is CF\_DSPTTEXT, Personal Communications returns the mouse input information in the following format:

```

typedef struct tagMOUSE_CF_DSPTTEXT
{
    unsigned char data[(sizeof(DDEDATA)-1)];
    unsigned short uPSPos; /* PS Offset of the Mouse position
    unsigned short uPSRowPos; /* ROW number of Mouse position
    unsigned short uPSColPos; /* Column number of Mouse position
    unsigned short uPSSize; /* Size of Presentation Space
    unsigned short uPSRows; /* Row number of PS
    unsigned short uPSCols; /* Column number of PS
    unsigned short uButtonType; /* Type of clicked mouse button
    unsigned short uClickType; /* Type of clicking
    unsigned char zClickString[1]; /* Retrieved string
} MOUSE_CF_DSPTTEXT;

typedef union tagDDE_MOUSE_CF_DSPTTEXT
{
    DDEDATA DDEdata;
    MOUSE_CF_DSPTTEXT DDEmouse;
} DDE_MOUSE_CF_DSPTTEXT, *1pDDE_MOUSE_CF_DSPTTEXT;

```

The following table shows the values in the parameters:

Parameter Name	Meaning	Value
uPSPos	PS offset of the position where the mouse was clicked	0 ... (uPSSize – 1)
uPSRowPos	Row number of the position where the mouse was clicked	0 ... (uPSRows – 1)
uPSColPos	Column number of the position where the mouse was clicked	0 ... (uPSCols – 1)
uPSSize	Size of the presentation space	
uPSRows	Number of rows of the presentation space	
uPSCols	Number of columns of the presentation space	
uButtonType	Type of the clicked mouse button	<b>0x0001</b> Left button <b>0x0002</b> Middle button <b>0x0003</b> Right button
uClickType	Type of clicking	<b>0x0001</b> Single click <b>0x0002</b> Double click
szClickString	Retrieved string that the mouse pointed to	A character string terminated with a '\0'

## Get Number of Close Requests

3270	5250	VT
Yes	Yes	Yes

The **Get Number of Close Requests** function returns to the client the number of the close requests that are intercepted by the **Start Close Intercept** function. The client sends the following message to receive the number of the close requests.

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELPARAM(cfFormat, aCLOSE) );
```

where:

### cfFormat

Identifies the format for the close intercept information. This must be CF\_DSPTEXT.

### aCLOSE

Identifies a close intercept data item.

## Personal Communications Response

Personal Communications either returns the number of the close requests in a DDE data message, or responds with one of these ACK messages:

- WM\_DDE\_DATA(hData, aCLOSE)
- WM\_DDE\_ACK(wStatus, aCLOSE)



If Personal Communications cannot return the close intercept information, one of the following status codes is returned in the low order byte of the wStatus word:

Return Code	Explanation
6	The specified format is not valid.
9	A system error occurred.

### Structure of the Number of the Close Requests Information

Personal Communications returns the close intercept information in the following structure:

```
typedef struct tagCLOSEREQ
{
    unsigned char data[(sizeof(DDEDATA)-1)];
    unsigned short uCloseReqCount; /* Number of the close requests.
} CLOSEREQ;

typedef union tagDDE_CLOSEREQ
{
    DDEDATA DDEdata;
    CLOSEREQ DDEclose;
} DDE_CLOSEREQ, *lpDDE_CLOSEREQ;
```

## Get Operator Information Area

3270	5250	VT
Yes	Yes	Yes

The **Get Operator Information Area** (OIA) function returns a copy of the OIA to the client. The client sends the following message to request the OIA.

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELPARAM(cfFormat, aOIA) );
```

where:

#### cfFormat

Identifies the format for the OIA. For the OIA, this format must be CF\_DSPTEXT.

**aOIA** Identifies the operator information area as the item.

## Personal Communications Response

Personal Communications either returns the OIA in a DDE data message, or responds with one of these ACK messages:

- WM\_DDE\_DATA(hData, aOIA)
- WM\_DDE\_ACK(wStatus, aOIA)

If Personal Communications cannot return the OIA, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
6	The specified format is not valid.
9	A system error occurred.

## Structure of the Operator Information Area

Personal Communications returns the operator information area in the following structure:

```
typedef struct tagOIADATA
{
    unsigned char data[(sizeof(DDEDATA)-1)];
    unsigned char OIA[80];
} OIADATA;

typedef union tagDDE_OIADATA
{
    DDEDATA DDEdata;
    OIADATA DDEoia;
} DDE_OIADATA, *lpDDE_OIADATA;
```

## Get Partial Presentation Space

3270	5250	VT
Yes	Yes	Yes

The **Get Partial Presentation Space** function returns all or part of the session presentation space to the client.

**Note:** The client must set the start PS position and either the PS length or End of Field (EOF) flag by using the **Set Presentation Space Service Condition** function before using this function. If the EOF flag is set to PCS\_EFFECTEOF, the function will return the entire field specified by the start PS position

The client sends the following command to get the presentation space.

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELPARAM(cfFormat, aEPS) );
```

where:

### cfFormat

Identifies the format for the presentation space. Valid values are CF\_TEXT or CF\_DSPTEXT. The structure of the presentation space, in these two formats, is shown below.

**aEPS** Identifies the session presentation space as the item.

## Personal Communications Response

Personal Communications either returns the presentation space data, or responds with one of these ACK messages containing an error code in the low order byte of the wStatus word:

- WM\_DDE\_DATA(hData, aEPS)
- WM\_DDE\_ACK(wStatus, aEPS)

If Personal Communications cannot return the presentation space, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
1	No prior <b>Set Presentation Space Service Condition</b> function was called, or an incorrect parameter was set.

Return Code	Explanation
6	The specified format is not valid.
9	A system error occurred.

## Structure of the Presentation Space

Personal Communications returns the part of the presentation space in the format specified in the **Get Partial Presentation Space** request.

If the format is CF\_DSPTTEXT, Personal Communications returns the presentation space in the following format:

```
typedef struct tagEPS_CF_DSPTTEXT
{
    unsigned char  data[(sizeof(DDEDATA)-1)];
    unsigned short uPSPosition;      /* Position of the part of PS
    unsigned short uPSLength;        /* Length of the part of the PS
    unsigned short uPSRows;          /* PS number of rows
    unsigned short uPSCols;          /* PS number of columns
    unsigned short uPSOffset;        /* Offset to the presentation space
    unsigned short uFieldCount;      /* Number of fields
    unsigned short uFieldOffset;     /* Offset to the field array
    unsigned char  PSData[1];        /* PS + Field list Array(1pPSFIELDS)
} EPS_CF_DSPTTEXT;

typedef union tagDDE_EPS_CF_DSPTTEXT
{
    DDEDATA      DDEdata;
    EPS_CF_DSPTTEXT DDEeps;
} DDE_EPS_CF_DSPTTEXT, *lpDDE_EPS_CF_DSPTTEXT;

# The PSFIELDS structure is replaced with below structure.

typedef struct tagPSFIELDS
{
    unsigned short uFieldStart;      /* Field start offset
    unsigned short uFieldLength;     /* Field Length
    unsigned char  cAttribute;       /* Attribute character
    unsigned char  ubReserved;       /* *** Reserved ***
} PSFIELDS, *lpPSFIELDS;
```

**Note:** The following examples show how to obtain long pointers to the PS and the PSFIELDS array.

```
lpDDE = (lpDDE_EPS_CF_DSPTTEXT)GlobalLock(hData);
lpPS = lpDDE->DDEeps.PSData + lpDDE->DDEeps.uPSOffset;
lpPSfields = lpDDE->DDEeps.PSData + lpDDE->DDEeps.uFieldOffset;
```

If the format is CF\_TEXT, Personal Communications returns the part of the presentation space in the following format:

```
typedef struct tagEPS_CF_TEXT
{
    unsigned char  data[(sizeof(DDEDATA)-1)];
    unsigned char  PSPOSITION[4]; /* Postion of part of the PS
    unsigned char  Tab1[1];       /* Tab character
    unsigned char  PSLENGTH[4];  /* Length of the part of the PS
    unsigned char  Tab2[1];       /* Tab character
    unsigned char  PSROWS[4];     /* Number of rows in the PS
    unsigned char  Tab3[1];       /* Tab character
    unsigned char  PSCOLS[4];     /* Number of Cols in the PS
    unsigned char  Tab4[1];       /* Tab character
    unsigned char  PS[1];         /* PS
} EPS_CF_TEXT;
```

```
typedef union tagDDE_EPS_CF_TEXT
{
    DDEDATA      DDEdata;
    EPS_CF_TEXT  DDEeps;
} DDE_EPS_CF_TEXT, *lpDDE_EPS_CF_TEXT;
```

Following the PS in the buffer is the following additional structure of fields that compose the field list.

```
typedef struct tagFL_CF_TEXT
{
    unsigned char  Tab5[1];          /* Tab character
    unsigned char  PSFldCount[4];    /* Number of fields in the PS
    unsigned char  Tab6[1];          /* Tab character
    PS_FIELD      Field[1];          /* Field List Array
} FL_CF_TEXT, *lpFL_CF_TEXT;
```

```
typedef struct tagPS_FIELD
{
    unsigned char  FieldStart[4];
    unsigned char  TabF1[1];
    unsigned char  FieldLength[4];
    unsigned char  TabF2[1];
}
```

**Note:** The following examples show how to obtain long pointers to the PS and the PS\_FIELD array.

```
lpDDE = (lpDDE_EPS_CF_TEXT)GlobalLock(hData);
lpps = lpDDE->DDEeps.PS;
lpps_field = lpDDE->DDEeps.PS
    + atoi(lpDDE->DDEeps.PSLENGTH)
    + ((atoi(lpDDE->DDEeps.PSROWS) - 1) * 2) // CR/LF
    + 1 + 1 + 4 + 1; // Tabs + size of field count
```

## Get Presentation Space

3270	5250	VT
Yes	Yes	Yes

The **Get Presentation Space** function returns the session presentation space to the client. The client sends the following command to get the presentation space.

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELPARAM(cfFormat, aPS) );
```

where:

### cfFormat

Identifies the format for the presentation space. Valid values are CF\_TEXT or CF\_DSPTEXT. The structure of the presentation space, in these two formats, is shown below.

**aPS** Identifies the session presentation space as the item.

## Personal Communications Response

Personal Communications either returns the presentation space and a list of the fields that comprise the presentation space, or responds with one of these ACK messages containing an error code in the low-order byte of the wStatus word:

- WM\_DDE\_DATA(hData, aPS)
- WM\_DDE\_ACK(wStatus, aPS)

If Personal Communications cannot return the presentation space, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
6	The specified format is not valid.
9	A system error occurred.

## Structure of the Presentation Space

Personal Communications returns the presentation space in the format specified in the **Get Presentation Space** request.

If the format is CF\_DSPTTEXT, Personal Communications returns the presentation space in the following format:

```
typedef struct tagPS_CF_DSPTTEXT
{
    unsigned char  data[(sizeof(DDEDATA)-1)];
    unsigned short uPSSize;          /* Size of the presentation space
    unsigned short uPSRows;         /* PS number of rows
    unsigned short uPSCols;        /* PS number of columns
    unsigned short uPSOffset;      /* Offset to the presentation space
    unsigned short uFieldCount;    /* Number of fields
    unsigned short uFieldOffset;   /* Offset to the field array
    unsigned char  PSData_1;       /* PS and Field list Array(lpPSFIELDS)
} PS_CF_DSPTTEXT;

typedef union tagDDE_PS_CF_DSPTTEXT
{
    DDEDATA      DDEdata;
    PS_CF_DSPTTEXT DDEps;
} DDE_PS_CF_DSPTTEXT, *lpDDE_PS_CF_DSPTTEXT;

typedef struct tagPSFIELDS
{
    unsigned short uFieldStart;    /* Field start offset
    unsigned short uFieldLength;  /* Field Length
    unsigned char  cAttribute;    /* Attribute character
    unsigned char  ubReserved;    /* *** Reserved ***
} PSFIELDS, *lpPSFIELDS;
```

**Note:** The following examples show how to obtain long pointers to the PS and the PSFIELDS array.

```
lpDDE = (lpDDE_PS_CF_DSPTTEXT)GlobalLock(hData);
lpps = lpDDE->DDEps.PSData + lpDDE->DDEps.uPSOffset;
lppsfields = lpDDE->DDEps.PSData + lpDDE->DDEps.uFieldOffset;
```

If the format is CF\_TEXT, Personal Communications returns the presentation space in the following format:

```
typedef struct tagPS_CF_TEXT
{
    unsigned char  data[(sizeof(DDEDATA)-1)];
    unsigned char  PSSIZE[4];      /* Size of the PS
    unsigned char  Tab1[1];       /* Tab character
    unsigned char  PSROWS[4];    /* Number of rows in the PS
    unsigned char  Tab2[1];       /* Tab character
    unsigned char  PSCOLS[4];    /* Number of Cols in the PS
    unsigned char  Tab3[1];       /* Tab character
    unsigned char  PS[1];        /* PS
} PS_CF_TEXT;

typedef union tagDDE_PS_CF_TEXT
```

```

{
  DDEDATA    DDEdata;
  PS_CF_TEXT DDEps;
} DDE_PS_CF_TEXT, *lpDDE_PS_CF_TEXT;

```

Following the PS in the buffer is the following additional structure of fields that compose the field list.

```

typedef struct tagPS_FIELD
{
  unsigned char  FieldStart[4];
  unsigned char  TabF1[1];
  unsigned char  FieldLength[4];
  unsigned char  TabF2[1];
  unsigned char  Attribute;
  unsigned char  TabF3[1];
} PS_FIELD, *lpPS_FIELD;

```

**Note:** The following example shows how to obtain long pointers to the PS and the PS\_FIELD array.

```

lpDDE = (lpDDE_PS_CF_TEXT)GlobalLock(hData);
lpps = lpDDE->DDEps.PS;
lpss_field = lpDDE->DDEps.PS
             + atoi(lpDDE->DDEps.PSSIZE)
             + ((atoi(lpDDE->DDEps.PSROWS) - 1) * 2) // CR/LF
             + 1 + 1 + 4 + 1; // Tabs + size of field count

```

## Get Session Status

3270	5250	VT
Yes	Yes	Yes

The **Get Session Status** function returns the status of the connected session. The client sends the following message to request session status:

```

PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELPARAM(cfFormat, aSSTAT) );

```

where:

### cfFormat

Identifies the DDE format for the status information. The value used is CF\_TEXT.

### aSSTAT

Identifies session status as the data item requested.

## Personal Communications Response

Personal Communications either returns the session status in a DDE data message, or responds with one of these ACK messages containing status information:

- WM\_DDE\_DATA(hData, aSSTAT)
- WM\_DDE\_ACK(wStatus, aSSTAT)

If Personal Communications cannot return the session status, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
6	The specified format is not valid.
9	A system error occurred.

## Format of Status Information

Personal Communications returns the session status as text in CF\_TEXT format. The following fields are returned with the following possible values:

Fields	Returned Values	Description
Status	Closed, Invisible, Maximized, Minimized, Normal	The window is in one of these states.
Usage	DDE, User	The session is connected in either a DDE session or a user session.
ScreenX	NN	Defines the horizontal size of the screen.
ScreenY	NN	Defines the vertical size of the screen.
CursorX	NN	Defines the horizontal position of the cursor. (0 ... ScreenX – 1)
CursorY	NN	Defines the vertical position of the cursor. (0 ... ScreenY – 1)
TrimRect Status	Closed, Moved, Sized	The current status of the trim rectangle.
Trim Rectangle X1	N	The top-left corner X position of the trim rectangle in character coordinates.
Trim Rectangle Y1	N	The top-left corner Y position of the trim rectangle in character coordinates.
Trim Rectangle X2	N	The lower-right corner X position of the trim rectangle in character coordinates.
Trim Rectangle Y2	N	The lower-right corner Y position of the trim rectangle in character coordinates.
Session Presentation Space Status	N	The current status of the presentation space. The following values are possible:  <b>0:</b> The presentation space is unlocked.  <b>4:</b> The presentation space is busy.  <b>5:</b> The presentation space is locked.
Session Window Handle	XXXX	Window handle of the session.

### Note:

- The status of each field is updated each time the status is requested.

- A new field might be added in a future version of Personal Communications.

## Get System Configuration

3270	5250	VT
Yes	Yes	Yes

The **Get System Configuration** function returns the level of Personal Communications support and other system-related values. Most of this information is for use by a service coordinator when a customer calls the IBM Support Center after receiving a system error.

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELPARAM(cfFormat, aSYSCON) );
```

where:

### cfFormat

Identifies the DDE format for the data item requested. The value used is CF\_TEXT.

### aSYSCON

Identifies system configuration as the data item requested.

## Personal Communications Response

Personal Communications either returns the system configuration data item in a DDE DATA message, or responds with one of these ACK messages containing status information:

- WM\_DDE\_DATA(hData, aSYSCON)
- WM\_DDE\_ACK(wStatus, aSYSCON)

If Personal Communications cannot return the system configuration, a DDE ACK message is returned with an error code in the low-order byte of the wStatus word:

```
WM_DDE_ACK(wStatus, aSYSCON)
```

Return Code	Explanation
9	A system error occurred.

## Format of System Configuration Information

Personal Communications returns the system configuration as text in CF\_TEXT format. The following fields are returned with the following possible values:

Fields	Returned values	Description
Version	N	The version of Personal Communications
Level	NN	The level of Personal Communications
Reserved	XXXXXX	Reserved
Reserved	XXXX	Reserved
Monitor Type	MONO, CGA, EGA, VGA, XGA	Type of the monitor
Country Code	NNNN	Country code used with 3270 or 5250



## Get System Formats

3270	5250	VT
Yes	Yes	Yes

The **Get System Formats** function returns the list of Windows clipboard formats supported by Personal Communications. The client application sends the following message to retrieve the format list supported by Personal Communications:

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELPARAM(cfFormat, aFORMATS) );
```

where:

### cfFormat

Identifies the DDE format for the data item requested. The value used is CF\_TEXT.

### aFORMATS

Identifies formats as the data item requested.

## Personal Communications Response

Personal Communications returns the list of supported Windows clipboard formats in CF\_TEXT format in a DDE DATA message.

```
WM_DDE_DATA(hData, aFORMATS)
```

The following Windows clipboard formats are supported by Personal Communications:

- CF\_TEXT
- CF\_DSPTEXT

If Personal Communications cannot return the formats data item, a DDE ACK message is returned with an error code in the low-order byte of the wStatus word:

```
WM_DDE_ACK(wStatus, aFORMATS)
```

Return Code	Explanation
9	A system error occurred.

## Get System Status

3270	5250	VT
Yes	Yes	Yes

The **Get System Status** function returns the status of each 3270 or 5250 session that is available with the current Personal Communications configuration. The client application sends the following message to retrieve the status data item:

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELPARAM(cfFormat, aSTATUS) );
```

where:

**cfFormat**

Identifies the DDE format for the data item requested. The value used is CF\_TEXT.

**aSTATUS**

Identifies status as the data item requested.

**Personal Communications Response**

Personal Communications returns the status data item in CF\_TEXT format in a DDE DATA message:

```
WM_DDE_DATA(hData, aSTATUS)
```

For each opened session, Personal Communications returns a line of status information. Each line contains a series of fields with the following range of values:

Fields	Range of values	Description
Session ID	A, B, ..., Z	The short ID of the session.
Host Type	370, 400, ASCII	The host system currently supported by Personal Communications.
Emulation Type	3270, 5250, VT	The emulation type supported by Personal Communications.
Session Status	Closed, Invisible, Normal, Minimized, Maximized	The current status of the session's window.

If Personal Communications cannot return the status data item, a DDE ACK message is returned with an error code in the low-order byte of the wStatus word:

```
WM_DDE_ACK(wStatus, aSTATUS)
```

Return Code	Explanation
9	A system error occurred.

**Get System Systems**

<i>3270</i>	<i>5250</i>	<i>VT</i>
<i>Yes</i>	<i>Yes</i>	<i>Yes</i>

Personal Communications supports the DDE system topic so that a client application can connect to the system topic and retrieve information about Personal Communications and the status of the sessions that Personal Communications is managing.

The **Get System Systems** function returns the list of data items available in the Personal Communications system topic. The client application sends the following message to get the system topic data items:

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELPARAM(cfFormat, aSYSITEMS) );
```

where:

**cfFormat**

Identifies the DDE format for the data item requested. The value used is CF\_TEXT.

### **aSYSITEMS**

Identifies SysItems as the data item requested.

## **Personal Communications Response**

Personal Communications returns the list of system topic data items in CF\_TEXT format in a DDE DATA message.

```
WM_DDE_DATA(hData, aSYSITEMS)
```

The following data items are supported by Personal Communications:

- SysItems
- Topics
- Status
- Formats
- SysCon

If Personal Communications cannot return the system data items, a DDE ACK message is returned with an error code in the low-order byte of the wStatus word:

```
WM_DDE_ACK(wStatus, aSYSITEMS)
```

<b>Return Code</b>	<b>Explanation</b>
9	A system error occurred.

## **Get System Topics**

<i>3270</i>	<i>5250</i>	<i>VT</i>
<i>Yes</i>	<i>Yes</i>	<i>Yes</i>

The Get System Topics function returns the list of active DDE topics currently supported by Personal Communications. The client application sends the following message to the system topic to retrieve the list of topics that are currently active:

```
PostMessage( hServerWnd,  
             WM_DDE_REQUEST,  
             hClientWnd,  
             MAKELPARAM(cfFormat, aTOPICS) );
```

where:

### **cfFormat**

Identifies the DDE format for the data item requested. The value used is CF\_TEXT.

### **aTOPICS**

Identifies topics as the data item requested.

## **Personal Communications Response**

Personal Communications returns the list of DDE topics in CF\_TEXT format in a DDE DATA message.

```
WM_DDE_DATA(hData, aTOPICS)
```

The following list of topics are supported by Personal Communications:

- System – System Topic
- SessionA – Session A Topic

- SessionZ – Session Z Topic

**Note:** The actual number of session topics supported depends on the number of sessions currently opened. The client program should always query the topics data item of the system topic to obtain the list of sessions currently opened.

If Personal Communications cannot return the list of topics, a DDE ACK message will be returned with an error code in the low-order byte of the wStatus word:

WM\_DDE\_ACK(wStatus, aTOPICS)

Return Code	Explanation
9	A system error occurred.

## Get Trim Rectangle

3270	5250	VT
Yes	Yes	Yes

The **Get Trim Rectangle** function returns to the client the area of the presentation space that is within the current trim rectangle. The client sends the following message to receive the trim rectangle.

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELPARAM(cfFormat, aTRIMRECT) );
```

where:

### cfFormat

Identifies the format for the trim rectangle. This is CF\_TEXT.

### aTRIMRECT

Identifies trim rectangle as the data item requested.

## Personal Communications Response

Personal Communications either returns trim rectangle in a DDE data message, or responds with one of these ACK messages:

- WM\_DDE\_DATA(hData, aTRIMRECT)
- WM\_DDE\_ACK(wStatus, aTRIMRECT)

If Personal Communications cannot return the trim rectangle, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
6	The specified format is not valid.
9	A system error occurred.

## Initiate Session Conversation

3270	5250	VT
Yes	Yes	Yes

The **Initiate Session Conversation** function connects a client application to an available session of Personal Communications. Once a session conversation has been established, the session is reserved for exclusive use by the client until the conversation is terminated.

The client application sends the following message to initiate a DDE conversation with a session:

```
SendMessage( -1,
             WM_DDE_INITIATE,
             hClientWnd,
             MAKELPARAM(aIBM327032, aSessionN) );
```

where:

**aIBM327032**

Identifies the application atom. The string used to create atom aIBM327032 is "IBM327032". In the PC400, the application atom is aIBM525032 and the string "IBM525032" is used to create it.

**aSessionN**

Identifies the topic atom. The string used to create atom aSessionN is either NULL or "Session" appended with the session ID "A", "B", ..., "Z".

### Personal Communications Response

If a specific topic is selected and Personal Communications can support a conversation with the client application, Personal Communications acknowledges the INITIATE transaction with:

```
WM_DDE_ACK(aIBM327032, aSessionN)
```

If a topic is not selected (aSessionN = NULL), Personal Communications responds by acknowledging all topics that are currently available:

```
WM_DDE_ACK(aIBM327032, aSystem)
WM_DDE_ACK(aIBM327032, aSessionA)
:
WM_DDE_ACK(aIBM327032, aSessionZ)
```

The client application selects the conversation it wishes to communicate with from the returned list of topics and terminates all other unwanted conversations.

## Initiate Structured Field Conversation

3270	5250	VT
Yes	Yes	Yes

The **Initiate Structured Field Conversation** function connects a client application and a host application. This allows the applications to send data to each other and to receive data from each other.

The client sends the following command to initiate a structured field conversation:

```
SendMessage( -1,
             WM_DDE_INITIATE,
             hClientWnd,
             MAKELPARAM(aIBM327032, aLUN_xxxx) );
```

Where:

**aIBM327032**

Identifies the application atom.

**aLUN\_xxxx**

Identifies the topic atom. The string used to create atom aLUN\_xxxx is "LU" appended with the session ID "A", "B", ..., "Z", appended with "\_", and appended with the user-defined string of any length.

**PC/3270 Response**

If PC/3270 can support a structured field conversation with the client application, it returns an acknowledgment message with the following parameter:

```
WM_DDE_ACK(aIBM327032, aLUN_xxxx)
```

**Initiate System Conversation**

3270	5250	VT
Yes	Yes	Yes

The **Initiate System Conversation** function connects a client application to the system conversation. Only one client can be connected to the system conversation at a given time. The client sends the following command to initiate a system conversation:

```
SendMessage( -1,
             WM_DDE_INITIATE,
             hClientWnd,
             MAKELPARAM(aIBM327032, aSystem) );
```

where:

**aIBM327032**

Identifies the application atom.

**aSystem**

Identifies the topic atom.

**Personal Communications Response**

If Personal Communications can support a system topic conversation with the client application, it returns an acknowledgment message with the following parameters:

```
WM_DDE_ACK(aIBM327032, aSystem)
```

**Put Data to Presentation Space**

3270	5250	VT
Yes	Yes	Yes

The **Put Data to Presentation Space** function sends an ASCIIZ data string to be written into the host presentation space at the location specified by the calling parameter. The client sends the following message to the session to send the string.

```
PostMessage( hServerWnd,
             WM_DDE_POKE,
             hClientWnd,
             PackDDE1Param(WM_DDE_POKE,
                           hdata, aEPS) );
```

where:

## hData

Identifies a handle to a Windows global memory object that contains the string to be sent to the session. The global memory object contains the following structure:

```
typedef struct tagPutString
{
    unsigned char  poke[(sizeof(DDEPOKE)-1)];
    unsigned short uPSstart;                /* PS Position
    unsigned short uEOFflag;                /* EOF effective switch
    unsigned char  szStringData[1];        /* String Data
} PUTSTRING;

typedef union tagDDE_PUTSTRING
{
    DDEPOKE  DDEpoke;
    PUTSTRING DDEputstring;
} DDE_PUTSTRING, *lpDDE_PUTSTRING;
```

These values are valid at the uEOFflag field:

```
PCS_UNEFFECTEOF 0    /* The string is not truncated at EOF.
PCS_EFFECTEOF   1    /* The string is truncated at EOF.
```

**aEPS** Identifies the presentation space atom as the item.

## Personal Communications Response

Personal Communications receives the string data and sends them to the presentation space, and returns a positive ACK message.

If the presentation space does not accept the string data, Personal Communications returns a negative ACK message containing one of the following status codes in the low-order byte of the wStatus word:

WM\_DDE\_ACK(wStatus, aEPS)

Return Code	Explanation
1	PS position is not valid.
2	Length is not valid.
3	The value of EOF flag is not valid.
5	Input to the target PS was inhibited.
6	The specified format is not valid.
7	The string was truncated (successful putting).
9	A system error occurred.

## Search for String

3270	5250	VT
Yes	Yes	Yes

This function allows a client application to examine the presentation space for a specified string in a specified area.

**Note:** The client must set the start PS position, string to be searched for, and either the PS Length and Search Direction or End of Field (EOF) flag by using the **Set Presentation Space Service Condition** function before using this

function. If the EOF flag is set to PCS\_EFFECTEOF, the function will search the entire field specified by the Start PS Position parameter.

The client sends the following message to search for the string.

```
PostMessage( hServerWnd,
            WM_DDE_REQUEST,
            hClientWnd,
            MAKELPARAM(cfFormat, aSTRING) );
```

where:

**cfFormat**

Identifies the format for the search information. This must be CF\_DSPTEXT.

**aSTRING**

Identifies the search data item.

**Personal Communications Response**

Personal Communications returns the start position of the string in a DDE data message if the string was found in the specified area:

- WM\_DDE\_DATA(hData, aSTRING)
- WM\_DDE\_ACK(wStatus, aSTRING)

If Personal Communications cannot return the start position of the string, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
1	PS position is not valid or the string is too long.
2	The string cannot be found.
6	The specified format is not valid.
9	A system error occurred.

**Structure of the Search Information**

Personal Communications returns the search information in the following structure:

```
typedef struct tagSEARCH
{
    unsigned char data[(sizeof(DDEDATA)-1)];
    unsigned short uFieldStart; /* String start offset
} SEARCH;

typedef union tagSEARCH
{
    DDEDATA DDEdata;
    SEARCH DDEsearch;
} DDE_SEARCH, *lpDDE_SEARCH;
```

**Send Keystrokes**

3270	5250	VT
Yes	Yes	Yes

The **Send Keystrokes** function sends keystrokes to the connected session. The client sends the following message to the session to send keystrokes.



```
PostMessage( hServerWnd,
            WM_DDE_POKE,
            hClientWnd,
            PackDDE1Param(WM_DDE_POKE,
                          hData, aKEYS) );
```

where:

**hData** Identifies a handle to a Windows global memory object that contains the keystrokes to be sent to the session. The global memory object contains the following structure:

```
typedef struct tagKeystrokes
{
    unsigned char  poke[(sizeof(DDEPOKE)-1)];
    unsigned short uTextType;           /* Type of keystrokes
    unsigned short uRetryCount;         /* Retry count 1 .. 16
    unsigned char  szKeyData[1];       /* Keystrokes
} KEYSTROKES;

typedef union tagDDE_SENDKEYSTROKES
{
    DDEPOKE      DDEpoke;
    KEYSTROKES   DDEkeys;
} DDE_SENDKEYSTROKES, *lpDDE_SENDKEYSTROKES;
```

The following key text types are supported:

```
PCS_PURETEXT    0           /* Pure text, no HLLAPI commands
PCS_HLLAPITEXT  1           /* Text, including HLLAPI tokens
```

**Note:** If the keystrokes are pure text, then specifying PCS\_PURETEXT will transfer the keystrokes to the host in the fastest possible manner. If PCS\_HLLAPITEXT is specified, then the keystroke data can contain HLLAPI commands interspersed with the text.

### aKEYS

Identifies keystrokes as the item.

## Personal Communications Response

Personal Communications receives the keystrokes and sends them to the presentation space. If the presentation space does not accept the keystrokes, a reset is sent to the presentation space and the keystrokes are sent again. This procedure continues until the presentation space accepts the keystrokes or the retry count is reached. If Personal Communications cannot send the keystrokes to the host, Personal Communications returns a negative ACK message containing one of the following status codes in the low-order byte of the wStatus word. Otherwise, Personal Communications returns a positive ACK message signalling the keystrokes have been sent.

```
WM_DDE_ACK(wStatus, aKEYS)
```

Return Code	Explanation
1	Retry count is not valid.
2	Type of key strokes is not valid.
6	The specified format is not valid.
9	A system error occurred.

## Session Execute Macro

3270	5250	VT
Yes	Yes	Yes

You can issue commands and macros with the DDE\_EXECUTE function. The DDE\_EXECUTE function passes command strings to Personal Communications. The command strings must conform to DDE specifications. Refer to *Microsoft Windows Software Development Kit Guide to Programming* for more information about the DDE command syntax.

The client sends the following command to issue a DDE\_EXECUTE function.

```
PostMessage ( hServerWnd,  
             WM_DDE_EXECUTE,  
             hClientWnd,  
             (LPARAM)hCommands ) ;
```

where:

### hCommands

Identifies a handle to a Windows global memory object containing Personal Communications commands. For a list of commands you can issue, see "Issuing Commands with the Session Execute Macro Function".

## Personal Communications Response

If Personal Communications can process the command string, Personal Communications returns an ACK message containing positive status information to the client. If Personal Communications cannot perform the command string, Personal Communications returns an ACK message containing this error code in the low-order word of the wStatus word:

Return Code	Explanation
9	A system error occurred.

## Issuing Commands with the Session Execute Macro Function

You can issue the following commands with the **Session Execute Macro** function:

- KEYBOARD
- RECEIVE
- SEND
- SENDKEY
- WAIT
- WINDOW

Use a separate DDE\_EXECUTE message for each command.

### Note:

- Enclose values that contain nonalphanumeric characters or blanks in double quotation marks ("*value value*").
- To include a double quotation mark within a string, type it twice (for example, "This is a double quotation mark:").
- The maximum length for any command is 255 characters.

## WINDOW Command

[WINDOW(*action* [, "*name*"])]

Performs window actions, where:

```
action = HIDE|RESTORE|MAXIMIZE|MINIMIZE|
          SHOW|CNGNAME
name = LT name or Switch List Entry name
```

**Note:** *name* should be specified when CNGNAME is specified at *action*. If *name* is a NULL string, the default caption will be displayed.

## KEYBOARD Command

[KEYBOARD(*action*)]

Enables or disables the session keyboard, including the mouse, where:

```
action= LOCK|UNLOCK
```

## SEND Command

[SEND("*pcfilename*", "*hostfilename*", "*options*")]

Sends files to the host, where:

```
pcfilename = [path]filename[.ext]
hostfilename =
  For VM system:
    filename filetype[filemode]
  For MVS system:
    [']filename[(membername)][']
  For CICS system:
  For OS/400 system:
    library name filename member name
```

*options* includes any combination of the following file transfer options: MVS, VM, CICS, QUIET, OS/400, and emulation-specific transfer options, separated by spaces.

Refer to *Personal Communications Version 4.2 for Windows and OS/2* for more information about the transfer options.

## RECEIVE Command

[RECEIVE("*pcfilename*", "*hostfilename*", "*options*")]

Receives files from the host, where:

```
pcfilename = [path]filename[.ext]
hostfilename =
  For VM system:
    filename filetype[filemode]
  For MVS system:
    [']filename[(membername)][']
  For CICS system:
  For OS/400 system:
    library name filename member name
```

*options* includes any combination of the following file transfer options: MVS, VM, CICS, QUIET, OS/400, and emulation-specific transfer options, separated by spaces.

Refer to *Personal Communications Version 4.2 for Windows and OS/2* for more information about the transfer options.

## SENDKEY Command

[SENDKEY(*token*,*token*)]

Sends keystrokes to Personal Communications, where:

*token* = *text string*|*command*|*macro macroname*

### Notes:

- Text strings are enclosed in double quotation marks.
  - Macros are prefixed with "macro".
  - The argument string for SENDKEY must be 255 characters or fewer.
  - The following commands are supported.

Table 16. SENDKEY Command List

Command Name	Token	PC/3270	PC400	VT
Alternate Cursor	alt cursor	Yes	Yes	No
Alternate Viewing Mode	alt view	Yes	Yes	No
Attention	sys attn	Yes	Yes	No
Backspace	backspace	Yes	Yes	Yes
Back Tab	backtab	Yes	Yes	No
Backtab Word	backtab word	Yes	Yes	No
Character Advance	character advance	No	Yes	No
Character Backspace	backspace valid	No	Yes	No
Clear Screen	clear	Yes	Yes	No
Clicker	click	Yes	Yes	No
Color Blue	blue	Yes	No	No
Color Field Inherit	field color	Yes	No	No
Color Green	green	Yes	No	No
Color Pink	pink	Yes	No	No
Color Red	red	Yes	No	No
Color Turquoise	turquoise	Yes	No	No
Color White	white	Yes	No	No
Color Yellow	yellow	Yes	No	No
Cursor Blink	cursor blink	Yes	Yes	No
Cursor Down	down	Yes	Yes	Yes
Cursor Left	left	Yes	Yes	Yes
Cursor Right	right	Yes	Yes	Yes
Cursor Select	cursor select	Yes	Yes	No

Table 16. SENDKEY Command List (continued)

Command Name	Token	PC/3270	PC400	VT
Cursor Up	up	Yes	Yes	Yes
Delete Character	delete char	Yes	Yes	No
Delete Word	delete word	Yes	Yes	No
Device Cancel	device cancel	Yes	Yes	No
Dup Field	dup	Yes	Yes	No
Edit Clear	edit-clear	Yes	Yes	Yes
Edit Copy	edit-copy	Yes	Yes	Yes
Edit Cut	edit-cut	Yes	Yes	Yes
Edit Paste	edit-paste	Yes	Yes	Yes
Edit Undo	edit-undo	Yes	Yes	Yes
End Field	end field	Yes	Yes	No
Enter	enter	Yes	Yes	No
Erase EOF	erase eof	Yes	Yes	No
Erase Field	erase field	Yes	No	No
Erase Input	erase input	Yes	Yes	No
Fast Cursor Down	fast down	Yes	Yes	No
Fast Cursor Left	fast left	Yes	Yes	No
Fast Cursor Right	fast right	Yes	Yes	No
Fast Cursor Up	fast up	Yes	Yes	No
Field Exit	field exit	No	Yes	No
Field Mark	field mark	Yes	Yes	No
Field +	field +	No	Yes	No
Field -	field -	No	Yes	No
Graphic Cursor	+cr	Yes	No	No
Help	help	Yes	Yes	No
Highlighting Field Inherit	field hilight	Yes	No	No
Highlighting Reverse	reverse	Yes	No	No
Highlighting Underscore	underscore	Yes	No	No
Home	home	Yes	Yes	No
Host Print	host print	Yes	No	No
Input	input	Yes	Yes	No
Input nondisplay	input nd	Yes	Yes	No
Insert Toggle	insert	Yes	Yes	No
Lower case	to lower	Yes	No	No
Mark Down	mark down	Yes	Yes	Yes
Mark Left	mark left	Yes	Yes	Yes
Mark Right	mark right	Yes	Yes	Yes
Mark Up	mark up	Yes	Yes	Yes
Move Mark Down	move down	Yes	Yes	Yes
Move Mark Left	move left	Yes	Yes	Yes

Table 16. SENDKEY Command List (continued)

Command Name	Token	PC/3270	PC400	VT
Move Mark Right	move right	Yes	Yes	Yes
Move Mark Up	move up	Yes	Yes	Yes
New Line	newline	Yes	Yes	Yes
Next Page	page down	No	Yes	No
Pause 1 second	pause	Yes	Yes	No
Previous Page	page up	No	Yes	No
Print Screen	local copy	Yes	Yes	Yes
Program Attention Key 1	pa1	Yes	No	No
Program Attention Key 2	pa2	Yes	No	No
Program Attention Key 3	pa3	Yes	No	No
Program Function Key 1	pf1	Yes	Yes	No
⋮	⋮	⋮	⋮	⋮
Program Function Key 5	pf5	Yes	Yes	No
Program Function Key 6	pf6	Yes	Yes	Yes
⋮	⋮	⋮	⋮	⋮
Program Function Key 20	pf20	Yes	Yes	Yes
Program Function Key 21	pf21	Yes	Yes	No
⋮	⋮	⋮	⋮	⋮
Program Function Key 24	pf24	Yes	Yes	No
Quit	quit	Yes	Yes	No
Reset	reset	Yes	Yes	No
Response Time Monitor	rtm	Yes	No	No
Roll Down	roll down	No	Yes	No
Roll Up	roll up	No	Yes	No
Rubout	rubout	Yes	Yes	Yes
Rule	rule	Yes	Yes	Yes
SO/SI Display	so si	Yes	Yes	No
SO/SI Generate	so si generate	No	Yes	No
System Request	sys req	Yes	Yes	No
Tab Field	tab field	Yes	Yes	Yes
Tab Word	tab word	Yes	Yes	No
Test	test request	No	Yes	No
Unmark	unmark	Yes	Yes	Yes
Upper case	to upper	Yes	No	No
Upper/Lower Change	to other	Yes	No	No
Wait for bind	wait app	Yes	Yes	No
Wait for System	wait sys	Yes	Yes	No
Wait transition	wait trn	Yes	Yes	No
Wait while input inh.	wait inp inh	Yes	Yes	No

Table 16. SENDKEY Command List (continued)

Command Name	Token	PC/3270	PC400	VT
Window Relocation 1	view 1	Yes	Yes	Yes
⋮	⋮	⋮	⋮	⋮
Window Relocation 8	view 8	X	X	X
VT compose	vt compose	No	No	Yes
VT find	vt find	No	No	Yes
VT hold screen	vt hold	No	No	Yes
VT insert here	vt insert	No	No	Yes
VT next screen	vt next	No	No	Yes
VT numeric keypad 0	vt numpad 0	No	No	Yes
VT numeric keypad 1	vt numpad 1	No	No	Yes
VT numeric keypad 2	vt numpad 2	No	No	Yes
VT numeric keypad 3	vt numpad 3	No	No	Yes
VT numeric keypad 4	vt numpad 4	No	No	Yes
VT numeric keypad 5	vt numpad 5	No	No	Yes
VT numeric keypad 6	vt numpad 6	No	No	Yes
VT numeric keypad 7	vt numpad 7	No	No	Yes
VT numeric keypad 8	vt numpad 8	No	No	Yes
VT numeric keypad 9	vt numpad 9	No	No	Yes
VT numeric keypad -	vt numpad minus	No	No	Yes
VT numeric keypad ,	vt numpad comma	No	No	Yes
VT numeric keypad .	vt numpad period	No	No	Yes
VT numeric keypad enter	vt numpad enter	No	No	Yes
VT PF1	vt pf1	No	No	Yes
VT PF2	vt pf2	No	No	Yes
VT PF3	vt pf3	No	No	Yes
VT PF4	vt pf4	No	No	Yes
VT prev. screen	vt prev	No	No	Yes
VT remove	vt remove	No	No	Yes
VT select	vt select	No	No	Yes
VT user defined function 6	vt user f6	No	No	Yes
VT user defined function 7	vt user f7	No	No	Yes
VT user defined function 8	vt user f8	No	No	Yes
VT user defined function 9	vt user f9	No	No	Yes
VT user defined function 10	vt user f10	No	No	Yes
VT user defined function 11	vt user f11	No	No	Yes
VT user defined function 12	vt 12	No	No	Yes
VT user defined function 13	vt user f13	No	No	Yes

Table 16. SENDKEY Command List (continued)

Command Name	Token	PC/3270	PC400	VT
VT user defined function 14	vt user f14	No	No	Yes
VT user defined function 15	vt user f15	No	No	Yes
VT user defined function 16	vt user f16	No	No	Yes
VT user defined function 17	vt user f17	No	No	Yes
VT user defined function 18	vt user f18	No	No	Yes
VT user defined function 19	vt user f19	No	No	Yes
VT user defined function 20	vt user f20	No	No	Yes

### Examples:

- To logon  
[SENDKEY("Logon")]
- To get reader list  
[SENDKEY("RDRL", enter)]

### WAIT Command

[WAIT("[*time out*"] [*wait condition*"])]

Waits until the timeout expires or the wait condition the client specified occurs. For this command, the client has to set at least one option, where:

*time out* (optional)

If the client sets a timeout value in the command statements, the following units are available in the wait statement.

- msec
- millisecond
- milliseconds
- sec
- second
- seconds
- minute
- minutes
- hour
- hours

*wait condition* (optional)

For the wait condition option, the client can select the following options:

**while cursor at (cursor row, cursor column)**

While the cursor is at (cursor row, cursor column), it keeps waiting.

**while "string"**

While the "string" is somewhere on the screen, it keeps waiting.

**while "string" at (cursor row, cursor column)**

While the "string" is at (cursor row, cursor column) on the screen, it keeps waiting.

**until cursor at (cursor row, cursor column)**

Until the cursor moves to (cursor row, cursor column), it keeps waiting.



**until "string"**

Until the "string" is displayed somewhere on the screen, it keeps waiting.

**until "string" at (cursor row, cursor column)**

Until the "string" is displayed at (cursor row, cursor column), it keeps waiting.

**Examples:**

- To wait 10 seconds  
[WAIT("10 seconds")]
- To wait while "ABCDEF" is displayed at (2,9) on the screen  
[WAIT("while ""ABCDEF"" at (2,9)")]
- To wait until "ABCDEF" is displayed at (2,9) on the screen, or after 8 seconds  
[WAIT("8 seconds until ""ABCDEF"" at (2,9)")]

## Set Cursor Position

3270	5250	VT
Yes	Yes	Yes

The **Set Cursor Position** function allows the client application to set the cursor position in the session window.

```
PostMessage( hServerWnd,
             WM_DDE_POKE,
             hClientWnd,
             PackDDELParm(WW_DDE_POKE,
                          hData, aSETCURSOR) );
```

where:

**hData**

Identifies a handle to a Windows global memory object that contains the cursor positioning information in the following structure:

```
typedef struct tagSETCURSOR
{
    unsigned char poke[(sizeof(DDEPOKE)-1)];
    unsigned short uSetCursorType; /* Cursor Set Type
    unsigned short uSetCursor1; /* Cursor Row or PS Offset
    unsigned short uSetCursor2; /* Cursor Col
} SETCURSOR;

typedef union tagDDE_SETCURSOR
{
    DDEPOKE DDEpoke;
    SETCURSOR DDEsetcursor;
} DDE_SETCURSOR, *lpDDE_SETCURSOR;
```

Personal Communications supports two ways to set the cursor position:

- PS Offset ( uSetCursorType = 0 )
- Row/Column number ( uSetCursorType = 1 )

The application specifies which method by setting the uSetCursorType field to the appropriate value, followed by setting the two other fields uSetCursor1 and uSetCursor2 to their appropriate values as follows:

- uSetCursorType = 0 offset
  - uSetCursor1: 0 ... (PSsize – 1)

- uSetCursorType = 1 row/col
  - uSetCursor1: 0 ... (PSrows – 1)
  - uSetCursor2: 0 ... (PScols – 1)

### aSETCURSOR

Identifies cursor position as the item.

## Personal Communications Response

Personal Communications receives the cursor information and moves the cursor to the specified position in the PS. If the cursor is positioned successfully, Personal Communications returns a positive ACK message to the client application. Otherwise, a negative ACK message is returned with one of the following error codes in the low-order byte of the wStatus word.

WM\_DDE\_ACK(wStatus, aSETCURSOR)

Return Code	Explanation
1	Cursor set type is not valid. Must be 0 or 1.
2	Cursor PS offset is not valid. Must be 0 ... (PSsize – 1).
3	Cursor row value is not valid. Must be 0 ... (PSrows – 1).
4	Cursor column value is not valid. Must be 0 ... (PScols – 1).
6	The specified format is not valid.
9	A system error occurred.

## Set Mouse Intercept Condition

3270	5250	VT
Yes	Yes	Yes

This function specifies the mouse input to be intercepted. The client sends the following command to set the mouse event to be intercepted.

```
PostMessage( hServerWnd,
             WM_DDE_POKE,
             hClientWnd,
             PackDDE1Param(WM_DDE_POKE,
                           hData, aMOUSE) );
```

where:

**hData** Identifies a handle to a Windows global memory object that specifies the condition of intercepting the mouse input.

If the format is CF\_TEXT, the client program sends the condition in the following structure:

```
typedef struct tagSETMOUSE_CF_TEXT
{
    unsigned char poke[(sizeof(DDEPOKE)-1)];
    unsigned char zMouseCondition[1];
} SETMOUSE_CF_TEXT;

typedef union tagDDE_SETMOUSE_CF_TEXT
{
```

```

DDEPOKE          DDEpoke;
SETMOUSE_CF_TEXT DDEcond;
} DDE_SETMOUSE_CF_TEXT, *lpDDE_SETMOUSE_CF_TEXT;

```

The following table shows the parameters' values:

Parameter Name	Meaning	Value
Condition	Condition of intercepting the mouse input	<p>A string terminated with '\0', consists of the constants defined as follows in any order:</p> <p><b>L</b> Enable intercepting the left button</p> <p><b>I</b> Disable intercepting the left button</p> <p><b>R</b> Enable intercepting the right button</p> <p><b>r</b> Disable intercepting the right button</p> <p><b>M</b> Enable intercepting the middle button</p> <p><b>m</b> Disable intercepting the middle button</p> <p><b>S</b> Enable intercepting a single click</p> <p><b>s</b> Disable intercepting a single click</p> <p><b>D</b> Enable intercepting a double click</p> <p><b>d</b> Disable intercepting a double click</p> <p><b>T</b> Retrieve the pointed string</p> <p><b>t</b> Do not retrieve the pointed string</p>

If the format is CF\_DSPTTEXT, the client program sends the condition in the following structure:

```

typedef struct tagSETMOUSE_CF_DSPTTEXT
{
    unsigned char poke[(sizeof(DDEPOKE)-1)];
    BOOL          bLeftButton;    /* Enable intercepting left button
    BOOL          bRightButton;   /* Enable intercepting right button
    BOOL          bMiddleButton;  /* Enable intercepting middle button
    BOOL          bSingleClick;   /* Enable intercepting single click
    BOOL          bDoubleClick;   /* Enable intercepting double click
    BOOL          bRetrieveString; /* Enable intercepting retrieve string
} SETMOUSE_CF_DSPTTEXT;

typedef union tagDDE_SETMOUSE_CF_DSPTTEXT
{
    DDEPOKE          DDEpoke;
    SETMOUSE_CF_DSPTTEXT DDEcond;
} DDE_SETMOUSE_CF_DSPTTEXT, *lpDDE_SETMOUSE_CF_DSPTTEXT;

```

The following table shows the values in the parameters:

Parameter Name	Meaning	Value
bLeftButton	Enable or disable interception of the left mouse button	<p><b>True</b> Enable intercepting the left button</p> <p><b>False</b> Disable intercepting the left button</p>
bRightButton	Enable or disable interception of the right mouse button	<p><b>True</b> Enable intercepting the right button</p> <p><b>False</b> Disable intercepting the right button</p>
bMiddleButton	Enable or disable interception of the middle mouse button	<p><b>True</b> Enable intercepting the middle button</p> <p><b>False</b> Disable intercepting the middle button</p>
bSingleClick	Enable or disable interception of the single click	<p><b>True</b> Enable intercepting the single click</p> <p><b>False</b> Disable intercepting the single click</p>
bDoubleClick	Enable or disable interception of the double click	<p><b>True</b> Enable intercepting the double click</p> <p><b>False</b> Disable intercepting the double click</p>
bRetrieveString	Retrieve or do not retrieve the pointed string	<p><b>True</b> Retrieve the pointed string</p> <p><b>False</b> Do not retrieve the pointed string</p>

#### aMOUSE

Identifies the mouse as the item.

### Personal Communications Response

When receiving the **Set Mouse Intercept Condition** request, Personal Communications returns an ACK message if it can set the intercept condition to the specified status. Otherwise, a negative ACK message is returned to the client with one of the following return codes in the low-order byte of the wStatus field:

WM\_DDE\_ACK(wStatus, aMOUSE)

Return Code	Explanation
2	A character in the Condition parameter is not valid.
6	The specified format is not valid.
9	A system error occurred.

# Set Presentation Space Service Condition

3270	5250	VT
Yes	Yes	Yes

The **Set Presentation Space Service Condition** function sets the condition for using the following functions:

- **Get Partial Presentation Space**
- **Find Field**
- **Search for String**

The client application sets the condition by calling a function such as:

- **Start PS position**
- **PS length**
- **EOF flag**
- **Search direction**
- **ASCIIZ string**

The client must specify the **Set Presentation Space Service Condition** function before invoking the functions listed above. The conditions set by this function remain in effect until the next **Set Presentation Space Service Condition** function is called. The client sends the following message to set the condition:

```
PostMessage( hServerWnd,
             WM_DDE_POKE,
             hClientWnd,
             PackDDELPParam(WM_DDE_POKE,
                             (hData, aEPSCOND) );
```

where:

**hData**

Identifies a handle to a Windows global memory object containing:

```
typedef struct tagPSSERVCOND
{
    unsigned char poke[(sizeof(DDEPOKE)-1)];
    unsigned short uPSStart;           /* PS Position
    unsigned short uPSLength;         /* Length of String or PS
    unsigned short uSearchDir;        /* Direction for search
    unsigned short uEOFflag;          /* EOF effective switch
    unsigned char szTargetString[1];  /* Target String
} PSSERVCOND;

typedef union tagDDE_PSSERVCOND
{
    DDEPOKE DDEpoke;
    PSSERVCOND DDEcond;
} DDE_PSSERVCOND, *lpDDE_PSSERVCOND;
```

The following values are valid at the uSearchDir field:

```
PCS_SRCHFRWD    0    /* Search forward.
PCS_SRCHBKWD    1    /* Search backward.
```

The following values are valid for the uEOFflag field:

```
PCS_UNEFFECTEOF 0    /* The PS Area is not truncated at End of Field (EOF).
PCS_EFFECTEOF   1    /* The PS Area is truncated at End of Field (EOF).
```

If the value of `uEOFflag` is `PCS_EFFECTEOF` then the PS length and Search Direction are not used.

### aEPSCOND

Identifies the item for the **Set Presentation Space Service Condition** function.

## Personal Communications Response

If Personal Communications can perform the **Set Presentation Space Service Condition** function, then Personal Communications returns an ACK message:

```
WM_DDE_ACK(wStatus, aEPSCOND)
```

If Personal Communications cannot perform the Set Presentation Space Service Condition function, then Personal Communications returns a negative ACK message containing the following return codes in the low-order byte of `wStatus`:

Return Code	Explanation
1	PS position is not valid.
2	Length is not valid.
3	The value of EOF flag is not valid.
4	The value of Search Direction is not valid.
6	The specified format is not valid.
9	A system error occurred.

## Set Session Advise Condition

3270	5250	VT
Yes	Yes	Yes

This function sets the condition for the `DDE_ADVISE` of the **Start Session Advise** function. The client can specify a search string and a region of the screen. When the advise condition is met, the server notifies the client of the condition according to the options specified by the **Start Session Advise** function.

**Note:** The client must specify the **Set Session Advise Condition** function before invoking **Start Session Advise**. If the advise condition is set after the **Start Session Advise** function is started, the advise condition will be ignored and the client will receive a negative ACK message. See “Start Session Advise” on page 217 for more information about starting the advise.

The client sends the following message to set the advise condition.

```
PostMessage( hServerWnd,
             WM_DDE_POKE,
             hClientWnd,
             PackDDE1Param(WM_DDE_POKE,
                           (hData, aPSCOND) ));
```

where:

**hData** Identifies a handle to a Windows global memory object containing:

```
typedef struct tagSEARCHDATA
{
    unsigned char poke[(sizeof(DDEPOKE)-1)];
    unsigned short uPSstart;           /* PS Position of string
    unsigned short uPSLength;         /* Length of String
```

```

        BOOL          bCaseSensitive;          /* Case Sensitive TRUE=YES
    unsigned char  SearchString[1]; /* Search String
    } SEARCHDATA;

typedef union tagDDE_SEARCHDATA
{
    DDEPOKE      DDEpoke;
    SEARCHDATA   DDEcond;
} DDE_SEARCHDATA, *lpDDE_SEARCHDATA;

```

**aPSCOND**

Identifies the item for the **Set Session Advise Condition** function.

**Personal Communications Response**

If Personal Communications can perform the **Set Session Advise Condition** function, Personal Communications returns this ACK message:

```
WM_DDE_ACK(wStatus, aPSCOND)
```

If Personal Communications cannot perform the **Set Session Advise Condition** function, then Personal Communications returns an negative ACK message containing one of the following return codes in the low-order byte of wStatus:

Return Code	Explanation
1	Advise is already active.
2	Advise condition is already active.
3	PS position is not valid.
4	String length is not valid.
6	The specified format is not valid.
9	A system error occurred.

**Set Structured Field Service Condition**

3270	5250	VT
Yes	Yes	Yes

The **Set Structured Field Service Condition** function passes the Query Reply data provided by the client application.

**Note:** The client must call the **Set Structured Field Service Condition** function before invoking the **Start Read SF** function or the **Write SF** function.

The client sends the following message to set the condition.

```

PostMessage( hServerWnd,
             WM_DDE_POKE,
             hClientWnd,
             PackDDE1Param(WM_DDE_POKE,
                           (hData, aSFCOND) ));

```

where:

**hData** Identifies a handle to a Windows global memory object containing:

```

typedef struct tagSFSERVCOND
{
    unsigned char  poke[(sizeof(DDEPOKE)-1)];
    unsigned short uBufferLength;          /* Buffer size of Read_SF
    unsigned short uQRLength;             /* Length of Query Reply dat

```

```

    unsigned char  szQueryReply[1];           /* Query Reply data
} SFSEVRCOND;

typedef union tagDDE_SFSEVRCOND
{
    DDEPOKE      DDEpoke;
    SFSEVRCOND  DDEcond;
} DDE_SFSEVRCOND, *lpDDE_SFSEVRCOND;

```

### aSFCOND

Identifies the item for the **Set Structured Field Service Condition** function.

## PC/3270 Response

PC/3270 checks the Query Reply ID and Type (not DOID) and the length. If they are valid, then PC/3270 returns an ACK message:

```
WM_DDE_ACK(wStatus, aSFCOND)
```

If PC/3270 cannot perform the **Set Structured Field Service Condition** function, then PC/3270 returns a negative ACK message containing one of the following return codes in the low-order byte of wStatus:

Return Code	Explanation
1	PS SF ID is not valid.
2	Length is not valid.
3	One DDM base type is already connected to this session.
4	Structured Field Service Condition is already set.
6	The specified format is not valid.
9	A system error occurred.

## Start Close Intercept

3270	5250	VT
Yes	Yes	Yes

The **Start Close Intercept** function allows a client application to intercept close requests generated when a user selects the close option from the emulator session window. This function intercepts the close request and discards it until the **Stop Close Intercept** function is requested. After using this function, the client receives DATA messages notifying it that close requests occurred (CLOSE).

The client sends the following command to begin a session advise.

```

PostMessage( hServerWnd,
             WM_DDE_ADVISE,
             hClientWnd,
             Pack DDE1Param(WM_DDE_ADVISE,
                             (hOptions, aCLOSE) );

```

where:

### hOptions

Is a handle to a Windows global memory object DDEADVISE structure.



If the value of `fDeferUpd` is 1, DDE Data messages will be sent to the client application with the `hData` set to NULL. The client must then issue a DDE REQUEST to request the data item.

If the value of `fAckReq` is 1, the server does not notify the client of further close requests until the server receives an ACK message from the client in response to any previous notification.

The `cfFormat` field specifies the format to send the close request. (Must be `CF_DSPTEXT`.)

### aCLOSE

Identifies close intercept as the item.

## Personal Communications Response

Personal Communications receives the **Start Close Intercept** and returns an ACK message if it can start the intercept. Otherwise a negative ACK message is returned to the client with one of the following return codes in the low-order byte of the `wStatus` field:

`WM_DDE_ACK(wStatus, aCLOSE)`

Return Code	Explanation
1	Close Intercept is already working.
6	The specified format is not valid.
9	A system error occurred.

Once the intercept starts, the client receives DATA messages notifying it that the close request is intercepted:

`WM_DDE_DATA(hData, aCLOSE)`

where:

**hData** Identifies a handle to a Windows global memory object containing:

```
typedef struct tagCLOSEREQ
{
    unsigned char data[(sizeof(DDEDATA)-1)];
    unsigned short uCloseReqCount; /* Number of the close requests.
} CLOSEREQ;

typedef union tagDDE_CLOSEREQ
{
    DDEDATA DDEdata;
    CLOSEREQ DDEclose;
} DDE_CLOSEREQ, *lpDDE_CLOSEREQ;
```

The DATA messages continue until a Stop Close Intercept message is sent to Personal Communications.

## Start Keystroke Intercept

3270	5250	VT
Yes	Yes	Yes

The Start Keystroke Intercept function allows a client application to filter any keystrokes sent to a session by a terminal operator. After a call to this function, keystrokes are intercepted, and the client receives them (KEYS).

The client sends the following command to begin intercept.

```
PostMessage( hServerWnd,  
            WM_DDE_ADVISE,  
            hClientWnd,  
            PackDDEIParam(WM_DDE_ADVISE,  
                          (hOptions, aKEYS) );
```

where:

### **hOptions**

Is a handle to a Windows global memory object DDEADVISE structure.

If the value of fDeferUpd is 1, DDE Data messages are sent to the client application with the hData set to NULL. The client then issues a DDE REQUEST to request the data item.

If the value of fAckReq is 1, the server does not notify the client of further keystrokes until the server receives an ACK message from the client in response to any previous keystrokes notification.

The cfFormat field specifies the format to send the keystrokes when the keystroke is sent by a terminal operator. (Must be CF\_DSPTXT.)

### **aKEYS**

Identifies keystrokes as the item.

## **Personal Communications Response**

Personal Communications receives the **Start Keystroke Intercept** and returns an ACK message if it can start the intercept. Otherwise a negative ACK message is returned to the client with one of the following return codes in the low-order byte of the wStatus field:

```
WM_DDE_ACK(wStatus, aKEYS)
```

<b>Return Code</b>	<b>Explanation</b>
1	Keystroke Intercept is already started.
6	The specified format is not valid.
9	A system error occurred.

Once the intercept has started, the client receives DATA messages notifying it that the keystroke is intercepted:

```
WM_DDE_DATA(hData, aKEYS)
```

The DATA messages continue until a Stop Keystroke Intercept message is sent to Personal Communications. The format of the data item is the same format as if the client requested the data item via a DDE\_REQUEST.

## **Start Mouse Input Intercept**

3270	5250	VT
Yes	Yes	Yes

The **Start Mouse Input Intercept** function allows a client application to intercept mouse input when a terminal operator presses the mouse button on an emulator session window. After calling this function, the client receives DATA messages that include the PS position where mouse input occurred.

The client sends the following command to begin to intercept the mouse input.

```
PostMessage( hServerWnd,
            WM_DDE_ADVISE,
            hClientWnd,
            PackDDE1Param(WM_DDE_ADVISE,
                          (hOptions, aMOUSE) );
```

where:

### hOptions

Is a handle to a Windows global memory object DDEADVISE structure.

If the value of fDeferUpd is 1, DDE Data messages will be sent to the client application with the hData set to NULL. The client must then issue a DDE REQUEST to request the data item.

If the value of fAckReq is 1, the server does not notify the client of further structured field data until the server receives an ACK message from the client in response to any previous notification.

The cfFormat field specifies the format to send the data item has been updated.

### aMOUSE

Identifies the mouse as the item.

## Personal Communications Response

Personal Communications receives the **Start Mouse Input Intercept** and returns an ACK message if it can start this function. Otherwise a negative ACK message is returned to the client with one of the following return codes in the low-order byte of the wStatus field:

```
WM_DDE_ACK(wStatus, aMOUSE)
```

Return Code	Explanation
1	Mouse Input Intercept has been already started.
6	The specified format is not valid.
9	A system error occurred.

Once the **Mouse Input Intercept** starts, the client receives DATA messages of the structured field:

```
WM_DDE_DATA(hData, aMOUSE)
```

where:

### hData

If the format is CF\_TEXT, Personal Communications returns the mouse input information in the following format:

```
typedef struct tagMOUSE_CF_TEXT
{
    unsigned char data[(sizeof(DDEDATA)-1)];
    unsigned char PSPos[4];      /* PS Offset - Mouse position
    unsigned char Tab1[1];      /* Tab character
    unsigned char PSRowPos[4];  /* ROW number of Mouse position
    unsigned char Tab2[1];      /* Tab character
    unsigned char PSColPos[4];  /* Col number of Mouse position
    unsigned char Tab3[1];      /* Tab character
    unsigned char PSSize[4];    /* Size of Presentation Space
    unsigned char Tab4[1];      /* Tab character
    unsigned char PSRows[4];    /* Row number of PS
```

```

    unsigned char Tab5[1];          /* Tab character
    unsigned char PSCols[4];        /* Column number of PS
    unsigned char Tab6[1];          /* Tab character
    unsigned char Button[1];        /* Type of clicked mouse butt n
    unsigned char Tab7[1];          /* Tab character
    unsigned char Click[1];         /* Type of clicking
    unsigned char Tab8[1];          /* Tab character
    unsigned char zClickString[1]; /* Retrieved string
} MOUSE_CF_TEXT;

typedef union tagDDE_MOUSE_CF_TEXT
{
    DDEDATA      DDEdata;
    MOUSE_CF_TEXT DDEmouse;
} DDE_MOUSE_CF_TEXT, *lpDDE_MOUSE_CF_TEXT;

```

The following table shows the values in the parameters:

Parameter Name	Meaning	Value
PSPos	PS offset of the position where mouse was clicked	0 ... (PSSize - 1)
PSRowPos	Row number of the position where mouse was clicked	0 ... (PSRows - 1)
PSColPos	Column number of the position where mouse was clicked	0 ... (PSCols - 1)
PSSize	Presentation space size	
PSRows	Number of presentation space rows	
PSCols	Number of presentation space columns	
ButtonType	Type of clicked mouse button	<b>L</b> Left button <b>M</b> Middle button <b>R</b> Right button
ClickType	Type of clicking	<b>S</b> Single click <b>D</b> Double click
ClickString	Retrieved string to which the mouse pointed	A character string terminated with a '\0'
Tab1-8	A tab character for delimiter	'\t'

If the format is CF\_DSPTTEXT, Personal Communications returns the mouse input information in the following format:

```

typedef struct tagMOUSE_CF_DSPTTEXT
{
    unsigned char data[(sizeof(DDEDATA)-1)];
    unsigned short uPSPos;          /* PS Offset - Mouse position
    unsigned short uPSRowPos;       /* ROW number - Mouse position
    unsigned short uPSColPos;       /* Col number - Mouse position
    unsigned short uPSSize;         /* Size of Presentation Space
    unsigned short uPSRows;         /* Row number of PS
    unsigned short uPSCols;         /* Column number of PS
    unsigned short uButtonType;     /* Type of clicked mouse button
    unsigned short uClickType;      /* Type of clicking
    unsigned char zClickString[1];  /* Retrieved string
} MOUSE_CF_DSPTTEXT;

```

```

typedef union tagDDE_MOUSE_CF_DSPTXT
{
    DDEDATA          DDEdata;
    MOUSE_CF_DSPTXT DDEmouse;
} DDE_MOUSE_CF_DSPTXT, *lpDDE_MOUSE_CF_DSPTXT;

```

The following table shows the values in the parameters:

Parameter Name	Meaning	Value
uPSPos	PS offset of the position where the mouse was clicked	0 ... (uPSSize - 1)
uPSRowPos	Row number of the position where the mouse was clicked	0 ... (uPSRows - 1)
uPSColPos	Column number of the position where the mouse was clicked	0 ... (uPSCols - 1)
uPSSize	Size of the presentation space	
uPSRows	Number of rows of the presentation space	
uPSCols	Number of columns of the presentation space	
uButtonType	Type of the clicked mouse button	<b>0x0001</b> Left button <b>0x0002</b> Middle button <b>0x0003</b> Right button
uClickType	Type of clicking	<b>0x0001</b> Single click <b>0x0002</b> Double click
szClickString	Retrieved string to which the mouse pointed	A character string terminated with a '\0'

The DATA messages continue until a Stop Mouse Input Intercept message is sent to Personal Communications.

## Start Read SF

3270	5250	VT
Yes	Yes	Yes

The **Start Read SF** function allows a client application to read structured field data from the host application. After using this function, the client receives DATA messages notifying it that close requests occurred.

**Note:** Before using this function, the client must call the **Set Structured Field Service Condition** function to pass the Query Reply data to the server.

The client sends the following command to begin a Read SF.

```

PostMessage( hServerWnd,
             WM_DDE_ADVISE,
             hClientWnd,
             PackDDE1Param(WM_DDE_ADVISE,
                           (hOptions, aSF) );

```

where:

### hOptions

Is a handle to a Windows global memory object DDEADVISE structure.

If the value of fDeferUpd is 1, DDE Data messages will be sent to the client application with the hData set to NULL. The client must then issue a DDE REQUEST to request the data item.

If the value of fAckReq is 1, the server does not notify the client of further structured field data until the server receives an ACK message from the client in response to any previous notification.

The cfFormat field specifies the format to send the structured field data. (It must be CF\_DSPTTEXT.)

**aSF** Identifies structured field as the item.

### PC/3270 Response

PC/3270 receives the Start Read SF and returns an ACK message if it can start the Read SF. Otherwise a negative ACK message is returned to the client with one of the following return codes in the low-order byte of the wStatus field:

WM\_DDE\_ACK(wStatus, aSF)

Return Code	Explanation
1	Read SF is already started.
3	No prior <b>Set Structured Field Service Condition</b> function was called.
6	The specified format is not valid.
9	A system error occurred.

Once the Read SF has started, the client receives DATA messages of the structured field:

WM\_DDE\_DATA(hData, aSF)

where:

**hData** Identifies a handle to a Windows global memory object containing:

```
typedef struct tagMOUSE_CF_DSPTTEXT
{
    unsigned char data[(sizeof(DDEDATA)-1)];
    unsigned short uPSPos; /* PS Offset - Mouse position
    unsigned short uPSRowPos; /* ROW number - Mouse position
    unsigned short uPSColPos; /* Col number - Mouse position
    unsigned short uPSSize; /* Size of Presentation Space
    unsigned short uPSRows; /* Row number of PS
    unsigned short uPSCols; /* Column number of PS
    unsigned short uButtonType; /* Type of clicked mouse button
    unsigned short uClickType; /* Type of clicking
    unsigned char zClickString[1]; /* Retrieved string
} MOUSE_CF_DSPTTEXT;

typedef union tagDDE_MOUSE_CF_DSPTTEXT
{
    DDEDATA DDEdata;
    MOUSE_CF_DSPTTEXT DDEmouse;
} DDE_MOUSE_CF_DSPTTEXT, *lpDDE_MOUSE_CF_DSPTTEXT;
typedef struct tagSFDATA
{
    unsigned char data[(sizeof(DDEDATA)-1)];
```

```

        unsigned short uSFLength;           /* Length of SF data
        unsigned char  szSFData[1];       /* SF data
    } SFDATA;

    typedef union tagDDE_SFDATA
    {
        DDEDATA  DDEdata;
        SFDATA   DDEsfdata;
    } DDE_SFDATA, *lpDDE_SFDATA;

```

The DATA messages continue until a Stop Read SF message is sent to PC/3270.

## Start Session Advise

3270	5250	VT
Yes	Yes	Yes

The **Start Session Advise** function establishes a link between the Personal Communications session and the client. This lets the client receive updates of the presentation space (PS), the operator information area (OIA), or the trim rectangle (TRIMRECT) when the data item is updated.

**Note:** If the client application needs conditional notification when the presentation space is updated, set an advise condition prior to invoking the advise function for the presentation space. See “Set Session Advise Condition” on page 208 .

The client sends the following command to begin a session advise.

```

PostMessage( hServerWnd,
             WM_DDE_ADVISE,
             hClientWnd,
             PackDDElParam(WM_DDE_ADVISE,
                           hOptions, aItem) );

```

where:

### hOptions

Is a handle to a Windows global memory object DDEADVISE structure. This is the structure:

```

typedef struct tagDDEADVISE
{
    unsigned reserved:14;           // Reserved
    unsigned fDeferUpd:1;          // Send notification only
    unsigned fAckReq:1;            // Client will ACK all notices
    WORD     cfFormat;             // Clipboard format to use
} DDEADVISE, *lpDDEADVISE;

```

If the value of fDeferUpd is 1, DDE Data messages are sent to the client application with the hData set to NULL. The client must then issue a DDE REQUEST to request the data item.

If the value of fAckReq is 1, the server does not notify the client of further changes to the data item until the server receives an ACK message from the client in response to any previous update notification.

The cfFormat field specifies the format to send the data item when the item has been updated.

**item** Specifies the item of information being requested; in this case, the value can be PS, OIA, or TRIMRECT.

## Personal Communications Response

Personal Communications receives the Start Session Advise and returns an ACK message if it can start the advise. Otherwise, a negative ACK message is returned to the client with one of the following return codes in the low-order byte of the wStatus field:

WM\_DDE\_ACK(wStatus, aItem)

Return Code	Explanation
1	Advise already active for data item.
6	Advise parameter not valid.
9	A system error occurred.

Once the advise has started, the client receives DATA messages notifying it that the data item (PS, OIA, or TRIMRECT) has changed:

WM\_DDE\_DATA(hData, aItem)

The DATA messages continue until a Stop Session Advise message is sent to Personal Communications. The format of the data item is the same as if the client requested the data item via a DDE\_REQUEST.

## Stop Close Intercept

3270	5250	VT
Yes	Yes	Yes

The **Stop Close Intercept** function ends a client application's ability to intercept close requests. The client sends the following command to perform the **Stop Close Intercept** function.

```
PostMessage( hServerWnd,
             WM_DDE_UNADVISE,
             hClientWnd,
             MAKELPARAM(NULL, aCLOSE) );
```

where:

### aCLOSE

Identifies close intercept as the item.

## Personal Communications Response

If Personal Communications can perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing positive status information to the client:

WM\_DDE\_ACK(wStatus, aCLOSE)

If Personal Communications cannot perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing negative status information and one of the following return codes in the low-order byte of the wStatus word:

Return Code	Explanation
1	Advise has not started yet.



Return Code	Explanation
9	A system error occurred.

## Stop Keystroke Intercept

3270	5250	VT
Yes	Yes	Yes

The **Stop Keystroke Intercept** function ends a client application's ability to intercept keystrokes. The client sends the following command to perform the **Stop Keystroke Intercept** function.

```
PostMessage( hServerWnd,
             WM_DDE_UNADVISE,
             hClientWnd,
             MAKELPARAM(NULL, aKEYS) );
```

where:

### **aKEYS**

Identifies keystrokes as the item.

## Personal Communications Response

If Personal Communications can perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing positive status information to the client:

```
WM_DDE_ACK(wStatus, aKEYS)
```

If Personal Communications cannot perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing negative status information and one of the following return codes in the low-order byte of the wStatus word.

Return Code	Explanation
1	Advise has not started yet.
9	A system error occurred.

## Stop Mouse Input Intercept

3270	5250	VT
Yes	Yes	Yes

The **Stop Mouse Input Intercept** function ends a client application's ability to intercept mouse input.

The client sends the following command to perform the **Stop Mouse Input Intercept** function.

```
PostMessage( hServerWnd,
             WM_DDE_UNADVISE,
             hClientWnd,
             MAKELPARAM(NULL, aMOUSE) );
```

where:

### **aMOUSE**

Identifies the mouse as the item.

## Personal Communications Response

If Personal Communications can perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing positive status information to the client:

```
WM_DDE_ACK(wStatus, aMOUSE)
```

If Personal Communications cannot perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing negative status information and one of the following return codes in the low-order byte of the wStatus word.

Return Code	Explanation
1	Advise has not started yet.
9	A system error occurred.

## Stop Read SF

3270	5250	VT
Yes	Yes	Yes

The **Stop Read SF** function ends a client application's ability to read structured field data.

The client sends the following command to perform the **Stop Read SF** function.

```
PostMessage( hServerWnd,  
            WM_DDE_UNADVISE,  
            hClientWnd,  
            MAKELPARAM(NULL, aSF) );
```

where:

**aSF** Identified structured field as the item.

## PC/3270 response

If PC/3270 can perform the DDE\_UNADVISE, PC/3270 returns an ACK message containing positive status information to the client:

```
WM_DDE_ACK(wStatus, aSF)
```

If PC/3270 cannot perform the DDE\_UNADVISE, PC/3270 returns an ACK message containing negative status information and one of the following return codes in the low-order byte of the wStatus word.

Return Code	Explanation
1	Advise has not started yet.
9	A system error occurred.

## Stop Session Advise

3270	5250	VT
Yes	Yes	Yes

The **Stop Session Advise** function disconnects a link between Personal Communications and the client. The client sends the following command to perform the **Stop Session Advise** function.

```
PostMessage( hServerWnd,
            WM_DDE_UNADVISE,
            hClientWnd,
            MAKELPARAM(NULL, aItem) );
```

where:

**altItem** Specifies the item of information being requested; in this case, the value can be PS, OIA, TRIMRECT, or NULL.

If the value of *altItem* is NULL, then the client has requested termination of all active notifications for the conversation.

## Personal Communications Response

If Personal Communications can perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing positive status information to the client:

```
WM_DDE_ACK(wStatus, aItem)
```

If Personal Communications cannot perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing negative status information and one of the following return codes in the low-order byte of the wStatus word.

Return Code	Explanation
1	Advise has not started yet.
9	A system error occurred.

## Terminate Session Conversation

3270	5250	VT
Yes	Yes	Yes

The **Terminate Session Conversation** function disconnects the client from the Personal Communications session the client has previously started a conversation with.

The client sends the following command to terminate a session conversation.

```
SendMessage( hServerWnd,
            WM_DDE_TERMINATE,
            hClientWnd,
            0 );
```

## Personal Communications Response

Personal Communications acknowledges the terminate command with a terminate message:

```
WM_DDE_TERMINATE
```

## Terminate Structured Field Conversation

3270	5250	VT
Yes	Yes	Yes

The **Terminate Structured Field Conversation** function disconnects the client from a structured field conversation.

The client sends the following command to terminate a structured field conversation.

```
SendMessage( hServerWnd,  
             WM_DDE_TERMINATE,  
             hClientWnd,  
             0 );
```

### PC/3270 Response

PC/3270 acknowledges the terminate command with a terminate message:

WM\_DDE\_TERMINATE

## Terminate System Conversation

3270	5250	VT
Yes	Yes	Yes

This disconnects the client from a system conversation.

The client sends the following command to terminate a system conversation.

```
SendMessage( hServerWnd,  
             WM_DDE_TERMINATE,  
             hClientWnd,  
             0 );
```

### Personal Communications Response

Personal Communications acknowledges the terminate command with this message:

WM\_DDE\_TERMINATE

When the user closes a Personal Communications session, any global memory blocks that were allocated by Personal Communications will be freed by Windows. This can cause problems for the client if the client retains any of these global memory objects for long periods of time. If the client application needs to keep the information in a global memory item for a long time, it is suggested that the client make a copy of global memory item into a global memory item the client application owns.

## Write SF

3270	5250	VT
Yes	Yes	Yes

The **Write SF** function allows a client application to write structured field data to the host application.

**Note:** The client must call the **Set Structured Field Service Condition** function before invoking the **Write SF** function.

The client sends the following message to write structured field data.

```
PostMessage( hServerWnd,  
            WM_DDE_POKE,  
            hClientWnd,  
            PackDDELPParam(WM_DDE_POKE,  
                           hData, aSF) );
```

where:

**hData** Identifies a handle to a Windows global memory object containing:

```
typedef struct tagWRITESF
{
    unsigned char  poke[(sizeof(DDEPOKE)-1)];
    unsigned short uSFLength;    /* Length of SF data
    unsigned char  Work[8];      /* Work area
    unsigned char  szSFData[1]; /* SF data
} WRITESF;

typedef union tagDDE_WRITESF
{
    DDEPOKE  DDEpoke;
    WRITESF  DDEwritesf;
} DDE_WRITESF, *lpDDE_WRITESF;
```

**aSF** Identifies structured field as the item.

## PC/3270 Response

PC/3270 receives structured field data and sends it to the host application. If the data transmission completes successfully, then PC/3270 returns an ACK message:

```
WM_DDE_ACK(wStatus, aSF)
```

Otherwise PC/3270 returns a negative ACK message containing one of the following return codes in the low-order byte of wStatus:

Return Code	Explanation
2	Length is not valid.
6	The specified format is not valid.
9	A system error occurred.

## DDE Menu Item API in a Windows 32-Bit Environment

Personal Communications supports the addition, deletion, and changing of attributes of a dynamic menu item to the session menu bar. A menu will then be created for this menu item with space for up to 16 submenu items.

Personal Communications supports two kinds of DDE conversation. One is Personal Communications, which acts as a DDE menu client application, and the other is Personal Communications, which acts as a DDE menu server.

### DDE Menu Client in a Windows 32-Bit Environment

To add, delete, and change menu items, the following DDE conversation must take place between the session and DDE menu server application.




Figure 3. DDE Menu Server Conversation

The following data hierarchy details the menu map Personal Communications expects when adding a dynamic menu item and submenu to a session menu bar:

```

POPUP "MyMenu"
BEGIN
  MENUITEM "Send Files to Host", SEND
  MENUITEM "Receive Files from Host", RECEIVE
  MENUITEM SEPARATOR
  MENUITEM "Convert Files", CONVERT
END
  
```

When the user selects a menu item from the new menu, Personal Communications will send a DDE Initiate with 3270MenuN or 5250MenuN as the application and itemN token as the topic. If an ACK is received from the DDE application, Personal Communications will inhibit the session from accepting user input. The menu client application can then display a dialog, and so on. When the menu server application has completed processing of the menu item, it will send a DDE Terminate to signal Personal Communications the process is complete. Personal Communications will then reenableView the window for the user.

### DDE Menu Server in a Windows 32-Bit Environment

To add, delete, and change menu items, the following DDE conversation must take place between the session and a DDE menu client application.




Figure 4. DDE Menu Client Conversation

When the user selects a menu item from the new menu, Personal Communications will send a DDE DATA with aSELECTMENU as the item. When Personal Communications sends DDE DATA to the client application, Personal Communications will inhibit the session from accepting user input. The menu client application can then display a dialog, and so on. When the menu client application has completed processing of the menu item, it will send a DDE ACK to signal Personal Communications the process is complete. Personal Communications will then reenale the window for the user.

## DDE Menu Functions in a Windows 32-Bit Environment

The following table lists the DDE Menu Item API functions that are available for use with Personal Communications and the page in this section where each function is more fully documented. PC/3270 Windows mode and PC400 provide all of the following functions.

Function	Page
Change Menu Item	226
Create Menu Item	232
Initiate Menu Conversation	233
Start Menu Advise	233

Function	Page
Stop Menu Advise	235
Terminate Menu Conversation	235

## Change Menu Item

3270	5250	VT
Yes	Yes	Yes

The **Change Menu Item** function appends, deletes, inserts, modifies, and removes menu items. The client sends the following message to the session to change a menu.

```
PostMessage( hServerWnd,
            WM_DDE_POKE,
            hClientWnd,
            PackDDElParam(WM_DDE_POKE,
                          hData,aCHANGEMENU));
```

where:

### hData

Identifies a handle to a Windows global memory object that contains the requests for changing a menu. The global memory object contains the following structure:

```
typedef struct tagChangeMenu
{
    unsigned char  poke[(sizeof(DDEPOKE)-1)];
    HWND          hMenu; /* Window handle of menu item
    unsigned long  wIDNew; /* Menu ID of new menu item
    unsigned short wPosition; /* The position of menu item
    unsigned short wOperation; /* Specifies the operation
    unsigned short wFlags; /* Specifies the options
    unsigned char  szItemName[1]; /* String of the item
} CHANGEMENU;

typedef union tagDDE_CHANGEMENU
{
    DDEPOKE DDEpoke;
    CHANGEMENU DDEmenu;
} DDE_CHANGEMENU,*lpDDE_CHANGEMENU;
```

The following operations are supported:

```
# MF_APPEND,MF_CHANGE ... MF_BYCOMMANDS are replaced with below commands.
PCS_INSERT      0x0000 /* Inserts a menu item into a menu.
PCS_CHANGE     0x0080 /* Modifies a menu item in a menu.
PCS_APPEND     0x0100 /* Appends a menu item to the end of a menu
PCS_DELETE     0x0200 /* Deletes a menu item from a menu,
                    /* destroying the menu item.
PCS_REMOVE     0x1000 /* Removes a menu item from a menu but
                    /* does not destroy the menu item.

PCS_CHECKED    0x0008 /* Places a checkmark next to the item.
PCS_DISABLED   0x0002 /* Disables the menu item so that it cannot
                    /* be selected, but does not gray it.
PCS_ENABLED    0x0000 /* Enables the menu item so that it can be
                    /* selected and restores from its grayed
                    /* state.
PCS_GRAYED     0x0001 /* Disables the menu item so that it cannot
                    /* be selected, and grays it.
PCS_MENUBARBREAK 0x0020 /* Same as PCS_MENUBREAK except that for
                    /* popup menus, separates the new column
```



PCS_MENUBREAK	0x0040	/* from the old column with a vertical line /* Places the item on a new line for menu /* bar items. For popup menus, places the /* item in a new column, with no dividing /* line between the columns.
PCS_SEPARATOR	0x0800	/* Draws a horizontal dividing line. Can /* only be used in a popup menu. This line /* cannot be grayed, disabled, or /* highlighted. The wIDNew and szItemName /* fields are ignored.
PCS_UNCHAKED	0x0000	/* Does not place a checkmark next to the /* item (default).
PCS_BYCOMMAND	0x0000	/* Specifies that the nPosition parameter /* gives the menu item control ID number. /* This is the default if neither item /* control ID number. This is the default /* if neither PCS_BYCOMMAND nor /* PCS_POSITION is set.
PCS_BYPOSITION	0x0400	/* Specifies that the nPosition parameter /* gives the position of the menu item /* to be deleted rather than an ID number.

If the MF\_APPEND is specified in the wOperation field, the following fields must be filled:

### hMenu

Identifies the menu to be appended. To append a new item to a pop-up menu, specify the handle that is returned from Personal Communications when the **Create Menu Item** function is executed. To append a new item to a top-level menu bar, specify NULL.

### wIDNew

Specifies the command ID of the new menu item. If a new item is added to the top-level menu bar, the handle of the menu item returned from Personal Communications when **Create Menu Item** function is executed.

### wFlags

The following options can be set:

MF_CHECKED	// Places a checkmark next to // the item.
MF_DISABLED	// Disables the menu item so // that it cannot be selected, // but does not gray it.
MF_ENABLED	// Enables the menu item so that // it can be selected and // restores from its grayed // state.
MF_GRAYED	// Disables the menu item so // that it cannot be selected, // and grays it.
MF_MENUBARBREAK	// Same as MF_MENUBREAK except // that for pop-up menus, // separates the new column from // the old column with a // vertical line.
MF_MENUBREAK	// Places the item on a new line // for menu bar items. // For pop-up menus, places the // item in a new column, with // no dividing line between the // columns.

```

MF_SEPARATOR    // Draws a horizontal dividing
                // line. Can only be used in a
                // pop-up menu. This line cannot
                // be grayed, disabled, or
                // highlighted. The wIDNew and
                // szItemName fields are
                // ignored.
MF_UNCHECKED    // Does not place a checkmark
                // next to the item (default).

```

### szItemName

Specifies the contents of the new menu item. Contains a null-terminated character string.

If the MF\_CHANGE is specified in the wOperation field, fill these fields:

### hMenu

Identifies the menu to be changed. To change an item of a pop-up menu, specify the handle that is returned from Personal Communications when the **Create Menu Item** function is executed. To change an item to a top-level menu bar, specify NULL.

### nPosition

Specifies the menu item to be changed. The interpretation of the wPosition parameter depends on the setting of the wFlags parameter.

#### MF\_BYPOSITION

Specifies the position of the existing menu item. The first item in the menu is at position zero.

#### MF\_BYCOMMAND

Specifies the command ID of the existing menu item.

### wIDNew

Specifies the command ID of the menu item. If an item of the top-level menu bar is changed, the handle of the menu item returned from Personal Communications when the **Create Menu Item** function is executed.

### wFlags

The following options can be set:

```

MF_BYCOMMAND    // Specifies that the nPosition
                // parameter gives the menu
                // item control ID number.
                // This is the default if
                // neither MF_BYCOMMAND nor
                // MF_BYPOSITION is set.
MF_BYPOSITION    // Specifies that the nPosition
                // parameter gives the position
                // of the menu item to be
                // changed rather than an ID
                // number.
MF_CHECKED      // Places a checkmark next to
                // the item.
MF_DISABLED     // Disables the menu item so
                // that it cannot be selected,
                // but does not gray it.
MF_ENABLED      // Enables the menu item so
                // that it can be selected and
                // restores from its grayed

```

```

MF_GRAYED           // state.
                    // Disables the menu item so
                    // that it cannot be selected,
                    // and grays it.
MF_MENUBARBREAK    // Same as MF_MENUBREAK except
                    // that for pop-up menus,
                    // separates the new column
                    // from the old column with a
                    // vertical line.
MF_MENUBREAK       // Places the item on a new
                    // line for menu bar items.
                    // For pop-up menus, places the
                    // item in a new column, with
                    // no dividing line between
                    // the columns.
MF_SEPARATOR       // Draws a horizontal dividing
                    // line. Can only be used in
                    // a pop-up menu. This line
                    // cannot be grayed, disabled,
                    // or highlighted. The wIDNew
                    // and szItemName fields are
                    // ignored.
MF_UNCHECKED       // Does not place a checkmark
                    // next to the item (default).

```

### szItemName

Specifies the contents of the menu item. Contains a null-terminated character string.

If the MF\_DELETE is specified in the wOperation field, fill these fields:

### hMenu

Identifies the menu to be deleted. To delete an item from a pop-up menu, specify the handle that is returned from Personal Communications when the **Create Menu Item**, function is executed. To delete an item from a top-level menu bar, specify NULL.

### nPosition

Specifies the menu item to be deleted. The interpretation of the nPosition parameter depends on the setting of the wFlags parameter.

#### MF\_BYPOSITION

Specifies the position of the existing menu item. The first item in the menu is at position zero.

#### MF\_BYCOMMAND

Specifies the command ID of the existing menu item.

### wFlags

The following options can be set:

```

MF_BYCOMMAND       // Specifies that the nPosition
                    // parameter gives the menu
                    // item control ID number.
                    // This is the default if
                    // neither MF_BYCOMMAND nor
                    // MF_BYPOSITION is set.
MF_BYPOSITION      // Specifies that the nPosition
                    // parameter gives the position
                    // of the menu item to be
                    // deleted rather than an ID
                    // number.

```

If the MF\_INSERT is specified in the wOperation field, the following fields must be filled:

### **hMenu**

Identifies the menu to be inserted. To insert an item to a pop-up menu, specify the handle that is returned from Personal Communications when the **Create Menu Item** function is executed. To change an item to a top-level menu bar, specify NULL.

### **nPosition**

Specifies the menu item before the new menu item is to be inserted. The interpretation of the nPosition parameter depends on the setting of the wFlags parameter.

#### **MF\_BYPOSITION**

Specifies the position of the existing menu item. The first item in the menu is at position zero.

#### **MF\_BYCOMMAND**

Specifies the command ID of the existing menu item.

### **wIDNew**

Specifies the command ID of the menu item or, if an item of the top-level menu bar is changed, the handle of the menu item returned from Personal Communications when the **Create Menu Item** function is executed.

### **wFlags**

The following options can be set:

```
MF_BYCOMMAND           // Specifies that the nPosition
                        // parameter gives the menu
                        // item control ID number. This
                        // is the default if neither
                        // MF_BYCOMMAND nor MF_BYPOSITION
                        // is set.
MF_BYPOSITION          // Specifies that the nPosition
                        // parameter gives the position
                        // of the menu item to be
                        // changed rather than an ID
                        // number.
MF_CHECKED             // Places a checkmark next to
                        // the item.
MF_DISABLED            // Disables the menu item so
                        // that it cannot be selected,
                        // but does not gray it.
MF_ENABLED             // Enables the menu item so
                        // that it can be selected and
                        // restores from its grayed
                        // state.
MF_GRAYED              // Disables the menu item so
                        // that it cannot be selected,
                        // and grays it.
MF_MENUBARBREAK       // Same as MF_MENUBREAK except
                        // that for pop-up menus,
                        // separates the new column
                        // from the old column with a
                        // vertical line.
MF_MENUBREAK          // Places the item on a new
                        // line for menu bar items.
                        // For pop-up menus, places the
                        // item in a new column, with
                        // no dividing line between the
```

```

MF_SEPARATOR           // columns.
                       // Draws a horizontal dividing
                       // line. Can only be used in
                       // a pop-up menu. This line
                       // cannot be grayed, disabled,
                       // or highlighted. The wIDNew
                       // and szItemName fields are
                       // ignored.
MF_UNCHECKED           // Does not place a checkmark
                       // next to the item (default).

```

### szItemName

Specifies the contents of the menu item. Contains a null-terminated character string.

If the MF\_REMOVE is specified in the wOperation field, the following fields must be filled:

### hMenu

Identifies the menu to be removed. To remove an item from a pop-up menu, specify the handle that is returned from Personal Communications when the **Create Menu Item** function is executed. To remove an item from a top-level menu bar, specify NULL.

### nPosition

Specifies the menu item to be removed. The interpretation of the nPosition parameter depends upon the setting of the wFlags parameter.

#### MF\_BYPOSITION

Specifies the position of the existing menu item. The first item in the menu is at position zero.

#### MF\_BYCOMMAND

Specifies the command ID of the existing menu item.

### wFlags

The following options can be set:

```

MF_BYCOMMAND           // Specifies that the nPosition
                       // parameter gives the menu
                       // item control ID number.
                       // This is the default if
                       // neither MF_BYCOMMAND nor
                       // MF_BYPOSITION is set.
MF_BYPOSITION          // Specifies that the nPosition
                       // parameter gives the
                       // position of the menu item to
                       // be removed rather than an ID
                       // number.

```

**Personal Communications Response:** Personal Communications receives the requests to change a menu and processes them. If the requests cannot be accepted, Personal Communications returns a negative ACK message containing one of the following status codes in the low-order byte of the wStatus word. Otherwise, Personal Communications returns a positive ACK message signalling that the keystrokes have been sent.

```
WM_DDE_ACK(wStatus,aCHANGEMENU)
```

Return code	Explanation
1	The specified parameters are not valid.
6	The specified format is not valid.
9	A system error occurred.

## Create Menu Item

3270	5250	VT
Yes	Yes	Yes

The **Create Menu Item** function requests Personal Communications to add a menu item to the menu bar. A pop-up menu will be created at the same time, but it is initially empty and can be filled with menu items by using this function. The string of the new menu item that will be added to a top-level menu bar, is also specified by using the **Change Menu Item** function.

The client sends the following message to create a menu item.

```
PostMessage( hServerWnd,
            WM_DDE_REQUEST,
            hClientWnd,
            MAKELPARAM(cfFormat,aCREATEMENU));
```

where:

### cfFormat

Identifies the format for the ID of the new menu item. The valid value is CF\_DSPTEXT.

### aCREATEMENU

Identifies the create menu item.

**Personal Communications Response:** Personal Communications returns the handle of the newly created menu item in a DDE data message if the Personal Communications can create a menu item.

```
WM_DDE_DATA(hData,aCREATEMENU)
```

where:

### hData

Identifies a handle to a windows global memory object that contains the handle of the menu item. The global memory object contains the following structure:

```
typedef struct tagCreateMenu
{
    unsigned char    data[(sizeof(DDEDATA)-1)];
    HWND             hMenuItem;    /* Handle of the menu item
} CREATEMENU;

typedef union tagDDE_CREATEMENU
{
    DDEDATA         DDEdata;
    CREATEMENU      DDEmenu;
} DDE_CREATEMENU,*lpDDE_CREATEMENU;
```

or

```
WM_DDE_ACK(wStatus,aCREATEMENU)
```

If Personal Communications cannot create a menu item, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
6	The specified format is not valid.
9	A system error occurred.

### Initiate Menu Conversation

3270	5250	VT
Yes	Yes	Yes

The **Initiate Menu Conversation** function connects a client application to an available session of Personal Communications. Once a menu conversation is established, the session menu is reserved exclusively for the client until the conversation is terminated.

The client application sends the following message to initiate a DDE conversation with a menu:

```
SendMessage( -1,
             WM_DDE_INITIATE,
             hClientWnd,
             MAKELPARAM(aIBM327032,SN));
```

where:

#### aIBM327032

Identifies the application atom. The string used to create atom aIBM327032 is IBM327032. In the PC400, the application atom is aIBM525032 and the string IBM525032 is used to create it.

#### SN

Identifies the topic atom. The string used to create atom a3270MenuSN is 3270MenuS appended with the session ID A, B, ..., Z. In the PC400, the topic atom is a5250MenuSN and the string 5250MenuS appended with the session ID A, B, ..., Z. is used to create it.

**Personal Communications Response:** If Personal Communications can support a conversation with the client application, Personal Communications acknowledges the INITIATE transaction with:

```
WM_DDE_ACK(aIBM327032,SN)
```

### Start Menu Advise

3270	5250	VT
Yes	Yes	Yes

The **Start Menu Advise** function allows a client application to process a user defined routine when the menu item that is added by the client application, is selected. After using this function, the client receives DATA messages indicating which menu item is selected.

The client sends the following command to begin a menu advise.

```
PostMessage( hServerWnd,
            WM_DDE_ADVISE,
            hClientWnd,
            PackDDE1Param(WM_DDE_ADVISE,
                          hOptions,aSELECTMENU));
```

where:

### hOptions

Is a handle to a Windows global memory object with the following structure:

```
typedef struct tagOPTIONS
{
    unsigned reserved:14;        // Reserved
    unsigned fDeferUpd:1;        // Send notification only
                                // (Must be 0)
    unsigned fAckReq:1;          // Client will ACK all notices
                                // (Must be 1)
    WORD    cfFormat;            // Always CF_DSPTEXT
} OPTIONS,FAR *lpOPTIONS;
```

### aSELECTMENU

Identifies a menu advise as the item.

**Personal Communications Response:** Personal Communications receives the **Start Menu Advise** and returns an ACK message if it can start the function. Otherwise, a negative ACK message is returned to the client with one of the following return codes in the low-order byte of the wStatus field.

Return Code	Explanation
1	Menu Advise has been already started.
6	The specified format is not valid.
9	A system error occurred.

```
WM_DDE_ACK(wStatus,aSELECTMENU)
```

Once the menu item (added to the client application) is selected, the client receives DATA messages notifying it which menu item is selected:

```
WM_DDE_DATA(hData,aSELECTMENU)
```

where:

### hData

Identifies a handle to a Windows global memory object containing:

```
typedef struct tagSELECTMENU
{
    unsigned char  data[(sizeof(DDEDATA)-1)];
    unsigned short uIDSelected; /* Command ID of the selected menu item
} SELECTMENU;

typedef union tagDDE_SELECTMENU
{
    DDEDATA    DDEdata;
    SELECTMENU DDEmenu;
} DDE_SELECTMENU,*lpDDE_SELECTMENU;
```

The DATA messages continue until a Stop Menu Advise message is sent to Personal Communications.



## Stop Menu Advise

3270	5250	VT
Yes	Yes	Yes

The **Stop Menu Advise** function ends a client application's ability to process a user-defined routine when the menu item added by the client application is selected. The client sends the following command to perform the **Stop Menu Advise** function.

```
PostMessage( hServerWnd,  
            WM_DDE_UNADVISE,  
            hClientWnd,  
            MAKELPARAM(NULL,aSELECTMENU));
```

where:

### aSELECTMENU

Identifies a menu advise as the item.

**Personal Communications Response:** If Personal Communications can perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing positive status information to the client:

```
WM_DDE_ACK(wStatus,aCLOSE)
```

If Personal Communications cannot perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing negative status information and one of the following return codes in the low-order byte of the wStatus word:

Return Code	Explanation
1	Advise has not started yet.
9	A system error occurred.

## Terminate Menu Conversation

3270	5250	VT
Yes	Yes	Yes

The **Terminate Menu Conversation** function disconnects the client from the Personal Communications session with which a conversation had been previously started.

The client sends the following command to terminate a session conversation:

```
SendMessage( hServerWnd,  
            WM_DDE_TERMINATE,  
            hClientWnd,  
            0 );
```

**Personal Communications Response:** Personal Communications acknowledges the terminate command with this message:

```
WM_DDE_TERMINATE
```

## Summary of DDE Functions in a Windows 32-Bit Environment

The following table lists the DDE functions that can be used with PC/3270 or PC400. The table lists the name of the DDE function, the command the client sends to PC/3270 or PC400, the values that can be used for the variables in the client command, and the server response.

Table 17. DDE Function Summary in a Windows 32-Bit Environment

function name	client command	server response
Initiate System Conversation (system)	SendMessage(-1, WM_DDE_INITIATE, hClientWnd, MAKELPARAM(aIBM327032, aSystem));	LOWORD/HIWORD to unpack WM_DDE_ACK(aIBM327032, aSystem)
Get System Configuration(system)	PostMessage(hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELPARAM(cfFormat, aSYSCON));	UnPackDDE1Param(WM_DDE_DATA, hData, aSYSCON) or UnPackDDE1Param(WM_DDE_ACK, wStatus, aSYSCON)
	cfFormat = CF_TEXT	
Get System Formats(system)	PostMessage(hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELPARAM(cfFormat, aFORMATS));	UnPackDDE1Param(WM_DDE_DATA, hData, aFORMATS) or UnPackDDE1Param(WM_DDE_ACK, wStatus, aFORMATS)
	cfFormat = CF_TEXT	
Get System Status(system)	PostMessage(hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELPARAM(cfFormat, aSTATUS));	UnPackDDE1Param(WM_DDE_DATA, hData, aSTATUS) or UnPackDDE1Param(WM_DDE_ACK, wStatus, aSTATUS)
	cfFormat = CF_TEXT	
Get System SysItems(system)	PostMessage(hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELPARAM(cfFormat, aSYSITEMS));	UnPackDDE1Param(WM_DDE_DATA, hData, aSYSITEMS) or UnPackDDE1Param(WM_DDE_ACK, wStatus, aSYSITEMS)
	cfFormat = CF_TEXT	

Table 17. DDE Function Summary in a Windows 32-Bit Environment (continued)

function name	client command	server response
Get System Topics(system)	<pre>PostMessage(hServerWnd,             WM_DDE_REQUEST,             hClientWnd,             MAKELPARAM(cfFormat,aTOPICS));</pre>	UnPackDDE1Param(WM_DDE_DATA,hData,aTOPICS) or UnPackDDE1Param(WM_DDE_ACK,wStatus,aTOPICS)
	cfFormat = CF_TEXT	
Terminate System Conversation(system)	<pre>SendMessage(hServerWnd,             WM_DDE_TERMINATE,             hClientWnd,             0);</pre>	WM_DDE_TERMINATE
Initiate Session Conversation(session)	<pre>SendMessage(-1,             WM_DDE_INITIATE,             hClientWnd,             MAKELPARAM(aIBM327032,aSessionN));</pre>	LOWORD/HIWORD to unpack WM_DDE_ACK(aIBM327032,aSessionN)
	N = a session letter A through Z.	
Find Field(session)	<pre>PostMessage(hServerWnd,             WM_DDE_REQUEST,             hClientWnd,             MAKELPARAM(cfFormat,aFIELD));</pre>	UnPackDDE1Param(WM_DDE_DATA,hData,aFIELD) or UnPackDDE1Param(WM_DDE_ACK,wStatus,aFIELD)
	cfFormat = CF_DSPTEXT	
Get Keystrokes(session)	<pre>PostMessage(hServerWnd,             WM_DDE_REQUEST,             hClientWnd,             MAKELPARAM(cfFormat,aKEYS));</pre>	UnPackDDE1Param(WM_DDE_DATA,hData,aKEYS) or UnPackDDE1Param(WM_DDE_ACK,wStatus,aKEYS)
	cfFormat = CF_DSPTEXT	
Get Mouse Input(session)	<pre>PostMessage(hServerWnd,             WM_DDE_REQUEST,             hClientWnd,             MAKELPARAM(cfFormat,aMOUSE));</pre>	UnPackDDE1Param(WM_DDE_DATA,hData,aMOUSE) or UnPackDDE1Param(WM_DDE_ACK,wStatus,aMOUSE)
	cfFormat = CF_TEXT   CF_DSPTEXT	

Table 17. DDE Function Summary in a Windows 32-Bit Environment (continued)

function name	client command	server response
Get Number of Close Requests(session)	<pre>PostMessage(hServerWnd,             WM_DDE_REQUEST,             hClientWnd,             MAKELPARAM(cfFormat,aCLOSE));</pre>	UnPackDDElParam(WM_DDE_DATA,hData,aCLOSE) or UnPackDDElParam(WM_DDE_ACK,wStatus,aCLOSE)
	<pre>cfFormat = CF_DSPTTEXT</pre>	
Get Operator Information Area(session)	<pre>PostMessage(hServerWnd,             WM_DDE_REQUEST,             hClientWnd,             MAKELPARAM(cfFormat,aOIA));</pre>	UnPackDDElParam(WM_DDE_DATA,hData,aOIA) or UnPackDDElParam(WM_DDE_ACK,wStatus,aOIA)
	<pre>cfFormat = CF_DSPTTEXT</pre>	
Get Partial Presentation Space(session)	<pre>PostMessage(hServerWnd,             WM_DDE_REQUEST,             hClientWnd,             MAKELPARAM(cfFormat,aEPS));</pre>	UnPackDDElParam(WM_DDE_DATA,hData,aEPS) or UnPackDDElParam(WM_DDE_ACK,wStatus,aEPS)
	<pre>cfFormat = CF_TEXT   CF_DSPTTEXT</pre>	
Get Presentation Space(session)	<pre>PostMessage(hServerWnd,             WM_DDE_REQUEST,             hClientWnd,             MAKELPARAM(cfFormat,aPS));</pre>	UnPackDDElParam(WM_DDE_DATA,hData,aPS) or UnPackDDElParam(WM_DDE_ACK,wStatus,aPS)
	<pre>cfFormat = CF_TEXT   CF_DSPTTEXT</pre>	
Get Session Status(session)	<pre>PostMessage(hServerWnd,             WM_DDE_REQUEST,             hClientWnd,             MAKELPARAM(cfFormat,aSSTAT));</pre>	UnPackDDElParam(WM_DDE_DATA,hData,aSSTAT) or UnPackDDElParam(WM_DDE_ACK,wStatus,aSSTAT)
	<pre>cfFormat = CF_TEXT</pre>	

Table 17. DDE Function Summary in a Windows 32-Bit Environment (continued)

function name	client command	server response
Get Trim Rectangle(session)	PostMessage(hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELPARAM(cfFormat,aTRIMRECT));	UnPackDDElParam(WM_DDE_DATA,hData,aTRIMRECT) or UnPackDDElParam(WM_DDE_ACK,wStatus,aTRIMRECT)
	cfFormat = CF_TEXT	
Put Data to Presentation Space(session)	PostMessage(hServerWnd, WM_DDE_POKE, hClientWnd, PackDDElParam(WM_DDE_POKE, hData,aEPS));	UnPackDDElParam(WM_DDE_ACK,wStatus,aEPS)
	hData = Handle to a global memory object	
Search for String(session)	PostMessage(hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELPARAM(cfFormat,aSTRING));	UnPackDDElParam(WM_DDE_DATA,hData,aSTRING) or UnPackDDElParam(WM_DDE_ACK,wStatus,aSTRING)
	cfFormat = CF_DSPTEXT	
Send Keystrokes(session)	PostMessage(hServerWnd, WM_DDE_POKE, hClientWnd, PackDDElParam(WM_DDE_POKE, hData,aKEYS));	UnPackDDElParam(WM_DDE_ACK,wStatus,aKEYS)
	hData = Handle to a global memory object	
Session Execute Macro(session)	PostMessage(hServerWnd, WM_DDE_EXECUTE, hClientWnd, (LPARAM)hCommands);	UnPackDDElParam(WM_DDE_ACK,wStatus, NULL)
	hCommands = Handle to a global memory object	

Table 17. DDE Function Summary in a Windows 32-Bit Environment (continued)

function name	client command	server response
Set Cursor Position(session)	<pre>PostMessage(hServerWnd,             WM_DDE_POKE,             hClientWnd,             PackDDE1Param(WM_DDE_POKE,                           hData,aSETCURSOR));</pre>	UnPackDDE1Param(WM_DDE_ACK,wStatus,aSETCURSOR)
	hData = Handle to a global memory object	
Set Mouse Intercept Condition(session)	<pre>PostMessage(hServerWnd,             WM_DDE_POKE,             hClientWnd,             PackDDE1Param(WM_DDE_POKE,                           hData,aMOUSE));</pre>	UnPackDDE1Param(WM_DDE_ACK,wStatus,aMOUSE)
	cFormat = CF_TEXT   CF_DSPTXT hData = Handle to a global memory object	
Set Presentation Space Service Condition(session)	<pre>PostMessage(hServerWnd,             WM_DDE_POKE,             hClientWnd,             PackDDE1Param(WM_DDE_POKE,                           hData,aEPSCOND));</pre>	UnPackDDE1Param(WM_DDE_ACK,wStatus,aEPSCOND)
	hData = Handle to a global memory object	
Set Session Advise Condition(session)	<pre>PostMessage(hServerWnd,             WM_DDE_POKE,             hClientWnd,             PackDDE1Param(WM_DDE_POKE,                           hData,aPSCOND));</pre>	UnPackDDE1Param(WM_DDE_ACK,wStatus,aPSCOND)
	hData = Handle to a global memory object	
Start Close Intercept(session)	<pre>SendMessage(hServerWnd,             WM_DDE_ADVISE,             hClientWnd,             PackDDE1Param(WM_DDE_ADVISE,                           hOptions,aCLOSE));</pre>	UnPackDDE1Param(WM_DDE_ACK,wStatus,aCLOSE) or UnPackDDE1Param(WM_DDE_DATA,hData,aCLOSE)
	hOptions = Handle to a global memory object	

Table 17. DDE Function Summary in a Windows 32-Bit Environment (continued)

function name	client command	server response
Start Keystroke Intercept(session)	SendMessage(hServerWnd, WM_DDE_ADVISE, hClientWnd, PackDDE1Param(WM_DDE_ADVISE, hOptions,aKEYS));	UnPackDDE1Param(WM_DDE_ACK,wStatus,aKEYS) or UnPackDDE1Param(WM_DDE_DATA,hData,aKEYS)
	hOptions = Handle to a global memory object	
Start Mouse Intercept(session)	SendMessage(hServerWnd, WM_DDE_ADVISE, hClientWnd, PackDDE1Param(WM_DDE_ADVISE, hOptions,aMOUSE));	UnPackDDE1Param(WM_DDE_ACK,wStatus,aMOUSE) or UnPackDDE1Param(WM_DDE_DATA,hData,aMOUSE)
	hOptions = Handle to a global memory object	
Start Session Advise(session)	PostMessage(hServerWnd, WM_DDE_ADVISE, hClientWnd, PackDDE1Param(WM_DDE_ADVISE, hOptions,aItem));	UnPackDDE1Param(WM_DDE_ACK,wStatus,aItem) or UnPackDDE1Param(WM_DDE_DATA,hData,aItem)
	hOptions = Handle to a global memory object aItem = OIA   PS   TRIMRECT	
Stop Close Intercept(session)	PostMessage(hServerWnd, WM_DDE_UNADVISE, hClientWnd, MAKELPARAM(NULL,aCLOSE));	UnPackDDE1Param(WM_DDE_ACK,wStatus,aCLOSE)
Stop Keystroke Intercept(session)	PostMessage(hServerWnd, WM_DDE_UNADVISE, hClientWnd, MAKELPARAM(NULL,aKEYS));	UnPackDDE1Param(WM_DDE_ACK,wStatus,aKEYS)
Stop Mouse Input Intercept(session)	PostMessage(hServerWnd, WM_DDE_UNADVISE, hClientWnd, MAKELPARAM(NULL,aMOUSE));	UnPackDDE1Param(WM_DDE_ACK,wStatus,aMOUSE)

Table 17. DDE Function Summary in a Windows 32-Bit Environment (continued)

function name	client command	server response
Stop Session Advise(session)	PostMessage(hServerWnd, WM_DDE_UNADVISE, hClientWnd, MAKELPARAM(NULL,aItem));	UnPackDDEIParam(WM_DDE_ACK,wStatus,aItem)
	aItem = SysItems   Topics   NULL	
Terminate Session Conversation(session)	SendMessage(hServerWnd, WM_DDE_TERMINATE, hClientWnd, 0);	WM_DDE_TERMINATE
Initiate Structured Field Conversation(structured field)	SendMessage(-1, WM_DDE_INITIATE, hClientWnd, MAKELPARAM(aIBM327032,aLUN_xxxx));	LOWORD/HIWORD to unpack WM_DDE_ACK(aIBM327032,aLUN_xxxx)
	N = a session letter A through Z. xxxx = a user defined string.	
Terminate Structured Field Conversation(structured field)	SendMessage(hServerWnd, WM_DDE_TERMINATE, hClientWnd, 0);	WM_DDE_TERMINATE
Set Structured Field Service Condition(structured field)	PostMessage(hServerWnd, WM_DDE_POKE, hClientWnd, PackDDEIParam(WM_DDE_POKE, hData,aSFCOND));	UnPackDDEIParam(WM_DDE_ACK,wStatus,aSFCOND)
	hData = Handle to a global memory object	
Start Read SF(structured field)	PostMessage(hServerWnd, WM_DDE_ADVISE, hClientWnd, PackDDEIParam(WM_DDE_ADVISE, hOptions,aSF));	UnPackDDEIParam(WM_DDE_ACK,wStatus,aSF) or UnPackDDEIParam(WM_DDE_DATA,hData,aSF)
	hOptions = Handle to a global memory object	
Stop Read SF(structured field)	PostMessage(hServerWnd, WM_DDE_UNADVISE, hClientWnd, MAKELPARAM(NULL,aSF));	UnPackDDEIParam(WM_DDE_ACK,wStatus,aSF)



Table 17. DDE Function Summary in a Windows 32-Bit Environment (continued)

function name	client command	server response
Write SF(structured field)	<pre>PostMessage(hServerWnd,             WM_DDE_POKE,             hClientWnd,             PackDDE1Param(WM_DDE_POKE,                           hData,aSF));</pre>	UnPackDDE1Param(WM_DDE_ACK,wStatus,aSF)
	hData = Handle to a global memory object	
Initiate Menu Conversation(menu)	<pre>SendMessage(-1,             WM_DDE_INITIATE,             hClientWnd,             MAKELPARAM(aIBM327032,a3270MenuSN));</pre>	LOWORD/HIWORD to unpack WM_DDE_ACK(aIBM327032,a3270MenuSN)
	N = a session letter A through Z	
Change Menu Item(menu)	<pre>PostMessage(hServerWnd,             WM_DDE_POKE,             hClientWnd,             PackDDE1Param(WM_DDE_POKE,                           hData,aCHANGEMENU));</pre>	UnPackDDE1Param(WM_DDE_ACK,wStatus,aCHANGEMENU)
	hData = Handle to a global memory object	
Create Menu Item(menu)	<pre>PostMessage(hServerWnd,             WM_DDE_REQUEST,             hClientWnd,             MAKELPARAM(cfFormat,aCREATEMENU));</pre>	UnPackDDE1Param(WM_DDE_DATA,hData,aCREATEMENU) or UnPackDDE1Param(WM_DDE_ACK,wStatus,aCREATEMENU)
	cfFormat = CF_DSPTTEXT	
Start Menu Advise(menu)	<pre>PostMessage(hServerWnd,             WM_DDE_ADVISE,             hClientWnd,             PackDDE1Param(WM_DDE_ADVISE,                           hOption,aSELECTMENU));</pre>	UnPackDDE1Param(WM_DDE_ACK,wStatus,aSELECTMENU) or UnPackDDE1Param(WM_DDE_DATA,hData,aSELECTMENU)
	hData = Handle to a global memory object	

Table 17. DDE Function Summary in a Windows 32-Bit Environment (continued)

function name	client command	server response
Stop Menu Advise(menu)	PostMessage(hServerWnd, WM_DDE_UNADVISE, hClientWnd, MAKELPARAM(NULL, aSELECTMENU));	UnPackDDElParam(WM_DDE_ACK, wStatus, aCLOSE)
Terminate Menu Conversation(menu)	SendMessage(hServerWnd, WM_DDE_TERMINATE, hClientWnd, 0);	WM_DDE_TERMINATE

## DDE Functions in an OS/2 Environment

Personal Communications provides a dynamic data exchange (DDE) interface that allows applications to exchange data. The exchange of data between two Presentation Manager or Windows applications can be thought of as a conversation between a client and a server. The *client* initiates DDE conversations. The *server* in turn responds to the client. Personal Communications is a DDE server for the open sessions that Personal Communications is managing. For more information about DDE, refer to *IBM OS/2 Technical Library Programming Guide* or the *Microsoft Windows Software Development Kit Guide to Programming*.

**Note:** If you use DDE functions with Visual Basic, see “Chapter 7. Using DDE Functions with a DDE Client Application” on page 325.

Personal Communications for Windows and OS/2 also supports 16-bit DDE applications. See “Appendix G. DDE Functions in a 16-Bit Environment” on page 397 .

## Personal Communications DDE Data Items (OS/2)

IBM OS/2 PM DDE or Microsoft Windows DDE uses a three-level naming scheme to identify data items: application, topic, and item. Table 18 on page 244 describes these levels.

Table 18. Naming Scheme for Data Items (OS/2)

Level	Description	Example
Application	A OS/2 task, a Windows task, or a particular task of an application. In this book, the application is Personal Communications.	IBM3270
Topic	A specific part of an application.	SessionA

Table 18. Naming Scheme for Data Items (OS/2) (continued)

Level	Description	Example
Item	A data object that can be passed in a data exchange. An item is an application-defined data item that conforms to one of the PM or Windows clipboard formats or to a private, application-defined, clipboard format. For more information regarding PM or Windows clipboard formats, refer to the <i>IBM OS/2 Technical Library Programming Guide</i> or the <i>Microsoft Windows Software Development Kit Guide to Programming</i>	PS (presentation space)

Personal Communications support the following application name as PM or Windows DDE server.

Table 19. Application for Personal Communications

Application	Description
IBM3270 IBM5250	S/390 host system connected by 3270 AS/400 host system connected by 5250

The following table lists the topics you can use.

Table 20. Topics for Personal Communications

Topics
<ul style="list-style-type: none"> <li>• System</li> <li>• SessionA, SessionB, ..., SessionZ</li> <li>• LUA_xxxx, LUB_xxxx, ..., LUZ_xxxx</li> </ul>

In PM DDE, ASCII strings are used to identify application names, topic names, and data items. Refer to the *IBM OS/2 Technical Library Programming Guide*.

In Windows DDE, *atoms* identify application names, topic names, and data items. Atoms represent a character string that is reduced to a unique integer value. The character string is added to an atom table, which can be referred to for the value of the string associated with an atom. Atoms are created with the GlobalAddAtom function call. Refer to *Microsoft Windows Software Development Kit Guide to Programming* for more information about how to create and use atoms.

## Using System Topic Data Items

Applications that provide a DDE interface should also provide a special topic SYSTEM. This topic provides a context for items of information that might be of general interest to an application. The SYSTEM topic for Personal Communications contains these associated data items:

Item	Function
<b>Formats</b>	Returns the list of clipboard formats (numbers) that Personal Communications is capable of rendering.
<b>Status</b>	Returns information about the status of each Personal Communications session.
<b>SysCon</b>	Returns the level of Personal Communications support and other system related values.
<b>Systems</b>	Returns the list of data items that are available when connected to the Personal Communications system topic.

Item	Function
<b>Topics</b>	Returns the list of Personal Communications topics that are available.

## Using Session Topic Data Items

For each Session topic, the following data items are supported:

Item	Function
<b>CONV</b>	Converts ASCII to EBCDIC or EBCDIC to ASCII.
<b>CLOSE</b>	Retrieves the window close requests.
<b>EPS</b>	Retrieves the session presentation space with additional data.
<b>EPSCOND</b>	Retrieves the presentation space service condition.
<b>FIELD</b>	Retrieves the field in the presentation space of the session.
<b>KEYS</b>	Retrieves the keystrokes.
<b>MOUSE</b>	Retrieves the mouse input.
<b>OIA</b>	Retrieves the operator information area status line.
<b>PS</b>	Retrieves the session presentation space.
<b>PSCOND</b>	Retrieves the session advise condition.
<b>SSTAT</b>	Retrieves the session status.
<b>STRING</b>	Retrieves the ASCII string data.
<b>TRIMRECT</b>	Retrieves the session presentation space within the current trim rectangle.

## Using LU Topic Data Items (3270 Only)

For each LU topic, the following data items are supported:

Item	Function
<b>SF</b>	Retrieves the destination/origin structured field data.
<b>SFCOND</b>	Retrieves the query reply data.

## DDE Functions

The following table lists the DDE functions that are available for use with Personal Communications, and the page number in this section where more details can be found.

Function	3270	5250	Page
Code Conversion	Yes	Yes	248
Find Field	Yes	Yes	249
Get Keystrokes	Yes	Yes	251
Get Mouse Input	Yes	Yes	253
Get Number of Close Requests	Yes	Yes	256
Get Operator Information Area	Yes	Yes	257
Get Partial Presentation Space	Yes	Yes	258
Get Presentation Space	Yes	Yes	260
Get Session Status	Yes	Yes	262
Get System Configuration	Yes	Yes	264
Get System Formats	Yes	Yes	265
Get System Status	Yes	Yes	266
Get System SysItems	Yes	Yes	267
Get System Topics	Yes	Yes	268
Get Trim Rectangle	Yes	Yes	269
Initiate Session Conversation	Yes	Yes	270
Initiate Structured Field Conversation	Yes	No	271
Initiate System Conversation	Yes	Yes	271
Put Data to Presentation Space	Yes	Yes	272

<b>Function</b>	<b>3270</b>	<b>5250</b>	<b>Page</b>
Search for String	Yes	Yes	273
Send Keystrokes	Yes	Yes	274
Session Execute Macro	Yes	Yes	275
Set Cursor Position	Yes	Yes	282
Set Mouse Intercept Condition	Yes	Yes	283
Set Presentation Space Service Condition	Yes	Yes	286
Set Session Advise Condition	Yes	Yes	287
Set Structured Field Service Condition	Yes	No	288
Start Close Intercept	Yes	Yes	289
Start Keystroke Intercept	Yes	Yes	291
Start Mouse Input Intercept	Yes	Yes	292
Start Read SF	Yes	No	295
Start Session Advise	Yes	Yes	296
Stop Close Intercept	Yes	Yes	297
Stop Keystroke Intercept	Yes	Yes	298
Stop Mouse Input Intercept	Yes	Yes	299
Stop Read SF	Yes	No	300
Stop Session Advise	Yes	Yes	300
Terminate Session Conversation	Yes	Yes	301
Terminate Structured Field Conversation	Yes	No	302
Terminate System Conversation	Yes	Yes	302
Write SF	Yes	No	302

Refer to “Summary of DDE Functions in an OS/2 Environment” on page 315 for a summary of the DDE functions.

## Naming Conventions for Parameters

Most DDE parameter names have local variables. These variables have a prefix that indicates the general type of the parameter, followed by one or more words that describe the content of the parameter. Prefixes presented in this book are:

- a** Atom
- c** Character (a 1-byte value)
- f** Bit flags packed into a 16-bit integer
- h** 32-bit handle
- p** Short (16-bit) pointer
- lp** Long (32-bit) pointer
- w** Short (16-bit) unsigned integer
- u** Unsigned integer
- sz** Null-terminated character string

## Notation for Return Codes

A table of return codes in the Personal Communications response section of each DDE function. The codes of 4–digits are in hexadecimal.

Personal Communications sets the high-order byte of 2–bytes (4–digits), and OS/2 sets the low-order byte.

Although all the low-order bytes set by OS/2 are "00" in return code table, OS/2 can actually set any value in the byte. For return codes from Personal Communications, refer only to the high-order byte.

## Code Conversion

3270	5250
X	X

The Code Conversion function allows a client application to convert ASCII to EBCDIC or EBCDIC to ASCII. The client sends the following message for the field information. The memory for source and target must be allocated from shared memory. Otherwise, access violation occurs.

```
WinDdePostMSG ( h3270Wnd,
                hClientWnd,
                WM_DDE_POKE,
                pddeStruct,
                DDEPM_RETRY | DDEPM_NOFREE);

typedef struct _DESTRUCT
{
    ULONG      cbData;           /* Data length : */
    USHORT     fsStatus;        /* Status : */
    USHORT     usFormat;        /* Data format : Always CF_DSPTXT */
    USHORT     offszItemName;    /* Offset to Item : CONV */
    USHORT     offfabData;       /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;
```

where:

### Data

```
typedef struct tagCONVDATA
{
    char *      hSourceBuffer;   // pointer to global memory object
                                // to store the data to convert
    char *      hTargetBuffer;  // pointer to global memory object
                                // to store converted data
    BYTE        ConvType;       // Conversion type (refer to note below)
    BYTE        ubReserved;     // *** Reserved ***
    unsigned short uSourceLength; // string length (source)
    unsigned short usTargetLength; // string length (target)
    unsigned short usStringLength; // string length (converted)
} CONVDATA, *lpCONVDATA;
```

**Note:** Following are the conversion types that are indicated by ConvType:

**X'01'** ASCII to EBCDIC

**X'02'** EBCDIC to ASCII

### ItemName

Identifies the Code Conversion item (CONV).

**Personal Communications Response:** Personal Communications converts ASCII to EBCDIC or EBCDIC to ASCII. If Personal Communications cannot convert the data, a DDE ACK message is returned with an error code in the high-order byte of the fsStatus word:

Return Code	Explanation
0000	Normal end. The latest converted code is SBCS.

0200	An incorrect conversion type or incorrect parameter was specified.
0600	An incorrect format was specified.
0900	A system error occurred.
1000	The destination buffer was exceeded.
1100	An internal translation error occurred.

## Find Field

3270	5250
Yes	Yes

The **Find Field** function returns information about the specified field to the client.

Send the message as follows:

```
WinPostMessage(h3270Wnd,
               hClientWnd,
               WM_DDE_REQUEST,
               pddeStruct,
               DDEPM_RETRY);

typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length           */
    USHORT fsStatus;       /* Status                */
    USHORT usFormat;       /* Data format:CF_TEXT or CF_DSPTEXT */
    USHORT offszItemName; /* Offset to Item : FIELD */
    USHORT offabData;     /* Offset to data : unused */
} DDESTRUCT, *pddeStruct;
```

where:

### usFormat

Identifies the format for the field information. This value can be either CF\_DSPTEXT or CF\_TEXT.

### ItemName

Is the atom that specifies the **Find Field**function. The string identified by the atom can have different values depending on the value of **usFormat**.

## CF\_DSPTEXT

If **CF\_DSPTEXT** is specified for **usFormat**then **ItemName**must be the string FIELD. The PS position must be specified in a previous call to the **Set Presentation Space Service Condition**function. This version will return information only about the field which contains that position. The information will be returned in a WM\_DDE\_DATA message where:

```
typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length ;           */
    USHORT fsStatus;       /* Status : 0x0011         */
    USHORT usFormat;       /* Data format :CF_DSPTEXT */
    USHORT offszItemName; /* Offset to Item : FIELD  */
    USHORT offabData;     /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;

typedef struct tagPSFIELDS
{
    unsigned short uFieldStart; // Field start offset
```

```

    unsigned short uFieldLength; // Field length;
    unsigned char  cAttribute;   // Attribute character
    unsigned char  ubReserved;   // *** Reserved ***
} PSFIELDS, *lpPSFIELDS;

```

## CF\_TEXT

If **CF\_TEXT** is specified for **usFormat** then **ItemName** must be the string, FIELD(pos, "XX") where \_

**pos** Is the PS position

**XX** Is a code representing which field relative to **pos** for which information will be returned. These codes are described below:

Type	Meaning
bb or Tb	The field containing <b>pos</b> .
Pb	The field previous to <b>pos</b> , either protected or unprotected.
PP	The previous protected field to <b>pos</b> .
PU	The previous unprotected field to <b>pos</b> .
Nb	The next field after <b>pos</b> , either protected or unprotected.
NP	The next protected field after <b>pos</b> .
NU	The next unprotected field after <b>pos</b> .

**Note:** The b symbol represents a required blank.

These codes must appear in quotes as demonstrated above. The information will be returned in a WM\_DDE\_DATA message where:

```

typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length ; */
    USHORT fsStatus;       /* Status : 0x0011 */
    USHORT usFormat;       /* Data format :CF_DSPTEXT */
    USHORT offszItemName;  /* Offset to Item : FIELD(pos,"XX") */
    USHORT offfabData;     /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;

```

```

typedef struct tagFINDFIELD_CF_TEXT
{
    BYTE data[offsetof(DDEDATA, Value)];
    BYTE Fielddata[80];
} FINDFIELD_CF_TEXT;

```

```

typedef FINDFIELD_CF_TEXT FAR *LPFINDFIELD_CF_TEXT;

```

## Personal Communications Response

If the function is successful, it will respond with a WM\_DDE\_DATA message with information as described above. If it fails, it will return with a WM\_DDE\_ACK. A result value is returned in the high-order byte of the fsStatus word. The following return codes are valid:

Return Code	Explanation
0x0001	PS position is not valid.
0x0002	PS is unformatted.



Return Code	Explanation
0x0006	The specified format is not valid.
0x0009	A system error occurred.

## Structure of the Field Information

The field information will be returned in the `Fielddata` member of the `FINDFIELD_CF_TEXT` structure as a string in the following format:

3270: "Formatted\t%01d\t%01d\t%01d\t%01d\t%04d\t%04d"		
FA bit 2	Unprotected / Protected	0 or 1
FA bit 3	Alphanumeric / Numeric	0 or 1
FA bit 4–5	Intensity / High / Normal	1, 2 or 3
FA bit 7	Unmodified / Modified	0 or 1
Start Pos	Field Start Position (excluding FA)	
Length	Field Length (excluding FA)	

5250: "Formatted\t%01d\t%01d\t%01d\t%01d\t%01d\t%01d\t%04d\t%04d"		
FA bit 0	Field Attribute Flag	0 or 1
FA bit 1	Invisible / Visible	0 or 1
FA bit 2	Unprotected / Protected	0 or 1
FA bit 3	Intensity Low/High	0 or 1
FA bit 4–6	Field Type 0 = Alphanumeric 1 = Alphabetic 2 = Numeric Shift 3 = Numeric 4 = Default 5 = Digits only 6 = Mag-Stripe Reader Data 7 = Signed Numeric	0 — 7
FA bit 7	Unmodified / Modified	0 or 1
Start Pos	Field Start Position (excluding FA)	
Length	Field Length (excluding FA)	

**Note:** FA = Field Attribute

## Get Keystrokes

3270	5250
Yes	Yes

The **Get Keystrokes** function returns to the client the keystrokes that are intercepted by the **Start Keystroke Intercept** function. The client sends the following message to receive the keystroke information.

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_REQUEST,
```

```

        pddeStruct,
        DDEPM_RETRY);

typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length : 0          */
    USHORT fsStatus;       /* Status :                 */
    USHORT usFormat;       /* Data format : Always CF_DSPTXT */
    USHORT offszItemName;  /* Offset to Item : KEYS    */
    USHORT offabData;      /* Offset to data : unused   */
} DDESTRUCT, *pddeStruct;

```

where:

#### **usFormat**

Identifies the format for the keystroke information. This must be CF\_DSPTXT.

#### **ItemName**

Identifies a keystroke data item (KEYS).

## **Personal Communications Response**

Personal Communications either returns the keystrokes in a DDE data message, or responds with one of these ACK messages containing status information:

- WM\_DDE\_DATA
- WM\_DDE\_ACK

If Personal Communications cannot return the keystroke information, one of the following status codes is returned in the high-order byte of the fsStatus word:

Return Code	Explanation
0200	No keystroke was intercepted.
0600	The specified format is not valid.
0900	A system error occurred.

## **Structure of the Keystroke Information**

Personal Communications returns the keystroke information in the following structure:

```

typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length : 0          */
    USHORT fsStatus;       /* Status :                 */
    USHORT usFormat;       /* Data format : Always CF_DSPTXT */
    USHORT offszItemName;  /* Offset to Item : KEYS    */
    USHORT offabData;      /* Offset to data : unused   */
} DDESTRUCT, *pddeStruct;

typedef struct tagKEYSTROKE
{
    unsigned short uTextType; // Type of keystrokes
    unsigned char szKeyData[1]; // Keystrokes
} KEYSTROKE, *lpKEYSTROKE;

```

The format for the keystrokes parameters is the same as for the **Session Execute Macro** function SENDKEY command.

The following key text types are supported:

```

PCS_PURETEXT 0      /* Pure text, no HLLAPI commands
PCS_HLLAPITEXT 1    /* Text, including HLLAPI tokens

```

## Get Mouse Input

3270	5250
Yes	Yes

The **Get Mouse Input** function returns the latest mouse input intercepted by the **Start Mouse Input Intercept** function to the client.

**Note:** The client must call the **Start Mouse Input Intercept** function before using this function.

The client sends the following command to receive the mouse input information.

```

WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_REQUEST,
               pddeStruct,
               DDEPM_RETRY);

typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length : 0          */
    USHORT fsStatus;       /* Status :                */
    USHORT usFormat;       /* Data format : CF_TEXT or CF_DSPTXT */
    USHORT offszItemName;  /* Offset to Item : MOUSE  */
    USHORT offabData;      /* Offset to data : unused  */
} DDESTRUCT, *pddeStruct;

```

where:

### usFormat

Identifies the format for the mouse input data. The format must be CF\_TEXT or CF\_DSPTXT. The structure of the mouse input data, in these two formats, is shown below.

### ItemName

Identifies the mouse item (MOUSE).

## Personal Communications Response

Personal Communications either returns the mouse input data in a DDE data message, or responds with one of these ACK messages:

- WM\_DDE\_DATA
- WM\_DDE\_ACK

If Personal Communications cannot return the mouse input information, one of the following status codes is returned in the high-order byte of the fsStatus word:

Return Code	Explanation
0200	No mouse input information was intercepted.
0600	The specified format is not valid.
0900	A system error occurred.

## Structure of the Mouse Input Information

If the format is CF\_TEXT, Personal Communications returns the mouse input information in the following format:

```
typedef struct tagMOUSE_CF_TEXT
{
    unsigned char PSColPos[4];    /* PS Offset - Mouse position
    unsigned char Tab1[1];        /* Tab character
    unsigned char PSRowPos[4];    /* ROW number of Mouse position
    unsigned char Tab2[1];        /* Tab character
    unsigned char PSColPos[4];    /* Col number of Mouse position
    unsigned char Tab3[1];        /* Tab character
    unsigned char PSSize[4];      /* Size of Presentation Space
    unsigned char Tab4[1];        /* Tab character
    unsigned char PSRows[4];     /* Row number of PS
    unsigned char Tab5[1];        /* Tab character
    unsigned char PSCols[4];     /* Column number of PS
    unsigned char Tab6[1];        /* Tab character
    unsigned char Button[1];     /* Type of clicked mouse button
    unsigned char Tab7[1];        /* Tab character
    unsigned char Click[1];      /* Type of clicking
    unsigned char Tab8[1];        /* Tab character
    unsigned char zClickString[1];/* Retrieved string
} MOUSE_CF_TEXT, *lpMOUSE_CF_TEXT;
```

The following table shows the values in the parameters:

Parameter Name	Meaning	Value
PSColPos	PS offset of the position where the mouse was clicked	0 ... (PSSize - 1)
PSRowPos	Row number of the position where the mouse was clicked	0 ... (PSRows - 1)
PSColPos	Column number of the position where the mouse was clicked	0 ... (PSCols - 1)
PSSize	Size of the presentation space	
PSRows	Number of rows of presentation space	
PSCols	Number of columns of presentation space	
ButtonType	Type of the clicked mouse button	<b>L</b> Left button <b>M</b> Middle button <b>R</b> Right button
ClickType	Type of clicking	<b>S</b> Single click <b>D</b> Double click
zClickString	Retrieved string to which the mouse pointed	A character string terminated with a '\0'
Tab1-8	A tab character for delimiter	'\t'

The following mouse buttons are supported:

```
PCS_MOUSE_TEXT_LEFT 'L' // Left button
PCS_MOUSE_TEXT_RIGHT 'R' // Right button
PCS_MOUSE_TEXT_MIDDLE 'M' // Middle button
```

The following clicks are supported:

```
PCS_MOUSE_TEXT_SINGLE 'S' // Single Click
PCS_MOUSE_TEXT_DOUBLE 'D' // Double Click
```

If the format is CF\_DSPTTEXT, Personal Communications returns the mouse input information in the following format:

```
typedef struct tagMOUSE_CF_DSPTTEXT
{
    unsigned short uPSPos;           /* PS Offset of the Mouse position
    unsigned short uPSRowPos;        /* ROW number of Mouse position
    unsigned short uPSColPos;       /* Column number of Mouse position
    unsigned short uPSSize;         /* Size of Presentation Space
    unsigned short uPSRows;         /* Row number of PS
    unsigned short uPSCols;         /* Column number of PS
    unsigned short uButtonType;     /* Type of clicked mouse button
    unsigned short uClickType;      /* Type of clicking
    unsigned char zClickString[1];  /* Retrieved string
} MOUSE_CF_DSPTTEXT, *lpMOUSE_CF_DSPTTEXT;
```

The following table shows the values in the parameters:

Parameter Name	Meaning	Value
uPSPos	PS offset of the position where the mouse was clicked	0 ... (uPSSize - 1)
uPSRowPos	Row number of the position where the mouse was clicked	0 ... (uPSRows - 1)
uPSColPos	Column number of the position where the mouse was clicked	0 ... (uPSCols - 1)
uPSSize	Size of the presentation space	
uPSRows	Number of rows of the presentation space	
uPSCols	Number of columns of the presentation space	
uButtonType	Type of the clicked mouse button	<b>0x0001</b> Left button <b>0x0002</b> Middle button <b>0x0003</b> Right button
uClickType	Type of clicking	<b>0x0001</b> Single click <b>0x0002</b> Double click
zClickString	Retrieved string that the mouse pointed to	A character string terminated with a '\0'

The following mouse buttons are supported:

```
PCS_MOUSE_LEFT    0x0001 // Left button
PCS_MOUSE_RIGHT   0x0002 // Right button
PCS_MOUSE_MIDDLE  0x0003 // Middle button
```

The following clicks are supported:

```
PCS_MOUSE_SINGLE  0x0001 // Single Click
PCS_MOUSE_DOUBLE  0x0002 // Double Click
```

## Get Number of Close Requests

3270	5250
Yes	Yes

The **Get Number of Close Requests** function returns to the client the number of the close requests that are intercepted by the **Start Close Intercept** function. The client sends the following message to receive the number of the close requests.

```
WinDdePostMsg( h3270Wnd,  
              hClientWnd,  
              WM_DDE_REQUEST,  
              pddeStruct,  
              DDEPM_RETRY);
```

```
typedef struct _DDESTRUCT  
{  
    ULONG cbData;           /* Data length : 0          */  
    USHORT fsStatus;       /* Status :                 */  
    USHORT usFormat;       /* Data format : Always CF_DSPTXT */  
    USHORT offszItemName;  /* Offset to Item : CLOSE   */  
    USHORT offabData;      /* Offset to data : unused  */  
} DDESTRUCT, *pddeStruct;
```

where:

### usFormat

Identifies the format for the close intercept information. This must be CF\_DSPTXT.

### ItemName

Identifies a close intercept data item (CLOSE).

## Personal Communications Response

Personal Communications either returns the number of the close requests in a DDE data message, or responds with one of these ACK messages:

- WM\_DDE\_DATA
- WM\_DDE\_ACK

If Personal Communications cannot return the close intercept information, one of the following status codes is returned in the high order byte of the fsStatus word:

Return Code	Explanation
0600	The specified format is not valid.
0900	A system error occurred.

## Structure of the Number of the Close Requests Information

Personal Communications returns the close intercept information in the following structure:

```
typedef struct _DDESTRUCT  
{  
    ULONG cbData;           /* Data length :           */  
    USHORT fsStatus;       /* Status : 0x0011        */  
    USHORT usFormat;       /* Data format : CF_DSPTXT */  
    USHORT offszItemName;  /* Offset to Item : CLOSE  */  
    USHORT offabData;      /* Offset to data : See the structure*/  
} DDESTRUCT, *pddeStruct;
```

```
typedef struct tagCLOSEREQ
{
    unsigned short uCloseReqCount;    // Number of the close requests.
} CLOSEREQ, *lpCLOSEREQ;
```

## Get Operator Information Area

3270	5250
Yes	Yes

The **Get Operator Information Area** (OIA) function returns a copy of the OIA to the client. The client sends the following message to request the OIA.

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_REQUEST,
               pddeStruct,
               DDEPM_RETRY);
```

```
typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length : 0          */
    USHORT fsStatus;       /* Status :                */
    USHORT usFormat;       /* Data format: Always CF_DSPTEXT */
    USHORT offszItemName;  /* Offset to Item : OIA    */
    USHORT offabData;      /* Offset to data : unused  */
} DDESTRUCT, *pddeStruct;
```

where:

### usFormat

Identifies the format for the OIA. For the OIA, this format must be CF\_DSPTEXT.

### ItemName

Identifies the operator information area as the item (OIA).

## Personal Communications Response

Personal Communications either returns the OIA in a DDE data message, or responds with one of these ACK messages:

- WM\_DDE\_DATA
- WM\_DDE\_ACK

If Personal Communications cannot return the OIA, one of the following status codes is returned in the high-order byte of the fsStatus word:

Return Code	Explanation
0600	The specified format is not valid.
0900	A system error occurred.

## Structure of the Operator Information Area

Personal Communications returns the operator information area in the following structure:

```
typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length :          */
    USHORT fsStatus;       /* Status : 0x0011       */
    USHORT usFormat;       /* Data format : CF_DSPTEXT */
}
```

```

        USHORT offszItemName;    /* Offset to Item : OIA          */
        USHORT offfabData;      /* Offset to data : See the structure */
    } DDESTRUCT, *pddeStruct;

typedef struct tagOIADATA
{
    unsigned char  OIA[80];
} OIADATA, *lpOIADATA;

```

## Get Partial Presentation Space

3270	5250
Yes	Yes

The **Get Partial Presentation Space** function returns all or part of the session presentation space to the client.

**Note:** The client must set the start PS position and either the PS length or End of Field (EOF) flag by using the **Set Presentation Space Service Condition** function before using this function. If the EOF flag is set to PCS\_EFFECTEOF, the function will return the entire field specified by the start PS position

The client sends the following command to get the presentation space:

```

WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_REQUEST,
               pddeStruct,
               DDEPM_RETRY);

```

```

typedef struct _DDESTRUCT
{
    ULONG  cbData;           /* Data length : 0          */
    USHORT fsStatus;        /* Status :                */
    USHORT usFormat;        /* Data format : CF_TEXT or CF_DSPTXT */
    USHORT offszItemName;   /* Offset to Item : EPS     */
    USHORT offfabData;      /* Offset to data : unused  */
} DDESTRUCT, *pddeStruct;

```

where:

### usFormat

Identifies the format for the presentation space. Valid values are CF\_TEXT or CF\_DSPTXT. The structure of the presentation space, in these two formats, is shown below.

### ItemName

Identifies the session presentation space as the item (EPS).

## Personal Communications Response

Personal Communications either returns the presentation space data, or responds with one of these ACK messages containing an error code in the high-order byte of the fsStatus word:

- WM\_DDE\_DATA
- WM\_DDE\_ACK

If Personal Communications cannot return the presentation space, one of the following status codes is returned in the high-order byte of the fsStatus word:



Return Code	Explanation
0100	No prior <b>Set Presentation Space Service Condition</b> function was called, or an incorrect parameter was set.
0600	The specified format is not valid.
0900	A system error occurred.

## Structure of the Presentation Space

Personal Communications returns the part of the presentation space in the format specified in the **Get Partial Presentation Space** request.

If the format is CF\_DSPTTEXT, Personal Communications returns the presentation space in the following format:

```
typedef struct _DDESTRUCT
{
    ULONG    cbData;           /* Data length : */
    USHORT   fsStatus;        /* Status : 0x0011 */
    USHORT   usFormat;        /* Data format : CF_TEXT or CF_DSPTTEXT */
    USHORT   offszItemName;   /* Offset to Item : EPS */
    USHORT   offabData;       /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;

typedef struct tagEPS_CF_DSPTTEXT
{
    unsigned short uPSPosition; /* Position of the part of PS
    unsigned short uPSLength;   /* Length of the part of the PS
    unsigned short uPSRows;     /* PS number of rows
    unsigned short uPSCols;     /* PS number of columns
    unsigned short uPSOffset;   /* Offset to the presentation space
    unsigned short uFieldCount; /* Number of fields
    unsigned short uFieldOffset; /* Offset to the field array
    unsigned char  PSData[1];   /* PS + Field list Array
} EPS_CF_DSPTTEXT, *lpEPS_CF_DSPTTEXT;

typedef struct tagPSFIELDS
{
    unsigned short uFieldStart; /* Field start offset
    unsigned short uFieldLength; /* Field Length
    unsigned char  cAttribute;   /* Attribute character
    unsigned char  ubReserved;   /* *** Reserved ***
} PSFIELDS, *lpPSFIELDS;
```

**Note:** The following examples show how to obtain long pointers to the PS and the PSFIELDS array.

```
lpps = (lp_EPS_CF_DSPTTEXT) lpEPS_CF_DSPTTEXT->PSData
      + lpEPS_CF_DSPTTEXT->uPSOffset;
lppsflds = (lpPSFIELDS) lpEPS_CF_DSPTTEXT->PSData
          + lpEPS_CF_DSPTTEXT->uFieldOffset;
```

If the format is CF\_TEXT, Personal Communications returns the part of the presentation space in the following format:

```
typedef struct tagEPS_CF_TEXT
{
    unsigned char  PSPOSITION[4]; /* Postion of part of the PS
    unsigned char  Tab1[1];       /* Tab character
    unsigned char  PSLENGTH[4];  /* Length of the part of the PS
    unsigned char  Tab2[1];       /* Tab character
    unsigned char  PSROWS[4];    /* Number of rows in the PS
    unsigned char  Tab3[1];       /* Tab character
```

```

    unsigned char  PSCOLS[4];    /* Number of Cols in the PS
    unsigned char  Tab4[1];     /* Tab character
    unsigned char  PS[1];      /* PS
} EPS_CF_TEXT, *lpEPS_CF_TEXT;

```

Following the PS in the buffer is the following additional structure of fields that compose the field list.

```

typedef struct tagFL_CF_TEXT
{
    unsigned char  Tab5[1];     /* Tab character
    unsigned char  PSFldCount[4]; /* Number of fields in the PS
    unsigned char  Tab6[1];     /* Tab character
    PS_FIELD      Field[1];     /* Field List Array
} FL_CF_TEXT, *lpFL_CF_TEXT;

typedef struct tagPS_FIELD
{
    unsigned char  FieldStart[4];
    unsigned char  TabF1[1];
    unsigned char  FieldLength[4];
    unsigned char  TabF2[1];
    unsigned char  Attribute;
    unsigned char  TabF3[1];
} PS_FIELD, *lpPS_FIELD;

```

**Note:** The following examples show how to obtain long pointers to the PS and the PS\_FIELD array.

```

lpPs = lpEPS_CF_TEXT->PS;
lpPs_field = (lpPS_FIELD) lpEPS_CF_TEXT->DDEeps.PS
             + atoi(lpEPS_CF_TEXT->PSLENGTH)
             + ((atoi(lpEPS_CF_TEXT->PSROWS) -1) * 2) // CR/LF
             + 1 + 1 + 4 + 1; // Tabs + size of field count

```

## Get Presentation Space

3270	5250
Yes	Yes

The **Get Presentation Space** function returns the session presentation space to the client. The client sends the following command to get the presentation space.

```

WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_REQUEST,
               pddeStruct,
               DDEPM_RETRY);

```

```

typedef struct _DDESTRUCT
{
    ULONG  cbData;           /* Data length : 0          */
    USHORT fsStatus;        /* Status :                */
    USHORT usFormat;        /* Data format : CF_TEXT or CF_DSPTEXT */
    USHORT offszItemName;   /* Offset to Item : PS     */
    USHORT offabData;       /* Offset to data : unused  */
} DDESTRUCT, *pddeStruct;

```

where:

### usFormat

Identifies the format for the presentation space. Valid values are CF\_TEXT or CF\_DSPTEXT. The structure of the presentation space, in these two formats, is shown below.

### ItemName

Identifies the session presentation space as the item (PS).

## Personal Communications Response

Personal Communications either returns the presentation space and a list of the fields that comprise the presentation space, or responds with one of these ACK messages containing an error code in the high-order byte of the fsStatus word:

- WM\_DDE\_DATA
- WM\_DDE\_ACK

If Personal Communications cannot return the presentation space, one of the following status codes is returned in the high-order byte of the wStatus word:

Return Code	Explanation
0600	The specified format is not valid.
0900	A system error occurred.

## Structure of the Presentation Space

Personal Communications returns the presentation space in the format specified in the **Get Presentation Space** request.

If the format is CF\_DSPTTEXT, Personal Communications returns the presentation space in the following format:

```
typedef struct _DDESTRUCT
{
    ULONG   cbData;           /* Data length : */
    USHORT  fsStatus;        /* Status : 0x0011 */
    USHORT  usFormat;       /* Data format : CF_TEXT or CF_DSPTTEXT */
    USHORT  offszItemName;   /* Offset to Item : PS */
    USHORT  offfabData;      /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;

typedef struct tagPS_CF_DSPTTEXT
{
    unsigned short uPSSize;    /* Size of the presentation space */
    unsigned short uPSRows;   /* PS number of rows */
    unsigned short uPSCols;   /* PS number of columns */
    unsigned short uPSOffset; /* Offset to the presentation space */
    unsigned short uFieldCount; /* Number of fields */
    unsigned short uFieldOffset; /* Offset to the field array */
    unsigned char  PSData[1]; /* PS and Field list Array */
} PS_CF_DSPTTEXT, *lpPS_CF_DSPTTEXT;

typedef struct tagPSFIELDS
{
    unsigned short uFieldStart; /* Field start offset */
    unsigned short uFieldLength; /* Field Length */
    unsigned char  cAttribute; /* Attribute character */
    unsigned char  ubReserved; /* *** Reserved *** */
} PSFIELDS, *lpPSFIELDS;
```

**Note:** The following examples show how to obtain long pointers to the PS and the PSFIELDS array.

```
lpps = (lp_PS_CF_DSPTTEXT) lp_PS_CF_DSPTTEXT->PSData
      + lpPS_CF_DSPTTEXT->uPSOffset;
lppsflds = (lpPSFIELDS) lpPS_CF_DSPTTEXT->PSData
          + lpPS_CF_DSPTTEXT->uFieldOffset;
```

If the format is CF\_TEXT, Personal Communications returns the presentation space in the following format:

```
typedef struct tagPS_CF_TEXT
{
    unsigned char  PSSIZE[4];      /* Size of the PS
    unsigned char  Tab1[1];      /* Tab character
    unsigned char  PSROWS[4];    /* Number of rows in the PS
    unsigned char  Tab2[1];      /* Tab character
    unsigned char  PSCOLS[4];    /* Number of Cols in the PS
    unsigned char  Tab3[1];      /* Tab character
    unsigned char  PS[1];        /* PS
} PS_CF_TEXT, *lpPS_CF_TEXT;
```

Following the PS in the buffer is the following additional structure of fields that compose the field list.

```
typedef struct tagFL_CF_TEXT
{
    unsigned char  Tab5[1];      // Tab character
    unsigned char  PSFldCount[4]; // Number of fields in the PS
    unsigned char  Tab6[1];      // Tab character
    PS_FIELD      Field[1];      // Field List Array
} FL_CF_TEXT, *lpFL_CF_TEXT;
```

```
typedef struct tagPS_FIELD
{
    unsigned char  FieldStart[4];
    unsigned char  TabF1[1];
    unsigned char  FieldLength[4];
    unsigned char  TabF2[1];
    unsigned char  Attribute;
    unsigned char  TabF3[1];
} PS_FIELD, *lpPS_FIELD;
```

**Note:** The following example shows how to obtain long pointers to the PS and the PS\_FIELD array.

```
lpPS = lpPS_CF_TEXT->PS;
lpPS_field = ((lpPS_FIELD) lpPS_CF_TEXT->PS
    + atoi(lpPS_CF_TEXT->PSSIZE)
    + ((atoi(lpPS_CF_TEXT->PSROWS) - 1) * 2) // CR/LF
    + 1 + 1 + 4 + 1; // Tabs + size of field count
```

## Get Session Status

3270	5250
Yes	Yes

The **Get Session Status** function returns the status of the connected session. The client sends the following message to request session status:

```
WinDdePostMsg( h3270Wnd,
    hClientWnd,
    WM_DDE_REQUEST,
    pddeStruct,
    DDEPM_RETRY);
```

```
typedef struct _DDESTRUCT
{
    ULONG  cbData;          /* Data length : 0          */
    USHORT fsStatus;       /* Status :                 */
    USHORT usFormat;       /* Data format : Always CF_TEXT */
    USHORT offszItemName;  /* Offset to Item : SSTAT   */
    USHORT offabData;      /* Offset to data : unused   */
} DDESTRUCT, *pddeStruct;
```

where:

**usFormat**

Identifies the DDE format for the status information. The value used is CF\_TEXT.

**ItemName**

Identifies session status as the data item requested (SSTAT).

### Personal Communications Response

Personal Communications either returns the session status in a DDE data message, or responds with one of these ACK messages containing status information:

- WM\_DDE\_DATA
- WM\_DDE\_ACK

If Personal Communications cannot return the session status, one of the following status codes is returned in the high-order byte of the fsStatus word:

Return Code	Explanation
0600	The specified format is not valid.
0900	A system error occurred.

### Format of Status Information

Personal Communications returns the session status as text in CF\_TEXT format. The following fields are returned with the following possible values:

Fields	Returned Values	Description
Status	Closed, Invisible, Maximized, Minimized, Normal	The window is in one of these states.
Usage	DDE, User	The session is connected in either a DDE session or a user session.
ScreenX	NN	Defines the horizontal size of the screen.
ScreenY	NN	Defines the vertical size of the screen.
CursorX	NN	Defines the horizontal position of the cursor. (0 ... ScreenX - 1)
CursorY	NN	Defines the vertical position of the cursor. (0 ... ScreenY - 1)
TrimRect Status	Closed, Moved, Sized	The current status of the trim rectangle.
Trim Rectangle X1	N	The top-left corner X position of the trim rectangle in character coordinates.
Trim Rectangle Y1	N	The top-left corner Y position of the trim rectangle in character coordinates.
Trim Rectangle X2	N	The lower-right corner X position of the trim rectangle in character coordinates.

Fields	Returned Values	Description
Trim Rectangle Y2	N	The lower-right corner Y position of the trim rectangle in character coordinates.
Session Presentation Space Status	N	The current status of the presentation space. The following values are possible:  <b>0:</b> The presentation space is unlocked.  <b>4:</b> The presentation space is busy.  <b>5:</b> The presentation space is locked.
Session Window Handle	XXXX	Window handle of the session.

**Note:** The status of each field is updated each time the status is requested.

## Get System Configuration

3270	5250
Yes	Yes

The **Get System Configuration** function returns the level of Personal Communications support and other system-related values. Most of this information is for use by a service coordinator when a customer calls the IBM Support Center after receiving a system error.

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_REQUEST,
               pddeStruct,
               DDEPM_RETRY);
```

```
typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length : 0          */
    USHORT fsStatus;       /* Status :                 */
    USHORT usFormat;       /* Data format : Always CF_TEXT */
    USHORT offszItemName;  /* Offset to Item : SysCon   */
    USHORT offabData;      /* Offset to data : unused   */
} DDESTRUCT, *pddeStruct;
```

where:

### usFormat

Identifies the DDE format for the data item requested. The value used is CF\_TEXT.

### ItemName

Identifies system configuration as the data item requested (SysCon).

## Personal Communications Response

Personal Communications either returns the system configuration data item in a DDE DATA message, or responds with one of these ACK messages containing status information:

- WM\_DDE\_DATA
- WM\_DDE\_ACK

If Personal Communications cannot return the system configuration, a DDE ACK message is returned with an error code in the high-order byte of the fsStatus word:

Return Code	Explanation
0900	A system error occurred.

## Format of System Configuration Information

Personal Communications returns the system configuration as text in CF\_TEXT format. The following fields are returned with the following possible values:

Fields	Returned values	Description
Version	N	The version of Personal Communications
Level	NN	The level of Personal Communications
Date	MMDDYY	The date of 3270 or 5250.
System model base number and submodel number	XXXX	The following numbers are examples only: <ul style="list-style-type: none"> <li>• FC04 = PS/2 Model 50</li> <li>• FC05 = PS/2 Model 60</li> <li>• F800 or F801 = PS/2 Model 80</li> </ul> For more information, see the <i>IBM OS/2 Control Programming Reference</i> .
Monitor Type	MONO, CGA, EGA, VGA, XGA	Type of the monitor
Country Code	NNNN	Country code used with 3270 or 5250

## Get System Formats

3270	5250
Yes	Yes

The **Get System Formats** function returns the list of PM/Windows clipboard formats supported by Personal Communications. The client application sends the following message to retrieve the format list supported by Personal Communications:

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_REQUEST,
               pddeStruct,
               DDEPM_RETRY);
```

```
typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length : 0          */
    USHORT fsStatus;       /* Status :                 */
}
```

```

    USHORT usFormat;          /* Data format : Always CF_TEXT      */
    USHORT offszItemName;    /* Offset to Item : Formats          */
    USHORT offabData;        /* Offset to data : unused           */
} DDESTRUCT, *pddeStruct;

```

where:

#### usFormat

Identifies the DDE format for the data item requested. The value used is CF\_TEXT.

#### ItemName

Identifies formats as the data item requested (Formats).

## Personal Communications Response

Personal Communications returns the list of supported PM/Windows clipboard formats in CF\_TEXT format in a DDE DATA message.

WM\_DDE\_DATA

The following PM/Windows clipboard formats are supported by Personal Communications:

```

    CF_TEXT
    CF_DSPTEXT

```

If Personal Communications cannot return the formats data item, a DDE ACK message is returned with an error code in the high-order byte of the fsStatus word:

WM\_DDE\_ACK

Return Code	Explanation
0900	A system error occurred.

## Get System Status

3270	5250
Yes	Yes

The **Get System Status** function returns the status of each 3270 or 5250 session that is available with the current Personal Communications configuration. The client application sends the following message to retrieve the status data item:

```

WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_REQUEST,
               pddeStruct,
               DDEPM_RETRY);

```

```

typedef struct _DDESTRUCT
{
    ULONG cbData;          /* Data length : 0                */
    USHORT fsStatus;      /* Status :                        */
    USHORT usFormat;     /* Data format : Always CF_TEXT   */
    USHORT offszItemName; /* Offset to Item : Status        */
    USHORT offabData;    /* Offset to data : unused        */
} DDESTRUCT, *pddeStruct;

```

where:



**usFormat**

Identifies the DDE format for the data item requested. The value used is CF\_TEXT.

**ItemName**

Identifies status as the data item requested (STATUS).

**Personal Communications Response**

Personal Communications returns the status data item in CF\_TEXT format in a DDE DATA message:

WM\_DDE\_DATA

For each opened session, Personal Communications returns a line of status information. Each line contains a series of fields with the following range of values:

Fields	Range of values	Description
Session ID	A, B, ..., Z	The short ID of the session.
Host Type	370, 400	The host system currently supported by Personal Communications.
Emulation Type	3270, 5250	The emulation type supported by Personal Communications.
Session Status	Closed, Invisible, Normal, Minimized, Maximized	The current status of the session's window.

If Personal Communications cannot return the status data item, a DDE ACK message is returned with an error code in the high-order byte of the fsStatus word:

WM\_DDE\_ACK

Return Code	Explanation
0900	A system error occurred.

**Get System Systems**

3270	5250
Yes	Yes

Personal Communications supports the DDE system topic so that a client application can connect to the system topic and retrieve information about Personal Communications and the status of the sessions that Personal Communications is managing.

The **Get System Systems** function returns the list of data items available in the Personal Communications system topic. The client application sends the following message to get the system topic data items:

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_REQUEST,
               pddeStruct,
               DDEPM_RETRY);
```

```
typedef struct _DDESTRUCT
```

```
{
    ULONG cbData;           /* Data length : 0 */
    USHORT fsStatus;       /* Status : */
}
```

```

    USHORT usFormat;          /* Data format : Always CF_TEXT      */
    USHORT offszItemName;    /* Offset to Item : SysItems        */
    USHORT offabData;        /* Offset to data : unused          */
} DDESTRUCT, *pddeStruct;

```

where:

#### usFormat

Identifies the DDE format for the data item requested. The value used is CF\_TEXT.

#### ItemName

Identifies SysItems as the data item requested (SysItems).

## Personal Communications Response

Personal Communications returns the list of system topic data items in CF\_TEXT format in a DDE DATA message.

WM\_DDE\_DATA

The following data items are supported by Personal Communications:

- Systems
- Topics
- Status
- Formats
- SysCon

If Personal Communications cannot return the system data items, a DDE ACK message is returned with an error code in the high-order byte of the fsStatus word:

WM\_DDE\_ACK

Return Code	Explanation
0900	A system error occurred.

## Get System Topics

3270	5250
Yes	Yes

The Get System Topics function returns the list of active DDE topics currently supported by Personal Communications. The client application sends the following message to the system topic to retrieve the list of topics that are currently active:

```

WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_REQUEST,
               pddeStruct,
               DDEPM_RETRY);

```

```

typedef struct _DDESTRUCT
{
    ULONG cbData;          /* Data length : 0                */
    USHORT fsStatus;      /* Status :                        */
    USHORT usFormat;      /* Data format : Always CF_TEXT   */
    USHORT offszItemName; /* Offset to Item : Topics        */
    USHORT offabData;     /* Offset to data : unused        */
} DDESTRUCT, *pddeStruct;

```

where:

**usFormat**

Identifies the DDE format for the data item requested. The value used is CF\_TEXT.

**aTOPICS**

Identifies topics as the data item requested (Topics).

**Personal Communications Response**

Personal Communications returns the list of DDE topics in CF\_TEXT format in a DDE DATA message.

WM\_DDE\_DATA

The following list of topics are supported by Personal Communications:

- System – System Topic
- SessionA – Session A Topic
- ⋮
- SessionZ – Session Z Topic

**Note:** The actual number of session topics supported depends on the number of sessions currently opened. The client program should always query the topics data item of the system topic to obtain the list of sessions currently opened.

If Personal Communications cannot return the list of topics, a DDE ACK message will be returned with an error code in the high-order byte of the fsStatus word:

WM\_DDE\_ACK

Return Code	Explanation
0900	A system error occurred.

**Get Trim Rectangle**

3270	5250
Yes	Yes

The **Get Trim Rectangle** function returns to the client the area of the presentation space that is within the current trim rectangle. The client sends the following message to receive the trim rectangle.

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_REQUEST,
               pddeStruct,
               DDEPM_RETRY);

typedef struct _DDESTRUCT
{
    ULONG   cbData;           /* Data length : 0           */
    USHORT  fsStatus;        /* Status :                  */
    USHORT  usFormat;        /* Data format : Always CF_TEXT */
    USHORT  offszItemName;   /* Offset to Item : TRIMRECT */
    USHORT  offabData;       /* Offset to data : unused   */
} DDESTRUCT, *pddeStruct;
```

where:

**usFormat**

Identifies the format for the trim rectangle. This is CF\_TEXT.

**ItemName**

Identifies trim rectangle as the data item requested (TRIMRECT).

**Personal Communications Response**

Personal Communications either returns trim rectangle in a DDE data message, or responds with one of these ACK messages:

- WM\_DDE\_DATA
- WM\_DDE\_ACK

If Personal Communications cannot return the trim rectangle, one of the following status codes is returned in the high-order byte of the fsStatus word:

Return Code	Explanation
0600	The specified format is not valid.
0900	A system error occurred.

**Initiate Session Conversation**

3270	5250
Yes	Yes

The **Initiate Session Conversation** function connects a client application to an available session of Personal Communications. Once a session conversation has been established, the session is reserved for exclusive use by the client until the conversation is terminated.

The client application sends the following message to initiate a DDE conversation with a session:

```
WinDdeInitiate( hClientWnd,
                pszAppName,
                pszTopicName,
                pContext);
```

where:

**AppName**

Identifies the application. The string is "IBM3270" in the 3270. In the 5250, it is "IBM5250".

**TopicName**

Identifies the topic. The string is either NULL or "Session" appended with the session ID "A", "B", ..., "Z".

**Personal Communications Response**

If a specific topic is selected and Personal Communications can support a conversation with the client application, Personal Communications acknowledges the INITIATE transaction with:

```
WM_DDE_INITIATEACK
typedef struct _DDEINIT
{
    ULONG cb;                /* Length of structure */
    */
```

```

    PSZ  pszAppName;      /* Application name : IBM3270 or IBM5250 */
    PSZ  pszTopic;       /* Topic : SYSTEM or SessionN */
    ULONG offConvContext; /* Conversation context */
} DDEINIT;

```

If a topic is not selected (TpoicName = NULL), Personal Communications responds by acknowledging all topics that are currently available:

```

WM_DDE_INITIATEACK from System
WM_DDE_INITIATEACK from SessionA
:
WM_DDE_INITIATEACK from SessionZ

```

The client application selects the conversation it wishes to communicate with from the returned list of topics and terminates all other unwanted conversations.

## Initiate Structured Field Conversation

3270	5250
Yes	No

The **Initiate Structured Field Conversation** function connects a client application to send and receive Structured Field data to or from a host application. Multiple clients can connect to one session with multiple connections.

The client sends the following command to initiate a structured field conversation:

```

WinDdeInitiate( hClientWnd,
                pszAppName,
                pszTopicName,
                pContext);

```

Where:

### AppName

Identifies the application. The string is "IBM3270".

### TpoicName

Identifies the topic. The string is "LU" appended with the session ID "A", "B", ..., "Z", then appended with "\_", and then appended with the user-defined string of any length.

## 3270 Response

If 3270 can support a structured field conversation with the client application, it returns an acknowledgment message with the following parameter:

```

WM_DDE_INITIATEACK
typedef struct _DDEINIT
{
    ULONG cb;          /* Length of structure */
    PSZ  pszAppName;   /* Application name : IBM3270 */
    PSZ  pszTopic;     /* Topic : LUN_xxxx */
    ULONG offConvContext; /* Conversation context */
} DDEINIT;

```

## Initiate System Conversation

3270	5250
Yes	No

The **Initiate System Conversation** function connects a client application to the system conversation. Only one client can be connected to the system conversation at a given time. The client sends the following command to initiate a system conversation:

```
WinDdeInitiate( hClientWnd,
                pszAppName,
                pszTopicName,
                pContext);
```

Where:

**AppName**

Identifies the application. The string is "IBM3270" in the 3270. In the 5250, it is "IBM5250".

**TpoicName**

Identifies the topic. The string is "SYSTEM".

**Personal Communications Response**

If Personal Communications can support a system topic conversation with the client application, it returns an acknowledgment message with the following parameters:

```
WM_DDE_INITIATEACK
typedef struct _DDEINIT
{
    ULONG cb; /* Length of structure */
    PSZ pszAppName; /* Application name : IBM3270 or IBM5250 */
    PSZ pszTopic; /* Topic : SYSTEM */
    ULONG offConvContext; /* Conversation context */
} DDEINIT;
```

**Put Data to Presentation Space**

3270	5250
Yes	Yes

The **Put Data to Presentation Space** function sends an ASCIIZ data string to be written into the host presentation space at the location specified by the calling parameter. The client sends the following message to the session to send the string.

```
WinDdePostMsg( h3270Wnd,
                hClientWnd,
                WM_DDE_POKE,
                pddeStruct,
                DDEPM_RETRY);
```

```
typedef struct _DDESTRUCT
{
    ULONG cbData; /* Data length : 0 */
    USHORT fsStatus; /* Status : */
    USHORT usFormat; /* Data format : Always CF_DSPTEXT */
    USHORT offszItemName; /* Offset to Item : Formats */
    USHORT offabData; /* Offset to data : unused */
} DDESTRUCT, *pddeStruct;
```

where:

**Data**

```

typedef struct tagPutString
{
    unsigned short uPSStart;           /* PS Position
    unsigned short uEOFflag;          /* EOF effective switch
    unsigned char  szStringData[1];   /* String Data
} PUTSTRING, *lpPUTSTRING;

```

These values are valid at the uEOFflag field:

```

PCS_EFFECTEOF    0    /* The string is truncated at EOF.
PCS_UNEFFECTEOF  1    /* The string is not truncated at EOF.

```

### ItemName

Identifies the presentation space as the item (EPS).

## Personal Communications Response

Personal Communications receives the string data and sends it to the presentation space, and returns a positive ACK message.

If the presentation space does not accept the string data, Personal Communications returns a negative ACK message containing one of the following status codes in the high-order byte of the fsStatus word:

WM\_DDE\_ACK

Return Code	Explanation
0100	PS position is not valid.
0200	Length is not valid.
0300	The value of EOF flag is not valid.
0500	Input to the target PS was inhibited.
0600	The specified format is not valid.
0700	The string was truncated (successful putting).
0900	A system error occurred.

## Search for String

3270	5250
Yes	Yes

This function allows a client application to examine the presentation space for a specified string in a specified area.

**Note:** The client must set the start PS position, string to be searched for, and either the PS Length and Search Direction or End of Field (EOF) flag by using the **Set Presentation Space Service Condition** function before using this function. If the EOF flag is set to PCS\_EFFECTEOF, the function will search the entire field specified by the Start PS Position parameter.

The client sends the following message to search for the string.

```

WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_REQUEST,
               pddeStruct,
               DDEPM_RETRY);

```

```

typedef struct _DDESTRUCT
{

```

```

    ULONG cbData;          /* Data length : 0          */
    USHORT fsStatus;      /* Status :                */
    USHORT usFormat;      /* Data format : Always CF_DSPTXT */
    USHORT offszItemName; /* Offset to Item : String  */
    USHORT offabData;     /* Offset to data : unused   */
} DDESTRUCT, *pddeStruct;

```

where:

**usFormat**

Identifies the format for the search information. This must be CF\_DSPTXT.

**ItemName**

Identifies the search data item (STRING).

**Personal Communications Response**

Personal Communications returns the start position of the string in a DDE data message if the string was found in the specified area:

- WM\_DDE\_DATA
- WM\_DDE\_ACK

If Personal Communications cannot return the start position of the string, one of the following status codes is returned in the high-order byte of the fsStatus word:

Return Code	Explanation
0100	PS position is not valid or the string is too long.
0200	The string cannot be found.
0600	The specified format is not valid.
0900	A system error occurred.

**Structure of the Search Information**

Personal Communications returns the search information in the following structure:

```

typedef struct _DDESTRUCT
{
    ULONG cbData;          /* Data length :          */
    USHORT fsStatus;      /* Status : 0x0011       */
    USHORT usFormat;      /* Data format : CF_DSPTXT */
    USHORT offszItemName; /* Offset to Item : String  */
    USHORT offabData;     /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;

typedef struct tagSEARCH
{
    unsigned short uFieldStart; /* String start offset */
} SEARCH, *lpSEARCH;

```

**Send Keystrokes**

3270	5250
Yes	Yes

The **Send Keystrokes** function sends keystrokes to the connected session. The client sends the following message to the session to send keystrokes.

```

WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_POKE,
               pddeStruct,

```



```

DDEPM_RETRY);

typedef struct _DDESTRUCT
{
    ULONG   cbData;           /* Data length : */
    USHORT  fsStatus;        /* Status : */
    USHORT  usFormat;        /* Data format : Always CF_DSPTXT */
    USHORT  offszItemName;    /* Offset to Item : KEYS */
    USHORT  offabData;        /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;

```

where:

### Data

```

typedef struct tagKeystrokes
{
    unsigned short uTextType;           /* Type of keystrokes */
    unsigned short uRetryCount;        /* Retry count 1 .. 16 */
    unsigned char  szKeyData[1];       /* Keystrokes */
} KEYSTROKES, *lpKEYSTROKES;

```

The following key text types are supported:

```

PCS_PURETEXT  0    /* Pure text, no AID, or included HLLAPI commands */
PCS_HLLAPITEXT 1   /* Text, including HLLAPI tokens */

```

**Note:** If the keystrokes are pure text, then specifying PCS\_PURETEXT will transfer the keystrokes to the host in the fastest possible manner. If PCS\_HLLAPITEXT is specified, then the keystroke data can contain HLLAPI commands interspersed with the text.

### ItemName

Identifies keystrokes as the item (KEYS).

## Personal Communications Response

Personal Communications receives the keystrokes and sends them to the presentation space. If the presentation space does not accept the keystrokes, a reset is sent to the presentation space and the keystrokes are sent again. This procedure continues until the presentation space accepts the keystrokes or the retry count is reached. If Personal Communications cannot send the keystrokes to the host, Personal Communications returns a negative ACK message containing one of the following status codes in the high-order byte of the fsStatus word. Otherwise, Personal Communications returns a positive ACK message signalling the keystrokes have been sent.

WM\_DDE\_ACK

Return Code	Explanation
0100	Retry count is not valid.
0200	Type of key strokes is not valid.
0600	The specified format is not valid.
0900	A system error occurred.

## Session Execute Macro

3270	5250
Yes	Yes

You can issue commands and macros with the DDE\_EXECUTE function. The DDE\_EXECUTE function passes command strings to Personal Communications. The command strings must conform to DDE specifications. Refer to *IBM OS/2 Technical Library Programming Guide* or the *Microsoft Windows Software Development Kit Guide to Programming* for more information about the DDE command syntax.

The client sends the following command to issue a DDE\_EXECUTE function.

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_EXECUTE,
               pddeStruct,
               DDEPM_RETRY);

typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length : */
    USHORT fsStatus;       /* Status : */
    USHORT usFormat;       /* Data format : */
    USHORT offszItemName;  /* Offset to Item : NULL */
    USHORT offabData;      /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;
```

where:

**Data** Identifies the Personal Communications commands. For a list of commands you can issue, see "Issuing Commands with the Session Execute Macro Function".

## Personal Communications Response

If Personal Communications can process the command string, Personal Communications returns an ACK message containing positive status information to the client. If Personal Communications cannot perform the command string, Personal Communications returns an ACK message containing this error code in the high-order word of the fsStatus word:

Return Code	Explanation
0900	A system error occurred.

## Issuing Commands with the Session Execute Macro Function

You can issue the following commands with the **Session Execute Macro** function:

- KEYBOARD
- RECEIVE
- SEND
- SENDKEY
- WAIT
- WINDOW

Use a separate DDE\_EXECUTE message for each command.

### Note:

- Enclose values that contain nonalphanumeric characters or blanks in double quotation marks ("*value value*").

- To include a double quotation mark within a string, type it twice (for example, "This is a double quotation mark:").
- The maximum length for any command is 255 characters.

## WINDOW Command

[WINDOW(*action* [, "*name*"])]

Performs window actions, where:

```
action = HIDE|RESTORE|MAXIMIZE|MINIMIZE|
          SHOW|CNGNAME
name = LT name or Switch List Entry name
```

**Note:** *name* should be specified when CNGNAME is specified at *action*. If *name* is a NULL string, the default caption will be displayed.

## KEYBOARD Command

[KEYBOARD(*action*)]

Enables or disables the session keyboard, including the mouse, where:

```
action= LOCK|UNLOCK
```

## SEND Command

[SEND("*pcfilename*", "*hostfilename*", "*options*")]

Sends files to the host, where:

```
pcfilename = [path]filename[.ext]
hostfilename =
  For VM system:
    filename filetype[filemode]
  For MVS system:
    [']filename[(membername)][']
  For CICS system:
    filename or *
  For OS/400 system:
    library name filename member name
```

*options* includes any combination of the following file transfer options: MVS, VM, CICS, QUIET, OS/400, and emulation-specific transfer options, separated by spaces.

## RECEIVE Command

[RECEIVE("*pcfilename*", "*hostfilename*", "*options*")]

Receives files from the host, where:

```
pcfilename = [path]filename[.ext]
hostfilename =
  For VM system:
    filename filetype[filemode]
  For MVS system:
    [']filename[(membername)][']
  For CICS system:
    filename or *
  For OS/400 system:
    library name filename member name
```

*options* includes any combination of the following file transfer options: MVS, VM, CICS, QUIET, OS/400, and emulation-specific transfer options, separated by spaces.

## SENDKEY Command

[SENDKEY(*token*,*token*)]

Sends keystrokes to Personal Communications, where:

*token* = *text string*|*command*|*macro macroname*

### Notes:

1.
  - Text strings are enclosed in double quotation marks.
  - Macros are prefixed with “macro”.
  - The argument string for SENDKEY must be 255 characters or fewer.
  - The following commands are supported.

Table 21. SENDKEY Command List

Command Name	Token	3270	5250
Alternate Cursor	alt cursor	Yes	Yes
Alternate Viewing Mode	alt view	Yes	Yes
Attention	sys attn	Yes	Yes
Backspace	backspace	Yes	Yes
Back Tab	backtab	Yes	Yes
Backtab Word	backtab word	Yes	Yes
Character Advance	character advance	No	Yes
Character Backspace	backspace valid	No	Yes
Clear Screen	clear	Yes	Yes
Clicker	click	Yes	Yes
Color Blue	blue	Yes	No
Color Field Inherit	field color	Yes	No
Color Green	green	Yes	No
Color Pink	pink	Yes	No
Color Red	red	Yes	No
Color Turquoise	turquoise	Yes	No
Color White	white	Yes	No
Color Yellow	yellow	Yes	No
Cursor Blink	cursor blink	Yes	Yes
Cursor Down	down	Yes	Yes
Cursor Left	left	Yes	Yes
Cursor Right	right	Yes	Yes
Cursor Select	cursor select	Yes	Yes
Cursor Up	up	Yes	Yes
Delete Character	delete char	Yes	Yes
Delete Word	delete word	Yes	Yes

Table 21. SENDKEY Command List (continued)

Command Name	Token	3270	5250
Device Cancel	device cancel	Yes	Yes
Dup Field	dup	Yes	Yes
Edit Clear	edit-clear	Yes	Yes
Edit Copy	edit-copy	Yes	Yes
Edit Cut	edit-cut	Yes	Yes
Edit Paste	edit-paste	Yes	Yes
Edit Undo	edit-undo	Yes	Yes
End Field	end field	Yes	Yes
Enter	enter	Yes	Yes
Erase EOF	erase eof	Yes	Yes
Erase Field	erase field	Yes	No
Erase Input	erase input	Yes	Yes
Fast Cursor Down	fast down	Yes	Yes
Fast Cursor Left	fast left	Yes	Yes
Fast Cursor Right	fast right	Yes	Yes
Fast Cursor Up	fast up	Yes	Yes
Field Exit	field exit	No	Yes
Field Mark	field mark	Yes	Yes
Field +	field +	No	Yes
Field -	field -	No	Yes
Graphic Cursor	+cr	Yes	No
Help	help	Yes	Yes
Highlighting Field Inherit	field hilight	Yes	No
Highlighting Reverse	reverse	Yes	No
Highlighting Underscore	underscore	Yes	No
Home	home	Yes	Yes
Host Print	host print	No	Yes
Input	input	Yes	Yes
Input nondisplay	input nd	Yes	Yes
Insert Toggle	insert	Yes	Yes
Lower case	to lower	Yes	No
Mark Down	mark down	Yes	Yes
Mark Left	mark left	Yes	Yes
Mark Right	mark right	Yes	Yes
Mark Up	mark up	Yes	Yes
Move Mark Down	move down	Yes	Yes
Move Mark Left	move left	Yes	Yes
Move Mark Right	move right	Yes	Yes
Move Mark Up	move up	Yes	Yes
New Line	newline	Yes	Yes

Table 21. SENDKEY Command List (continued)

Command Name	Token	3270	5250
Next Page	page down	No	Yes
Pause 1 second	pause	Yes	Yes
Previous Page	page up	No	Yes
Print Screen	local copy	Yes	Yes
Program Attention Key 1	pa1	Yes	No
Program Attention Key 2	pa2	Yes	No
Program Attention Key 3	pa3	Yes	No
Program Function Key 1	pf1	Yes	Yes
⋮	⋮	⋮	⋮
Program Function Key 5	pf5	Yes	Yes
Program Function Key 6	pf6	Yes	Yes
⋮	⋮	⋮	⋮
Program Function Key 20	pf20	Yes	Yes
Program Function Key 21	pf21	Yes	Yes
⋮	⋮	⋮	⋮
Program Function Key 24	pf24	Yes	Yes
Quit	quit	Yes	Yes
Reset	reset	Yes	Yes
Response Time Monitor	rtm	Yes	No
Roll Down	roll down	No	Yes
Roll Up	roll up	No	Yes
Rubout	rubout	Yes	Yes
Rule	rule	Yes	Yes
SO/SI Display	so si	Yes	Yes
SO/SI Generate	so si generate	No	Yes
System Request	sys req	Yes	Yes
Tab Field	tab field	Yes	Yes
Tab Word	tab word	Yes	Yes
Test	test request	No	Yes
Unmark	unmark	Yes	Yes
Upper case	to upper	Yes	No
Upper/Lower Change	to other	Yes	No
Wait for bind	wait app	Yes	Yes
Wait for System	wait sys	Yes	Yes
Wait transition	wait trn	Yes	Yes
Wait while input inh.	wait inp inh	Yes	Yes
Window Relocation 1	view 1	Yes	Yes
⋮	⋮	⋮	⋮
Window Relocation 8	view 8	X	X

**Examples:**

1. To logon  
[SENDKEY("Logon")]

2. To get reader list  
[SENDKEY("RDRL", enter)]

## WAIT Command

[WAIT("[*time out*][*wait condition*")]

Waits until the timeout expires or the wait condition the client specified occurs. For this command, the client has to set at least one option, where:

*time out* (optional)

If the client sets a timeout value in the command statements, the following units are available in the wait statement.

- msec
- millisecond
- milliseconds
- sec
- second
- seconds
- minute
- minutes
- hour
- hours

*wait condition* (optional)

For the wait condition option, the client can select the following options:

**while cursor at (cursor row, cursor column)**

While the cursor is at (cursor row, cursor column), it keeps waiting.

**while "string"**

While the "string" is somewhere on the screen, it keeps waiting.

**while "string" at (cursor row, cursor column)**

While the "string" is at (cursor row, cursor column) on the screen, it keeps waiting.

**until cursor at (cursor row, cursor column)**

Until the cursor moves to (cursor row, cursor column), it keeps waiting.

**until "string"**

Until the "string" is displayed somewhere on the screen, it keeps waiting.

**until "string" at (cursor row, cursor column)**

Until the "string" is displayed at (cursor row, cursor column), it keeps waiting.

### Examples:

1. To wait 10 seconds  
[WAIT("10 seconds")]
2. To wait while "ABCDEF" is displayed at (2,9) on the screen  
[WAIT("while ""ABCDEF"" at (2,9)")]
3. To wait until "ABCDEF" is displayed at (2,9) on the screen, or after 8 seconds  
[WAIT("8 seconds until ""ABCDEF"" at (2,9)")]

## Set Cursor Position

3270	5250
Yes	Yes

The **Set Cursor Position** function allows the client application to set the cursor position in the session window.

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_POKE,
               pddeStruct,
               DDEPM_RETRY);
```

```
typedef struct _DDESTRUCT
{
    ULONG   cbData;           /* Data length : */
    USHORT  fsStatus;        /* Status : */
    USHORT  usFormat;        /* Data format : Always CF_DSPTEXT */
    USHORT  offszItemName;   /* Offset to Item : SETCURSOR */
    USHORT  offfabData;      /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;
```

where:

### Data

```
typedef struct tagSETCURSOR
{
    unsigned short uSetCursorType; /* Cursor Set Type
    unsigned short uSetCursor1;   /* Cursor Row or PS Offset
    unsigned short uSetCursor2;   /* Cursor Col
} SETCURSOR, *lpSETCURSOR;
```

Personal Communications supports two ways to set the cursor position:

- PS Offset ( uSetCursorType = 0 )
- Row/Column number ( uSetCursorType = 1 )

The application specifies which method by setting the uSetCursorType field to the appropriate value, followed by setting the two other fields uSetCursor1 and uSetCursor2 to their appropriate values as follows:

- uSetCursorType = 0 offset
  - uSetCursor1: 0 ... (PSsize – 1)
- uSetCursorType = 1 row/col
  - uSetCursor1: 0 ... (PSrows – 1)
  - uSetCursor2: 0 ... (PScols – 1)

### ItemName

Identifies cursor position as the item (SETCURSOR).

## Personal Communications Response

Personal Communications receives the cursor information and moves the cursor to the specified position in the PS. If the cursor is positioned successfully, Personal Communications returns a positive ACK message to the client application.

Otherwise, a negative ACK message is returned with one of the following error codes in the high-order byte of the fsStatus word.

```
WM_DDE_ACK
```



Return Code	Explanation
0100	Cursor set type is not valid. Must be 0 or 1.
0200	Cursor PS offset is not valid. Must be 0 ... (PSsize – 1).
0300	Cursor row value is not valid. Must be 0 ... (PSrows – 1).
0400	Cursor column value is not valid. Must be 0 ... (PScols – 1).
0600	The specified format is not valid.
0900	A system error occurred.

## Set Mouse Intercept Condition

3270	5250
Yes	Yes

This function specifies the mouse input to be intercepted. The client sends the following command to set the mouse event to be intercepted.

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_POKE,
               pddeStruct,
               DDEPM_RETRY);
```

```
typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length : */
    USHORT fsStatus;       /* Status : */
    USHORT usFormat;       /* Data format : CF_TEXT or CF_DSPTEXT*/
    USHORT offszItemName;  /* Offset to Item : MOUSE */
    USHORT offabData;      /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;
```

where:

### usFormat

Identifies the format for the mouse input data. This must be CF\_TEXT or CF\_DSPTEXT.

### ItemName

Identifies the mouse item (MOUSE).

**Data** Specifies the intercepted mouse events in the following structures.

If the format is CF\_TEXT, the client program sends the condition in the following structure:

```
typedef struct tagSETMOUSE_CF_TEXT
{
    unsigned char zMouseCondition[1];
} SETMOUSE_CF_TEXT, *lpSETMOUSE_CF_TEXT;
```

The following table shows the parameters' values:

Parameter Name	Meaning	Value
zMouseCondition	Condition of intercepting the mouse input	<p>A string terminated with '\0', consists of the constants defined as follows in any order:</p> <p><b>L</b> Enable intercepting the left button</p> <p><b>I</b> Disable intercepting the left button</p> <p><b>R</b> Enable intercepting the right button</p> <p><b>r</b> Disable intercepting the right button</p> <p><b>M</b> Enable intercepting the middle button</p> <p><b>m</b> Disable intercepting the middle button</p> <p><b>S</b> Enable intercepting a single click</p> <p><b>s</b> Disable intercepting a single click</p> <p><b>D</b> Enable intercepting a double click</p> <p><b>d</b> Disable intercepting a double click</p> <p><b>T</b> Retrieve the pointed string</p> <p><b>t</b> Do not retrieve the pointed string</p>

The following values are valid at the zMouseCondition:

```

PCS_SETMOUSE_TEXT_LEFTON    'L' // Enable intercepting Left button
PCS_SETMOUSE_TEXT_LEFTOFF  'l' // Disable intercepting Left button
PCS_SETMOUSE_TEXT_RIGHTON   'R' // Enable intercepting Right button
PCS_SETMOUSE_TEXT_RIGHTOFF  'r' // Disable intercepting Right button
PCS_SETMOUSE_TEXT_MIDDLEON  'M' // Enable intercepting Middle button
PCS_SETMOUSE_TEXT_MIDDLEOFF 'm' // Disable intercepting Middle button
PCS_SETMOUSE_TEXT_SINGLEON  'S' // Enable intercepting Single click
PCS_SETMOUSE_TEXT_SINGLEOFF 's' // Disable intercepting Single click
PCS_SETMOUSE_TEXT_DOUBLEON  'D' // Enable intercepting Double click
PCS_SETMOUSE_TEXT_DOUBLEOFF 'd' // Disable intercepting Double click
PCS_SETMOUSE_TEXT_RETSTRON  'T' // Retrieve the pointed string
PCS_SETMOUSE_TEXT_RETSTROFF 't' // Not retrieve the pointed string

```

If the format is CF\_DSPTTEXT, the client program sends the condition in the following structure:

```

typedef struct tagSETMOUSE_CF_DSPTTEXT
{
    BOOL    bLeftButton;    /* Enable intercepting left button
    BOOL    bRightButton;   /* Enable intercepting right button
    BOOL    bMiddleButton;  /* Enable intercepting middle button
    BOOL    bSingleClick;   /* Enable intercepting single click

```

```

        BOOL          bDoubleClick; /* Enable intercepting double click
        BOOL          bRetrieveString; /* Enable intercepting retrieve string
    } SETMOUSE_CF_DSPTEXT, *1SETMOUSE_CF_DSPTEXT;

```

The following table shows the values in the parameters:

Parameter Name	Meaning	Value
bLeftButton	Enable or disable interception of the left mouse button	<b>True</b> Enable intercepting the left button <b>False</b> Disable intercepting the left button
bRightButton	Enable or disable interception of the right mouse button	<b>True</b> Enable intercepting the right button <b>False</b> Disable intercepting the right button
bMiddleButton	Enable or disable interception of the middle mouse button	<b>True</b> Enable intercepting the middle button <b>False</b> Disable intercepting the middle button
bSingleClick	Enable or disable interception of the single click	<b>True</b> Enable intercepting the single click <b>False</b> Disable intercepting the single click
bDoubleClick	Enable or disable interception of the double click	<b>True</b> Enable intercepting the double click <b>False</b> Disable intercepting the double click
bRetrieveString	Retrieve or do not retrieve the pointed string	<b>True</b> Retrieve the pointed string <b>False</b> Do not retrieve the pointed string

## Personal Communications Response

When receiving the **Set Mouse Intercept Condition** request, Personal Communications returns an ACK message if it can set the intercept condition to the specified status. Otherwise, a negative ACK message is returned to the client with one of the following return codes in the high-order byte of the fsStatus field:

WM\_DDE\_ACK

Return Code	Explanation
0200	A character in the Condition parameter is not valid.
0600	The specified format is not valid.
0900	A system error occurred.

## Set Presentation Space Service Condition

3270	5250
Yes	Yes

The **Set Presentation Space Service Condition** function sets the condition for using the following functions:

- **Get Partial Presentation Space**
- **Find Field**
- **Search for String**

By calling this function, the client application sets such condition as:

- **Start PS position**
- **PS length**
- **EOF flag**
- **Search direction**
- **ASCIIZ string**

The client must specify the **Set Presentation Space Service Condition** function before invoking the functions listed above. The conditions set by this function remain in effect until the next **Set Presentation Space Service Condition** function is called. The client sends the following message to set the condition:

```
WinDdePostMsg( h3270Wnd,  
               hClientWnd,  
               WM_DDE_POKE,  
               pddeStruct,  
               DDEPM_RETRY);
```

```
typedef struct _DDESTRUCT  
{  
    ULONG cbData;           /* Data length : */  
    USHORT fsStatus;       /* Status : */  
    USHORT usFormat;      /* Data format : Always CF_DSPTXT */  
    USHORT offszItemName;  /* Offset to Item : EPSCOND */  
    USHORT offabData;     /* Offset to data : See the structure */  
} DDESTRUCT, *pddeStruct;
```

where:

### Data

```
typedef struct tagPSSERVCOND  
{  
    unsigned short uPSStart;           /* PS Position */  
    unsigned short uPSLength;         /* Length of String or PS */  
    unsigned short uSearchDir;       /* Direction for search */  
    unsigned short uEOFflag;         /* EOF effective switch */  
    unsigned char szTargetString[1]; /* Target String */  
} PSSERVCOND, *lpPSSERVCOND;
```

The following values are valid at the uSearchDir field:

```
PCS_SRCHFRWD  0    /* Search forward.  
PCS_SRCHBKWD  1    /* Search backward.
```

The following values are valid for the uEOFflag field:

```
PCS_UNEFFECTEOF 0 /* The PS Area is not truncated at End of Field (EOF).  
PCS_EFFECTEOF   1 /* The PS Area is truncated at End of Field (EOF).
```

If the value of `uEOFflag` is `PCS_EFFECTEOF` then the PS Length and Search Direction are not used.

**ItemName**

Identifies the item for the **Set Presentation Space Service Condition** function (EPSCOND).

**Personal Communications Response**

If Personal Communications can perform the **Set Presentation Space Service Condition** function, then Personal Communications returns an ACK message:

`WM_DDE_ACK`

If Personal Communications cannot perform the Set Presentation Space Service Condition function, then Personal Communications returns a negative ACK message containing the following return codes in the high-order byte of `fsStatus`:

Return Code	Explanation
0100	PS position is not valid.
0200	Length is not valid.
0300	The value of EOF flag is not valid.
0400	The value of Search Direction is not valid.
0600	The specified format is not valid.
0900	A system error occurred.

**Set Session Advise Condition**

<i>3270</i>	<i>5250</i>
<i>Yes</i>	<i>Yes</i>

This function sets the condition for the `DDE_ADVISE` of the **Start Session Advise** function. The client can specify a search string and a region of the screen. When the advise condition is met, the server notifies the client of the condition according to the options specified by the **Start Session Advise** function.

**Note:** The client must specify the **Set Session Advise Condition** function before invoking **Start Session Advise**. If the advise condition is set after the **Start Session Advise** function is started, the advise condition will be ignored and the client will receive a negative ACK message. See “Start Session Advise” on page 296 for more information about starting the advise.

The client sends the following message to set the advise condition.

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_POKE,
               pddeStruct,
               DDEPM_RETRY);

typedef struct _DDESTRUCT
{
    ULONG   cbData;           /* Data length : */
    USHORT  fsStatus;        /* Status : */
    USHORT  usFormat;        /* Data format : Always CF_DSPTXT */
    USHORT  offszItemName;   /* Offset to Item : PSCOND */
    USHORT  offabData;       /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;
```

where:

### Data

```
typedef struct tagSEARCHDATA
{
    unsigned short uPSStart;           /* PS Position of string
    unsigned short uPSLength;         /* Length of String
    BOOL          bCaseSensitive;     /* Case Sensitive TRUE=YES
    unsigned char SearchString[1];    /* Search String
} SEARCHDATA, *lpSEARCHDATA;
```

### ItemName

Identifies the item for the **Set Session Advise Condition** function (PSCOND).

## Personal Communications Response

If Personal Communications can perform the **Set Session Advise Condition** function, Personal Communications returns this ACK message:

WM\_DDE\_ACK

If Personal Communications cannot perform the **Set Session Advise Condition** function, then Personal Communications returns an negative ACK message containing one of the following return codes in the high-order byte of fsStatus:

Return Code	Explanation
0100	Advise is already active.
0200	Advise condition is already active.
0300	PS position is not valid.
0400	String length is not valid.
0600	The specified format is not valid.
0900	A system error occurred.

## Set Structured Field Service Condition

3270	5250
Yes	No

The **Set Structured Field Service Condition** function passes the Query Reply data provided by the client application.

**Note:** The client must call the **Set Structured Field Service Condition** function before invoking the **Start Read SF** function or the **Write SF** function.

The client sends the following message to set the condition.

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_POKE,
               pddeStruct,
               DDEPM_RETRY);
```

```
typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length : */
    USHORT fsStatus;       /* Status : */
}
```

```

    USHORT usFormat;           /* Data format : Always CF_DSPTXT */
    USHORT offszItemName;     /* Offset to Item : SFCOND */
    USHORT offabData;        /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;

```

where:

### Data

```

typedef struct tagSFSEVCOND
{
    unsigned short uBufferLength;           /* Buffer size of Read_SF
    unsigned short uQRLength;              /* Length of Query Reply dat
    unsigned char  szQueryReply[1];        /* Query Reply data
} SFSEVCOND, *lpSFSEVCOND;

```

### ItemName

Identifies the item for the **Set Structured Field Service Condition** function (SFCOND).

## 3270 Response

3270 checks the Query Reply ID and Type (not DOID) and the length. If they are valid, then 3270 returns an ACK message:

```
WM_DDE_ACK
```

If 3270 cannot perform the **Set Structured Field Service Condition** function, then 3270 returns a negative ACK message containing one of the following return codes in the high-order byte of fsStatus:

Return Code	Explanation
0100	PS SF ID is not valid.
0200	Length is not valid.
0300	One DDM base type is already connected to this session.
0400	Structured Field Service Condition is already set.
0600	The specified format is not valid.
0900	A system error occurred.

## Start Close Intercept

3270	5250
Yes	Yes

The **Start Close Intercept** function allows a client application to intercept close requests generated when a user selects the close option from the emulator session window. This function intercepts the close request and discards it until the **Stop Close Intercept** function is requested. After using this function, the client receives DATA messages notifying it that close requests occurred (CLOSE).

The client sends the following command to begin a session advise.

```

WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_ADVISE,
               pddeStruct,
               DDEPM_RETRY);

```

```

typedef struct _DDESTRUCT
{

```

```

    ULONG  cbData;          /* Data length : 0          */
    USHORT fsStatus;       /* Status :                */
    USHORT usFormat;       /* Data format :           */
    USHORT offszItemName;  /* Offset to Item : CLOSE  */
    USHORT offabData;      /* Offset to data : unused */
} DDESTRUCT, *pddeStruct;

```

where:

### fsStatus

If the value of DDE\_FNODATA is 1, DDE Data messages will be sent to the client application with the offabData set to NULL. The client must then issue a DDE REQUEST to request the data item.

If the value of DDE\_FACKREQ is 1, the server does not notify the client of further close requests until the server receives an ACK message from the client in response to any previous notification.

### usFormat

Specifies the format to send the close request.

### ItemName

Identifies close intercept as the item (CLOSE).

## Personal Communications Response

Personal Communications receives the **Start Close Intercept** and returns an ACK message if it can start the intercept. Otherwise a negative ACK message is returned to the client with one of the following return codes in the high-order byte of the fsStatus field:

WM\_DDE\_ACK

Return Code	Explanation
0100	Close Intercept is already working.
0600	The specified format is not valid.
0900	A system error occurred.

Once the intercept starts, the client receives DATA messages notifying it that the close request is intercepted:

WM\_DDE\_DATA

where:

### Data

```

typedef struct _DDESTRUCT
{
    ULONG  cbData;          /* Data length :          */
    USHORT fsStatus;       /* Status : 0x0011       */
    USHORT usFormat;       /* Data format : Always CF_DSPTEXT */
    USHORT offszItemName;  /* Offset to Item : CLOSE  */
    USHORT offabData;      /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;

typedef struct tagCLOSEREQ
{
    unsigned short uCloseReqCount; /* Number of the close requests. */
} CLOSEREQ, *lpCLOSEREQ;

```

The DATA messages continue until a Stop Close Intercept message is sent to Personal Communications.



# Start Keystroke Intercept

3270	5250
Yes	Yes

The Start Keystroke Intercept function allows a client application to filter any keystrokes sent to a session by a terminal operator. After a call to this function, keystrokes are intercepted, and the client receives them (KEYS).

The client sends the following command to begin intercept.

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_ADVISE,
               pddeStruct,
               DDEPM_RETRY);

typedef struct _DDESTRUCT
{
    ULONG   cbData;           /* Data length : 0          */
    USHORT  fsStatus;        /* Status :                */
    USHORT  usFormat;        /* Data format :           */
    USHORT  offszItemName;   /* Offset to Item : KEYS   */
    USHORT  offfabData;      /* Offset to data : unused */
} DDESTRUCT, *pddeStruct;
```

where:

**fsStatus**

If the value of DDE\_FNODEATA is 1, DDE data messages are sent to the client application with the offfabData set to NULL. The client must then issue a DDE REQUEST to request the data item.

If the value of DDE\_FACKREQ is 1, the server does not notify the client of further keystrokes until the server receives an ACK message from the client in response to any previous keystrokes notification.

**usFormat**

Specifies the format to send the keystrokes when the keystroke is sent by a terminal operator. (Must be CF\_DSPTTEXT.)

**ItemName**

Identifies keystrokes as the item (KEYS).

## Personal Communications Response

Personal Communications receives the **Start Keystroke Intercept** and returns an ACK message if it can start the intercept. Otherwise a negative ACK message is returned to the client with one of the following return codes in the high-order byte of the fsStatus field:

WM\_DDE\_ACK

Return Code	Explanation
0100	Keystroke Intercept is already started.
0600	The specified format is not valid.
0900	A system error occurred.

Once the intercept has started, the client receives DATA messages notifying it that the keystroke is intercepted:

WM\_DDE\_DATA

The DATA messages continue until a Stop Keystroke Intercept message is sent to Personal Communications. The format of the data item is the same format as if the client requested the data item via a DDE\_REQUEST.

## Start Mouse Input Intercept

3270	5250
Yes	Yes

The **Start Mouse Input Intercept** function allows a client application to intercept mouse input when a terminal operator presses the mouse button on an emulator session window. After calling this function, the client receives DATA messages that include the PS position where mouse input occurred.

The client sends the following command to begin to intercept the mouse input.

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_ADVISE,
               pddeStruct,
               DDEPM_RETRY);

typedef struct _DDESTRUCT
{
    ULONG   cbData;           /* Data length : 0          */
    USHORT  fsStatus;        /* Status :                */
    USHORT  usFormat;        /* Data format :           */
    USHORT  offszItemName;   /* Offset to Item : MOUSE  */
    USHORT  offabData;       /* Offset to data : unused */
} DDESTRUCT, *pddeStruct;
```

where:

### fsStatus

If the value of DDE\_FNODEATA is 1, DDE Data messages will be sent to the client application with the offabData set to NULL. The client must then issue a DDE REQUEST to request the data item.

If the value of DDE\_FACKREQ is 1, the server does not notify the client of further structured field data until the server receives an ACK message from the client in response to any previous notification.

### usFormat

Specifies the format to send the data item has been updated. It is CF\_TEXT or CF\_DSPTEXT.

### ItemName

Identifies the mouse as the item (MOUSE).

## Personal Communications Response

Personal Communications receives the **Start Mouse Input Intercept** and returns an ACK message if it can start this function. Otherwise a negative ACK message is returned to the client with one of the following return codes in the high-order byte of the fsStatus field:

WM\_DDE\_ACK

Return Code	Explanation
0100	Mouse Input Intercept has been already started.
0600	The specified format is not valid.

Return Code	Explanation
0900	A system error occurred.

Once the **Mouse Input Intercept** starts, the client receives DATA messages of the structured field:

WM\_DDE\_DATA

where:

### Data

If the format is CF\_TEXT, Personal Communications returns the mouse input information in the following format:

```
typedef struct tagMOUSE_CF_TEXT
{
    unsigned char PPos[4];           /* PS Offset - Mouse position
    unsigned char Tab1[1];          /* Tab character
    unsigned char PRowPos[4];       /* ROW number of Mouse position
    unsigned char Tab2[1];          /* Tab character
    unsigned char PColPos[4];       /* Col number of Mouse position
    unsigned char Tab3[1];          /* Tab character
    unsigned char PSSize[4];        /* Size of Presentation Space
    unsigned char Tab4[1];          /* Tab character
    unsigned char PRows[4];         /* Row number of PS
    unsigned char Tab5[1];          /* Tab character
    unsigned char PCols[4];         /* Column number of PS
    unsigned char Tab6[1];          /* Tab character
    unsigned char Button[1];        /* Type of clicked mouse button
    unsigned char Tab7[1];          /* Tab character
    unsigned char Click[1];         /* Type of clicking
    unsigned char Tab8[1];          /* Tab character
    unsigned char zClickString[1]; /* Retrieved string
} MOUSE_CF_TEXT, *lpMOUSE_CF_TEXT;
```

The following table shows the values in the parameters:

Parameter Name	Meaning	Value
PSPos	PS offset of the position where mouse was clicked	0 ... (PSSize - 1)
PSRowPos	Row number of the position where mouse was clicked	0 ... (PRows - 1)
PSColPos	Column number of the position where mouse was clicked	0 ... (PCols - 1)
PSSize	Presentation space size	
PRows	Number of presentation space rows	
PCols	Number of presentation space columns	
ButtonType	Type of clicked mouse button	<b>L</b> Left button <b>M</b> Middle button <b>R</b> Right button
ClickType	Type of clicking	<b>S</b> Single click <b>D</b> Double click

Parameter Name	Meaning	Value
zClickString	Retrieved string to which the mouse pointed	A character string terminated with a '\0'
Tab1-8	A tab character for delimiter	'\t'

The following mouse buttons are supported:

```
PCS_MOUSE_TEXT_LEFT   'L' // Left button
PCS_MOUSE_TEXT_RIGHT  'R' // Right button
PCS_MOUSE_TEXT_MIDDLE 'M' // Middle button
```

The following clicks are supported:

```
PCS_MOUSE_TEXT_SINGLE 'S' // Single Click
PCS_MOUSE_TEXT_DOUBLE 'D' // Double Click
```

If the format is CF\_DSPTTEXT, Personal Communications returns the mouse input information in the following format:

```
typedef struct tagMOUSE_CF_DSPTTEXT
{
    unsigned char data[(sizeof(DDEDATA)-1)];
    unsigned short uPSPos; /* PS Offset - Mouse position
    unsigned short uPSRowPos; /* ROW number - Mouse position
    unsigned short uPSColPos; /* Col number - Mouse position
    unsigned short uPSSize; /* Size of Presentation Space
    unsigned short uPSRows; /* Row number of PS
    unsigned short uPSCols; /* Column number of PS
    unsigned short uButtonType; /* Type of clicked mouse button
    unsigned short uClickType; /* Type of clicking
    unsigned char zClickString[1]; /* Retrieved string
} MOUSE_CF_DSPTTEXT, *lpMOUSE_CF_DSPTTEXT;
```

The following table shows the values in the parameters:

Parameter Name	Meaning	Value
uPSPos	PS offset of the position where the mouse was clicked	0 ... (uPSSize - 1)
uPSRowPos	Row number of the position where the mouse was clicked	0 ... (uPSRows - 1)
uPSColPos	Column number of the position where the mouse was clicked	0 ... (uPSCols - 1)
uPSSize	Size of the presentation space	
uPSRows	Number of rows of the presentation space	
uPSCols	Number of columns of the presentation space	
uButtonType	Type of the clicked mouse button	<b>0x0001</b> Left button <b>0x0002</b> Middle button <b>0x0003</b> Right button
uClickType	Type of clicking	<b>0x0001</b> Single click <b>0x0002</b> Double click

Parameter Name	Meaning	Value
zClickString	Retrieved string to which the mouse pointed	A character string terminated with a '\0'

The following mouse buttons are supported:

```
PCS_MOUSE_LEFT    0x0001 // Left button
PCS_MOUSE_RIGHT   0x0002 // Right button
PCS_MOUSE_MIDDLE  0x0003 // Middle button
```

The following clicks are supported:

```
PCS_MOUSE_SINGLE  0x0001 // Single Click
PCS_MOUSE_DOUBLE  0x0002 // Double Click
```

The DATA messages continue until a Stop Mouse Input Intercept message is sent to Personal Communications.

## Start Read SF

3270	5250
Yes	No

The **Start Read SF** function allows a client application to read structured field data from the host application. After using this function, the client receives DATA messages notifying it that close requests occurred.

**Note:** Before using this function, the client must call the **Set Structured Field Service Condition** function to pass the Query Reply data to the server.

The client sends the following command to begin a Read SF.

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_ADVISE,
               pddeStruct,
               DDEPM_RETRY);

typedef struct _DDESTRUCT
{
    ULONG  cbData;           /* Data length : 0          */
    USHORT fsStatus;        /* Status :                */
    USHORT usFormat;        /* Data format :           */
    USHORT offszItemName;   /* Offset to Item : SF     */
    USHORT offabData;       /* Offset to data : unused */
} DDESTRUCT, *pddeStruct;
```

where:

### fsStatus

If the value of DDE\_FNODATA is 1, DDE Data messages will be sent to the client application with the offabData set to NULL. The client must then issue a DDE REQUEST to request the data item.

If the value of DDE\_FACKREQ is 1, the server does not notify the client of further structured field data until the server receives an ACK message from the client in response to any previous notification.

### usFormat

The cfFormat field specifies the format to send the structured field data. (It must be CF\_DSPTEXT.)

**ItemName**

Identifies structured field as the item (SF).

**3270 Response**

3270 receives the Start Read SF and returns an ACK message if it can start the Read SF. Otherwise a negative ACK message is returned to the client with one of the following return codes in the high-order byte of the fsStatus field:

WM\_DDE\_ACK

Return Code	Explanation
0100	Read SF is already started.
0300	No prior <b>Set Structured Field Service Condition</b> function was called.
0600	The specified format is not valid.
0900	A system error occurred.

Once the Read SF has started, the client receives DATA messages of the structured field:

WM\_DDE\_DATA

where:

**Data**

```
typedef struct tagSFDATA
{
    unsigned short uSFLength;           /* Length of SF data
    unsigned char  szSFData[1];       /* SF data
} SFDATA, *lpSFDATA;
```

The DATA messages continue until a Stop Read SF message is sent to 3270.

**Start Session Advise**

3270	5250
Yes	Yes

The **Start Session Advise** function establishes a link between the Personal Communications session and the client. This lets the client receive updates of the presentation space (PS), the operator information area (OIA), or the trim rectangle (TRIMRECT) when the data item is updated.

**Note:** If the client application needs conditional notification when the presentation space is updated, set an advise condition prior to invoking the advise function for the presentation space. See “Set Session Advise Condition” on page 287 .

The client sends the following command to begin a session advise.

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_ADVISE,
               pddeStruct,
               DDEPM_RETRY);
```

```
typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length : 0 */
    /*
```

```

USHORT fsStatus;          /* Status :          */
USHORT usFormat;         /* Data format :     */
USHORT offszItemName;    /* Offset to Item :  TRIMRECT */
USHORT offfabData;       /* Offset to data :  unused   */
} DDESTRUCT, *pddeStruct;

```

where:

### fsStatus

If the value of DDE\_FNODATA is 1, DDE Data messages are sent to the client application with the hData set to NULL. The client must then issue a DDE REQUEST to request the data item.

If the value of DDE\_FACKREQ is 1, the server does not notify the client of further changes to the data item until the server receives an ACK message from the client in response to any previous update notification.

### usFormat

Specifies the format to send the data item when the item has been updated.

### ItemName

Specifies the item of information being requested; in this case, the value can be PS, OIA, or TRIMRECT.

## Personal Communications Response

Personal Communications receives the Start Session Advise and returns an ACK message if it can start the advise. Otherwise, a negative ACK message is returned to the client with one of the following return codes in the high-order byte of the fsStatus field:

WM\_DDE\_ACK

Return Code	Explanation
0100	Advise already active for data item.
0600	Advise parameter not valid.
0900	A system error occurred.

Once the advise has started, the client receives DATA messages notifying it that the data item (PS, OIA, or TRIMRECT) has changed:

WM\_DDE\_DATA

The DATA messages continue until a Stop Session Advise message is sent to Personal Communications. The format of the data item is the same as if the client requested the data item via a DDE\_REQUEST.

## Stop Close Intercept

3270	5250
Yes	Yes

The **Stop Close Intercept** function ends a client application's ability to intercept close requests. The client sends the following command to perform the **Stop Close Intercept** function.

```

WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_UNADVISE,
               pddeStruct,

```

```

        DDEPM_RETRY);

typedef struct _DDESTRUCT
{
    ULONG   cbData;           /* Data length : 0           */
    USHORT  fsStatus;        /* Status :                  */
    USHORT  usFormat;        /* Data format :            */
    USHORT  offszItemName;   /* Offset to Item : CLOSE   */
    USHORT  offfabData;      /* Offset to data : unused  */
} DDESTRUCT, *pddeStruct;

```

where:

**ItemName**

Identifies close intercept as the item (CLOSE).

**Personal Communications Response**

If Personal Communications can perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing positive status information to the client:

WM\_DDE\_ACK

If Personal Communications cannot perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing negative status information and one of the following return codes in the high-order byte of the fsStatus word:

Return Code	Explanation
0100	Advise has not started yet.
0900	A system error occurred.

**Stop Keystroke Intercept**

3270	5250
Yes	Yes

The **Stop Keystroke Intercept** function ends a client application's ability to intercept keystrokes. The client sends the following command to perform the **Stop Keystroke Intercept** function.

```

WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_UNADVISE,
               pddeStruct,
               DDEPM_RETRY);

typedef struct _DDESTRUCT
{
    ULONG   cbData;           /* Data length : 0           */
    USHORT  fsStatus;        /* Status :                  */
    USHORT  usFormat;        /* Data format :            */
    USHORT  offszItemName;   /* Offset to Item : KEYS    */
    USHORT  offfabData;      /* Offset to data : unused  */
} DDESTRUCT, *pddeStruct;

```

where:

**ItemName**

Identifies keystrokes as the item (KEYS).



## Personal Communications Response

If Personal Communications can perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing positive status information to the client:

WM\_DDE\_ACK

If Personal Communications cannot perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing negative status information and one of the following return codes in the high-order byte of the fsStatus word.

Return Code	Explanation
0100	Advise has not started yet.
0900	A system error occurred.

## Stop Mouse Input Intercept

3270	5250
Yes	Yes

The **Stop Mouse Input Intercept** function ends a client application's ability to intercept mouse input.

The client sends the following command to perform the **Stop Mouse Input Intercept** function.

```
WinDdePostMsg( h3270Wnd,  
              hClientWnd,  
              WM_DDE_UNADVISE,  
              pddeStruct,  
              DDEPM_RETRY);
```

```
typedef struct _DDESTRUCT  
{  
    ULONG cbData;           /* Data length : 0          */  
    USHORT fsStatus;        /* Status :                 */  
    USHORT usFormat;        /* Data format :           */  
    USHORT offszItemName;   /* Offset to Item : MOUSE  */  
    USHORT offfabData;      /* Offset to data : unused  */  
} DDESTRUCT, *pddeStruct;
```

where:

### ItemName

Identifies the mouse as the item (MOUSE).

## Personal Communications Response

If Personal Communications can perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing positive status information to the client:

WM\_DDE\_ACK

If Personal Communications cannot perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing negative status information and one of the following return codes in the high-order byte of the fsStatus word.

Return Code	Explanation
0100	Advise has not started yet.
0900	A system error occurred.

## Stop Read SF

3270	5250
Yes	No

The **Stop Read SF** function ends a client application's ability to read structured field data.

The client sends the following command to perform the **Stop Read SF** function.

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_UNADVISE,
               pddeStruct,
               DDEPM_RETRY);

typedef struct _DDESTRUCT
{
    ULONG   cbData;           /* Data length : 0          */
    USHORT  fsStatus;        /* Status :                */
    USHORT  usFormat;        /* Data format :           */
    USHORT  offszItemName;   /* Offset to Item : SF     */
    USHORT  offfabData;      /* Offset to data : unused */
} DDESTRUCT, *pddeStruct;
```

where:

### ItemName

Identified structured field as the item (SF).

### 3270 response

If 5250 can perform the DDE\_UNADVISE, 3270 returns an ACK message containing positive status information to the client:

WM\_DDE\_ACK

If 3270 cannot perform the DDE\_UNADVISE, 3270 returns an ACK message containing negative status information and one of the following return codes in the high-order byte of the fsStatus word.

Return Code	Explanation
0100	Advise has not started yet.
0900	A system error occurred.

## Stop Session Advise

3270	5250
Yes	Yes

The **Stop Session Advise** function disconnects a link between Personal Communications and the client. The client sends the following command to perform the **Stop Session Advise** function.

```

WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_UNADVISE,
               pddeStruct,
               DDEPM_RETRY);

typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length : 0          */
    USHORT fsStatus;       /* Status :                */
    USHORT usFormat;       /* Data format :           */
    USHORT offszItemName;  /* Offset to Item : PS, OIA, TRIMRECT */
                          /* or NULL                 */
    USHORT offabData;      /* Offset to data : unused  */
} DDESTRUCT, *pddeStruct;

```

where:

### ItemName

Specifies the item of information being requested; in this case, the value can be PS, OIA, TRIMRECT, or NULL.

If the value of *item* is NULL, then the client has requested termination of all active notifications for the conversation.

## Personal Communications Response

If Personal Communications can perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing positive status information to the client:

WM\_DDE\_ACK

If Personal Communications cannot perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing negative status information and one of the following return codes in the high-order byte of the fsStatus word.

Return Code	Explanation
0100	Advise has not started yet.
0900	A system error occurred.

## Terminate Session Conversation

3270	5250
Yes	Yes

The **Terminate Session Conversation** function disconnects the client from the Personal Communications session the client has previously started a conversation with.

The client sends the following command to terminate a session conversation.

```

WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_TERMINATE,
               NULL,
               DDEPM_RETRY);

```

## Personal Communications Response

Personal Communications acknowledges the terminate command with a terminate message:

WM\_DDE\_TERMINATE

## Terminate Structured Field Conversation

3270	5250
Yes	No

The **Terminate Structured Field Conversation** function disconnects the client from a structured field conversation.

The client sends the following command to terminate a structured field conversation.

```
WinDdePostMsg( h3270Wnd,  
               hClientWnd,  
               WM_DDE_TERMINATE,  
               NULL,  
               DDEPM_RETRY);
```

### 3270 Response

3270 acknowledges the terminate command with a terminate message:

WM\_DDE\_TERMINATE

## Terminate System Conversation

3270	5250
Yes	Yes

This disconnects the client from a system conversation.

The client sends the following command to terminate a system conversation.

```
WinDdePostMsg( hServerWnd,  
               WM_DDE_TERMINATE,  
               hClientWnd,  
               MAKELONG(NULL, NULL));
```

## Personal Communications Response

Personal Communications acknowledges the terminate command with this message:

WM\_DDE\_TERMINATE

## Write SF

3270	5250
Yes	No

The **Write SF** function allows a client application to write structured field data to the host application.

**Note:** The client must call the **Set Structured Field Service Condition** function before invoking the **Write SF** function.

The client sends the following message to write structured field data.

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_POKE,
               pddeStruct,
               DDEPM_RETRY);

typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length : */
    USHORT fsStatus;       /* Status : */
    USHORT usFormat;       /* Data format : Always CF_DSPTXT */
    USHORT offszItemName;  /* Offset to Item : SF */
    USHORT offabData;      /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;
```

where:

**Data**

```
typedef struct tagWRITESF
{
    unsigned short uSFLength; /* Length of SF data */
    unsigned char szSFData[1]; /* SF data */
} WRITESF, *lpWRITESF;
```

**ItemName**

Identifies structured field as the item (SF).

**3270 Response**

3270 receives structured field data and sends it to the host application. If the data transmission completes successfully, then 3270 returns an ACK message:

```
WM_DDE_ACK
```

Otherwise 3270 returns an negative ACK message containing one of the following return codes in the high-order byte of fsStatus:

Return Code	Explanation
0200	Length is not valid.
0600	The specified format is not valid.
0900	A system error occurred.

**DDE Menu Item API in OS/2 Environment**

Personal Communications supports the addition, deletion, and changing of attributes of a dynamic menu item to the session menu bar. A menu will then be created for this menu item with space for up to 16 submenu items.

Personal Communications supports two kinds of DDE conversation. One is Personal Communications, which acts as a DDE menu client application, and the other is Personal Communications, which acts as a DDE menu server.

**DDE Menu Client in an OS/2 Environment**

To add, delete, and change menu items, the following DDE conversation must take place between the session and DDE menu server application.




Figure 5. DDE Menu Server Conversation

The following data hierarchy details the menu map Personal Communications expects when adding a dynamic menu item and submenu to a session menu bar:

```

POPUP "MyMenu"
BEGIN
  MENUITEM "Send Files to Host", SEND
  MENUITEM "Receive Files from Host", RECEIVE
  MENUITEM SEPARATOR
  MENUITEM "Convert Files", CONVERT
END
  
```

When the user selects a menu item from the new menu, Personal Communications will send a DDE Initiate with 3270MenuN or 5250MenuN as the application and itemN token as the topic. If an ACK is received from the DDE application, Personal Communications will inhibit the session from accepting user input. The menu client application can then display a dialog, and so on. When the menu server application has completed processing of the menu item, it will send a DDE Terminate to signal Personal Communications the process is complete. Personal Communications will then reenableView the window for the user.

### DDE Menu Server in an OS/2 Environment

To add, delete, and change menu items, the following DDE conversation must take place between the session and a DDE menu client application.




Figure 6. DDE Menu Client Conversation

When the user selects a menu item from the new menu, Personal Communications will send a DDE DATA with aSELECTMENU as the item. When Personal Communications sends DDE DATA to the client application, Personal Communications will inhibit the session from accepting user input. The menu client application can then display a dialog, and so on. When the menu client application has completed processing of the menu item, it will send a DDE ACK to signal Personal Communications the process is complete. Personal Communications will then reenble the window for the user.

## DDE Menu Functions

The following table lists the DDE Menu Item API functions that are available for use with Personal Communications and the page in this section where each function is more fully documented. Personal Communications provides all of the following functions.

Function	Page
Change Menu Item	306
Create Menu Item	311
Initiate Menu Conversation	312
Start Menu Advise	313

Function	Page
Stop Menu Advise	314
Terminate Menu Conversation	315

Refer to Summary of DDE Functions in an OS/2 Environment on page 315 for a summary of the DDE Menu Item API Functions.

## Change Menu Item

3270	5250
Yes	Yes

The **Change Menu Item** function appends, deletes, inserts, modifies, and removes menu items. The client sends the following message to the session to change a menu.

```
WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_POKE,
               pddeStruct,
               DDEPM_RETRY);
```

```
typedef struct _DDESTRUCT
{
    ULONG   cbData;           /* Data length : */
    USHORT  fsStatus;        /* Status : */
    USHORT  usFormat;        /* Data format : Always CF_DSPTXT */
    USHORT  offszItemName;   /* Offset to Item : CHANGEMENU */
    USHORT  offfabData;     /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;
```

where:

### Data

```
typedef struct tagChangeMenu
{
    HWND      hMenu;           /* Window handle of menu item */
    unsigned long wIDNew;      /* Menu ID of new menu item */
    unsigned short wPosition;  /* The position of menu item */
    unsigned short wOperation; /* Specifies the operation */
    unsigned short wFlags;     /* Specifies the options */
    unsigned char szItemName[1]; /* String of the item */
} CHANGEMENU, *lpCHANGEMENU;
```

The following operations are supported:

```
PCS_APPEND    /* Appends a menu item to the end of a menu */
PCS_CHANGE    /* Modifies a menu item in a menu. */
PCS_DELETE    /* Deletes a menu item from a menu,
              /* destroying the menu item. */
PCS_INSERT    /* Inserts a menu item into a menu. */
PCS_REMOVE    /* Removes a menu item from a menu but
              /* does not destroy the menu item.
```

If the PCS\_APPEND is specified in the wOperation field, the following fields must be filled:

### hMenu

Identifies the menu to be appended. To append a new item to a pop-up menu, specify the handle that is returned from Personal



Communications when the **Create Menu Item** function is executed. To append a new item to a top-level menu bar, specify NULL.

#### wIDNew

Specifies the command ID of the new menu item. If a new item is added to the top-level menu bar, the handle of the menu item returned from Personal Communications when **Create Menu Item** function is executed.

#### wFlags

The following options can be set:

```
PCS_CHECKED      // Places a checkmark next to
                  // the item.
PCS_DISABLED     // Disables the menu item so
                  // that it cannot be selected,
                  // but does not gray it.
PCS_ENABLED      // Enables the menu item so that
                  // it can be selected and
                  // restores from its grayed
                  // state.
PCS_GRAYED       // Disables the menu item so
                  // that it cannot be selected,
                  // and grays it.
PCS_MENUBARBREAK // Same as PCS_MENUBREAK except
                  // that for pop-up menus,
                  // separates the new column from
                  // the old column with a
                  // vertical line.
PCS_MENUBREAK    // Places the item on a new line
                  // for menu bar items.
                  // For pop-up menus, places the
                  // item in a new column, with
                  // no dividing line between the
                  // columns.
PCS_SEPARATOR    // Draws a horizontal dividing
                  // line. Can only be used in a
                  // pop-up menu. This line cannot
                  // be grayed, disabled, or
                  // highlighted. The wIDNew and
                  // szItemName fields are
                  // ignored.
PCS_UNCHECKED    // Does not place a checkmark
                  // next to the item (default).
```

#### szItemName

Specifies the contents of the new menu item. Contains a null-terminated character string.

If the PCS\_CHANGE is specified in the wOperation field, fill these fields:

#### hMenu

Identifies the menu to be changed. To change an item of a pop-up menu, specify the handle that is returned from Personal Communications when the **Create Menu Item** function is executed. To change an item to a top-level menu bar, specify NULL.

#### wIDNew

Specifies the command ID of the menu item. If an item of the top-level menu bar is changed, the handle of the menu item returned from Personal Communications when the **Create Menu Item** function is executed.

## wPosition

Specifies the menu item to be changed. The interpretation of the wPosition parameter depends on the setting of the wFlags parameter.

### PCS\_BYPOSITION

Specifies the position of the existing menu item. The first item in the menu is at position zero.

### PCS\_BYCOMMAND

Specifies the command ID of the existing menu item.

## wFlags

The following options can be set:

```
PCS_BYCOMMAND    // Specifies that the wPosition
                  // parameter gives the menu
                  // item control ID number.
                  // This is the default if
                  // neither PCS_BYCOMMAND nor
                  // PCS_BYPOSITION is set.
PCS_BYPOSITION    // Specifies that the wPosition
                  // parameter gives the position
                  // of the menu item to be
                  // changed rather than an ID
                  // number.
PCS_CHECKED       // Places a checkmark next to
                  // the item.
PCS_DISABLED      // Disables the menu item so
                  // that it cannot be selected,
                  // but does not gray it.
PCS_ENABLED       // Enables the menu item so
                  // that it can be selected and
                  // restores from its grayed
                  // state.
PCS_GRAYED        // Disables the menu item so
                  // that it cannot be selected,
                  // and grays it.
PCS_MENUBARBREAK // Same as PCS_MENUBREAK except
                  // that for pop-up menus,
                  // separates the new column
                  // from the old column with a
                  // vertical line.
PCS_MENUBREAK     // Places the item on a new
                  // line for menu bar items.
                  // For pop-up menus, places the
                  // item in a new column, with
                  // no dividing line between
                  // the columns.
PCS_SEPARATOR     // Draws a horizontal dividing
                  // line. Can only be used in
                  // a pop-up menu. This line
                  // cannot be grayed, disabled,
                  // or highlighted. The wIDNew
                  // and szItemName fields are
                  // ignored.
PCS_UNCHECKED     // Does not place a checkmark
                  // next to the item (default).
```

## szItemName

Specifies the contents of the menu item. Contains a null-terminated character string.

If the PCS\_DELETE is specified in the wOperation field, fill these fields:

### **hMenu**

Identifies the menu to be deleted. To delete an item from a pop-up menu, specify the handle that is returned from Personal Communications when the **Create Menu Item**, function is executed. To delete an item from a top-level menu bar, specify NULL.

### **wPosition**

Specifies the menu item to be deleted. The interpretation of the wPosition parameter depends on the setting of the wFlags parameter.

#### **PCS\_BYPOSITION**

Specifies the position of the existing menu item. The first item in the menu is at position zero.

#### **PCS\_BYCOMMAND**

Specifies the command ID of the existing menu item.

### **wFlags**

The following options can be set:

```
PCS_BYCOMMAND    // Specifies that the wPosition
                  // parameter gives the menu
                  // item control ID number.
                  // This is the default if
                  // neither PCS_BYCOMMAND nor
                  // PCS_BYPOSITION is set.
PCS_BYPOSITION   // Specifies that the wPosition
                  // parameter gives the position
                  // of the menu item to be
                  // deleted rather than an ID
                  // number.
```

If the PCS\_INSERT is specified in the wOperation field, the following fields must be filled:

### **hMenu**

Identifies the menu to be inserted. To insert an item to a pop-up menu, specify the handle that is returned from Personal Communications when the **Create Menu Item** function is executed. To change an item to a top-level menu bar, specify NULL.

### **wIDNew**

Specifies the command ID of the menu item or, if an item of the top-level menu bar is changed, the handle of the menu item returned from Personal Communications when the **Create Menu Item** function is executed.

### **wPosition**

Specifies the menu item before the new menu item is to be inserted. The interpretation of the wPosition parameter depends on the setting of the wFlags parameter.

#### **PCS\_BYPOSITION**

Specifies the position of the existing menu item. The first item in the menu is at position zero.

#### **PCS\_BYCOMMAND**

Specifies the command ID of the existing menu item.

## wFlags

The following options can be set:

```
PCS_BYCOMMAND      // Specifies that the wPosition
                   // parameter gives the menu
                   // item control ID number. This
                   // is the default if neither
                   // PCS_BYCOMMAND nor PCS_BYPOSITION
                   // is set.
PCS_BYPOSITION     // Specifies that the wPosition
                   // parameter gives the position
                   // of the menu item to be
                   // changed rather than an ID
                   // number.
PCS_CHECKED        // Places a checkmark next to
                   // the item.
PCS_DISABLED       // Disables the menu item so
                   // that it cannot be selected,
                   // but does not gray it.
PCS_ENABLED        // Enables the menu item so
                   // that it can be selected and
                   // restores from its grayed
                   // state.
PCS_GRAYED         // Disables the menu item so
                   // that it cannot be selected,
                   // and grays it.
PCS_MENUBARBREAK  // Same as PCS_MENUBREAK except
                   // that for pop-up menus,
                   // separates the new column
                   // from the old column with a
                   // vertical line.
PCS_MENUBREAK     // Places the item on a new
                   // line for menu bar items.
                   // For pop-up menus, places the
                   // item in a new column, with
                   // no dividing line between the
                   // columns.
PCS_SEPARATOR     // Draws a horizontal dividing
                   // line. Can only be used in
                   // a pop-up menu. This line
                   // cannot be grayed, disabled,
                   // or highlighted. The wIDNew
                   // and szItemName fields are
                   // ignored.
PCS_UNCHECKED     // Does not place a checkmark
                   // next to the item (default).
```

## szItemName

Specifies the contents of the menu item. Contains a null-terminated character string.

If the PCS\_REMOVE is specified in the wOperation field, the following fields must be filled:

## hMenu

Identifies the menu to be removed. To remove an item from a pop-up menu, specify the handle that is returned from Personal Communications when the **Create Menu Item** function is executed. To remove an item from a top-level menu bar, specify NULL.

## wPosition

Specifies the menu item to be removed. The interpretation of the wPosition parameter depends upon the setting of the wFlags parameter.

**PCS\_BYPOSITION**

Specifies the position of the existing menu item. The first item in the menu is at position zero.

**PCS\_BYCOMMAND**

Specifies the command ID of the existing menu item.

**wFlags**

The following options can be set:

```

PCS_BYCOMMAND      // Specifies that the wPosition
                    // parameter gives the menu
                    // item control ID number.
                    // This is the default if
                    // neither PCS_BYCOMMAND nor
                    // PCS_BYPOSITION is set.
PCS_BYPOSITION     // Specifies that the wPosition
                    // parameter gives the
                    // position of the menu item to
                    // be removed rather than an ID
                    // number.

```

**Personal Communications Response:** Personal Communications receives the requests to change a menu and processes them. If the requests cannot be accepted, Personal Communications returns a negative ACK message containing one of the following status codes in the high-order byte of the fsStatus word. Otherwise, Personal Communications returns a positive ACK message signalling that the keystrokes have been sent.

WM\_DDE\_ACK

Return code	Explanation
0100	The specified parameters are not valid.
0600	The specified format is not valid.
0900	A system error occurred.

**Create Menu Item**

3270	5250
Yes	Yes

The **Create Menu Item** function requests Personal Communications to add a menu item to the menu bar. A pop-up menu will be created at the same time, but it is initially empty and can be filled with menu items by using this function. The string of the new menu item that will be added to a top-level menu bar, is also specified by using the **Change Menu Item** function.

The client sends the following message to create a menu item.

```

WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_REQUEST,
               pddeStruct,
               DDEPM_RETRY);

typedef struct _DDESTRUCT
{
    ULONG cbData;           /* Data length : 0 */
}

```

```

    USHORT fsStatus;          /* Status : */
    USHORT usFormat;         /* Data format : Always CF_DSPTEXT */
    USHORT offszItemName;    /* Offset to Item : CREATEMENU */
    USHORT offabData;        /* Offset to data : unused */
} DDESTRUCT, *pddeStruct;

```

where:

### usFormat

Identifies the format for the ID of the new menu item. The valid value is CF\_DSPTEXT.

### ItemName

Identifies the create menu item (CREATEMENU).

**Personal Communications Response:** Personal Communications returns the handle of the newly created menu item in a DDE data message if the Personal Communications can create a menu item.

WM\_DDE\_DATA

```

typedef struct _DDESTRUCT
{
    ULONG cbData;          /* Data length : */
    USHORT fsStatus;      /* Status : */
    USHORT usFormat;      /* Data format : Always CF_DSPTEXT */
    USHORT offszItemName; /* Offset to Item : CREATEMENU */
    USHORT offabData;     /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;

```

where:

### Data

Identifies a handle to a windows global memory object that contains the handle of the menu item. The global memory object contains the following structure:

```

typedef struct tagCreateMenu
{
    HWND hMenuItem; /* Handle of the menu item */
} CREATEMENU,*lPCREATEMENU;

```

or

WM\_DDE\_ACK

If Personal Communications cannot create a menu item, one of the following status codes is returned in the high-order byte of the fsStatus word:

Return Code	Explanation
0600	The specified format is not valid.
0900	A system error occurred.

### Initiate Menu Conversation

3270	5250
Yes	Yes

The **Initiate Menu Conversation** function connects a client application to an available session of Personal Communications. Once a menu conversation is established, the session menu is reserved exclusively for the client until the conversation is terminated.

The client application sends the following message to initiate a DDE conversation with a menu:

```
WinDdeInitiate( hClientWnd,
                pszAppName,
                pszTopicName,
                pContext);
```

where:

#### AppName

Identifies the application. The string is *IBM3270*. In the 5250, the string is *IBM5250*.

#### TopicName

Identifies the topic. The string for 3270 is *3270MenuS* appended with the session ID *A, B, ..., Z*. In the 5250, the string is *5250MenuS* appended with the session ID *A, B, ..., Z*.

**Personal Communications Response:** If Personal Communications can support a conversation with the client application, Personal Communications acknowledges the INITIATE transaction with:

```
WM_DDE_INITIATEACK
```

#### Start Menu Advise

<i>3270</i>	<i>5250</i>
<i>Yes</i>	<i>Yes</i>

The **Start Menu Advise** function allows a client application to process a user defined routine when the menu item that is added by the client application, is selected. After using this function, the client receives DATA messages indicating which menu item is selected.

The client sends the following command to begin a menu advise.

```
WinDdePostMsg( h3270Wnd,
                hClientWnd,
                WM_DDE_ADVISE,
                pddeStruct,
                DDEPM_RETRY);
```

```
typedef struct _DDESTRUCT
{
    ULONG   cbData;           /* Data length : 0          */
    USHORT  fsStatus;        /* Status :                */
    USHORT  usFormat;        /* Data format : Always CF_DSPTEXT */
    USHORT  offszItemName;   /* Offset to Item : SELECTMENU */
    USHORT  offabData;       /* Offset to data : unused   */
} DDESTRUCT, *pddeStruct;
```

where:

#### fsStatus

The value of DDE\_FNODATA must be 0 and DDE data messages are sent to the client application with the offabData set to selected menu item data.

The value of DDE\_FACKREQ must be 1; the server does notify the client of further close requests.

### ItemName

Identifies a menu advise as the item (SELECTMENU).

**Personal Communications Response:** Personal Communications receives the **Start Menu Advise** and returns an ACK message if it can start the function. Otherwise, a negative ACK message is returned to the client with one of the following return codes in the high-order byte of the fsStatus field.

WM\_DDE\_ACK

Return Code	Explanation
0100	Menu Advise has been already started.
0600	The specified format is not valid.
0900	A system error occurred.

Once the menu item (added to the client application) is selected, the client receives DATA messages notifying it which menu item is selected:

WM\_DDE\_DATA

```
typedef struct _DDESTRUCT
{
    ULONG   cbData;           /* Data length : */
    USHORT  fsStatus;        /* Status : */
    USHORT  usFormat;        /* Data format : */
    USHORT  offszItemName;    /* Offset to Item : SELECTMENU */
    USHORT  offfabData;       /* Offset to data : See the structure */
} DDESTRUCT, *pddeStruct;
```

where:

### Data

Identifies a handle to a Windows global memory object containing:

```
typedef struct tagSELECTMENU
{
    unsigned short uIDSelected; /* Command ID of the selected menu item */
} SELECTMENU, *lpSELECTMENU;
```

The DATA messages continue until a Stop Menu Advise message is sent to Personal Communications.

### Stop Menu Advise

3270	5250
Yes	Yes

The **Stop Menu Advise** function ends a client application's ability to process a user-defined routine when the menu item added by the client application is selected. The client sends the following command to perform the **Stop Menu Advise** function.

```
WinDdePostMsg( h3270Wnd,
                hClientWnd,
                WM_DDE_UNADVISE,
                pddeStruct,
                DDEPM_RETRY);
```

```
typedef struct _DDESTRUCT
```



```

{
    ULONG  cbData;           /* Data length : 0           */
    USHORT fsStatus;        /* Status :                  */
    USHORT usFormat;        /* Data format :             */
    USHORT offszItemName;   /* Offset to Item : SELECTMENU */
    USHORT offabData;       /* Offset to data : unused    */
} DDESTRUCT, *pddeStruct;

```

where:

**ItemName**

Identifies a menu advise as the item (SELECTMENU).

**Personal Communications Response:** If Personal Communications can perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing positive status information to the client:

WM\_DDE\_ACK

If Personal Communications cannot perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing negative status information and one of the following return codes in the high-order byte of the fsStatus word:

Return Code	Explanation
0100	Advise has not started yet.
0900	A system error occurred.

**Terminate Menu Conversation**

3270	5250
Yes	Yes

The **Terminate Menu Conversation** function disconnects the client from the Personal Communications session with which a conversation had been previously started.

The client sends the following command to terminate a session conversation:

```

WinDdePostMsg( h3270Wnd,
               hClientWnd,
               WM_DDE_TERMINATE,
               NULL,
               DDEPM_RETRY);

```

**Personal Communications Response:** Personal Communications acknowledges the terminate command with this message:

WM\_DDE\_TERMINATE

**Summary of DDE Functions in an OS/2 Environment**

The following table lists the DDE functions that can be used with Personal Communications. The table lists the name of the DDE function, the command the client sends to Personal Communications, the values that can be used for the variables in the client command, and the server response.

Table 22. DDE Function Summary in an OS/2 Environment

function name	client command
Code Conversion(system)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_POKE,                 pddeStruct,                 DDEPM_RETRY   DDEPM_NOFREE);</pre>
	<pre>usFormat = CF_DSPTXT ItemName = "CONV" Data = See the structure</pre>
Initiate System Conversation(system)	<pre>WinDdeInitiate( hClientWnd,                  pszAppName,                  pszTopicName,                  pContext);</pre>
	<pre>AppName = "IBM3270" TopicName = "SYSTEM"</pre>
Get System Configuration(system)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_REQUEST,                 pddeStruct,                 DDEPM_RETRY);</pre>
	<pre>usFormat = CF_TEXT ItemName = "SysCon"</pre>
Get System Formats(system)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_REQUEST,                 pddeStruct,                 DDEPM_RETRY);</pre>
	<pre>usFormat = CF_TEXT ItemName = "Formats"</pre>
Get System Status(system)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_REQUEST,                 pddeStruct,                 DDEPM_RETRY);</pre>
	<pre>usFormat = CF_TEXT ItemName = "Status"</pre>

Table 22. DDE Function Summary in an OS/2 Environment (continued)

function name	client command
Get System SysItems(system)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_REQUEST, pddeStruct, DDEPM_RETRY);
	usFormat = CF_TEXT ItemName = "SysItems"
Get System Topics(system)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_REQUEST, pddeStruct, DDEPM_RETRY);
	usFormat = CF_TEXT ItemName = "Topics"
Terminate System Conversation(system)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_TERMINATE, NULL, DDEPM_RETRY);
Initiate Session Conversation(session)	WinDdeInitiate( hClientWnd, pszAppname, pszTopicName, pContext);
	AppName = "IBM3270"   "IBM5250" TopicName = "Session" + N N = a session letter A through Z.
Find Field(session)	WinPostMessage(h3270Wnd, hClientWnd, WM_DDE_REQUEST, pddeStruct, DDEPM_RETRY);
	usFormat = CF_DSPTXT   CF_DSPTXT itemName = "FIELD"
Get Keystrokes(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_REQUEST, pddeStruct, DDEPM_RETRY);
	usFormat = CF_DSPTXT ItemName = "KEYS"

Table 22. DDE Function Summary in an OS/2 Environment (continued)

function name	client command
Get Mouse Input(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_REQUEST, pddeStruct, DDEPM_RETRY);
	usFormat = CF_TEXT   CF_DSPTXT ItemName = "MOUSE"
Get Number of Close Requests(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_REQUEST, pddeStruct, DDEPM_RETRY);
	usFormat = CF_DSPTXT ItemName = "CLOSE"
Get Operator Information Area(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_REQUEST, pddeStruct, DDEPM_RETRY);
	usFormat = CF_DSPTXT ItemName = "OIA"
Get Partial Presentation Space(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_REQUEST, pddeStruct, DDEPM_RETRY);
	usFormat = CF_TEXT   CF_DSPTXT ItemName = "EPS"
Get Presentation Space(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_REQUEST, pddeStruct, DDEPM_RETRY);
	usFormat = CF_TEXT   CF_DSPTXT ItemName = "PS"

Table 22. DDE Function Summary in an OS/2 Environment (continued)

function name	client command
Get Session Status(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_REQUEST, pddeStruct, DDEPM_RETRY);
	usFormat = CF_TEXT ItemName = "SSTAT"
Get Trim Rectangle(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_REQUEST, pddeStruct, DDEPM_RETRY);
	usFormat = CF_TEXT ItemName = "TRIMRECT"
Put Data to Presentation Space(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_POKE, pddeStruct, DDEPM_RETRY);
	usFormat = CF_DSPTXT ItemName = "EPS" Data = See the structure
Search for String(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_REQUEST, pddeStruct, DDEPM_RETRY);
	usFormat = CF_DSPTXT ItemName = "STRING"
Send Keystrokes(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_POKE, pddeStruct, DDEPM_RETRY);
	usFormat = CF_DSPTXT ItemName = "KEYS" Data = See the structure

Table 22. DDE Function Summary in an OS/2 Environment (continued)

function name	client command
Session Execute Macro(session)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_EXECUTE,                 pddeStruct,                 DDEPM_RETRY);</pre>
	<pre>usFormat = CF_DSPTTEXT ItemName = NULL Data = See the structure</pre>
Set Cursor Position(session)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_POKE,                 pddeStruct,                 DDEPM_RETRY);</pre>
	<pre>usFormat = CF_DSPTTEXT ItemName = "SETCURSOR" Data = See the structure</pre>
Set Mouse Intercept Condition(session)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_POKE,                 pddeStruct,                 DDEPM_RETRY);</pre>
	<pre>usFormat = CF_TEXT   CF_DSPTTEXT ItemName = "MOUSE" Data = See the structure</pre>
Set Presentation Space Service Condition(session)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_POKE,                 pddeStruct,                 DDEPM_RETRY);</pre>
	<pre>usFormat = CF_DSPTTEXT ItemName = "EPSCOND" Data = See the structure</pre>
Set Session Advise Condition(session)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_POKE,                 pddeStruct,                 DDEPM_RETRY);</pre>
	<pre>usFormat = CF_DSPTTEXT ItemName = "PSCOND" Data = See the structure</pre>

Table 22. DDE Function Summary in an OS/2 Environment (continued)

function name	client command
Start Close Intercept(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_ADVISE, pddeStruct, DDEPM_RETRY);
	ItemName = "CLOSE"
Start Keystroke Intercept(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_ADVISE, pddeStruct, DDEPM_RETRY);
	ItemName = "KEYS"
Start Mouse Input Intercept(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_ADVISE, pddeStruct, DDEPM_RETRY);
	ItemName = "MOUSE"
Start Session Advise(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_ADVISE, pddeStruct, DDEPM_RETRY);
	ItemName = OIA   PS   TRIMRECT
Stop Close Intercept(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_UNADVISE, pddeStruct, DDEPM_RETRY);
	ItemName = "CLOSE"
Stop Keystroke Intercept(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_UNADVISE, pddeStruct, DDEPM_RETRY);
	ItemName = "KEYS"

Table 22. DDE Function Summary in an OS/2 Environment (continued)

function name	client command
Stop Mouse Input Intercept(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_UNADVISE, pddeStruct, DDEPM_RETRY);
	ItemName = "MOUSE"
Stop Session Advise(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_UNADVISE, pddeStruct, DDEPM_RETRY);
	ItemName = OIA   PS   TRIMRECT   NULL
Terminate Session Conversation(session)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_TERMINATE, NULL, DDEPM_RETRY);
Initiate Structured Field Conversation(structured field)	WinDdeInitiate( hClientWnd, pszAppName, pszTopicName, pContext);
	AppName = "IBM3270"   "IBM5250" TopicName = "LU" + N + "_" + xxxx N = a session letter A through Z. xxxx = a user defined string.
Terminate Structured Field Conversation(structured field)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_TERMINATE, NULL, DDEPM_RETRY);
Set Structured Field Service Condition(structured field)	WinDdePostMsg( h3270Wnd, hClientWnd, WM_DDE_POKE, pddeStruct, DDEPM_RETRY);
	usFormat = CF_DSPTXT ItemName = "SFCOND" Data = See the structure



Table 22. DDE Function Summary in an OS/2 Environment (continued)

function name	client command
Start Read SF(structured field)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_ADVISE,                 pddeStruct,                 DDEPM_RETRY);</pre>
	<pre>ItemName = "SF"</pre>
Stop Read SF(structured field)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_UNADVISE,                 pddeStruct,                 DDEPM_RETRY);</pre>
	<pre>ItemName = "SF"</pre>
Write SF(structured field)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_REQUEST,                 pddeStruct,                 DDEPM_RETRY);</pre>
	<pre>usFormat = CF_DSPTXT ItemName = "SF" Data = See the structure</pre>
Initiate Menu Conversation(menu)	<pre>WinDdeInitiate( hClientWnd,                  pszAppName,                  pszTopicName,                  pContext);</pre>
	<pre>AppName = "IBM3270"   "IBM5250" TopicName = "3270MenuS" + N N = a session letter A through Z</pre>
Change Menu Item(menu)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_POKE,                 pddeStruct,                 DDEPM_RETRY);</pre>
	<pre>ItemName = "CHANGEMENU" Data = See the structure</pre>

Table 22. DDE Function Summary in an OS/2 Environment (continued)

function name	client command
Create Menu Item(menu)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_REQUEST,                 pddeStruct,                 DDEPM_RETRY);</pre>
	<pre>usFormat = CF_DSPTEXT ItemName = "CREATEMENU"</pre>
Start Menu Advise(menu)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_ADVISE,                 pddeStruct,                 DDEPM_RETRY);</pre>
	<pre>ItemName = "SELECTMENU" Data = See the structure</pre>
Stop Menu Advise(menu)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_UNADVISE,                 pddeStruct,                 DDEPM_RETRY);</pre>
	<pre>ItemName = "SELECTMENU"</pre>
Terminate Menu Conversation(menu)	<pre>WinDdePostMsg( h3270Wnd,                 hClientWnd,                 WM_DDE_TERMINATE,                 NULL,                 DDEPM_RETRY);</pre>

---

## Chapter 7. Using DDE Functions with a DDE Client Application

Windows and OS/2 allow users to run multiple Windows application programs and to exchange data between Windows application programs. Dynamic data exchange (DDE) allows users this data exchange. Data exchange among Windows application programs can be considered as conversations between *server* and *client* application programs. The client application is an application program that starts DDE, and the server application is an application program that responds to the client application.

The client application needs three names (application program name, topic name, and item name) that are recognized by the server application to start the conversation to exchange data. The client application starts a DDE conversation with the server application by specifying the application program and topic names, and defines the exchange data by specifying the item name.

Personal Communications has a function as a DDE server, and can establish DDE conversations with other Windows application programs (Microsoft Visual Basic, Microsoft Excel, Microsoft Word) that have DDE client functions.

---

### Using the Personal Communications DDE Interface

To start a DDE conversation and data exchange with Personal Communications, client application programs need to know the application program name, topic name, and item name that Personal Communications can recognize. The exchange data type between an application program and Personal Communications is defined with the combination of these names.

Table 23. Naming Scheme for Data Items

Level	Description	Example
Application	A Windows 95, Windows 98, and Windows NT task, a Windows task, or a specific task of the application. In this book, application programs are Personal Communications.	IBM327032
Topic	A specific part of application programs.	SessionA
Item	Type of data passed during DDE conversation.	PS (Presentation Space)

#### Application

As a Windows DDE server, Personal Communications supports application name *IBM327032* or *IBM525032* for 32-bit applications, *IBM3270* or *IBM5250* for 16-bit applications.

**Topic** Topic specifies the corresponding topic in the application. The following table shows the topics available to the users:

Table 24. Topics for Personal Communications

Topic	Conversation Name	Conversation Type
System	System conversation	Cold link
SessionA, SessionB, ..., SessionZ	Session conversation	Cold link and hot link

Table 24. Topics for Personal Communications (continued)

Topic	Conversation Name	Conversation Type
SessA_XXXX, SessB_XXXX, ..., SessZ_XXXX	Session conversation	Hot link

**Item** The client application programs can exchange data and information with Personal Communications. Types of data and information are specified by item name.

Explanations for topic conversation procedures and data items to be used follow.

## System Conversation

To use the Personal Communications system DDE interface, do as follows:

1. Start the system conversation.
2. Request system information.
3. Terminate the system conversation.

### Starting the DDE System Conversation with Personal Communications

To use the DDE interface with Personal Communications, the client application should first start a DDE conversation with Personal Communications. To start a DDE conversation, specify *IBM327032* or *IBM525032* as an application name for 32-bit applications; *IBM3270* or *5250* for 16-bit applications and *System* as a topic name in the DDE function (Initiate) in the client application.

### Requesting System Information

After starting the DDE conversation, the client application can request data or information using the DDE function. System information can be requested by specifying the following item names in the DDE function (Request) in the client application:

Item	Return Data	DDE Function
Formats	List of supported Windows clipboard format	Get System Formats
Status	Each session status information	Get System Status
SysCon	Information of emulator support-level and other system-related values	Get System Configuration
SysItems	List of available data items	Get System SysItems
Topics	List of available topics	Get System Topics

### Terminating the DDE System Conversation with Personal Communications

To complete the conversation, the client application needs to terminate the DDE conversation with Personal Communications. To terminate the conversation, use the DDE function (Terminate) in the client application.

## Session Conversation

To use the Personal Communications session DDE interface, do as follows:

1. Start the session conversation.

2. Use DDE functions (Request, Poke, Execute).
3. Terminate the session conversation.

## Starting the DDE Session Conversation

To use the DDE interface with Personal Communications sessions, the client application should start the DDE conversation with Personal Communications. To start DDE conversation, specify *IBM327032* or *IBM525032* as an application name for 32-bit applications; *IBM3270* or *IBM5250* for 16-bit applications and *SessionA*, *SessionB*, ..., *SessionZ* as topic names in the DDE function (Initiate) in the client application.

## Requesting Data

After starting the DDE conversation, the client application can request data using the DDE function. Session information can be requested by specifying the following item names in the DDE function (Request) in the client application:

Item	Return Data	DDE Function
EPS(pos,len,bEOF)	All or a part of session presentation space	Get Partial Presentation Space
FIELD(pos,"type")	Field information	Find Field
OIA	Operator Information Area (OIA) status line information	Get Operator Information Area
PS	Session presentation space	Get Presentation Space
SSTAT	Session status information	Get System Status
STRING(pos,bDir,"string")	String offset start	Search for string
TRIMRECT *	Session presentation space of trim rectangle	Get Trim Rectangle
*: Parameter should be added.		

## Sending Data to the Emulator Window (Poke)

After starting the DDE conversation, the client application can send data to Personal Communications sessions using the DDE functions. The following table shows the valid items for the DDE functions:

Item	Explanation	DDE Function
EPS(pos,bEOF)	Sends an ASCII data string to the host presentation space	Put Data to Presentation Space
SETCURSOR	Sets the cursor position	Set Cursor Position

## Executing Commands

After starting a DDE conversation, the client application can send commands to the Personal Communications session window using the DDE functions. Specify the command in the DDE function (Execute) of the client application. See "Session Execute Macro" on page 196 for details.

## Terminating the DDE Session Conversation

The client application should terminate the DDE conversation with Personal Communications when completing the task. To terminate the conversation, use the DDE function (Terminate) in the client application.

## Session Conversation (Hot Link)

To use the Personal Communications session DDE interface, do as follows:

1. Start the session conversation.
2. Start the **Advise** function.
3. Stop the **Advise** function.
4. Terminate the session conversation.

### Starting the DDE Session Conversation (Hot Link)

To use the DDE interface with Personal Communications sessions, the client application should start the DDE conversation with Personal Communications. To start the DDE conversation, specify *IBM327032* or *IBM525032* as an application name for 32-bit applications; *IBM3270* or *IBM5250* for 16-bit applications, and *SessionA*, *SessionB*, ..., *SessionZ* as topic names in the DDE function (Initiate) in the client application.

### Starting the Hot Link with the Session Window

After starting the DDE conversation, the client application can start the **Advise** function. Specify the following item names in the DDE function (Advise) in the client application to start the hot link, which enables the automatic data update:

Item	Explanation	DDE Function
CLOSE	Starts to intercept Window Close requests	Start Close Intercept
KEYS	Starts to intercept keystrokes	Start Keystroke Intercept
PS * OIA TRIMRECT *	Start to retrieve data of PS, OIA, or trim rectangle	Start Session Advise
*: Parameter should be added.		

### Stopping the Hot Link with the Session Window

To terminate the **Advise** function, the client application needs to use the DDE function. Specify the following item names in the DDE function (Unadvise) in the client application to stop the hot link, which enables the automatic data update:

Item	Explanation	DDE function
CLOSE	Stops to intercept Close request	Stop Close Intercept
KEYS	Stops to intercept keystrokes	Stop Keystroke Intercept
PS * OIA TRIMRECT *	Stops to Advise function for the session	Stop Session Advise
*: Use the same parameter that is used when Start Session Advise was called.		

### Terminating the DDE Session Conversation

The client application should terminate the DDE conversation with Personal Communications when completing the task. To terminate the conversation, use the DDE function (Terminate) in the client application.

---

## Personal Communications DDE Interface

This section describes the DDE functions that can be used from the other applications, such as Microsoft Excel, Microsoft Word, and Microsoft Visual Basic.

- DDE functions for system conversation

Function	Page
Initiate System Conversation	332
Get System Configuration	330
Get System Formats	330
Get System Status	330
Get System SysItems	331
Get System Topics	331
Terminate System Conversation	332

- DDE functions for session conversation

Function	Page
Initiate Session Conversation *1	332
Find Field	332
Get Operator Information Area	334
Get Partial Presentation Space	335
Get Presentation Space	335
Get Session Status	336
Get Trim Rectangle	336
Put Data to Presentation Space	337
Search for String	338
Session Execute Macro	339
Set Cursor Position	339
Terminate Session Conversation *2	344

- DDE functions for session conversation (hot link)

Function	Page
Initiate Session Conversation (same as *1)	340
Start Close Intercept	340
Start Keystroke Intercept	341
Start Session Advise	342
Stop Close Intercept	343
Stop Keystroke Intercept	343
Stop Session Advise	344
Terminate Session Conversation (same as *2)	344

---

## DDE Functions for System Conversation

The following DDE functions are provided for Personal Communications system conversation.

### Get System Configuration

The **Get System Configuration** function returns Personal Communications support-level and other system-related values.

DDE Parameter	Value
Item	SysCon

The client application can use the Personal Communications DDE function by specifying the DDE function (Request) of the client application with the topic name (System).

#### Personal Communications Response

The Personal Communications system returns the Personal Communications system configuration data item.

**Returned Information:** See “Get System Configuration” on page 186 for details.

If Personal Communications do not return the system configuration data item, it may be because:

- An incorrect item name was specified.
- A system error has occurred.

### Get System Formats

The **Get System Formats** function returns a list of Windows Clipboard formats that are supported by Personal Communications.

DDE Parameter	Value
Item	Formats

The client application can use the Personal Communications DDE function by specifying the DDE function (Request) of the client application with the item name (Formats).

#### Personal Communications Response

Personal Communications returns a list of supported Windows Clipboard formats.

If Personal Communications do not return the format data item, it may be because:

- An incorrect item name was specified.
- A system error has occurred.

### Get System Status

The **Get System Status** function returns the status of each configured Personal Communications session.



DDE Parameter	Value
Item	SysCon

The client application can use the Personal Communications DDE function by specifying the DDE function (Request) of the client application with the item name (SysCon).

## Personal Communications Response

Personal Communications returns a series of status information to each open session.

**Returned Information:** See “Get System Status” on page 187 for details.

If Personal Communications do not return the status data item, it may be because:

- An incorrect item name was specified.
- A system error has occurred.

## Get System Systems

The **Get System Systems** function returns a list of data items that can be used with the Personal Communications system topic.

DDE Parameter	Value
Item	SysItems

The client application can use the Personal Communications DDE function by specifying the DDE function (Request) of the client application with the item name (SysItems).

## Personal Communications Response

Personal Communications returns a list of Personal Communications system topic data items. The following data items are supported by Personal Communications:

- Systems
- Topics
- Status
- Formats
- SysCon

If Personal Communications do not return the system data item, it may be because:

- An incorrect item name was specified.
- A system error has occurred.

## Get System Topics

The **Get System Topics** function returns a list of active DDE topics that are supported by Personal Communications.

DDE Parameter	Value
Item	Topics

The client application can use the Personal Communications DDE function by specifying the DDE function (Request) of the client application with the item name (Topics).

## Personal Communications Response

The following topics are supported by Personal Communications:

- System
- SessionA, SessionB, ..., SessionZ

If Personal Communications do not return the system data item, it may be because:

- An incorrect item name was specified.
- A system error has occurred.

## Initiate System Conversation

The **Initiate System Conversation** function starts the system conversation. Only one client application can be connected to one system.

DDE Parameter	Value
Topic	System

The client application should start DDE conversation using the DDE function (Initiate) with the Personal Communications application name (IBM327032 or IBM525032 for 32-bit applications) or (IBM3270 or IBM5250 for 16-bit applications) and the topic name (System).

## Terminate System Conversation

The **Terminate System Conversation** function terminates the system conversation. Use the DDE function (Terminate) to terminate the DDE conversation from the client application.

---

## DDE Functions for Session Conversation

The following DDE functions are provided for Personal Communications session conversation.

### Find Field

The **Find Field** function passes the field information to the client application.

DDE Parameter	Value
Item	FIELD (pos, "type")

Parameter	Value	Explanation
pos	NNNN	PS position.
"type"	"bb" or "Tb" "Pb" "Nb" "NP" "NU" "PP" "PU"	This field. The previous field, either protected or unprotected. The next field, either protected or unprotected. The next protected field. The next unprotected field. The previous protected field. The previous unprotected field.

**Note:** The `b` symbol represents a required blank.

An item in the IBM Personal Communications Version 3.1 format is also supported.

The client application can use the Personal Communications DDE function by specifying the DDE function (Request) of the client application with the foregoing item name.

## Personal Communications Response

The following table shows the field information that PC/3270 returns:

Field	Returned Information	Explanation
Formatted/Unformatted	Formatted, Unformatted	Whether the presentation space is formatted or unformatted. If Unformatted is specified, no other field information will be returned.
Unprotected/Protected	N	0=Unprotected data field. 1=Protected data field.
A/N	N	0=Alphanumeric. 1=Numeric.
I/SPD	N	0=Normal intensity, undetectable. 1=Normal intensity, detectable. 2=High intensity, detectable. 3=Nondisplay, undetectable.
MDT	N	0=Field is not changed. 1=Field is changed.
Field start offset	NNNN	Field starts this field position.
Field length	NNNN	Field length.

The following table shows the field information that PC400 returns:

Field	Returned Information	Explanation
Formatted/Unformatted	Formatted, Unformatted	Whether the presentation space is formatted or unformatted. If Unformatted is specified, no other field information will be returned.
Field attribute	N	0 = Not field attribute byte. 1 = Field attribute byte.
Visibility	N	0 = Nondisplay. 1 = Display.
Unprotected/Protected	N	0 = Unprotected data field. 1 = Protected data field.
Intensity	N	0 = Normal. 1 = High.
Field Type	N	0 = Alphanumeric: all characters allowed. 1 = Alphabet only: uppercase and lowercase letters, comma, period, hyphen, blank, and Dup key allowed. 2 = Numeric shift: automatic shift for numerics. 3 = Numeric only: numbers 0–9, comma, period, plus, minus, blank, and Dup key allowed. 5 = Digits only: numbers 0–9 and Dup key allowed. 6 = Magnetic stripe reader data only. 7 = Sighed numeric: numbers 0–9, plus, minus, and Dup key allowed.
MDT	N	0=Field is not changed. 1=Field is changed.

Field	Returned Information	Explanation
Field start offset	NNNN	Field starts this field position.
Field length	NNNN	Field length.

If Personal Communications do not return the field information, it may be because:

- An incorrect item name was specified.
- A system error has occurred.

## Get Operator Information Area

The **Get Operator Information Area** function returns the OIA data information to the client application.

**DDE Parameter**    **Value**  
**Item**                    OIA

The client application can use the Personal Communications DDE function by specifying the DDE function (Request) of the client application with the item name (OIA).

## Personal Communications Response

The following table shows the OIA information that Personal Communications returns:

Offset	Returned Information	Meaning
0	ONLINE LU-LU SSCP-LU	Online, the screen is unowned LU-LU session owns the screen SSCP-LU session owns the screen
9	X X MCHK X CCHK X PCHK X DNW X BUSY X TWAIT X -S X -f X MUCH X UA X -fUA X DEAD X WRONG X SYSTEM X II	Input inhibit Machine check Communication check Program check Device not working Printing Terminal waiting Minus symbol Minus function Input too much Unauthorized operator Unauthorized operator Minus function Incorrect dead key combination Wrong position System waiting Operator input error (PC400)
19	COMM	Communication error
25	MW	Message waiting (PC400)
36	APL	APL (PC/3270)
42	U NUM	Uppercase Numeric
43	A	Caps lock
47	S I	High intensity, operator selectable High intensity, field inherit
49	CS CI	Color, operator selectable Color, field inherit
52	^	Insert mode
61	P-MAL P-PRN P-ASS	Printer malfunction Printer printing Printer assignment

If Personal Communications do not return the OIA information, it may be because:

- An incorrect item name was specified.

- A system error has occurred.

## Get Partial Presentation Space

The **Get Partial Presentation Space** function returns whole or partial presentation space data to the client application.

**DDE Parameter**    **Value**  
**Item**                EPS (pos, len, bEOF)

Parameter	Value	Explanation
pos	NNNN	PS position
len	NNNN	PS length
bEOF	1 or 0	EOF switch <b>1</b> Yes <b>0</b> No

**Note:** An item in the IBM Personal Communications Version 3.1 format is also supported.

The client application can use the Personal Communications DDE function by specifying the DDE function (Request) of the client application with the foregoing item names.

## Personal Communications Response

The following table shows the information Personal Communications returns:

Field	Returned Information	Explanation
PS start position	NNNN	Specified by pos parameter
PS length	NNNN	Specified by len parameter
PS rows	NNNN	Specified by the number of rows
PS columns	NNNN	Specified by the number of columns
PS	NNNN	PS data starts from this position

If Personal Communications do not return the format data items, it may be because:

- An incorrect item name was specified.
- A system error has occurred.

## Get Presentation Space

The **Get Presentation Space** function returns presentation space data to the client application.

**DDE Parameter**    **Value**  
**Item**                PS

The client application can use the Personal Communications DDE function by specifying the DDE function (Request) of the client application with the item name (PS).

## Personal Communications Response

The following table shows the information Personal Communications returns:

Field	Returned Information	Explanation
PS size	NNNN	Size of presentation space
PS rows	NNNN	Number of rows
PS columns	NNNN	Number of columns
PS	NNNN	PS data starts from this position

If Personal Communications do not return the format data items, it may be because:

- An incorrect item name was specified.
- A system error has occurred.

## Get Session Status

The **Get Session Status** function returns the connected session status to the client application.

DDE Parameter	Value
Item	SSTAT

The client application can use the Personal Communications DDE function by specifying the DDE function (Request) of the client application with the item name (SSTAT).

## Personal Communications Response

Refer to “Get Session Status” on page 411 for the returned information.

If Personal Communications do not return the format data items, it may be because:

- An incorrect item name was specified.
- A system error has occurred.

## Get Trim Rectangle

The **Get Trim Rectangle** function returns the presentation space area of the current (or specified) trim rectangle to the client application.

DDE Parameter	Value
Item	TRIMRECT (row1, col1, row2, col2) TRIMRECT (pos1, pos2) TRIMRECT

Parameter	Value	Explanation
row1	NN	Top-left corner row of the trim rectangle
col1	NN	Top-left corner column of the trim rectangle
row2	NN	Bottom-right corner row of the trim rectangle
col2	NN	Bottom-right corner column of the trim rectangle
pos1	NNNN	PS position of the top-left corner of the trim rectangle

Parameter	Value	Explanation
pos2	NNNN	PS position of the bottom-right corner of the trim rectangle

**Note:** An item in the IBM Personal Communications Version 3.1 format is also supported.

The current specified PS trim rectangle is used unless the client application specifies the PS trim rectangle in the parameter.

The client application can use the Personal Communications DDE function by specifying the DDE function (Request) of the client application with the item name (TRIMRECT).

## Personal Communications Response

The information returned from Personal Communications is as follows:

Field	Returned Information	Explanation
PS		PS data starts from this position.

If Personal Communications do not return the trim rectangle items, it may be because:

- An incorrect item name was specified.
- A system error has occurred.

## Initiate Session Conversation

The **Initiate Session Conversation** function starts a DDE conversation in the available session window. Only one client application can be connected to one session conversation:

**DDE Parameter**    **Value**  
**Topic**            SessionA, SessionB, ..., SessionZ

Parameter Value	Explanation
SessionA, SessionB, ..., SessionZ	"SessionA" implies a string combined "Session" and a session ID "A", "B", ..., "Z".

The client application should start the DDE conversation by specifying the DDE function (Initiate) of the client application with the topic name (SessionA, SessionB, ..., SessionZ).

## Personal Communications Response

If a topic is not specified, Personal Communications responds after confirming the following available topics:

- System
- SessionA, SessionB, ..., SessionZ

## Put Data to Presentation Space

The **Put Data to Presentation Space** function sends an ASCII data string to write on the specified host presentation space.

**DDE Parameter Value**  
**Item** EPS (pos, bEOF)

Parameter	Value	Explanation
pos	NNNN	PS position to start writing the data
bEOF	1 or 0	EOF switch <b>1</b> Yes <b>0</b> No

**Note:** An item in the IBM Personal Communications Version 3.1 format is also supported.

The client application can use the Personal Communications DDE function by specifying the DDE function (Poke) of the client application with the foregoing item name.

### Personal Communications Response

If Personal Communications do not accept the string data, it may be because:

- An incorrect item name was specified.
- The PS position is not valid.
- The length is not valid.
- The PS input was inhibited.
- A system error has occurred.

## Search for String

Using the **Search for String** function, the client application can check whether the specified strings exist within the specified presentation space area.

**DDE Parameter Value**  
**Item** STRING (pos, bDir, "string")

Parameter	Value	Explanation
pos	NNNN	PS start position of the string search
bDir	1 or 0	Search Direction <b>1</b> Forward <b>0</b> Backward
"string"		Search string <ul style="list-style-type: none"> <li>• Enclose a string including blanks with double quotation marks.</li> <li>• To specify a double quotation mark within the string, enclose the double quotation mark with another set of double quotation marks. Example: <i>This is a double quotation</i> mark. is specified as <i>"This is a double quotation" mark.</i></li> </ul>

**Note:** An item in the IBM Personal Communications Version 3.1 format is also supported.



The maximum length of the search string is 255.

The client application can use the Personal Communications DDE function by specifying the DDE function (Request) of the client application with the foregoing item names.

## Personal Communications Response

Personal Communications returns the following information:

Field	Returned Information	Explanation
String start offset	NNNN, None	"None" is returned if the string is not found.

If Personal Communications do not return the string start position, it may be because:

- An incorrect item name was specified.
- The PS position is not valid, or the string is too long.
- A system error has occurred.

## Session Execute Macro

The **Session Execute Macro** function enables users to send commands and macro strings to Personal Communications.

Refer to “Session Execute Macro” on page 422 for details of commands and macro strings.

The client application can use the Personal Communications DDE function by specifying the DDE function (Execute) of the client application.

## Personal Communications Response

A system error can cause Personal Communications not to return the string start position.

## Set Cursor Position

Using the **Set Cursor Position** function, the client application can set the cursor position in the session window.

<b>DDE Parameter</b>	<b>Value</b>
<b>Item</b>	SETCURSOR
<b>Data (Cursor position)</b>	NNNN or Rn1Rn2

Parameter Value	Explanation
NNNN	PS offset
Rn1Rn2	Row/column <b>n1</b> PS position row <b>n2</b> PS position column

The client application can use the Personal Communications DDE function by specifying the DDE function (Poke) of the client application with the foregoing item names.

## Personal Communications Response

If Personal Communications do not move the cursor to the specified PS position, it may be because:

- An incorrect item name was specified.
- The Cursor PS offset is not valid (it must be from 0 to PS size-1).
- The Cursor row value is not valid (it must be from 0 to PS row-1).
- The Cursor column value is not valid (it must be from 0 to PS column-1).
- A system error has occurred.

## Terminate Session Conversation

The **Terminate Session Conversation** function terminates the DDE conversation between the client application and Personal Communications.

Use the DDE function (Terminate) of the client application to terminate the DDE conversation.

---

## DDE Functions for Session Conversation (Hot Link)

The following DDE functions are provided for Personal Communications session conversation with hot link connection.

### Initiate Session Conversation

The **Initiate Session Conversation** function starts a DDE conversation with the available session window.

DDE Parameter	Value
Topic	SessionA, SessionB, ..., SessionZ or SessA_xxxx, SessB_xxxx, ..., SessZ_xxxx

**Note:** If SessA\_xxxx, SessB\_xxxx, ..., SessZ\_xxxx is used, the client application allows only hot link session conversation.

Parameter Value	Explanation
SessA_xxxx, SessB_xxxx, ..., SessZ_xxxx	String 'SessA_xxxx' indicates session A (SessA_) with any user-defined strings (xxxx). The length of the user-defined strings is not limited.

Specify the Personal Communications application name and the foregoing topic name in the DDE function (Initiate) of the client application to start a DDE conversation.

### Start Close Intercept

Using the **Start Close Intercept** function, the client application can intercept the Close request generated by selecting the Close option from the emulator session window. When this service is started, the client application receives the Close

request event data.

<b>DDE Parameter</b>	<b>Value</b>
<b>Item</b>	CLOSE

The client application can use the Personal Communications DDE function by specifying the DDE function (Advise) of the client application with the foregoing item name.

## Personal Communications Response

Personal Communications returns the following information:

Field	Returned Information	Explanation
Number of PS close request	NNNN	When a Close request is generated, the client application receives "0001".

If Personal Communications do not start to Close intercept, it may be because:

- An incorrect item name was specified.
- The Close intercept for the session has already started with the same topic name.
- A system error has occurred.

## Start Keystroke Intercept

Using the **Start Keystroke Intercept** function, the client application can filter keystrokes that are entered by the terminal operator. When started, the keystrokes are intercepted and received by the client application.

<b>DDE Parameter</b>	<b>Value</b>
<b>Item</b>	KEYS

The client application can use the Personal Communications DDE function by specifying the DDE function (Advise) of the client application with the foregoing item name.

## Personal Communications Response

Personal Communications returns the following information:

Field	Returned Information	Explanation
Keys		Refer to Table 16 "SENDKEY Command List" of Chapter 6. DDE Functions for Windows and OS/2 Session Execute Macro on page 198.

If Personal Communications do not start KeyStroke Intercept, it may be because:

- An incorrect item name was specified.
- The Keystroke Intercept for the session has already started with the same topic name.
- A system error has occurred.

## Start Session Advise

The **Start Session Advise** function establishes the link between the client application and Personal Communications. As the data item is changed, the client application receives the changed data of the presentation space (PS), operator information area (OIA), or trim rectangle (TRIMRECT).

DDE Parameter	Value
Item	PS (pos, len, bCaseSen, "string") PS TRIMRECT (row1, col1, row2, col2) TRIMRECT (pos1, pos2) TRIMRECT OIA

The maximum length of the search string is 255.

Parameter	Value	Explanation
pos	NNNN	PS start position of the string search (PS offset)
len	NNNN	Length of the search string
bCaseSen	1 or 0	Case sensitivity <b>1</b> Yes <b>0</b> No
"string"		Search string <ul style="list-style-type: none"> <li>Enclose a string including blanks with double quotation marks.</li> <li>To specify a double quotation mark within the string, enclose the double quotation mark with another set of double quotation marks. Example: <i>This is a double quotation mark.</i> is specified as <i>"This is a double quotation"" mark."</i></li> </ul>

**Note:** An item in the IBM Personal Communications Version 3.1 format is also supported.

To receive a conditional advice when the presentation space is updated, the client application needs to set the advise conditions as well as the foregoing parameter values. The foregoing parameter values can be used when the presentation space is specified as the item name.

Parameter	Value	Explanation
row1	NN	Top-left corner row of the trim rectangle
col1	NN	Top-left corner column of the trim rectangle
row2	NN	Bottom-right corner row of the trim rectangle
col2	NN	Bottom-right corner column of the trim rectangle
pos1	NNNN	PS position of the top-left corner of the trim rectangle
pos2	NNNN	PS position of the bottom-right corner of the trim rectangle

**Note:** An item in the IBM Personal Communications Version 3.1 format is also supported.

The current specified presentation space trim rectangle is used unless the client application specifies the presentation space trim rectangle in the item name parameter. This parameter value can be used when TRIMRECT is specified as the item name.

The client application can use the Personal Communications DDE function by specifying the DDE function (Advise) of the client application with the foregoing item name.

### **Personal Communications Response**

Refer to “Get Partial Presentation Space” on page 335, “Get Operator Information Area” on page 334, and “Get Trim Rectangle” on page 336.

If Personal Communications do not start Advise, it may be because:

- An incorrect item name was specified.
- The Advise for the session has already started with the same topic name
- A system error has occurred.

## **Stop Close Intercept**

Using the **Stop Close Intercept** function, the client application stops intercepting the close requests.

<b>DDE Parameter</b>	<b>Value</b>
<b>Item</b>	CLOSE

The client application can use the Personal Communications DDE function by specifying the DDE function (Unadvise) of the client application with the foregoing item name.

### **Personal Communications Response**

If Personal Communications do not stop Close Intercept, it may be because:

- The Advise has not been started.
- A system error has occurred.

## **Stop Keystroke Intercept**

Using the **Stop Close Intercept** function, the client application stops intercepting the keystrokes.

<b>DDE Parameter</b>	<b>Value</b>
<b>Item</b>	KEYS

The client application can use the Personal Communications DDE function by specifying the DDE function (Unadvise) of the client application with the foregoing item name.

### **Personal Communications Response**

If Personal Communications do not stop Keystroke Intercept, it may be because:

- An incorrect item name was specified.
- The Advise has not been started.

- A system error has occurred.

## Stop Session Advise

The **Stop Session Advise** function closes the link between the client application and Personal Communications.

DDE Parameter	Value
Item	PS (pos, len, bCaseSen, "string") PS TRIMRECT (row1, col1, row2, col2) TRIMRECT (pos1, pos2) TRIMRECT OIA

The maximum length of the search string is 255.

The item name must be the same item name that was used when **Start Session Advise** was called.

The client application can use the Personal Communications DDE function by specifying the DDE function (Unadvise) of the client application with the foregoing item name.

## Personal Communications Response

If Personal Communications do not stop Advise, it may be because:

- An incorrect item name was specified.
- The Advise has not been started
- A system error has occurred.

## Terminate Session Conversation

The **Terminate Session Conversation** function terminates the DDE conversation between the client application and the Personal Communications session.

Use the DDE function (Terminate) of the client application to terminate the DDE conversation.

## Visual Basic Sample Program

Following is a sample program with Visual Basic:

**Note:** This sample program is simplified and differs from the actual sample file provided.

```

' /*****
'/*
'/*      System conversation
'/*
' /*****

'*****
'***
'***      Initiate System Conversation
'***
'*****
'
'      Start DDE Conversation with system
'
Sub Command1_Click ()
On Error GoTo ErrHandlerInit

```

```

    Dim COLD As Integer
    COLD = 2
    FunctionComp& = True

    DoEvents
    Text1.LinkTopic = "|System"
    Text1.LinkMode = COLD

    If FunctionComp&= False Then
        MsgBox "Error has occurred", 48, "DDE sample"
    End If
    Exit Sub

ErrHandlerInit:
    FunctionComp& = False
    Resume Next
End Sub

'-- note -----
'
' If you use VisualBasic Version2.0, use "DoEvents"
' function before starting DDE conversation by
' calling "LinkMode" function.
'
'-----
'*****
'***                                     ***
'***   Get System Format                 ***
'***                                     ***
'*****
'
'   Request a list of Personal Communications'   Clipboard Format
'
Sub Command2_Click ()
On Error GoTo ErrHandler
    FunctionComp& = True

    Text1.LinkItem = "Formats"
    Text1.LinkRequest

    If FunctionComp&= False Then
        MsgBox "Error has occurred", 48, "DDE sample"
    End If
    Exit Sub

ErrHandler:
    FunctionComp& = False
    Resume Next
End Sub

'*****
'***                                     ***
'***   Get System Status                 ***
'***                                     ***
'*****
'
'   Requests each Personal Communications'   Session Status
'
Sub Command2_Click ()
On Error GoTo ErrHandler
    FunctionComp& = True

    Text1.LinkItem = "Status"
    Text1.LinkRequest

    If FunctionComp&= False Then
        MsgBox "Error has occurred", 48, "DDE sample"
    End If
    Exit Sub

```

```

        End If
        Exit Sub

ErrorHandler:
    FunctionComp& = False
    Resume Next
End Sub

'*****
'***                                     ***
'***   Get System Configuration         ***
'***                                     ***
'*****
'
'   Requests Personal Communications'   System Configuration Values
'
Sub Command2_Click ()
On Error GoTo ErrorHandler
    FunctionComp& = True

    Text1.LinkItem = "SysCon"
    Text1.LinkRequest

    If FunctionComp&= False Then
        MsgBox "Error has occurred", 48, "DDE sample"
    End If
    Exit Sub

ErrorHandler:
    FunctionComp& = False
    Resume Next
End Sub

'*****
'***                                     ***
'***   Get System SysItems             ***
'***                                     ***
'*****
'
'   Requests a list of Data Items for
'   Personal Communications System Conversation
'
Sub Command2_Click ()
On Error GoTo ErrorHandler
    FunctionComp& = True

    Text1.LinkItem = "SysItems"
    Text1.LinkRequest

    If FunctionComp&= False Then
        MsgBox "Error has occurred", 48, "DDE sample"
    End If
    Exit Sub

ErrorHandler:
    FunctionComp& = False
    Resume Next
End Sub

'*****
'***                                     ***
'***   Get System Topics               ***
'***                                     ***
'*****
'
'   Requests a list of Personal Communications'   Topics
'

```



```

Sub Command2_Click ()
On Error GoTo ErrHandler
    FunctionComp& = True

    Text1.LinkItem = "Topics"
    Text1.LinkRequest

    If FunctionComp&= False Then
        MsgBox "Error has occurred", 48, "DDE sample"
    End If
    Exit Sub

ErrHandler:
    FunctionComp& = False
    Resume Next
End Sub

'*****
'***                                     ***
'***   Terminate System Conversation   ***
'***                                     ***
'*****
'
'   Terminates DDE Conversation with system
'
Sub Command3_Click ()
On Error GoTo ErrHandler
    Dim NONE As IntegerTerm
    NONE = 0
    FunctionComp& = True

    Text1.LinkMode = NONE

    If FunctionComp&= False Then
        MsgBox "Error has occurred", 48, "DDE sample"
    End If
    Exit Sub

ErrHandlerTerm:
    FunctionComp& = False
    Resume Next
End Sub

'*****/
'/*                                     */
'/*   Session conversation             */
'/*                                     */
'*****/

'*****
'***                                     ***
'***   Initiate Session Conversation   ***
'***                                     ***
'*****
'
'   Initiate DDE Conversation with system
'
Sub Command1_Click ()
On Error GoTo ErrHandlerInit
    Dim COLD As Integer
    COLD = 2
    FunctionComp& = True

    DoEvents
    Text1.LinkTopic = "|SessionA"
    Text1.LinkMode = COLD

```

```

    If FunctionComp&= False Then
        MsgBox "Error has occurred", 48, "DDE sample"
    End If
    Exit Sub

ErrHandlerInit:
    FunctionComp& = False
    Resume Next
End Sub

'-- note -----
'
' If you use VisualBasic Version2.0, use "DoEvents"
' function before starting DDE conversation by
' calling "LinkMode" function.
'
'-----
'*****
'***                                     ***
'***   Find Field                       ***
'***                                     ***
'*****
'
'   Requests 100 Field Information of PS Position
'
Sub Command2_Click ()
On Error GoTo ErrHandler
    FunctionComp& = True

    Text1.LinkItem = "FILED(100," " ")
    Text1.LinkRequest

    If FunctionComp&= False Then
        MsgBox "Error has occurred", 48, "DDE sample"
    End If
    Exit Sub

ErrHandler:
    FunctionComp& = False
    Resume Next
End Sub

'*****
'***                                     ***
'***   Get Operator Information Area     ***
'***                                     ***
'*****
'
'   Requests OIA Data
'
Sub Command2_Click ()
On Error GoTo ErrHandler
    FunctionComp& = True

    Text1.LinkItem = "OIA"
    Text1.LinkRequest

    If FunctionComp&= False Then
        MsgBox "Error has occurred", 48, "DDE sample"
    End If
    Exit Sub

ErrHandler:
    FunctionComp& = False
    Resume Next
End Sub
'*****

```

```

'***                                     ***
'***   Get Partial Presentation Space   ***
'***                                     ***
'*****
'
'   Requests PS Data Bytes from PS Position from 100 to 1000
'
Sub Command2_Click ()
On Error GoTo ErrHandler
FunctionComp& = True

Text1.LinkItem = "EPS(100,1000,1)"
Text1.LinkRequest

If FunctionComp&= False Then
MsgBox "Error has occurred", 48, "DDE sample"
End If
Exit Sub

ErrHandler:
FunctionComp& = False
Resume Next
End Sub

'*****
'***                                     ***
'***   Get Presentation Space           ***
'***                                     ***
'*****
'
'   Requests PS Data
'
Sub Command2_Click ()
On Error GoTo ErrHandler
FunctionComp& = True

Text1.LinkItem = "PS"
Text1.LinkRequest

If FunctionComp&= False Then
MsgBox "Error has occurred", 48, "DDE sample"
End If
Exit Sub

ErrHandler:
FunctionComp& = False
Resume Next
End Sub

'*****
'***                                     ***
'***   Get Session Status               ***
'***                                     ***
'*****
'
'   Requests Session Connection Status
'
Sub Command2_Click ()
On Error GoTo ErrHandler
FunctionComp& = True

Text1.LinkItem = "SSTAT"
Text1.LinkRequest

If FunctionComp&= False Then
MsgBox "Error has occurred", 48, "DDE sample"
End If

```

```

Exit Sub

ErrorHandler:
    FunctionComp& = False
    Resume Next
End Sub
'*****
'***                                     ***
'***   Get Trim Rectangle                 ***
'***                                     ***
'*****
'
'   Requests PS Data in Current Specified Trim Rectangle
'
Sub Command2_Click ()
On Error GoTo ErrorHandler
    FunctionComp& = True

    Text1.LinkItem = "TRIMRECT"
    Text1.LinkRequest

    If FunctionComp&= False Then
        MsgBox "Error has occurred", 48, "DDE sample"
    End If
Exit Sub

ErrorHandler:
    FunctionComp& = False
    Resume Next
End Sub

'*****
'***                                     ***
'***   Put Data to Presentation Space     ***
'***                                     ***
'*****
'
'   Writes string "Hello, World!" from PS Position 200
'
Sub Command2_Click ()
On Error GoTo ErrorHandler
    FunctionComp& = True

    Text1.Text      = "Hello, World!"
    Text1.LinkItem = "EPS(200,1)"
    Text1.LinkPoke

    If FunctionComp&= False Then
        MsgBox "Error has occurred", 48, "DDE sample"
    End If
Exit Sub

ErrorHandler:
    FunctionComp& = False
    Resume Next
End Sub

'*****
'***                                     ***
'***   Search for String                   ***
'***                                     ***
'*****
'
'   Search forward for string "Hello!" from PS Position 1
'
Sub Command2_Click ()

```

```

On Error GoTo ErrHandler
FunctionComp& = True

Text1.LinkItem = "STRING(1,1,""Hello!"")"
Text1.LinkRequest

If FunctionComp&= False Then
MsgBox "Error has occurred", 48, "DDE sample"
End If
Exit Sub

ErrHandler:
FunctionComp& = False
Resume Next
End Sub

'*****
'***                                     ***
'***   Session Execute Macro           ***
'***                                     ***
'*****
'
'   Maximize the Session
'
Sub Command2_Click ()
On Error GoTo ErrHandler
FunctionComp& = True

Text1.LinkExecute "[WINDOW(MAXIMIZE)]"

If FunctionComp&= False Then
MsgBox "Error has occurred", 48, "DDE sample"
End If
Exit Sub

ErrHandler:
FunctionComp& = False
Resume Next
End Sub

'*****
'***                                     ***
'***   Set Cursor Position             ***
'***                                     ***
'*****
'
'   Set Cursor Position (Row,Column) = (1,1)
'
Sub Command2_Click ()
On Error GoTo ErrHandler
FunctionComp& = True

Text1.Text      = "RIC1"
Text1.LinkItem = "SETCURSOR"
Text1.LinkPoke

If FunctionComp&= False Then
MsgBox "Error has occurred", 48, "DDE sample"
End If
Exit Sub

ErrHandler:
FunctionComp& = False
Resume Next
End Sub

'*****

```

```

'***                                     ***
'***   Terminate Session Conversation   ***
'***                                     ***
'*****
'
'   Terminate DDE Conversation with session
'
Sub Command3_Click ()
On Error GoTo ErrHandlerTerm
Dim NONE As Integer
NONE = 0
FunctionComp& = True

Text1.LinkMode = NONE

If FunctionComp&= False Then
MsgBox "Error has occurred", 48, "DDE sample"
End If
Exit Sub

ErrHandlerTerm:
FunctionComp& = False
Resume Next
End Sub

'*****/
'/*                                     */
'/*   Session conversation(Hot Link)   */
'/*                                     */
'*****/

'*****
'***                                     ***
'***   Start Close Intercept           ***
'***                                     ***
'*****
'
'   Start Intercepting Close request
'
Sub Command1_Click ()
On Error GoTo ErrHandlerInit
Dim HOT As Integer
HOT = 1
FunctionComp& = True

DoEvents
Text1.LinkTopic = "|SessionA"
Text1.LinkItem = "CLOSE"
Text1.LinkMode = HOT

If FunctionComp&= False Then
MsgBox "Error has occurred", 48, "DDE sample"
End If
Exit Sub

ErrHandlerInit:
FunctionComp& = False
Resume Next
End Sub

'-- note -----
'
' If you use VisualBasic Version2.0, use "DoEvents"
' function before starting DDE conversation by
' calling "LinkMode" function.
'
'-----

```

```

'*****
'***                                     ***
'***   Start Keystroke Intercept         ***
'***                                     ***
'*****
'
'   Start Intercepting Keystrokes
'
Sub Command1_Click ()
On Error GoTo ErrHandlerInit
    Dim HOT As Integer
    HOT = 1
    FunctionComp& = True

    DoEvents
    Text1.LinkTopic = "|SessionA"
    Text1.LinkItem = "KEYS"
    Text1.LinkMode = HOT

    If FunctionComp&= False Then
        MsgBox "Error has occurred", 48, "DDE sample"
    End If
    Exit Sub

ErrHandlerInit:
    FunctionComp& = False
    Resume Next
End Sub

'-- note -----
'
' If you use VisualBasic Version2.0, use "DoEvents"
' function before starting DDE conversation by
' calling "LinkMode" function.
'
'-----
'*****
'***                                     ***
'***   Start Session Advise(PS)         ***
'***                                     ***
'*****
'
'   Receives PS Data when updated
'   (only when "Hello!" is displayed from PS Position 1)
'
Sub Command1_Click ()
On Error GoTo ErrHandlerInit
    Dim HOT As Integer
    HOT = 1
    FunctionComp& = True

    DoEvents
    Text1.LinkTopic = "|SessA_PS"
    Text1.LinkItem = "PS(1,6,1,""Hello!"" )"
    Text1.LinkMode = HOT

    If FunctionComp&= False Then
        MsgBox "Error has occurred", 48, "DDE sample"
    End If

    Exit Sub

ErrHandlerInit:
    FunctionComp& = False
    Resume Next
End Sub

```

```

'-- note -----
'
' If you use VisualBasic Version2.0, use "DoEvents"
' function before starting DDE conversation by
' calling "LinkMode" function.
'
'-----
'*****
'***                                     ***
'***   Start Session Advise(TRIMRECT)   ***
'***                                     ***
'*****
'
'   Receives PS Data in Trim Rectangle when PS Data in Trim Rectangle
'   specified by R1C1:R20C40 is changed
'
Sub Command1_Click ()
On Error GoTo ErrHandlerInit
Dim HOT As Integer
HOT = 1
FunctionComp& = True

DoEvents
Text1.LinkTopic = "|SessA_TRIMRECT"
Text1.LinkItem = "TRIMRECT(1,1,20,40)"
Text1.LinkMode = HOT

If FunctionComp&= False Then
MsgBox "Error has occurred", 48, "DDE sample"
End If
Exit Sub

ErrHandlerInit:
FunctionComp& = False
Resume Next
End Sub

'-- note -----
'
' If you use VisualBasic Version2.0, use "DoEvents"
' function before starting DDE conversation by
' calling "LinkMode" function.
'
'-----
'*****
'***                                     ***
'***   Start Session Advise(OIA)       ***
'***                                     ***
'*****
'
'   Receives OIA Data when changed
'
Sub Command1_Click ()
On Error GoTo ErrHandlerInit
Dim HOT As Integer
HOT = 1
FunctionComp& = True

DoEvents
Text1.LinkTopic = "|SessA_OIA"
Text1.LinkItem = "OIA"
Text1.LinkMode = HOT

If FunctionComp&= False Then
MsgBox "Error has occurred", 48, "DDE sample"
End If
Exit Sub

```



```

ErrHandlerInit:
    FunctionComp& = False
    Resume Next
End Sub

'-- note -----
'
' If you use VisualBasic Version2.0, use "DoEvents"
' function before starting DDE conversation by
' calling "LinkMode" function.
'
'-----
'*****
'***                                     ***
'***   Terminate Session Conversation(Hot Link) ***
'***                                     ***
'*****
'
'   Terminate DDE Conversation with session (Hot Link)
'
Sub Command3_Click ()
On Error GoTo ErrHandlerTerm
    Dim NONE As Integer
    NONE = 0
    FunctionComp& = True

    Text1.LinkMode = NONE

    If FunctionComp&= False Then
        MsgBox "Error has occurred", 48, "DDE sample"
    End If
Exit Sub

ErrHandlerTerm:
    FunctionComp& = False
    Resume Next
End Sub

```



---

## Chapter 8. Server-Requester Programming Interface (SRPI) Support

The Server-Requester Programming Interface (SRPI) is an API that provides access to IBM Enhanced Connectivity Facility (ECF) providing the tools to write SRPI requester programs. SRPI uses a single verb, SEND\_REQUEST, to provide a synchronous call-return interface to remote server programs.

**Note:** SRPI is not available on Personal Communications for AS/400 and will not work when connected to an AS/400 host.

PC/3270 SRPI for Windows 95/98/NT supports the following programs:

- 32-bit SRPI Requester Program written in C or C++
- The existing 16-bit SRPI Requester Program for PC/3270 for Windows 3.1

---

### How to Use SRPI

You can write the application program using the SRPI in C or C++ for Windows 95/98/NT. To develop a SRPI application, do as follows:

1. Prepare the source code and add the appropriate SRPI calls.
2. Include the header file UCCPRB.H in the application program.
3. Compile the source code.
4. Link the resultant .OBJ files with the appropriate object file or libraries.

You must also link it with the SRPI import library, PCSCAL32.LIB for 32-bit and PCSCALLS.LIB for 16-bit.

---

### SRPI Compatibility

PC/3270 supports the SRPI function with:

- SRPI interface is the same as Personal Communications Version 3.1.
- The SRPI interface has the same function calls as the API calls and parameters of CM/2, except that multiple concurrent SRPI requester applications support the same 3270 logical terminal session.
- The return codes for errors or successful operations are the same as with CM/2.
- The SRPI interface is usable via a host connect of the emulator in all modes (except asynchronous and Control Unit Terminal connection) when the physical connection to the host is through a token ring or a coaxial cable, or through SNA or non-SNA protocols.
- If a call is made to the SRPI interface but there is no response from the host due to a communication failure, an associated error is returned to the caller.
- SRPI and EHLLAPI are capable of concurrent operations.
- SRPI is supported only for C requester.
- Server Alias is not supported.
- The 3270 screen update notify is not supported.

**PCSSRPI.DLL** is provided to support the existing 16-bit SRPI applications for Personal Communications **PCSSRPI.DLL** converts 16-bit addressing to 32-bit addressing and passes it to PC/3270 SRPI DLL.




Figure 7. Example of PC/3270 SRPI Requester and Server

## Using the Server-Requester Programming Interface

The API between SRPI requesters from the workstation and servers on the host computer is the Server-Requester Programming Interface (SRPI).

**Note:** For information about a corresponding interface for servers on the IBM host computer, see one of the following publications:

- *TSO/E Version 2 Guide to the Server-Requester Programming Interface*
- *IBM Programmer's Guide to the Server-Requester Programming Interface for VM/System Product*

When used on a workstation, SRPI supports only SRPI requesters. It provides a call-return function for application-to-application communication. Using the **SEND\_REQUEST** function, a program on a workstation calls (requests) for service from a partner program on a host computer, which returns (services) the results.

See Figure 8 for an illustration of the workstation and host computer relationship.




Figure 8. IBM Workstation Requester and IBM Host Computer Server Relationship

Applications use SRPI by issuing the **SEND\_REQUEST** verb.

When a workstation SRPI requester issues the **SEND\_REQUEST** verb using SRPI:

1. The SRPI router converts the request into a structure that the host computer router recognizes.
2. The SRPI router passes the request to the host computer router, using the appropriate 3270 terminal emulation session.
3. The host computer router passes the request to the appropriate host computer server.
4. The host computer server processes the request and passes a reply back to the host computer router.
5. The host computer router passes the reply back to the SRPI router.
6. The SRPI router converts and returns the reply to the originating SRPI requester application. See Figure 9 for for an illustration of the requester and server flow.




Figure 9. Example of an SRPI Requester and Server Flow

## SEND\_REQUEST Parameters

The SRPI router sends the request to the host computer using the communication facilities provided by 3270 terminal emulation. SRPI returns control to the SRPI requester with an appropriate return code, optional parameters, and optional data.

The parameters and data associated with the **SEND\_REQUEST** function are described in Table 25 on page 361 and in Table 26 on page 362.

# Supplied Parameters

Table 25. Parameters Supplied by the SRPI Requester

Name of Parameter	Required/Optional	Default Value	Description
Server name	Required	Blanks	The name of the host computer server must be 8 bytes long (PC/ASCII), left-justified, and padded with blanks (X'20'); leading blanks, embedded blanks, and names consisting of all blanks are not valid. The valid PC/ASCII characters are A through Z (uppercase and lowercase), 0 through 9, \$, #, and @. The name is converted to EBCDIC before the request is sent to the host computer.
Function ID	Optional	0	A 2-byte unsigned binary number that specifies the server function being requested. Values of 0 through 65535 are valid for specification by an SRPI requester.
Request parameters length	Optional	0	A 2-byte unsigned binary number that specifies the byte length of the request parameters to be passed to the server. Values of 0 through 32763 are valid. A value of 0 indicates that there are no request parameters to be passed.
Request parameters pointer	Optional	0	The 4-byte address of the parameters, if any, to be passed to the server. A nonzero value in the request parameters length indicates that there are parameters to be passed.
Request data length	Optional	0	A 2-byte unsigned binary number that specifies the byte length of the request data to be passed to the server. Values of 0 through 65535 are valid. A value of 0 indicates that there is no request data to be passed.
Request data pointer	Optional	0	The 4-byte address of the data, if any, to be passed to the server. A nonzero value in the request data length indicates that there is data to be passed.

Table 25. Parameters Supplied by the SRPI Requester (continued)

Name of Parameter	Required/Optional	Default Value	Description
Reply parameters buffer length	Optional	0	A 2-byte unsigned binary number that specifies the length in bytes of the reply parameter buffer supplied by the SRPI requester. Values of 0 through 32763 are valid. A value of 0 indicates that no reply parameters are expected from the server.
Reply parameters buffer pointer	Optional	0	The 4-byte address of the reply parameter buffer. Its presence is indicated by a nonzero value in the reply parameters buffer length.
Reply data buffer length	Optional	0	A 2-byte unsigned binary number that specifies the length in bytes of the reply data buffer supplied by the SRPI requester. Values of 0 through 65535 are valid. A value of 0 indicates that no reply data is expected from the server.
Reply data buffer pointer	Optional	0	The 4-byte address of the reply data buffer. A nonzero value in the reply data buffer length indicates that there is reply data to be received.

## Returned Parameters

Table 26. Parameters Returned to the SRPI Requester

Name of Parameter	Description
SRPI return code	A 4-byte value that specifies the results of the <b>SEND_REQUEST</b> execution. See Appendix F., for a complete description of SRPI return codes.
Server return code	A 4-byte value returned by the server. The contents and meaning of the return status are defined by the requester or the server, but the length of the field is always 32 bits.
Replied parameter length	A 2-byte unsigned binary storage location that specifies the number, in bytes, of parameters returned by the server. Values of 0 through 32763 are valid. A value of 0 indicates that no reply parameters were received from the server.
Replied data length	A 2-byte unsigned binary storage location that specifies the length in bytes of the data returned by the server. Values of 0 through 65535 are valid. A value of 0 indicates that no reply data was received from the server.

### Notes:

1. You can set the default values by using the appropriate request record initialization function.
2. The server name is used to route the **SEND\_REQUEST** to a 3270 session and to invoke the host server.



3. SRPI requesters and servers determine the contents and meaning of the application data and parameters pointed to by the addresses in the connectivity programming request block (CPRB).

---

## How PC/3270 Applications Use SRPI

A local application running on PC/3270 can issue the **SEND\_REQUEST** verb to an application on a connected remote computer. The local application is the SRPI requester and the remote application is the intended server. The SRPI requester can identify a specific function of the server by specifying a function ID.

If the contact is successful, the remote application can provide its services to the SRPI requester. Information on invoking and implementing the **SEND\_REQUEST** function follows.

---

## Invoking SEND\_REQUEST

When an application invokes **SEND\_REQUEST**, it appears to the program that the main routine (the local application) calls a subroutine (the remote application). The programmer who writes the requester application must perform the following tasks:

1. Obtain storage for the connectivity programming request block (CPRB).
2. Initialize the CPRB. This involves setting the default values and completing the application parameters.

PC/3270 provides initialization routines and macros for each supported language. These initialization facilities insulate the application from the CPRB mapping and call mechanisms.

3. Call the SRPI dynamic link library (DLL) by issuing **SEND\_REQUEST**.
4. Validate the SRPI return code received in the CPRB.

The **SEND\_REQUEST** function is implemented as a DLL.

---

## Performance Considerations

The size of the data transfer buffers used by the SRPI router to exchange data with the host computer is calculated automatically by PC/3270. If your SRPI requester produces requests that transfer large blocks of data to and from the server, performance might be improved by overriding the data transfer buffer size calculated by PC/3270. This is accomplished by changing the definition of the logical 3270 display terminals used for SRPI.

The data transfer buffer-size override parameter supplied on the Create/Change Logical 3270 Display Terminal window is used to change the buffer size used by SRPI. A value of 0 indicates that PC/3270 calculates the buffer size. Other values (from 1 through 32) specify the buffer size in multiples of 1024 bytes. Be aware that large values (such as 30) might improve SRPI performance at the expense of overall system performance. Note that the data transfer buffer-size override parameter also sets the size of the data transfer buffers used by the File Transfer feature.

---

## Handling the Interrupt (Ctrl+Break) Key

During processing of a **SEND\_REQUEST** verb, all signals (except numeric coprocessor signals) are delayed until verb completion. In particular, pressing the Interrupt (Ctrl+Break) key does not cancel a program during execution of a **SEND\_REQUEST** verb.

---

## C Requesters

This section is for programmers who want to write a requester in the C language. It describes:

- C `send_request` function
- SRPI record definition
- **Send\_request** function definition
- SRPI return codes

Sample programs are supplied on Personal Communications Version 4.3 for Windows 95, Windows 98, and Windows NTCD-ROM media.

**Note:** To follow C conventions, the function called **SEND\_REQUEST** in other sections is spelled **send\_request** in this section.

## C `send_request` Function

The **send\_request** parameters are grouped into a single C structure of type `UERCPRB`. The **init\_send\_req\_parms** function is provided to initialize all **send\_request** parameters in the `UERCPRB` structure to their defaults. This allows the default values to be set once for parameters not used by a requester. The **send\_request** function is provided to make synchronous calls to the server program.

The **init\_send\_req\_parms** and **send\_request** functions must be linked with your C application. `PCSSRP32.DLL` for 32-bit interface and `PCSSRPI.DLL` for 16-bit interface; both of these object files are provided with PC/3270.

The **send\_request** function copies the contents of the `UERCPRB` structure into a connectivity programming request block (CPRB) and calls the `PCSSRP32.DLL`. After the server has completed its processing, the **send\_request** procedure copies the returned parameters from the CPRB into the `UERCPRB` structure and returns control to the C application.

If the request parameters or data consist of several structures, the application must convert the data or parameters into a single flat structure that consists of a contiguous sequence of bytes that are stored in a buffer. The requesting program must package the request parameters and data in a format recognizable by the server.

`UERCPRB` is a packed structure. That is, each structure member after the first member is stored at the first available byte.

The memory used for the request parameters can also be used for the reply parameters; the memory used for the request data can also be used for the reply

data. The application program must ensure that the reply data and parameters are written into the request data and parameters buffer only when the request data and parameters are no longer needed.

## SRPI Record Definition

The UERCPRB record type defines a record passed to the SRPI router using the **send\_request** function. The record is defined in an application program by using the `#include` preprocessor directive to include the UUCCPRB.H file. For the definitions and value ranges of the supplied and returned parameters, see “Supplied Parameters” on page 361 and “Returned Parameters” on page 362.

## SRPI Return Codes

See “Appendix F. SRPI Return Codes” on page 389 for the SRPI return codes.



---

## Appendix A. Query Reply Data Structures Supported by EHLLAPI

This appendix lists and defines the query reply structures supported by the EHLLAPI structured field interface for PC/3270. See the *IBM 3270 Information Display System Data Stream Programmer's Reference* or, in the case of an IBM licensed program, the documentation for the specific licensed program.

### Notes:

1. EHLLAPI must scan the query reply buffers to locate the destination/origin ID (DOID) self-defining parameter (SDP) for the structured field support to work and be reliable. The DOID field is then filled in with the assigned ID.
2. The application should build the query reply data structures in the application's private memory.
3. Only cursory checking is performed on the query reply data. Only the ID and the length of the structure are checked for validity.
4. The 2-byte length field at the beginning of each query reply **is not byte reversed**.
5. Only one distributed data management (DDM) base-type connection is allowed per host session. If the DDM connection supports the SDP for the DOID, multiple connections are allowed.
6. If a nonzero return code is received indicating that an application is already connected to the selected session (RC 32 or 39), use that presentation space with caution. Conflicts with SRPI, File Transfer, and other EHLLAPI applications might result.

---

## The DDM Query Reply

Several DDM query reply formats are supported. Here are some of them:

Table 27. DDM Query Reply Base Format

Offset	Length	Content	Meaning
0	1 word	Length	Length of structure
2	1 byte	X'81'	Query reply ID
3	1 byte	X'95'	Query reply type
4-5	2 bytes	FLAGS	Reserved
6-7	2 bytes	LIMIN	Maximum DDM bytes allowed in inbound transmission
8-9	2 bytes	LIMOUT	Maximum DDM bytes allowed in outbound transmission
10	1 byte	NSS	Number of subsets identifier
11	1 byte	DDMSS	DDM subset identifier

## DDM Application Name Self-Defining Parameter

The DDM application name self-defining parameter provides the host application with the name of the application containing control of the DDM auxiliary device. The controlling application is identified by the DOID in the Direct Access self-defining parameter.

This self-defining parameter is optional, but it is necessary if a host application is to identify a distinct DDM auxiliary device when more than one application is in existence at a remote workstation.

Table 28. DDM Application Name Self-Defining Parameter

Offset	Length	Content	Meaning
0	1 byte	Length	Parameter length
1	1 byte	X'02'	DDM application name
2–n	n–2 bytes	NAME	Name of the remote application program

- **NAME.** The name consists of 8 characters or less and is the means by which a host application can relate to an application in a remote workstation. It is the responsibility of the host and remote application users to ensure that the name is understood by the application at each end.

## PCLK protocol controls Self-Defining Parameter

The PCLK Protocol Controls self-defining parameter indicates that the PCLK Protocol Controls structured field, ID = X'1013', can be used for both inbound and outbound in data streams destined to or from the DDM auxiliary device processor.

Table 29. DDM PCLK Auxiliary Device Self-Defining Parameter

Offset	Length	Content	Meaning
0	1 byte	X'04'	Parameter length
1	1 byte	X'03'	PCLK protocol controls
2–3	2 bytes	VERS	Protocol version

- **VERS.** The value given in VERS is used to indicate the versions of PCLK installed in the terminal at the time the query reply is returned. For example, X'0001' indicates PCLK Version 1.1.

See the *IBM 3270 Information Display System Data Stream Programmer's Reference* for the field definitions for this query reply.

## Base DDM Query Reply Formats

The following query reply formats are *examples* of some of the Base + SDP (self-defining parameter) combinations possible. Not all of the combinations are shown.

Table 30. Base DDM Query Reply Format with Name and Direct Access Self-Defining Parameters

Offset	Length	Content	Meaning
0	1 word	Length	Length of structure (includes self-defining parameters)
2	1 byte	X'81'	Query reply ID
3	1 byte	X'95'	Query Reply type
4–5	2 bytes	FLAGS	Reserved
6–7	2 bytes	LIMIN	Maximum DDM bytes allowed in inbound transmission
8–9	2 bytes	LIMOUT	Maximum DDM bytes allowed in outbound transmission
10	1 byte	NSS	Number of subsets supported
11	1 byte	DDMSS	DDM subset identifier
12	1 byte	Length (n+2)	Parameter length
13	1 byte	X'02'	DDM application name
14– (13+n)	n bytes	Name	Name of the remote application program
14+n	1 byte	X'04'	Parameter length
15+n	1 byte	X'01'	Direct access ID
16+n – 17+n	2 bytes	DOID	Destination/origin ID assigned by the subsystem

The self-defining parameters begin at offsets 12 and (14 + n) where n is the length of the application name supplied at offset 14.

See the *IBM 3270 Information Display System Data Stream Programmer's Reference* for the field definitions for this query reply.

Table 31. Base DDM Query Reply Format with Direct Access and Name Self-Defining Parameters

Offset	Length	Content	Meaning
0	1 word	Length	Length of structure (includes self-defining parameters)
2	1 byte	X'81'	Query reply ID
3	1 byte	X'95'	Query reply type
4–5	2 bytes	FLAGS	Reserved
6–7	2 bytes	LIMIN	Maximum DDM bytes allowed in inbound transmission
8–9	2 bytes	LIMOUT	Maximum DDM bytes allowed in outbound transmission

Table 31. Base DDM Query Reply Format with Direct Access and Name Self-Defining Parameters (continued)

Offset	Length	Content	Meaning
10	1 byte	NSS	Number of subsets supported
11	1 byte	DDMSS	DDM subset identifier
12	1 byte	X'04'	Parameter length
13	1 byte	X'01'	Direct access ID
14–15	2 bytes	DOID	Destination/origin ID assigned by the subsystem
16	1 byte	Length (n+2)	Parameter length
17	1 byte	X'02'	DDM application name
16+n – 17+n	n bytes	Name	Name of the remote application program

The self-defining parameters begin at offsets 12 and 16.

See the *IBM 3270 Information Display System Data Stream Programmer's Reference* for the field definitions for this query reply.

---

## The IBM Auxiliary Device Query Reply

The Auxiliary Device Reply is used to indicate to the host application the support of an IBM auxiliary device that uses a data stream defined by IBM, see the *IBM 3270 Information Display System Data Stream Programmer's Reference* for more details.

When the function is supported, the query reply is transmitted inbound in reply to a Read Partition structured field specifying Query or Query List (QCODE List = X'9E', Equivalent, or All).

When a workstation supports multiple auxiliary devices, the IBM auxiliary devices query reply must be sent for each device.

### Optional Parameters:

All parameters shown in the “base” part of the query reply must be present. Parameters not used are set to X'00'.

At least one self-defining parameter must be present.

Table 32. IBM Auxiliary Device Base Format with Direct Access Self-Defining Parameter

Offset	Length	Content	Meaning
0–1	1 word	Length	Length of structure (includes self-defining parameters)
2	1 byte	X'81'	Query reply ID
3	1 byte	X'9E'	IBM auxiliary device reply



Table 32. IBM Auxiliary Device Base Format with Direct Access Self-Defining Parameter (continued)

Offset	Length	Content	Meaning
4	1 byte	FLAGS	Reserved
	BIT 0	QUERY B'1'	Read Part (Query, Query List) Auxiliary device supports Query
	1–7	RES	Reserved, must be B'0's
5	1 byte	FLAGS	Reserved
6–7	2 bytes	LIMIN	Maximum DDM bytes allowed in inbound transmission
8–9	2 bytes	LIMOUT	Maximum DDM bytes allowed in outbound transmission
10	1 byte	TYPE X'01' X'02' Others	Type of auxiliary device supported IBM auxiliary device display IBM auxiliary device printer Reserved
11	1 byte	X'04'	Parameter length
12	1 byte	X'01'	Direct access
13–14	1 word	DOID	Destination/origin ID assigned by the subsystem

**QUERY** This bit must be set to B'1' for all IBM auxiliary devices to indicate that it supports receiving a Read Partition (Query, Query List). The host applications can then use a Read Partition directed to the auxiliary device to determine its characteristics. The destination/origin structured field is used to direct the Read Partition structured field to the auxiliary device.

The minimum support level for the IBM auxiliary device is to return the Null query reply in response to the Read Partition.

**LIMIN** States the maximum number of bytes that can be sent in an inbound transmission. A LIMIN value of X'0000' indicates no implementation limit on the number of bytes transmitted inbound.

**LIMOUT** States the maximum number of bytes that can be sent to an IBM auxiliary device in an outbound transmission. A LIMOUT value of X'0000' indicates no implementation limit on the number of bytes transmitted outbound.

**TYPE** Identifies the auxiliary device being supported. Two values are valid. One identifies an auxiliary display and the other identifies an auxiliary printer. All other values are reserved.

The IBM auxiliary device processor supports two self-defining parameters, 01 and 03. These are defined in Table 33.

## Direct Access Self-Defining Parameter

The direct access self-defining parameter provides the ID for use in the destination/origin structured field in the direct access of the IBM auxiliary device.

This SDP is always required to accompany the base query reply.

Table 33. IBM Auxiliary Device Direct Access Self-Defining Parameter

Offset	Length	Content	Meaning
0	1 byte	X'04'	Parameter length

Table 33. IBM Auxiliary Device Direct Access Self-Defining Parameter (continued)

Offset	Length	Content	Meaning
1	1 byte	X'01'	Direct access ID
2-3	2 bytes	DOID	Destination/origin ID

- **DOID.** The value in these bytes is used in the ID field of the destination/origin structured field to identify the auxiliary device as the destination or origin of the data that follows.

## PCLK Protocol Controls Self-Defining Parameter

The presence of the PCLK protocol controls self-defining parameter indicates that the PCLK protocol controls structured field, ID = X'1013', can be used for both inbound and outbound in data streams destined to or from the IBM auxiliary device processor.

Table 34. IBM Auxiliary Device PCLK Self-Defining Parameter

Offset	Length	Content	Meaning
0	1 byte	X'04'	Parameter length
1	1 byte	X'03'	PCLK protocol controls
2-3	2 bytes	VERS	Protocol version

- **VERS.** The value given in VERS is used to indicate the versions of PCLK installed in the terminal at the time the query reply is returned. For example, X'0001' indicates PCLK version 1.1.

See the *IBM 3270 Information Display System Data Stream Programmer's Reference* for the field definitions for this query reply.

---

## The OEM Auxiliary Device Query Reply

The OEM Auxiliary Device query reply format is as follows:

Table 35. OEM Auxiliary Device Base Format with Direct Access Self-Defining Parameter

Offset	Length	Content	Meaning
0-1	1 word	Length	Length of structure (includes self-defining parameters)
2	1 byte	X'81'	Query reply ID
3	1 byte	X'8F'	OEM query reply
4-5	2 bytes	FLAGS	Reserved
6-13	4 words	DTYPE	Device type
14-21	4 words	UNAME	User assigned name
22	1 byte	X'04'	Parameter length
23	1 byte	X'01'	Direct access
24-25	1 word	DOID	Destination/origin ID assigned by the subsystem

See the *IBM 3270 Information Display System Data Stream Programmer's Reference* for the field definitions for this query reply.

The OEM auxiliary device processor supports two self-defining parameters, 01 and 03. These are defined in Table 36.

## Direct Access Self-Defining Parameter

The direct access self-defining parameter provides the ID for use in the destination/origin structured field in the direct access of the OEM auxiliary device.

Table 36. OEM Auxiliary Device Direct Access Self-Defining Parameter

Offset	Length	Content	Meaning
0	1 byte	X'04'	Parameter length
1	1 byte	X'01'	Direct access ID
2–3	2 bytes	DOID	Destination/origin ID

- **DOID.** The value in these bytes is used in the ID field of the destination/origin structured field to identify the auxiliary device as the destination or origin of the data that follows.

## PCLK Protocol Controls Self-Defining Parameter

The presence of the PCLK protocol controls self-defining parameter indicates that the PCLK Protocol Controls structured field, ID = X'1013', can be used for both inbound and outbound in data streams destined to or from the OEM auxiliary device processor.

Table 37. IBM Auxiliary Device PCLK Self-Defining Parameter

Offset	Length	Content	Meaning
0	1 byte	X'04'	Parameter length
1	1 byte	X'03'	PCLK protocol controls
2–3	2 bytes	VERS	Protocol version

- **VERS.** The value given in VERS is used to indicate the versions of PCLK installed in the terminal at the time the query reply is returned. For example, X'0001' indicates PCLK version 1.1.

---

## The Cooperative Processing Requester Query Reply

The Cooperative Processing Requester query reply is also called the SRPI query reply or CPSI query reply. The format is as follows:

Table 38. CPR Query Reply Buffer Format

Offset	Length	Content	Meaning
0	1 word	Length	Length of structure (includes self-defining parameters)
2	1 byte	X'81'	Query reply ID
3	1 byte	X'AB'	Query reply type
4–5	2 bytes	FLAGS	Reserved
6–7	2 bytes	LIMIN	Maximum DDM bytes allowed in inbound transmission

Table 38. CPR Query Reply Buffer Format (continued)

Offset	Length	Content	Meaning
8–9	2 bytes	LIMOUT	Maximum DDM bytes allowed in outbound transmission
10	1 byte	FETAL	Length (in bytes) of the following feature information
11–12	1 word	FEATS	CPR length and feature flags
13– (N*2)+12	0–2 bytes	FEATsS	Additional flags
(N*2)+12	1 byte	X'04'	Length of DOID SDP
(N*2)+13	1 byte	X'01'	Type of D/O ID
(N*2)+14	1 word	DOID	Destination/origin ID assigned by the subsystem

See the *IBM 3270 Information Display System Data Stream Programmer's Reference* for the field definitions for this query reply.

## The Product-Defined Query Reply

This query reply is used by IBM products using registered subidentifiers within the X'9C' data structure. The Product-Defined Data Stream query reply indicates support of a 3270DS workstation auxiliary device that uses an IBM product-defined data stream. The data stream is *not* defined by a format architecture document having an identifiable control point such as an architecture review board.

When an auxiliary device supports an IBM product-defined data stream, this query reply is transmitted inbound in reply to a Query List (QCODE List = X'9C' or All).

## Optional Parameters

All parameters shown in the base part of the query reply and the direct access self-defining parameter must be present.

The format of the Product-Defined query reply is as follows:

Table 39. IBM Product-Defined Query Reply Base Format

Offset	Length	Content	Meaning
0–1	1 word	Length	Length of structure (includes self-defining parameters)
2	1 byte	X'81'	Query reply ID
3	1 byte	X'9C'	IBM product-defined data stream
4–5	2 bytes	FLAGS	Reserved
6	1 byte	REFID	Reference identifier
7	1 byte	SSID	Subset identifier
8	1 byte	X'04'	Parameter length

Table 39. IBM Product-Defined Query Reply Base Format (continued)

Offset	Length	Content	Meaning
9	1 byte	X'01'	Direct access
10–11	1 word	DOID	Destination/origin ID assigned by the subsystem

Valid values for REFID (offset 6) and SSID (offset 7) of the Product-Defined query reply are as follows:

Table 40. Valid REFID and SSID Values for the IBM Product-Defined Query Reply

REFID	SSID	Product and Data Stream Documentation
X'01'		5080 Graphics System:  This reference ID indicates the 5080 Graphics System data stream is supported by the auxiliary device. Descriptions of the 5080 Graphics Architecture, structured field, subset ID, DOID, and associated function sets are defined in the <i>IBM 5080 Graphics System Principles of Operation</i>
	X'01' X'02'	5080 HGFD Graphics Subset 5080 RS232 Ports Subset
X'02'		WHIP API (replaced by SRL name when written)  This reference ID indicates that the WHIP API data stream is supported by the auxiliary device. A description of the WHIP API architecture is defined in <i>IBM RT PC Workstation Host Interface Program Version 1.1 User's Guide and Reference Manual</i>
	X'01'	WHIP Subset 1
X'03' to X'FF'		All other values are reserved.

The IBM product-defined processor supports only the direct access self-defining parameter. It is defined in Table 41.

## Direct Access Self-Defining Parameter

The presence of the Direct Access ID self-defining parameter indicates that the auxiliary device can be accessed directly by using the destination/origin structured field. When multiple auxiliary devices are supported that use a product-defined data stream, separate Product-Defined Data Stream query replies must be provided, each of which has a unique DOID.

Table 41. IBM Product-Defined Direct Access Self-Defining Parameter

Offset	Length	Content	Meaning
0	1 byte	X'04'	Parameter length
1	1 byte	X'01'	Direct access ID
2–3	2 bytes	DOID	Destination/origin ID

- **DOID.** The value in these bytes is used in the ID field of the destination/origin structured field to identify the auxiliary device as the destination or origin of the data that follows.

## The Document Interchange Architecture Query Reply

This query reply indicates the Document Interchange Architecture (DIA) function set supported. The format of the DIA Query Reply is as follows:

Table 42. IBM DIA Base Format

Offset	Length	Content	Meaning
0	1 word	Length	Length of structure (includes self-defining parameters)
2	1 byte	X'81'	Query reply ID
3	1 byte	X'97'	IBM DIA
4–5	2 bytes	FLAGS	Reserved
6–7	2 bytes	LIMIN	Maximum DDM bytes allowed in inbound transmission
8–9	2 bytes	LIMOUT	Maximum DDM bytes allowed in outbound transmission
10	1 byte	NFS	Number of 3-byte function set IDs that follow
11–13	3 bytes	DIAFS	DIA function set identifier
14– (13+(N*3))	N*3 bytes	DIAFSs	Additional DIA function set IDs
14+(N*3)	1 byte	X'04'	Parameter length
15+(N*3)	1 byte	X'01'	Direct access
16+(N*3)	1 word	DOID	Destination/origin ID assigned by the subsystem

The DIA auxiliary device processor supports only the direct access self-defining parameter. It is defined in Table 43.

### Direct Access Self-Defining Parameter

The presence of the direct access ID self-defining parameter indicates that the auxiliary device can be accessed directly by using the destination/origin structured field.

Table 43. IBM Product-Defined Direct Access Self-Defining Parameter

Offset	Length	Content	Meaning
0	1 byte	X'04'	Parameter length
1	1 byte	X'01'	Direct access ID
2–3	2 bytes	DOID	Destination/origin ID

- **DOID.** The value in these bytes is used in the ID field of the destination/origin structured field to identify the auxiliary device as the destination or origin of the data that follows.

See the *IBM 3270 Information Display System Data Stream Programmer's Reference* for the field definitions for this query reply.





---

## Appendix B. Compatibility with Personal Communications 4.1 for Windows 3.1

This appendix describes the compatibility between EHLLAPI/DDE of Personal Communications for Windows 95, Windows 98, or Windows NT and that for Windows 3.1.

The EHLLAPI of Personal Communications for Windows 95, Windows 98 or Windows NT is different from that for Windows 3.1 in the following ways:

- The entry point name *hllapiw* that is provided by Personal Communications for Windows 3.1 is not supported.
- The event object is newly supported for the asynchronous mode of the notification used by **Start Close Intercept** (41), **Start Host Notification** (23), **Read Structured Fields** (126) and **Write Structured Fields** (127). It can be used by 32-bit applications for Windows 95, Windows 98, or Windows NT.

The DDE of Personal Communications for Windows 95, Windows 98, or Windows NT is different from that for Windows 3.1 in the following ways:

- Code conversion is not supported, use an appropriate API on Personal Communications for EBCDIC/ASCII conversion.
- The application name *IBM3270* or *IBM5250* is for 16-bit applications. *IBM327032* and *IBM525032* are for 32-bit applications.



---

## Appendix C. Compatibility with Communications Manager/2

This appendix describes the compatibility between EHLLAPI of Personal Communications for Windows 95, Windows 98, and Windows NT and Communications Manager/2 (CM/2).

The following EHLLAPI function is not supported by Personal Communications:

- **Storage Manager** (17)

The following EHLLAPI functions are different from those with the same names in CM/2. You need to understand the differences when you use these functions:

- **Set Session Parameter** (9)
- **Copy OIA** (13)
- **Copy String to PS** (15)
- **Copy String to Field** (33)
- **Get Key** (51)
- **Window Status** (104)
- **Query Sessions** (10)
- **Connect for Structured Field** (120)
- **Allocate Communications Buffer** (123)
- ASCII mnemonics

---

### Set Session Parameter (9)

#### Set Options

Personal Communications does not provide the following set options provided by Communications Manager:

OLDOIA, NEWOIA  
COMPCASE, COMPICASE  
OLD5250OIA, NEW5250OIA

#### Return Parameters

When the **Set Session Parameter** (9) function is terminated, Communications Manager returns a length of the valid data string as the third parameter, the data string length. However, Personal Communications returns a number of the valid set options as the data string length.

#### EAB Option

In CM/2, a color remap affects the value of the character color in the EAB attribute copied by **Copy PS** (5) or **Copy PS to String** (8) function when the EAB option is specified in the **Set Session Parameter** (9) function.

In Personal Communications, however, the value of the character color in the EAB attribute depends on the contents of the presentation space regardless of a color remap, and it is not affected by a color remap.

---

## Copy OIA (13)

The **Copy OIA** (13) function has the following differences between CM/2 and Personal Communications. For more information of the group and the column positions, refer to “Copy OIA (13)” on page 44.

- Byte Position 21
  - Personal Communications returns X'F6'.
  - CM/2 returns X'20'.
- Byte Positions 61–63
  - Personal Communications does not return the printer information.
  - CM/2 returns the printer information.
- Group 3: Shift State

CM/2 does not return the value of bit 2. Bit 2 is reserved, and bit 0 contains both the Upper Shift and the Caps Lock.
- Group 8 Byte 1: Input Inhibited
  - Personal Communications does not return bit 6 (Device not working).
  - CM/2 can return bit 6.
- Group 8 Byte 3: Input Inhibited
  - Personal Communications does not return bit 1 (Operator unauthorized) and bit 2 (Operator unauthorized -f).
  - CM/2 can return bits 1 and 2.
- Group 8 Byte 4: Input Inhibited
  - Personal Communications does not return bit 2 (System wait).
  - CM/2 can return bit 2.
- Group 10: Highlight Group 2
  - Personal Communications does not return bit 0 (Selected).
  - CM/2 can return bit 0.
- Group 11: Color Group 2
  - Personal Communications does not return bit 0 (Selected).
  - CM/2 can return bit 0.
- Group 13: Printer Status
  - In Personal Communications, this group is reserved.
  - CM/2 can return this group.
- Group 14: Graphics

CM/2 does not return bit 0 (Graphic cursor).

---

## Copy String to PS (15)

In CM/2, the EAB option of the **Set Session Parameter** (9) function affects the **Copy String to PS** function. When you specify the EAB option, pass the attribute data that has the same size as the text data to the function with the text data.

In Personal Communications, however, the data to be passed is only text data regardless of EAB option. If you want to use the same interface with CM/2, use the PUTEAB option of **Set Session Parameter** (9).

---

## Storage Manager (17)

**Storage Manager** (17) function provided by CM/2 is not supported by Personal Communications. Use the APIs provided by Windows 95, Windows 98, and Windows NT to allocate the memory for the applications.

---

## Copy String to Field (33)

In CM/2, when the EAB option of the **Set Session Parameter** (9) function is specified, the attribute data is passed to the function as a part of the data. Therefore, when you specify the EAB option, pass the attribute data that has the same size as the text data to the function with the text data.

In Personal Communications, however, the EAB option does not affect the data contents of the **Copy String to Field** (33) function. The data to be passed is not the attribute data, but only the text data. If you want to use the same interface with CM/2, use the PUTEAB option of **Set Session Parameter** (9).

---

## Get Key (51)

CM/2 returns shift state using @A, @S, or @r, if the shift state of a passed key is not a key or function recognized by the emulator session. Personal Communications does not support these ASCII mnemonics.

---

## Window Status (104)

EHLAPI function 104 (PM\_WINDOW\_STATUS) 'query extended status' command (0x03) will return the handle of the emulator presentation space window. This is consistent with the definition of the function and the CM/2 implementation. However, Personal Communications AS/400 and 3270 for Windows EHLAPI return the handle of the frame window. EHLAPI applications written for Personal Communications AS/400 and 3270 for Windows using this function need to use the parent of the window handle returned.

---

## Query Sessions (10)

In CM/2 and Personal Communications for OS/2, the descriptor for personal computer is returned.

But in Personal Communications for Window, it is not returned.

---

## Connect for Structured Fields (120)

The event object for communication connection status provided by CM/2 is not in Personal Communications.

---

## Allocate Communications Buffer (123)

In CM/2, the maximum value of the requested buffer size is 64 KB minus 8 bytes (X'FFF8').

In Personal Communications, however, it is 64 KB minus 256 bytes (X'FF00').

---

## ASCII Mnemonics

The following ASCII mnemonics are not supported in Personal Communications:

Mnemonics	Meaning
@A@N	Get Cursor
@A@O	Locate Cursor
@A@X	Hexadecimal
@A@Y	Cmd (Function) Key
@A@a	Destructive Backspace
@S@A	Erase EOL
@S@B	Field Advance
@S@C	Field Backspace
@S@D	Valid Character Backspace
@S@P	POR (For sending only)
@S@T	Jump to Task Manager
@/	Overrun of queue (Only in the <b>Get Key</b> function)

---

## Get Request Completion (125)

Personal Communications does not support a blank or null session ID.

---

## Appendix D. DOS-Mode EHLLAPI (Windows 95, Windows 98, and Windows NT)

IBM eNetwork Personal Communications Version 4.3 supports EHLLAPI applications for DOS. This appendix provides information about this support.

---

### Installation

To install DOS EHLLAPI support for IBM eNetwork Personal Communications Version 4.3 do the following:

1. Select the Emulator Utilities folder from the Utilities folder in the IBM Personal Communications folder.
2. Select DOS EHLLAPI application from the Emulator Utilities folder.
3. Select the check box of the DOS MODE EHLLAPI to enable DOS EHLLAPI support.
4. Enter the major DOS version for which your DOS EHLLAPI applications are written. (For example, 2 for DOS Emulator Version 2.x).
5. Select OK to enable changes.
6. Shut down the workstation and restart it again.

For windows NT, this procedure adds the following statement in config.nt.

```
device=%SystemRoot%\system32\drivers\hll1drv.sys
```

For Windows 95 and Windows 98, this procedure adds the following statement in system.ini.

```
device=<drive:>\windows\system\doshll.vxd
```

**Note:** DOS EHLLAPI applications assert interrupt X'7F' to request EHLLAPI services. Any other proprietary DOS application using interrupt X'7F' will not work with DOS EHLLAPI enabled and vice-versa.

---

### Compatibility

The EHLLAPI of Personal Communications for Windows 95, Windows 98, and Windows NT is different from the EHLLAPI of Personal Communications for Windows 3.1 in the following ways:

- The Asynchronous Update Notification of **Start Close Intercept (41)** function is not supported.
- The Asynchronous Update Notification of **Start Host Notification (23)** function is not supported.
- The entry point name **hllapiw**, is not supported.

The EHLLAPI of Personal Communications for Windows 95, Windows 98, and Windows NT is different from the EHLLAPI of Personal Communications for DOS in the following ways:

- **Storage Manager (27)** function is not supported.





---

## Appendix E. DOS-Mode EHLLAPI (OS/2)

Personal Communications for OS/2 supports EHLLAPI applications for DOS. This chapter provides information about this support.

---

### Installation

If you want to use EHLLAPI applications for PC/3270 for DOS, install the DOS-mode EHLLAPI virtual device driver.

If you want to use EHLLAPI applications for PC/3270 or PC400 for Windows 3.1, install both the DOS-mode EHLLAPI virtual device driver and the PC/3270•5250–Windows Interface Module. This allows execution of Windows 3.1 EHLLAPI applications in a WinOS2 session.

For the installation procedure, refer to the following sections.

### Installation of the DOS-Mode EHLLAPI Virtual Device Driver

When you install the DOS-mode EHLLAPI virtual device driver, do the following:

1. Select the API setting ... from the toolbar.
2. Select the check box of the DOS Mode EHLLAPI.
3. Close the session following the messages.
4. Shut down the workstation and restart it again.

This procedure adds the following statements in CONFIG.SYS:

```
device=c:\pcomos2\vhapi.os2
```

**Note:** c:\pcomos2\ is the directory where PC/3270 or PC400 for OS/2 was installed.

### Installation of the PC/3270•5250–Windows Interface Module

The PC/3270•5250–Windows Interface Module is saved as the name pcsh11.d11 in the directory where Personal Communications for OS/2 was installed.

Copy it into the directory specified in the PATH environment parameter of Win-OS2. Refer to the following example, where OS/2, and Personal Communications for OS/2, were installed in drive C::

```
[C:\]cd \pcomos2
[C:\PCOMOS2]copy pcsh11.d11 c:\os2\mdos\winos2
1 file(s) copied.
```

---

### How to Use DOS-Mode EHLLAPI Applications

When you execute the DOS-mode EHLLAPI application, do as follows:

1. Configure and start the Personal Communications for OS/2 Display Session.
2. Start DOS box or Win-OS2.
3. Start the EHLLAPI application for PC/3270 for DOS, PC/3270 for Windows, or PC400 for Windows.

---

## Compatibility

The EHLLAPI of Personal Communications for OS/2 is different from the EHLLAPI of Personal Communications for Windows 3.1 in the following ways:

- The Asynchronous Update Notification of Start Close Intercept (41) function is not supported.
- The Asynchronous Update Notification of Start Host Notification (23) function is not supported.
- The entry point name `h11apiw`, that is provided by Personal Communications for Windows 3.1, is not supported.

The EHLLAPI of Personal Communications for OS/2 is different from the EHLLAPI of Personal Communications for DOS in the following ways:

- Storage Manager (17) function is not supported.

---

## Appendix F. SRPI Return Codes

This appendix describes error handling in the SRPI environment. Types 0, 1, 2, and 3 return codes and their definitions are listed. Exception class definitions, code values, and object values are listed. Server return codes are also discussed.

---

### Error Handling

An unsuccessful service request in the SRPI environment can result from problems at any of the different layers. SRPI shields applications from transport layer errors as much as possible. Errors within server processing are handled by the applications. The other errors are caused by SRPI and are treated accordingly.

### Transport Layer Errors

SRPI tries to recover from transport layer errors. When recovery is not possible, SRPI returns to the requester with a return code indicating transport layer failure. The programmer should handle such failures using the problem determination procedures of the transport mechanism.

### Application Errors

SRPI is responsible for routing requests to servers and returning replies to requesters. Requesters and servers are responsible for handling errors (except for abend) that servers encounter. When a server ends abnormally, SRPI returns to the requester with an abend notice in the SRPI return code.

The server return code is set by the server on the IBM host computer running under VM or MVS. The value and meaning of the server return code is dependent on the requester or the server.

### SEND\_REQUEST Processing Errors

SRPI return codes can encounter a number of errors in processing the **SEND\_REQUEST** function. Such errors include:

- Incorrect function parameters
- Unidentified server
- Inability to contact the server

There are also system error codes for internal SRPI errors.

---

### Types of SRPI Return Codes

SRPI return codes include types 0, 1, 2, and 3:

#### Type 0

Indicates successful completion of the **SEND\_REQUEST** function.

#### Type 1

Indicates errors detected by the SRPI router that prevent a request from being processed.

### Type 2

Indicates errors detected by the SRPI router and reported to the remote computer by an acknowledge interchange unit.

### Type 3

Indicates errors detected by the remote computer and reported to the SRPI router by an acknowledge interchange unit.

The return code values are word-reversed and byte-reversed within each word. For example, the SRPI return code X'0100 0402' is stored in the CPRB memory as X'0204 0001'.

## Type 0 Return Code Definitions

The type 0 return code (constant return code UERERROK) has the following format: X'0000 0000'. This return code value indicates that the SRPI function completed successfully.

## Type 1 Return Code Definitions

Type 1 return codes have the following format: X'0100 nnnn'.

The *nnnn* bytes are the hexadecimal value that indicates the specific error detected.

The return code definitions and descriptions are listed in Table 44.

Table 44. Type 1 Return Code Definitions and Descriptions

Hexadecimal Return Code	Constant Return Code	Description
X'0100 0402'	UERERRT1START	SRPI is not started because the host ECF program is not started.
X'0100 0404'	UERERRT1LOAD	The SRPI router is not loaded.
X'0100 0408'	UERERRT1BUSY	The SRPI router is busy. This return code is not used by the Personal Communications program.
X'0100 040A'	UERERRT1VER	The version ID in the CPRB passed to the SRPI router is not supported by the resident portion of the SRPI router. The version ID is automatically put into the CPRB by the C interface facility.
X'0100 040C'	UERERRT1EMU	Personal Communications is not loaded.
X'0100 040E'	UERERRT1ROUT	The server name supplied in the CPRB is not defined in the server routing table. Default routing is not configured so SRPI is unable to route the request. Use a valid server name or update the configuration to include the server name.
X'0100 0410'	UERERRT1COMMR	Communications resource not available.
X'0100 0412'	UERERRT1REST	3270 emulation has been restarted since the application last used SRPI. End the application and restart it before using SRPI.

Table 44. Type 1 Return Code Definitions and Descriptions (continued)

Hexadecimal Return Code	Constant Return Code	Description
X'0100 0414'	UERERRT1INUSE	The request has been routed to a communication session that is in use by File Transfer.
X'0100 0602'	UERERRT1QPLEN	Request parameters length exceeds the maximum value. The maximum value allowed is 32763.
X'0100 0604'	UERERRT1RPLEN	Reply parameters buffer length exceeds the maximum value. The maximum value allowed is 32763.
X'0100 0606'	UERERRT1VERB	Incorrect or unsupported verb type. The verb type in the CPRB passed to the SRPI router is not recognized. The verb type is put into the CPRB automatically by the C interface facility.
X'0100 0608'	UERERRT1SERV	Incorrect server name. One or more characters in the server name could not be converted to EBCDIC for sending to the host.
X'0100 060C'	UERERRT1QPAD	One of the following conditions exists: <ul style="list-style-type: none"> <li>• The request parameter address is not valid.</li> <li>• The request parameter length extends beyond the end of the request parameter buffer.</li> <li>• The request parameter address is 0 with a nonzero request parameter length.</li> </ul>
X'0100 060E'	UERERRT1QDAD	One of the following conditions exists: <ul style="list-style-type: none"> <li>• The request data address is not valid.</li> <li>• The request data length extends beyond the end of the request data buffer.</li> <li>• The request data address is 0 with a nonzero request data length.</li> </ul>
X'0100 0610'	UERERRT1RPAD	One of the following conditions exists: <ul style="list-style-type: none"> <li>• The reply parameter buffer address is not valid.</li> <li>• The reply parameter buffer length extends beyond the end of the reply parameter buffer.</li> <li>• The reply parameter buffer address is 0 with a nonzero reply parameter length.</li> </ul>

Table 44. Type 1 Return Code Definitions and Descriptions (continued)

Hexadecimal Return Code	Constant Return Code	Description
X'0100 0612'	UERERRT1RDAD	One of the following conditions exists: <ul style="list-style-type: none"> <li>• The reply data buffer address is not valid.</li> <li>• The reply data buffer length extends beyond the end of the reply data buffer.</li> <li>• The reply data buffer address is 0 with a nonzero reply data length.</li> </ul>
X'0100 0616'	UERERRT1TOPV	The TopView environment is not supported. This return code is not used by the Personal Communications program.
X'0100 0622'	UERERRT1INV3270 d	Notification of 3270 screen update indicator is not valid. The Notification of 3270 screen update indicator must be set to X'00' (notify user of 3270 screen update) or X'FF' (suppress user notification of 3270 screen update) in the CPRB.
X'0100 0624'	UERERRT1INVCPRB	Incorrect CPRB segment. The CPRB address points to a truncated CPRB structure. Use a read/write data segment large enough to contain the entire CPRB structure.
X'0100 0802'	UERERRT1CNCL	The remote computer canceled the communication session while the request was being processed. You can cause this to happen by stopping the remote program with the F3 key in the emulator session. However, use of this value is not limited to user-initiated cancellation of the session. It is used any time SRPI receives notification from the host that the session is canceled while processing a request.
X'0100 0C00'	UERERRT1CONV	A system error occurred. Conversation with the host ended for one of the following reasons: <ul style="list-style-type: none"> <li>• The host communication session is not active.</li> <li>• A link-level communication error occurred.</li> <li>• The system was unable to transmit data reliably to or from the host. For example, a sequence error occurred.</li> </ul>
X'0100 0C02'	UERERRT1ISE	A system error occurred because of an internal software error in the SRPI router.
X'0100 0C04'	UERERRT1PROT	A system error occurred. This is a protocol violation error or a system software error in the SRPI router or the host.

Table 44. Type 1 Return Code Definitions and Descriptions (continued)

Hexadecimal Return Code	Constant Return Code	Description
X'0100 0C06'	UERERRT1SYIN	A system error occurred. The error is caused by system inconsistency. This is a system software error in the SRPI router.

## Type 2 Return Code Definitions

Type 2 return codes have the following format: X'02xx yyzz'.

The 3 error-specific bytes consist of the following exception conditions from the acknowledge interchange unit:

- xx exception class
- yy exception code
- zz exception object

**Note:** No constants are supplied.

## Type 3 Return Code Definitions

Type 3 return codes have the following format: X'03xx yyzz'.

The 3 error-specific bytes consist of the following exception conditions from the acknowledge interchange unit:

- xx exception class
- yy exception code
- zz exception object

The return code definitions and descriptions are listed in Table 45.

Table 45. Type 3 Return Code Definitions and Descriptions

Hexadecimal Return Code	Constant Return Code	Description
X'0304 1D00'	UERERRT3NORES	A resource required by the host SRPI router to process the request is not available. This might be a temporary condition.
X'0304 1E00'	UERERRT3NOSER	The server is unknown at the host.
X'0304 1F00'	UERERRT3UNSER	The server is not available at the host.
X'0304 2200'	UERERRT3TERMS	The server terminated in a normal fashion but did not send a reply.
X'0304 2300'	UERERRT3ABNDS	The server terminated abnormally and did not send a reply.

---

## Class Definitions for Type 2 and Type 3

The exception classes are syntax, semantic, and process.

- **Syntax exception class.** This class reports violations of the transmission unit syntax rules (for example, omitting the server return code parameter: X'0202 1A08'). In general, a return code reporting a syntax exception indicates a system software error in the SRPI router or in the host.
- **Semantic exception class.** This class reports conflicting parameters (for example, an incorrect correlation value: X'0203 1B00'). In general, a return code reporting a semantic exception indicates a system software error in the SRPI router or in the host.
- **Process exception class.** This class reports exception conditions during request processing (for example, server unknown: X'0304 1E00').

The exception class definitions are listed in Table 46.

Table 46. Class Definitions for Type 2 and Type 3

Value	Definition
X'00' to X'01'	Reserved
X'02'	Syntax
X'03'	Semantic
X'04'	Process
X'05' to X'FF'	Reserved

---

## Exception Code Values for Type 2 and Type 3

The exception code defines a specific error condition and is required with every error. The exception code values are listed in Table 47.

Table 47. Exception Code Values for Type 2 and Type 3

Value	Definition
X'00'	Reserved
X'08'	Segmentation
X'0C'	Incorrect operand ID
X'0F'	Incorrect length
X'16'	Incorrect subfield type
X'18'	Incorrect subfield value
X'19'	Required operand missing
X'1A'	Required subfield missing
X'1B'	Correlation error
X'1C'	Data exceeds allowable maximum length
X'1D'	Resource not available
X'1E'	Server unknown
X'1F'	Server not available
X'20'	Parameter length
X'21'	Data length
X'22'	Normal termination
X'23'	Abnormal termination (server abend)
X'24'	Multiple occurrences of a subfield
X'25'	Multiple occurrences of operand



**Note:** All exception code values not specified in this table are reserved.

---

## Exception Object Values for Type 2 and Type 3

The exception object defines the incorrect transmission unit object. An exception object is required with syntax errors. The exception object values are listed in Table 48.

*Table 48. Exception Object Values for Type 2 and Type 3*

Value	Definition
X'00'	Not specified
X'01'	Prefix
X'07'	Command operand
X'08'	Command subfields
X'1C'	Parameters operand
X'1D'	Data operand
X'13'	Suffix

**Note:** All exception object values not specified in this table are reserved.

---

## Server Return Codes

A server return code is a doubleword (4-byte) return code supplied by the server program and is returned to the requester program. The contents and meaning of the return status are defined by the requester or the server. For information about server return codes, contact your host personnel or see one of the following manuals:

- *TSO/E Version 2 Guide to the Server-Requester Programming Interface*
- *IBM Programmer's Guide to the Server-Requester Programming Interface for VM/System Product*



---

## Appendix G. DDE Functions in a 16-Bit Environment

This appendix describes DDE functions in 16-bit mode. This is useful information when you are migrating from 16-bit to 32-bit mode.

PC/3270 Windows mode and PC400 provide a dynamic data exchange (DDE) interface that allows applications to exchange data. The exchange of data between two Windows applications can be thought of as a conversation between a client and a server. The *client* initiates DDE conversations. The *server* in turn responds to the client. Personal Communications is a DDE server for the open sessions that Personal Communications are managing. For more information about DDE, refer to *Microsoft Windows Software Development Kit Guide to Programming*.

**Note:** If you use DDE functions with Visual Basic, see “Chapter 7. Using DDE Functions with a DDE Client Application” on page 325.

---

### Personal Communications DDE Data Items in a 16-Bit Environment

Microsoft Windows DDE uses a three-level naming scheme to identify data items: application, topic, and item. Table 49 on page 397 describes these levels.

Table 49. Naming Scheme for Data Items

Level	Description	Example
Application	A Windows task or a particular task of an application. In this book, the application is Personal Communications.	IBM3270
Topic	A specific part of an application.	SessionA
Item	A data object that can be passed in a data exchange. An item is an application-defined data item that conforms to one of the Windows clipboard formats or to a private, application-defined, clipboard format. For more information regarding Windows clipboard formats, refer to <i>Microsoft Windows Software Development Kit Guide to Programming</i>	PS (presentation space)

Personal Communications support one application name as Windows DDE server.

Table 50. Applications for Personal Communications

Application
IBM3270 IBM5250

The following table lists the topics you can use.

Table 51. Topics for Personal Communications

Topics
System SessionA, SessionB, ..., SessionZ LUA_xxxx, LUB_xxxx, ..., LUZ_xxxx

In DDE, *atoms* identify application names, topic names, and data items. Atoms represent a character string that is reduced to a unique integer value. The character string is added to an atom table, which can be referred to for the value of the string associated with an atom. Atoms are created with the GlobalAddAtom function call.

Refer to *Microsoft Windows Software Development Kit Guide to Programming* for more information about how to create and use atoms.

## Using System Topic Data Items

Applications that provide a DDE interface should also provide a special topic SYSTEM. This topic provides a context for items of information that might be of general interest to an application. The SYSTEM topic for Personal Communications contains these associated data items:

Item	Function
<b>Formats</b>	Returns the list of clipboard formats (numbers) that Personal Communications is capable of rendering.
<b>Status</b>	Returns information about the status of each Personal Communications session.
<b>SysCon</b>	Returns the level of Personal Communications support and other system related values.
<b>Systems</b>	Returns the list of data items that are available when connected to the Personal Communications system topic.
<b>Topics</b>	Returns the list of Personal Communications topics that are available.

## Using Session Topic Data Items

For each Session topic, the following data items are supported:

Item	Function
<b>CLOSE</b>	Retrieves the window close requests.
<b>EPS</b>	Retrieves the session presentation space with additional data.
<b>EPSCOND</b>	Retrieves the presentation space service condition.
<b>FIELD</b>	Retrieves the field in the presentation space of the session.
<b>KEYS</b>	Retrieves the keystrokes.
<b>MOUSE</b>	Retrieves the mouse input.
<b>OIA</b>	Retrieves the operator information area status line.
<b>PS</b>	Retrieves the session presentation space.
<b>PSCOND</b>	Retrieves the session advise condition.
<b>SSTAT</b>	Retrieves the session status.
<b>STRING</b>	Retrieves the ASCII string data.
<b>TRIMRECT</b>	Retrieves the session presentation space within the current trim rectangle.

## Using LU Topic Data Items (PC/3270 Only)

For each LU topic, the following data items are supported:

Item	Function
<b>SF</b>	Retrieves the destination/origin structured field data.
<b>SFCOND</b>	Retrieves the query reply data.

---

## DDE Functions in a 16-Bit Environment

The following table lists the DDE functions that are available for use with Personal Communications and the page

Function	PC/3270 Windows	PC400	Page
Find Field	Yes	Yes	400
Get Keystrokes	Yes	Yes	401

Function	PC/3270 Windows	PC400	Page
Get Mouse Input	Yes	Yes	402
Get Number of Close Requests	Yes	Yes	405
Get Operator Information Area	Yes	Yes	406
Get Partial Presentation Space	Yes	Yes	406
Get Presentation Space	Yes	Yes	409
Get Session Status	Yes	Yes	411
Get System Configuration	Yes	Yes	412
Get System Formats	Yes	Yes	413
Get System Status	Yes	Yes	414
Get System SysItems	Yes	Yes	415
Get System Topics	Yes	Yes	416
Get Trim Rectangle	Yes	Yes	416
Initiate Session Conversation	Yes	Yes	417
Initiate Structured Field Conversation	Yes	No.	418
Initiate System Conversation	Yes	Yes	418
Put Data to Presentation Space	Yes	Yes	419
Search for String	Yes	Yes	420
Send Keystrokes	Yes	Yes	421
Session Execute Macro	Yes	Yes	422
Set Cursor Position	Yes	Yes	428
Set Mouse Intercept Condition	Yes	Yes	429
Set Presentation Space Service Condition	Yes	Yes	431
Set Session Advise Condition	Yes	Yes	433
Set Structured Field Service Condition	Yes	No	434
Start Close Intercept	Yes	Yes	434
Start Keystroke Intercept	Yes	Yes	436
Start Mouse Input Intercept	Yes	Yes	437
Start Read SF	Yes	No	441
Start Session Advise	Yes	Yes	442
Stop Close Intercept	Yes	Yes	443
Stop Keystroke Intercept	Yes	Yes	444
Stop Mouse Input Intercept	Yes	Yes	444
Stop Read SF	Yes	No	445
Stop Session Advise	Yes	Yes	446
Terminate Session Conversation	Yes	Yes	446
Terminate Structured Field Conversation	Yes	No	447
Terminate System Conversation	Yes	Yes	447
Write SF	Yes	No	448

Refer to “Summary of DDE Functions in a 16-Bit Environment” on page 448 for a summary of the 16-bit DDE functions.

## Naming Conventions for Parameters

Most DDE parameter names and local variables. These variables have a prefix that indicates the general type of the parameter, followed by one or more words that describe the content of the parameter. Prefixes presented in this book are:

- a** Atom
- c** Character (a 1-byte value)
- f** Bit flags packed into a 16-bit integer
- h** 16-bit handle

<b>p</b>	Short (16-bit) pointer
<b>lp</b>	Long (32-bit) pointer
<b>w</b>	Short (16-bit) unsigned integer
<b>u</b>	Unsigned integer
<b>sz</b>	Null-terminated character string

## Find Field

3270	5250	VT
Yes	Yes	Yes

The **Find Field** function returns to the client the information of the field specified by the **Set Presentation Space Service Condition** function.

**Note:** The client must set the PS position by using the **Set Presentation Service Condition** function before using this function.

The client sends this following message to receive the field information.

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELONG(cfFormat, aFIELD) );
```

where:

**cfFormat** Identifies the format for the field information. This must be CF\_DSPTTEXT.  
**aFIELD** Identifies field data item.

The **Find Field** function supports a new format like Visual Basic. Using the new format, the **Find Field** function can find a field with specifying its type. The new format is:

FIELD (pos, type)

**pos** Position where Personal Communications starts to search a target field.  
**type** Target field type. The field type are:

Type	Meaning
bb or Tb	This field.
Pb	The previous field, either protected or unprotected.
Nb	The next field, either protected or unprotected.
NP	The next protected field.
NU	The next unprotected field.
PP	The previous protected field.
PU	The previous unprotected field.

**Note:** The b symbol represents a required blank.

## Personal Communications Response

Personal Communications returns the following information of the field in a DDE data message,

- Start PS position

- Length
- Attribute value

WM\_DDE\_DATA(hData, aFIELD)

or responds with an ACK message containing status information.

WM\_DDE\_ACK(wStatus, aFIELD)

If Personal Communications cannot return the field information, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
1	PS position is not valid.
2	PS is unformatted.
6	The specified format is not valid.
9	A system error occurred.

### Structure of the Field Information

Personal Communications returns the field information in the following structure:

```
typedef struct tagFINDFIELD
{
    unsigned unused:12;           // *** unused ***
    unsigned fResponse:1;        // TRUE = DDE_REQUEST response
    unsigned fRelease:1;         // TRUE = Client frees this data
    unsigned reserved:1;         // *** reserved ***
    unsigned fAckReq:1;          // TRUE = Client returns DDE_ACK
    int    cfFormat;             // Format of Field data CF_DSPTEXT
    unsigned char cAttribute;    // Attribute character
    unsigned uFieldStart;        // Field start offset
    unsigned uFieldLength;       // Field Length;
} FINDFIELD, far *lpFINDFIELD;
```

## Get Keystrokes

3270	5250	VT
Yes	Yes	Yes

The **Get Keystrokes** function returns to the client the keystrokes that are intercepted by the **Start Keystroke Intercept** function. The client sends the following message to receive the keystroke information.

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELONG(cfFormat, aKEYS) );
```

where:

- cfFormat** Identifies the format for the keystroke information. This must be CF\_DSPTEXT.
- aKEYS** Identifies keystroke data item.

### Personal Communications Response

Personal Communications either returns the keystrokes in a DDE data message, or responds with one of these ACK messages containing status information:

- WM\_DDE\_DATA(hData, aKEYS)

- WM\_DDE\_ACK(wStatus, aKEYS)

If Personal Communications cannot return the keystroke information, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
2	No keystroke was intercepted.
6	The specified format is not valid.
9	A system error occurred.

## Structure of the Keystroke Information

Personal Communications returns the keystroke information in the following structure:

```
typedef struct tagKEYSTROKE
{
    unsigned unused:12;           // *** unused ***
    unsigned fResponse:1;        // TRUE = DDE_REQUEST response
    unsigned fRelease:1;         // TRUE = Client frees this data
    unsigned reserved:1;         // *** reserved ***
    unsigned fAckReq:1;          // TRUE = Client returns DDE_ACK
    int    cfFormat;             // Format of keystroke data CF_DSPTXT
    unsigned uTextType;          // Type of keystrokes
    unsigned char szKeyData[1]; // Keystrokes
} KEYSTROKE, far *lpKEYSTROKE;
```

The format for the keystrokes parameters is the same as for the **Session Execute Macro** function SENDKEY command.

The following key text types are supported:

```
WC_CHARACTER 0 // Pure text, no command
WC_TOKEN     1 // including commands
```

## Get Mouse Input

3270	5250	VT
Yes	Yes	Yes

The **Get Mouse Input** function returns the latest mouse input that are intercepted by **Start Mouse Input Intercept** function to the client.

**Note:** The client must call the **Start Mouse Input Intercept** function before using this function.

The client sends the following command to receive the mouse input information.

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELONG(cfFormat, aMOUSE) );
```

where:

- cfFormat** Identifies the format for the presentation space. Valid values are CF\_TEXT or CF\_DSPTXT. The structure of the mouse input data, in these two formats, is shown below.
- aMOUSE** Identifies the mouse input as the item.



## Personal Communications Response

Personal Communications either returns the mouse input data in a DDE data message, or responds with one of these ACK messages:

- WM\_DDE\_DATA(hData, aMOUSE)
- WM\_DDE\_ACK(wStatus, aMOUSE)

If Personal Communications cannot return the mouse input information, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
2	No mouse input information was intercepted.
6	The specified format is not valid.
9	A system error occurred.

## Structure of the Mouse Input Information

If the format is CF\_TEXT, Personal Communications returns the mouse input information in the following format:

```
typedef struct tagMOUSE_CF_TEXT
{
    unsigned    unused:12,        // **** Unused ****
    unsigned    fRespons:1,      // TRUE = DDE_REQUEST response
    unsigned    fRelease:1,      // TRUE = Client frees this data
    unsigned    reserved:1,      // **** Reserved ****
    unsigned    fAckReq:1;       // TRUE = Client returns DDE_ACK
    int         cfFormat;        // CF_TEXT
    unsigned char PSPos[4];      // PS position
    unsigned char Tab1[1];       // TAB character
    unsigned char PSRowPos[4];   // PS row position
    unsigned char Tab2[1];       // TAB character
    unsigned char PSColPos[4];   // PS columns position
    unsigned char Tab3[1];       // TAB character
    unsigned char PSSize[4];     // Size of the PS
    unsigned char Tab4[1];       // TAB character
    unsigned char PSRows[4];     // PS number of rows
    unsigned char Tab5[1];       // TAB character
    unsigned char PSCols[4];     // PS number of columns
    unsigned char Tab6[1];       // TAB character
    unsigned char ButtonType[1]; // Pressed button type
    unsigned char Tab7[1];       // TAB character
    unsigned char ClickType[1];  // Click type
    unsigned char Tab8[1];       // TAB character
    unsigned char ClickString[1]; // Retrieved string
} MOUSE_CF_TEXT, FAR *lpMOUSE_CF_TEXT;
```

The following table shows the values in the parameters:

Parameter Name	Meaning	Value
PSPos	PS offset of the position where mouse was clicked	0 ... (PSSize - 1)
PSRowPos	Row number of the position where mouse was clicked	0 ... (PSRows - 1)
PSColPos	Column number of the position where mouse was clicked	0 ... (PSCols - 1)
PSSize	Size of the presentation space	

Parameter Name	Meaning	Value
PSRows	Number of rows of presentation space	
PSCols	Number of columns of presentation space	
ButtonType	Type of the clicked mouse button	<b>L</b> Left button <b>M</b> Middle button <b>R</b> Right button
ClickType	Type of clicking	<b>S</b> Single click <b>D</b> Double click
ClickString	Retrieved string to which the mouse pointed	A character string terminated with a '\0'
Tab1-8	A tab character for delimiter	'\t'

If the format is CF\_DSPTTEXT, Personal Communications returns the mouse input information in the following format:

```
typedef struct tagMOUSE_CF_DSPTTEXT
{
    unsigned    unused:12,        // **** Unused ****
    unsigned    fRespons:1,      // TRUE = DDE_REQUEST response
    unsigned    fRelease:1,      // TRUE = client frees the storage
    unsigned    reserved:1,      // **** Reserved ****
    unsigned    fAckReq:1;       // TRUE = client returns DDE_ACK
    int         cfFormat;        // CF_DSPTTEXT
    unsigned    uPSPos;          // PS position
    unsigned    uPSRowPos;       // PS row position
    unsigned    uPSColPos;       // PS column position
    unsigned    uPSSize;         // Size of the presentation space
    unsigned    uPSRows;         // PS number of rows
    unsigned    uPSCols;         // PS number of columns
    unsigned    uButtonType;     // Pressed button type
    unsigned    uClickType;      // Click type
    unsigned char szClickString[1]; // Retrieved string
} MOUSE_CF_DSPTTEXT, FAR *lpMOUSE_CF_DSPTTEXT;
```

The following table shows the values in the parameters:

Parameter Name	Meaning	Value
uPSPos	PS offset of the position where mouse was clicked	0 ... (uPSSize - 1)
uPSRowPos	Row number of the position where mouse was clicked	0 ... (uPSRows - 1)
uPSColPos	Column number of the position where mouse was clicked	0 ... (uPSCols - 1)
uPSSize	Size of the presentation space	
uPSRows	Number of rows of the presentation space	
uPSCols	Number of columns of the presentation space	

Parameter Name	Meaning	Value
uButtonType	Type of the clicked mouse button	<b>0x0001</b> Left button <b>0x0002</b> Middle button <b>0x0003</b> Right button
uClickType	Type of clicking	<b>0x0001</b> Single click <b>0x0002</b> Double click
szClickString	Retrieved string that the mouse pointed to	A character string terminated with a '\0'

## Get Number of Close Requests

3270	5250	VT
Yes	Yes	Yes

The **Get Number of Close Requests** function returns to the client the number of the close requests that are intercepted by the **Start Close Intercept** function. The client sends the following message to receive the number of the close requests.

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELONG(cfFormat, aCLOSE) );
```

where:

**cfFormat** Identifies the format for the close intercept information. This must be CF\_DSPTTEXT.

**aCLOSE** Identifies close intercept data item.

## Personal Communications Response

Personal Communications either returns the number of the close requests in a DDE data message, or responds with one of these ACK messages:

- WM\_DDE\_DATA(hData, aCLOSE)
- WM\_DDE\_ACK(wStatus, aCLOSE)

If Personal Communications cannot return the close intercept information, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
6	The specified format is not valid.
9	A system error occurred.

## Structure of the Number of the Close Requests Information

Personal Communications returns the close intercept information in the following structure:

```
typedef struct tagCLOSEREQ
{
    unsigned unused:12;           // *** unused ***
    unsigned fResponse:1;        // TRUE = DDE_REQUEST response
    unsigned fRelease:1;         // TRUE = Client frees this data
};
```

```

unsigned reserved:1;      // *** reserved ***
unsigned fAckReq:1;      // TRUE = Client returns DDE_ACK
int    cfFormat;         // Format of close intercept data CF_DSPTEXT
unsigned uCloseReqCount; // Number of the close requests.
} CLOSEREQ, far *lpCLOSEREQ;

```

## Get Operator Information Area

3270	5250	VT
Yes	Yes	Yes

The Get Operator Information Area (OIA) function returns a copy of the OIA to the client. The client sends the following message to request the OIA.

```

PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELONG(cfFormat, aOIA) );

```

where:

**cfFormat** Identifies the format for the OIA. For the OIA this format must be CF\_DSPTEXT.

**aOIA** Identifies the operator information area as the item.

## Personal Communications Response

Personal Communications either returns the OIA in a DDE data message, or responds with one of these ACK messages:

- WM\_DDE\_DATA(hData, aOIA)
- WM\_DDE\_ACK(wStatus, aOIA)

If Personal Communications cannot return the OIA, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
6	The specified format is not valid.
9	A system error occurred.

## Structure of the Operator Information Area

Personal Communications returns the operator information area in the following structure:

```

typedef struct tagOIADATA
{
    unsigned unused:12;      // *** unused ***
    unsigned fResponse:1;   // TRUE = DDE_REQUEST response
    unsigned fRelease:1;    // TRUE = Client frees this data
    unsigned reserved:1;    // *** reserved ***
    unsigned fAckReq:1;     // TRUE = Client returns DDE_ACK
    int    cfFormat;        // Format of OIA data CF_DSPTEXT
} OIADATA, far *lpOIADATA;

```

## Get Partial Presentation Space

3270	5250	VT
Yes	Yes	Yes

The **Get Partial Presentation Space** function returns all or part of the session presentation space to the client.

**Note:** The client must set the start PS position and the length (or set the EOF flag) by using the **Set Presentation Space Service Condition** function before using this function.

The client sends the following command to get the presentation space.

```
PostMessage( hServerWnd,
            WM_DDE_REQUEST,
            hClientWnd,
            MAKELONG(cfFormat, aEPS) );
```

where:

**cfFormat** Identifies the format for the presentation space. Valid values are CF\_TEXT or CF\_DSPTEXT. The structure of the presentation space, in these two formats, is shown below.

**aEPS** Identifies presentation space atom as the item.

## Personal Communications Response

Personal Communications either returns the presentation space data, or responds with one of these ACK messages containing an error code in the low-order byte of the wStatus word:

- WM\_DDE\_DATA(hData, aEPS)
- WM\_DDE\_ACK(wStatus, aEPS)

If Personal Communications cannot return the presentation space, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
1	No prior <b>Set Presentation Space Service Condition</b> function was called, or an incorrect parameter was set.
6	The specified format is not valid.
9	A system error occurred.

## Structure of the Presentation Space

Personal Communications returns the part of the presentation space in the format specified in the **Get Partial Presentation Space** request.

If the format is CF\_DSPTEXT, Personal Communications returns the presentation space in the following format:

```
typedef struct tagEPS_CF_DSPTEXT
{
    unsigned Unused:12,           // Unused
    unsigned fResponse:1,        // TRUE = DDE_REQUEST response
    unsigned fRelease:1,         // TRUE = client frees the storage
    unsigned reserved:1,         // **** Reserved ****
    unsigned fAckReq:1,          // TRUE = DDE_ACK requested
    int     cfFormat;             // Format data is rendered in
    unsigned uPSPosition;        // Start PS position
    unsigned uPSLength;          // Length of the part of the PS
    unsigned uPSRows;            // PS number of rows
    unsigned uPSCols;            // PS number of columns
    unsigned uPSOffset;          // Offset to the presentation space
    unsigned uFieldCount;        // Number of fields
};
```

```

    unsigned uFieldOffset;        // Offset to the field array
    unsigned char PSData[1];      // PS and Field list Array
} EPS_CF_DSPTXT, FAR *lpEPS_CF_DSPTXT;

```

```

typedef struct tagPSFIELDS
{
    unsigned char cAttribute;     // Attribute Character
    unsigned uFieldStart;        // Field start offset
    unsigned uFieldLength;       // Field Length
} PSFIELDS, FAR *lpPSFIELDS;

```

**Note:** The following examples show how to obtain long pointers to the PS and the PSFIELDS array.

```

lppls = (lp_EPS_CF_DSPTXT) lpEPS_CF_DSPTXT->PSData
        + lpEPS_CF_DSPTXT->uPSOffset;
lpplsfields = (lpPSFIELDS) lpEPS_CF_DSPTXT->PSData
              + lpEPS_CF_DSPTXT->uFieldOffset;

```

If the format is CF\_TEXT, Personal Communications returns the part of the presentation space in the following format:

```

typedef struct tagEPS_CF_TEXT
{
    unsigned    Unused:12;        // **** Unused ****
    unsigned    fResponse:1;     // TRUE = DDE_REQUEST response
    unsigned    fRelease:1;      // TRUE = Client frees this data
    unsigned    reserved:1;      // **** Reserved ****
    unsigned    fAckReq:1;       // TRUE = Client returns DDE_ACK
    int         cfFormat;        // Format of the data
    unsigned char PSPOSITION[4]; // Start PS position
    unsigned char Tab1[1];       // Tab character
    unsigned char PSENGTH[4];    // Length of the part of the PS
    unsigned char Tab2[1];       // Tab character
    unsigned char PSROWS[4];     // Number of rows in the Partial PS
    unsigned char Tab3[1];       // Tab character
    unsigned char PSCOLS[4];     // Number of columns in the PS
    unsigned char Tab4[1];       // Tab character
    unsigned char PS[1];         // PS
} EPS_CF_TEXT, FAR *lpEPS_CF_TEXT;

```

Following the PS in the buffer is the following additional structure of fields that compose the field list.

```

typedef struct tagFL_CF_TEXT
{
    unsigned char Tab5[1];       // Tab character
    unsigned char PSFldCount[4]; // Number of fields in the PS
    unsigned char Tab6[1];       // Tab character
    PS_FIELD     Field[1];       // Field List Array
} FL_CF_TEXT, FAR *lpFL_CF_TEXT;

```

```

typedef struct tagPS_FIELD
{
    unsigned char FieldStart[4];
    unsigned char TabF1[1];
    unsigned char FieldLength[4];
    unsigned char TabF2[1];
    unsigned char Attribute;
    unsigned char TabF3[1];
} PS_FIELD, FAR *lpPS_FIELD;

```

**Note:** The following examples show how to obtain long pointers to the PS and the PS\_FIELD array.

```

lpps = lpEPS_CF_TEXT->PS;
lpps_field = (lpPS_FIELD) lpEPS_CF_TEXT->PS
             + atoi(lpEPS_CF_TEXT->PSLENGTH)
             + ((atoi(lpEPS_CF_TEXT->PSROWS) - 1) * 2) // CR/LF
             + 1 + 1 + 4 + 1; // Tabs + size of field count

```

## Get Presentation Space

3270	5250	VT
Yes	Yes	Yes

The **Get Presentation Space** function returns the session presentation space to the client. The client sends the following command to get the presentation space.

```

PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELONG(cfFormat, aPS) );

```

where:

**cfFormat** Identifies the format for the presentation space. Valid values are CF\_TEXT or CF\_DSPTXT. The structure of the presentation space, in these two formats, is shown below.

**aPS** Identifies presentation space atom as the item.

## Personal Communications Response

Personal Communications either returns the presentation space and a list of the fields that comprise the presentation space, or responds with one of these ACK messages containing an error code in the low-order byte of the wStatus word:

- WM\_DDE\_DATA(hData, aPS)
- WM\_DDE\_ACK(wStatus, aPS)

If Personal Communications cannot return the presentation space, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
6	The specified format is not valid.
9	A system error occurred.

## Structure of the Presentation Space

Personal Communications returns the presentation space in the format specified in the **Get Presentation Space** request.

If the format is CF\_DSPTXT, Personal Communications returns the presentation space in the following format:

```

typedef struct tagPS_CF_DSPTXT
{
    unsigned Unused:12,           // Unused
    unsigned fResponse:1,        // TRUE = DDE_REQUEST response
    unsigned fRelease:1,         // TRUE = client frees the storage
    unsigned reserved:1,         // **** Reserved ****
    unsigned fAckReq:1,          // TRUE = DDE_ACK requested
    int      cfFormat;           // Format data is rendered in
    unsigned uPSSize;            // Size of the presentation space
    unsigned uPSRows;            // PS number of rows
    unsigned uPSCols;            // PS number of columns
    unsigned uPSOffset;          // Offset to the presentation space

```

```

unsigned uFieldCount;          // Number of fields
unsigned uFieldOffset;        // Offset to the field array
unsigned char PSData[1];      // PS and Field list Array
} PS_CF_DSPTXT, FAR *lpPS_CF_DSPTXT;

```

```

typedef struct tagPSFIELDS
{
    unsigned char cAttribute;    // Attribute Character
    unsigned uFieldStart;        // Field start offset
    unsigned uFieldLength;      // Field Length
} PSFIELDS, FAR *lpPSFIELDS;

```

**Note:** The following examples show how to obtain long pointers to the PS and the PSFIELDS array.

```

lpps = (lp_PS_CF_DSPTXT) lpPS_CF_DSPTXT->PSData
        + lpPS_CF_DSPTXT->uPSOffset;
lppsfields = (lpPSFIELDS) lpPS_CF_DSPTXT->PSData
        + lpPS_CF_DSPTXT->uFieldOffset;

```

If the format is CF\_TEXT, Personal Communications returns the presentation space in the following format:

```

typedef struct tagPS_CF_TEXT
{
    unsigned    Unused:12;        // **** Unused ****
    unsigned    fResponse:1;      // TRUE = DDE_REQUEST response
    unsigned    fRelease:1;       // TRUE = Client frees this data
    unsigned    reserved:1;       // **** Reserved ****
    unsigned    fAckReq:1;        // TRUE = Client returns DDE_ACK
    int         cfFormat;         // Format of the data
    unsigned char PSSIZE[4];       // Size of the PS
    unsigned char Tab1[1];        // Tab character
    unsigned char PSROWS[4];      // Number of rows in the PS
    unsigned char Tab2[1];        // Tab character
    unsigned char PSCOLS[4];      // Number of Cols in the PS
    unsigned char Tab3[1];        // Tab character
    unsigned char PS[1];          // PS
} PS_CF_TEXT, FAR *lpPS_CF_TEXT;

```

Following the PS in the buffer is the following additional structure of fields that compose the field list.

```

typedef struct tagFL_CF_TEXT
{
    unsigned char Tab4[1];        // Tab character
    unsigned char PSFldCount[4]; // Number of fields in the PS
    unsigned char Tab5[1];        // Tab character
    PS_FIELD      Field[1];       // Field List Array
} FL_CF_TEXT, FAR *lpFL_CF_TEXT;

```

```

typedef struct tagPS_FIELD
{
    unsigned char FieldStart[4];
    unsigned char TabF1[1];
    unsigned char FieldLength[4];
    unsigned char TabF2[1];
    unsigned char Attribute;
    unsigned char TabF3[1];
} PS_FIELD, FAR *lpPS_FIELD;

```

**Note:** The following example shows how to obtain long pointers to the PS and the PS\_FIELD array.



```

lpps = lpPS_CF_TEXT->PS;
lpps_field = (lpPS_FIELD) lpPS_CF_TEXT->PS
             + atoi(lpPS_CF_TEXT->PSSIZE)
             + ((atoi(lpPS_CF_TEXT->PSROWS) - 1) * 2) // CR/LF
             + 1 + 1 + 4 + 1; // Tabs + size of field count

```

## Get Session Status

3270	5250	VT
Yes	Yes	Yes

The **Get Session Status** function returns the status of the connected session. The client sends the following message to request session status:

```

PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELONG(cfFormat, aSSTAT) );

```

where:

**cfFormat** Identifies the DDE format for the status information. The value used is CF\_TEXT.

**aSSTAT** Identifies session status as the data item requested.

## Personal Communications Response

Personal Communications either returns the session status in a DDE data message, or responds with one of these ACK messages containing status information:

- WM\_DDE\_DATA(hData, aSSTAT)
- WM\_DDE\_ACK(wStatus, aSSTAT)

If Personal Communications cannot return the session status, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
6	The specified format is not valid.
9	A system error occurred.

## Format of Status Information

Personal Communications returns the session status as text in CF\_TEXT format. The following fields are returned with the following possible values:

Fields	Returned values	Description
Status	Closed, Invisible, Maximized, Minimized, Normal	The window is in one of these states.
Usage	DDE, User	The session is connected in either a DDE session or a user session.
ScreenX	NN	Defines the horizontal size of the screen.
ScreenY	NN	Defines the vertical size of the screen.

Fields	Returned values	Description
CursorX	NN	Defines the horizontal position of the cursor. (0 ... ScreenX – 1)
CursorY	NN	Defines the vertical position of the cursor. (0 ... ScreenY – 1)
TrimRect Status	Closed, Moved, Sized	The current status of the trim rectangle.
Trim Rectangle X1	N	The top-left corner X position of the trim rectangle in character coordinates.
Trim Rectangle Y1	N	The top-left corner Y position of the trim rectangle in character coordinates.
Trim Rectangle X2	N	The lower-right corner X position of the trim rectangle in character coordinates.
Trim Rectangle Y2	N	The lower-right corner Y position of the trim rectangle in character coordinates.
Session Presentation Space Status	N	The current status of the presentation space. The following values are possible:  <b>0:</b> The presentation space is unlocked.  <b>4:</b> The presentation space is busy.  <b>5:</b> The presentation space is locked.
Session Window Handle	XXXX	Window handle of the session.

**Notes:**

1. The status of each field is updated each time the status is requested.
2. A new field might be added in a future version of Personal Communications.

## Get System Configuration

<i>3270</i>	<i>5250</i>	<i>VT</i>
Yes	Yes	Yes

The **Get System Configuration** function returns the level of Personal Communications support and other system-related values. Most of this information is for use by a service coordinator when a customer calls the IBM Support Center after receiving a system error.

```
PostMessage( hServerWnd,
            WM_DDE_REQUEST,
            hClientWnd,
            MAKELONG(cfFormat, aSYSCON) );
```

where:

- cfFormat** Identifies the DDE format for the data item requested. The value used is CF\_TEXT.
- aSYSCON** Identifies system configuration as the data item requested.

## Personal Communications Response

Personal Communications either returns the system configuration data item in a DDE DATA message, or responds with one of these ACK messages containing status information:

- WM\_DDE\_DATA(hData, aSYSCON)
- WM\_DDE\_ACK(wStatus, aSYSCON)

If Personal Communications cannot return the system configuration, a DDE ACK message will be returned with an error code in the low-order byte of the wStatus word:

WM\_DDE\_ACK(wStatus, aSYSCON)

Return Code	Explanation
9	A system error occurred.

## Format of System Configuration information

Personal Communications returns the system configuration as text in CF\_TEXT format. The following fields are returned with the following possible values:

Fields	Returned values	Description
Version	N	The version of Personal Communications
Level	NN	The level of Personal Communications
Reserved	XXXXXX	Reserved
Reserved	XXXX	Reserved
Monitor Type	MONO, CGA, EGA, VGA, XGA	Type of the monitor
Country Code	NNNN	Country code used with 3270 or 5250

## Get System Formats

3270	5250	VT
Yes	Yes	Yes

The Get System Formats function returns the list of Windows clipboard formats supported by Personal Communications. The client application sends the following message to retrieve the format list supported by Personal Communications:

```
PostMessage( hServerWnd,  
            WM_DDE_REQUEST,  
            hClientWnd,  
            MAKELONG(cfFormat, aFORMATS) );
```

where:

- cfFormat** Identifies the DDE format for the data item requested. The value used is CF\_TEXT.

**aFORMATS** Identifies formats as the data item requested.

## Personal Communications Response

Personal Communications returns the list of supported Windows clipboard formats in CF\_TEXT format in a DDE DATA message.

WM\_DDE\_DATA(hData, aFORMATS)

The following Windows Clipboard formats are supported by Personal Communications:

- CF\_TEXT
- CF\_DSPTEXT

If Personal Communications cannot return the formats data item, a DDE ACK message is returned with an error code in the low-order byte of the wStatus word:

WM\_DDE\_ACK(wStatus, aFORMATS)

Return Code	Explanation
9	A system error occurred.

## Get System Status

3270	5250	VT
Yes	Yes	Yes

The **Get System Status** function returns the status of each 3270 or 5250

```
PostMessage( hServerWnd,  
            WM_DDE_REQUEST,  
            hClientWnd,  
            MAKELONG(cfFormat, aSTATUS) );
```

where:

**cfFormat** Identifies the DDE format for the data item requested. The value used is CF\_TEXT.

**aSTATUS** Identifies status as the data item requested.

## Personal Communications Response

Personal Communications returns the status data item in CF\_TEXT format in a DDE DATA message:

WM\_DDE\_DATA(hData, aSTATUS)

For each opened session, Personal Communications returns a line of status information. Each line contains a series of fields with the following range of values:

Fields	Range of values	Description
Session ID	A, B, ..., Z	The short ID of the session.
Host Type	370, 400	The host system currently supported by Personal Communications.
Emulation Type	3270, 5250	The emulation type supported by Personal Communications.

Fields	Range of values	Description
Session Status	Closed, Invisible, Normal, Minimized, Maximized	The current status of the session's window.

If Personal Communications cannot return the status data item, a DDE ACK message is returned with an error code in the low-order byte of the wStatus word:

`WM_DDE_ACK(wStatus, aSTATUS)`

Return Code	Explanation
9	A system error occurred.

## Get System Systems

3270	5250	VT
Yes	Yes	Yes

Personal Communications supports the DDE system topic so that a client application can connect to the system topic and retrieve information about Personal Communications and the status of the sessions that Personal Communications is managing.

The **Get System Systems** function returns the list of data items available in the Personal Communications system topic. The client application sends the following message to get the system topic data items:

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELONG(cfFormat, aSYSITEMS) );
```

where:

**cfFormat** Identifies the DDE format for the data item requested. The value used is `CF_TEXT`.

**aSYSITEMS** Identifies SysItems as the data item requested.

## Personal Communications Response

Personal Communications returns the list of system topic data items in `CF_TEXT` format in a DDE DATA message.

`WM_DDE_DATA(hData, aSYSITEMS)`

The following data items are supported by Personal Communications:

- Systems
- Topics
- Status
- Formats
- SysCon

If Personal Communications cannot return the system data items, a DDE ACK message is returned with an error code in the low-order byte of the wStatus word:

`WM_DDE_ACK(wStatus, aSYSITEMS)`

Return Code	Explanation
9	A system error occurred.

## Get System Topics

3270	5250	VT
Yes	Yes	Yes

The **Get System Topics** function returns the list of active DDE topics currently supported by Personal Communications. The client application sends the following message to the system topic to retrieve the list of topics that are currently active:

```
PostMessage( hServerWnd,  
            WM_DDE_REQUEST,  
            hClientWnd,  
            MAKELONG(cfFormat, aTOPICS) );
```

where:

**cfFormat** Identifies the DDE format for the data item requested. The value used is CF\_TEXT.

**aTOPICS** Identifies topics as the data item requested.

## Personal Communications Response

Personal Communications returns the list of DDE topics in CF\_TEXT format in a DDE DATA message.

```
WM_DDE_DATA(hData, aTOPICS)
```

The following topics are supported by Personal Communications:

- System – System Topic
- SessionA – Session A Topic
- ⋮
- SessionZ – Session Z Topic

**Note:** The actual number of session topics supported depends on the number of sessions currently opened. The client program should always query the topics data item of the system topic to obtain the list of sessions currently opened.

If Personal Communications cannot return the list of topics, a DDE ACK message is returned with an error code in the low-order byte of the wStatus word:

```
WM_DDE_ACK(wStatus, aTOPICS)
```

Return Code	Explanation
9	A system error occurred.

## Get Trim Rectangle

3270	5250	VT
Yes	Yes	Yes

The **Get Trim Rectangle** function returns to the client the area of the presentation space that is within the current trim rectangle. The client sends the following message to receive the trim rectangle.

```
PostMessage( hServerWnd,  
            WM_DDE_REQUEST,  
            hClientWnd,  
            MAKELONG(cfFormat, aTRIMRECT) );
```

where:

**cfFormat** Identifies the format for the trim rectangle. This is CF\_TEXT.  
**aTRIMRECT** Identifies trim rectangle as the data item requested.

## Personal Communications Response

Personal Communications either returns trim rectangle in a DDE data message, or responds with one of these ACK messages:

- WM\_DDE\_DATA(hData, aTRIMRECT)
- WM\_DDE\_ACK(wStatus, aTRIMRECT)

If Personal Communications cannot return the trim rectangle, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
6	The specified format is not valid.
9	A system error occurred.

## Initiate Session Conversation

3270	5250	VT
Yes	Yes	Yes

The **Initiate Session Conversation** function connects a client application to an available session of Personal Communications. Once a session conversation has been established, the session is reserved for exclusive use by the client until the conversation is terminated.

The client application sends the following message to initiate a DDE conversation with a session:

```
SendMessage( -1,  
             WM_DDE_INITIATE,  
             hClientWnd,  
             MAKELONG(aIBM327032, aSessionN) );
```

where:

**aIBM327032** Identifies the application atom. The string used to create atom aIBM3270 is "IBM3270". In the PC400, the application atom is aIBM5250 and the string "IBM5250" is used to create it.

**aSessionN** Identifies the topic atom. The string used to create atom aSessionN is either NULL or "Session" appended with the session ID "A", "B", ..., "Z".

## Personal Communications Response

If a specific topic is selected and Personal Communications can support a conversation with the client application, Personal Communications acknowledges the INITIATE transaction with:

```
WM_DDE_ACK(aIBM327032, aSessionN)
```

If a topic is not selected (aSessionN = NULL), Personal Communications responds by acknowledging all topics that are currently available:

```

WM_DDE_ACK(aIBM327032, aSystem)
WM_DDE_ACK(aIBM327032, aSessionA)
:
:
WM_DDE_ACK(aIBM327032, aSessionZ)

```

The client application selects the conversation it wishes to communicate with from the returned list of topics and terminates all other unwanted conversations.

## Initiate Structured Field Conversation

3270	5250	VT
Yes	Yes	Yes

The **Initiate Structured Field** Conversation function connects a client application and a host application. This allows the applications to send data to each other and to receive data from each other.

The client sends the following command to initiate a structured field conversation:

```

SendMessage( -1,
             WM_DDE_INITIATE,
             hClientWnd,
             MAKELONG(aIBM3270, aLUN_xxxx) );

```

where:

**aIBM3270** Identifies the application atom.  
**aLUN\_xxxx** Identifies the topic atom. The string used to create atom aLUN\_xxxx is "LU" appended with the session ID "A", "B", ..., "Z", appended with "\_", and appended with the user-defined string of any length.

## PC/3270 Response

If PC/3270 can support a structured field conversation with the client application, it returns an acknowledgment message with the following parameter:

```

WM_DDE_ACK(aIBM3270, aLUN_xxxx)

```

## Initiate System Conversation

3270	5250	VT
Yes	Yes	Yes

The **Initiate System Conversation** function connects a client application to the system conversation. Only one client can be connected to the system conversation at a given time. The client sends the following command to initiate a system conversation:

```

SendMessage( -1,
             WM_DDE_INITIATE,
             hClientWnd,
             MAKELONG(aIBM327032, aSystem) );

```

where:

**aIBM327032** Identifies the application atom.  
**aSystem** Identifies the topic atom.



## Personal Communications Response

If Personal Communications can support a system topic conversation with the client application, it returns an acknowledgment message with the following parameters:

```
WM_DDE_ACK(aIBM327032, aSystem)
```

## Put Data to Presentation Space

3270	5250	VT
Yes	Yes	Yes

The **Put Data to Presentation Space** function sends an ASCIIZ data string to be written into the host presentation space at the location specified by the calling parameter. The client sends the following message to the session to send the string.

```
PostMessage( hServerWnd,
             WM_DDE_POKE,
             hClientWnd,
             MAKELONG(hData, aEPS) );
```

where:

**hData** Identifies a handle to a Windows global memory object that contains the string to be sent to the session. The global memory object contains the following structure:

```
typedef struct tagPutString
{
    unsigned unused:13;           // ** unused **
    unsigned fRelease:1;         // Session frees memory
    unsigned fReserved:2;        // ** reserved **
    int      cfFormat;           // Always CF_DSPTXT
    unsigned uPSStart;           // PS Position
    unsigned uEOFflag;           // EOF effective switch
    char     szStringData[1];    // String Data
} PUTSTRING, FAR *lpPUTSTRING;
```

These values are valid at the uEOFflag field:

```
WC_EFFECTEOF 0 // The string is truncated at EOF.
WC_UNEFFECTEOF 1 // The string is not truncated at EOF.
```

**aEPS** Identifies the presentation space atom as the item.

## Personal Communications Response

Personal Communications receives the string data and sends them to the presentation space, and returns a positive ACK message.

If the presentation space does not accept the string data, Personal Communications returns a negative ACK message containing one of the following status codes in the low-order byte of the wStatus word:

```
WM_DDE_ACK(wStatus, aEPS)
```

Return Code	Explanation
1	PS position is not valid.
2	Length is not valid.
3	The value of EOF flag is not valid.
5	Input to the target PS was inhibited.

Return Code	Explanation
6	The specified format is not valid.
7	The string was truncated (successful putting).
9	A system error occurred.

## Search for String

3270	5250	VT
Yes	Yes	Yes

This function allows a client application to examine the presentation space for a specified string in a specified area.

**Note:** The client must set the start PS position, search direction, a string to be searched, and EOF flag by using the **Set Presentation Space Service Condition** function before using this function.

The client sends the following message to search for the string.

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELONG(cfFormat, aSTRING) );
```

where:

**cfFormat**      Identifies the format for the search information. This is CF\_DSPTXT.  
**aSTRING**        Identifies the search data item.

## Personal Communications Response

Personal Communications returns the start position of the string in a DDE data message if the string was found in the specified area:

- WM\_DDE\_DATA(hData, aSTRING)
- WM\_DDE\_ACK(wStatus, aSTRING)

If Personal Communications cannot return the start position of the string, one of the following status codes is returned in the low-order byte of the wStatus word:

Return Code	Explanation
1	PS position is not valid or the string is too long.
2	The string cannot be found.
6	The specified format is not valid.
9	A system error occurred.

## Structure of the Search Information

Personal Communications returns the Search information in the following structure:

```
typedef struct tagSEARCH
{
    unsigned unused:12;            // *** unused ***
    unsigned fResponse:1;        // TRUE = DDE_REQUEST response
    unsigned fRelease:1;         // TRUE = Client frees this data
    unsigned reserved:1;         // *** reserved ***
};
```

```

unsigned fAckReq:1;      // TRUE = Client returns DDE_ACK
int      cfFormat;      // Format of Search data CF_DSPTXT
unsigned uFieldStart;    // String start offset
} SEARCH, far *lpSEARCH;

```

## Send Keystrokes

3270	5250	VT
Yes	Yes	Yes

The **Send Keystrokes** function sends keystrokes to the connected session. The client sends the following message to the session to send keystrokes.

```

PostMessage( hServerWnd,
             WM_DDE_POKE,
             hClientWnd,
             MAKELONG(hData, aKEYS) );

```

where:

**hData** Identifies a handle to a Windows global memory object that contains the keystrokes to be sent to the session. The global memory object contains the following structure:

```

typedef struct tagKeystrokes
{
    unsigned unused:13;          // ** unused **
    unsigned fRelease:1;        // Session frees memory
    unsigned fReserved:2;       // ** reserved **
    int      cfFormat;          // Always CF_DSPTXT
    unsigned uTextType;         // Type of keystrokes
    unsigned uRetryCount;       // Retry count 1 .. 16
    unsigned char szKeyData[1]; // Keystrokes
} KEYSTROKES, FAR *lpKEYSTROKES;

```

The following key text types are supported:

```

WC_PURETEXT  0 // Pure text, no AID, or included HLLAPI
               // commands
WC_HLLAPITEXT 1 // Text, including HLLAPI tokens

```

**Note:** If the keystrokes are pure text then specifying WC\_PURETEXT will transfer the keystrokes to the host in the fastest possible manner. If WC\_HLLAPITEXT is specified then the keystroke data can contain HLLAPI commands interspersed with the text.

**aKEYS** Identifies keystrokes as the item.

## Personal Communications Response

Personal Communications receives the keystrokes and sends them to the presentation space. If the presentation space does not accept the keystrokes, a reset is sent to the presentation space and the keystrokes are sent again. This procedure continues until the presentation space accepts the keystrokes or the retry count is reached. If Personal Communications cannot send the keystrokes to the host, Personal Communications returns a negative ACK message containing one of the following status codes in the low-order byte of the wStatus word. Otherwise, Personal Communications returns a positive ACK message signalling the keystrokes have been sent.

```
WM_DDE_ACK(wStatus, aKEYS)
```

Return Code	Explanation
1	Retry count is not valid.

Return Code	Explanation
2	Type of key strokes is not valid.
6	The specified format is not valid.
9	A system error occurred.

## Session Execute Macro

3270	5250	VT
Yes	Yes	Yes

You can issue commands and macros with the **DDE\_EXECUTE** function. The **DDE\_EXECUTE** function passes command strings to Personal Communications. The command strings must conform to DDE specifications. Refer to *Microsoft Windows Software Development Kit Guide to Programming* for more information about the DDE command syntax.

The client sends the following command to issue a **DDE\_EXECUTE** function.

```
PostMessage ( hServerWnd,
              WM_DDE_EXECUTE,
              hClientWnd,
              MAKELONG(NULL, hCommands) );
```

where:

### hCommands

Identifies a handle to a Windows global memory object containing Personal Communications commands. For a list of commands you can issue, see "Issuing Commands with the Session Execute Macro Function".

## Personal Communications Response

If Personal Communications can process the command string, Personal Communications returns an ACK message containing positive status information to the client. If Personal Communications cannot perform the command string, Personal Communications returns an ACK message containing this error code in the low-order word of the wStatus word:

Return Code	Explanation
9	A system error occurred.

## Issuing Commands with the Session Execute Macro Function

You can issue the following commands with the **Session Execute Macro** function:

- WINDOW
- KEYBOARD
- SEND
- RECEIVE
- SENDKEY
- WAIT

Use a separate DDE\_EXECUTE message for each command.

**Note:**

- Enclose values that contain nonalphanumeric characters or blanks in double quotation marks ("*value value*").
- To include a double quotation mark within a string, type it twice (for example, "This is a double quotation mark:").
- The maximum length for any command is 255 characters.

**WINDOW Command**

```
[WINDOW(action [, "name"])]
```

Performs window actions, where:

```
action = HIDE|RESTORE|MAXIMIZE|MINIMIZE|
          SHOW|CNGNAME
name = LT name or Switch List Entry name
```

**Note:** *name* should be specified when CNGNAME is specified at *action*. If *name* is a NULL string, the default caption will be displayed.

**KEYBOARD Command**

```
[KEYBOARD(action)]
```

Enables or disables the session keyboard, including the mouse, where:

```
action= LOCK|UNLOCK
```

**SEND Command**

```
[SEND("pcfilename", "hostfilename", "options")]
```

Sends files to the host, where:

```
pcfilename = [path]filename[.ext]
hostfilename =
  For VM system:
    filename filetype[filemode]
  For MVS system:
    [']filename[(membername)][']
  For CICS system:
  For OS/400 system:
    library name filename member name
```

*options* includes any combination of the following file transfer options: MVS, VM, CICS, QUIET, OS/400, and emulation-specific transfer options, separated by spaces.

Refer to *Personal Communications Version 4.3 Reference* for more information about the transfer options.

**RECEIVE Command**

```
[RECEIVE("pcfilename", "hostfilename", "options")]
```

Receives files from the host, where:

```
pcfilename = [path]filename[.ext]
hostfilename =
  For VM system:
    filename filetype[filemode]
  For MVS system:
```

```

[']filename[(membername)][']
For CICS system:
For OS/400 system:
  library name filename member name

```

*options* includes any combination of the following file transfer options: MVS, VM, CICS, QUIET, OS/400, and emulation-specific transfer options, separated by spaces.

Refer to *Personal Communications Version 4.3 Reference* for more information about the transfer options.

## SENDKEY Command

```
[SENDKEY(token,token)]
```

Sends keystrokes to Personal Communications, where:

```
token = text string|command|macro macroname
```

### Note:

- Text strings are enclosed in double quotation marks.
- Macros are prefixed with “macro”.
- The argument string for SENDKEY must be 255 characters or less.
- The following commands are supported.

Table 52. SENDKEY Command List

Command Name	Token	PC/3270	PC400
Alternate Cursor	alt cursor	Yes	Yes
Alternate Viewing Mode	alt view	Yes	Yes
Attention	sys attn	Yes	Yes
Backspace	backspace	Yes	Yes
Back Tab	backtab	Yes	Yes
Backtab Word	backtab word	Yes	Yes
Character Advance	character advance	No	Yes
Character Backspace	backspace valid	No	Yes
Clear Screen	clear	Yes	Yes
Clicker	click	Yes	Yes
Color Blue	blue	Yes	No
Color Field Inherit	field color	Yes	No
Color Green	green	Yes	No
Color Pink	pink	Yes	No
Color Red	red	Yes	No
Color Turquoise	turquoise	Yes	No
Color White	white	Yes	No
Color Yellow	yellow	Yes	No
Cursor Blink	cursor blink	Yes	Yes
Cursor Down	down	Yes	Yes

Table 52. SENDKEY Command List (continued)

Command Name	Token	PC/3270	PC400
Cursor Left	left	Yes	Yes
Cursor Right	right	Yes	Yes
Cursor Select	cursor select	Yes	Yes
Cursor Up	up	Yes	Yes
Delete Character	delete char	Yes	Yes
Delete Word	delete word	Yes	Yes
Device Cancel	device cancel	Yes	Yes
Dup Field	dup	Yes	Yes
Edit Clear	edit-clear	Yes	Yes
Edit Copy	edit-copy	Yes	Yes
Edit Cut	edit-cut	Yes	Yes
Edit Paste	edit-paste	Yes	Yes
Edit Undo	edit-undo	Yes	Yes
End Field	end field	Yes	Yes
Enter	enter	Yes	Yes
Erase EOF	erase eof	Yes	Yes
Erase Field	erase field	Yes	No
Erase Input	erase input	Yes	Yes
Fast Cursor Down	fast down	Yes	Yes
Fast Cursor Left	fast left	Yes	Yes
Fast Cursor Right	fast right	Yes	Yes
Fast Cursor Up	fast up	Yes	Yes
Field Exit	field exit	No	Yes
Field Mark	field mark	Yes	Yes
Field +	field +	No	Yes
Field -	field -	No	Yes
Graphic Cursor	+cr	Yes	No
Help	help	Yes	Yes
Highlighting Field Inherit	field hilight	Yes	No
Highlighting Reverse	reverse	Yes	No
Highlighting Underscore	underscore	Yes	No
Home	home	Yes	Yes
Host Print	host print	Yes	No
Input	input	Yes	Yes
Input nondisplay	input nd	Yes	Yes
Insert Toggle	insert	Yes	Yes
Lower case	to lower	Yes	No
Mark Down	mark down	Yes	Yes
Mark Left	mark left	Yes	Yes

Table 52. SENDKEY Command List (continued)

Command Name	Token	PC/3270	PC400
Mark Right	mark right	Yes	Yes
Mark Up	mark up	Yes	Yes
Move Mark Down	move down	Yes	Yes
Move Mark Left	move left	Yes	Yes
Move Mark Right	move right	Yes	Yes
Move Mark Up	move up	Yes	Yes
New Line	newline	Yes	Yes
Next Page	page down	No	Yes
Pause 1 second	pause	Yes	Yes
Previous Page	page up	No	Yes
Print Screen	local copy	Yes	Yes
Program Attention Key 1	pa1	Yes	No
Program Attention Key 2	pa2	Yes	No
Program Attention Key 3	pa3	Yes	No
Program Function Key 1 : : Program Function Key 24	pf1 : : pf24	Yes : : X	Yes : : X
Quit	quit	Yes	Yes
Reset	reset	Yes	Yes
Response Time Monitor	rtm	Yes	No
Roll Down	roll down	No	Yes
Roll Up	roll up	No	Yes
Rubout	rubout	Yes	Yes
Rule	rule	Yes	Yes
SO/SI Display	so si	Yes	Yes
SO/SI Generate	so si generate	No	Yes
System Request	sys req	Yes	Yes
Tab Field	tab field	Yes	Yes
Tab Word	tab word	Yes	Yes
Test	test request	No	Yes
Unmark	unmark	Yes	Yes
Upper case	to upper	Yes	No
Upper/Lower Change	to other	Yes	No
Wait for bind	wait app	Yes	Yes
Wait for System	wait sys	Yes	Yes
Wait transition	wait trn	Yes	Yes
Wait while input inh.	wait inp inh	Yes	Yes



Table 52. SENDKEY Command List (continued)

Command Name	Token	PC/3270	PC400
Window Relocation 1	view 1	Yes	Yes
⋮	⋮	⋮	⋮
Window Relocation 8	view 8	X	X

**Examples:**

1. To logon  
[SENDKEY("Logon")]
2. To get reader list  
[SENDKEY("RDRL", enter)]

**WAIT Command**

[WAIT("[time out][wait condition]")]

Waits until the timeout expires or the wait condition the client specified occurs. For this command, the client has to set at least one option, where:

*time out* (optional)

If the client sets a timeout value in the command statements, the following units are available in the wait statement.

- msec
- millisecond
- milliseconds
- sec
- second
- seconds
- minute
- minutes
- hour
- hours

*wait condition* (optional)

For the wait condition option, the client can select the following options:

**while cursor at (cursor row, cursor column)**

While the cursor is at (cursor row, cursor column), it keeps waiting.

**while "string"**

While the "string" is somewhere on the screen, it keeps waiting.

**while "string" at (cursor row, cursor column)**

While the "string" is at (cursor row, cursor column) on the screen, it keeps waiting.

**until cursor at (cursor row, cursor column)**

Until the cursor moves to (cursor row, cursor column), it keeps waiting.

**until "string"**

Until the "string" is displayed somewhere on the screen, it keeps waiting.

**until "string" at (cursor row, cursor column)**

Until the "string" is displayed at (cursor row, cursor column), it keeps waiting.

### Examples:

1. To wait 10 seconds  
[WAIT("10 seconds")]
2. To wait while "ABCDEF" is displayed at (2,9) on the screen  
[WAIT("while ""ABCDEF"" at (2,9)")]
3. To wait until "ABCDEF" is displayed at (2,9) on the screen, or after 8 seconds  
[WAIT("8 seconds until ""ABCDEF"" at (2,9)")]

## Set Cursor Position

3270	5250	VT
Yes	Yes	Yes

The **Set Cursor Position** function allows the client application to set the cursor position in the session window.

```
PostMessage( hServerWnd,  
            WM_DDE_POKE,  
            hClientWnd,  
            MAKELONG(hData, aSETCURSOR) );
```

where:

**hData** Identifies a handle to a Windows global memory object that contains the cursor positioning information in the following structure:

```
typedef struct tagSETCURSOR  
{  
    unsigned unused:13;           // ** unused **  
    unsigned fRelease:1;         // TRUE = Session frees memory  
    unsigned fReserved:2;        // ** reserved **  
    int cfFormat;                // Always CF_DSPTXT  
    unsigned uSetCursorType;     // Cursor Set Type  
    unsigned uSetCursor1;        // Cursor Row or PS Offset  
    unsigned uSetCursor2;        // Cursor Col  
} SETCURSOR, FAR *lpSETCURSOR;
```

Personal Communications supports two ways to set the cursor position:

- PS Offset ( uSetCursorType = 0 )
- Row/Column number ( uSetCursorType = 1 )

The application specifies which method by setting the uSetCursorType field to the appropriate value, followed by setting the two other fields uSetCursor1 and uSetCursor2 to their appropriate values as follows:

- uSetCursorType = 0 offset
  - uSetCursor1: 0 ... (PSsize – 1)
- uSetCursorType = 1 row/col
  - uSetCursor1: 0 ... (PSrows – 1)
  - uSetCursor2: 0 ... (PScols – 1)

**aSETCURSOR** Identifies cursor position as the item.

## Personal Communications Response

Personal Communications receives the cursor information and moves the cursor to the specified position in the PS. If the cursor is positioned successfully, Personal Communications returns a positive ACK message to the client application.

Otherwise, a negative ACK message is returned with one of the following error codes in the low-order byte of the wStatus word.

WM\_DDE\_ACK(wStatus, aSETCURSOR)

Return Code	Explanation
1	Cursor set type is not valid. Must be 0 or 1.
2	Cursor PS offset is not valid. Must be 0 ... (PSSize - 1).
3	Cursor row value is not valid. Must be 0 ... (PSrows - 1).
4	Cursor column value is not valid. Must be 0 ... (PScols - 1).
6	The specified format is not valid.
9	A system error occurred.

## Set Mouse Intercept Condition

3270	5250	VT
Yes	Yes	Yes

This function specifies the mouse input to be intercepted. The client sends the following command to set the mouse event to be intercepted.

```
PostMessage( hServerWnd,
             WM_DDE_POKE,
             hClientWnd,
             MAKELONG(hData, aMOUSE) );
```

where:

**hData** Identifies a handle to a Windows global memory object that specifies the condition of intercepting the mouse input, CF\_TEXT or CF\_DSPTEXT.  
**aMOUSE** Identifies Mouse atom as the item.

If the format is CF\_TEXT, the client program sends the condition in the following structure:

```
typedef struct tagSETMOUSE_CF_TEXT
{
    unsigned    unused:12,        //
    unsigned    fRelease:1,      //
    unsigned    fReserved:3;     //
    int         cfFormat;        // Always CF_TEXT
    unsigned char Condition[1]   //
} SETMOUSE_CF_TEXT, FAR *lpSETMOUSE_CF_TEXT;
```

The following table shows the parameters' values:

Parameter Name	Meaning	Value
Condition	Condition of intercepting the mouse input	<p>A string terminated with \0, consists of the constants defined as follows in any order:</p> <p><b>L</b> Enable intercepting the left button</p> <p><b>I</b> Disable intercepting the left button</p> <p><b>R</b> Enable intercepting the right button</p> <p><b>r</b> Disable intercepting the right button</p> <p><b>M</b> Enable intercepting the middle button</p> <p><b>m</b> Disable intercepting the middle button</p> <p><b>S</b> Enable intercepting a single click</p> <p><b>s</b> Disable intercepting a single click</p> <p><b>D</b> Enable intercepting a double click</p> <p><b>d</b> Disable intercepting a double click</p> <p><b>T</b> Retrieve the pointed string</p> <p><b>t</b> Do not retrieve the pointed string</p>

If the format is CF\_DSPTTEXT, the client program sends the condition in the following structure:

```
typedef struct tagSETMOUSE_CF_DSPTTEXT
{
    unsigned    unused:12,        //
    unsigned    fRelease:1,      //
    unsigned    fReserved:3;     //
    int         cfFormat;        // Always CF_DSPTTEXT
    BOOL        bLeftButton;     //
    BOOL        bRightButton;    //
    BOOL        bMiddleButton;   //
    BOOL        bSingleClick;    //
    BOOL        bDoubleClick;    //
    BOOL        bRetrieveString; //
} SETMOUSE_CF_DSPTTEXT, FAR *lpSETMOUSE_CF_DSPTTEXT;
```

The following table shows the values in the parameters:

Parameter Name	Meaning	Value
bLeftButton	Enable or disable interception of the left mouse button	<p><b>True</b> Enable intercepting the left button</p> <p><b>False</b> Disable intercepting the left button</p>
bRightButton	Enable or disable interception of the right mouse button	<p><b>True</b> Enable intercepting the right button</p> <p><b>False</b> Disable intercepting the right button</p>

Parameter Name	Meaning	Value
bMiddleButton	Enable or disable interception of the middle mouse button	<b>True</b> Enable intercepting the middle button <b>False</b> Disable intercepting the middle button
bSingleClick	Enable or disable interception of the single click	<b>True</b> Enable intercepting the single click <b>False</b> Disable intercepting the single click
bDoubleClick	Enable or disable interception of the double click	<b>True</b> Enable intercepting the double click <b>False</b> Disable intercepting the double click
bRetrieveString	Retrieve or do not retrieve the pointed string	<b>True</b> Retrieve the pointed string <b>False</b> Do not retrieve the pointed string

## Personal Communications Response

When receiving the **Set Mouse Intercept Condition** request, Personal Communications returns an ACK message if it can set the intercept condition to the specified status. Otherwise, a negative ACK message is returned to the client with one of the following return codes in the low-order byte of the wStatus field:

WM\_DDE\_ACK(wStatus, aMOUSE)

Return Code	Explanation
2	A character in Condition parameter is not valid.
6	The specified format is not valid.
9	A system error occurred.

## Set Presentation Space Service Condition

3270	5250	VT
Yes	Yes	Yes

The **Set Presentation Space Service Condition** function sets the condition for using the following functions:

- **Get Partial Presentation Space**
- **Find Field**
- **Search for String**

The client application sets the condition by calling this function such as:

- Start PS position
- PS length
- EOF flag

- Search direction
- ASCIIZ string

The client must specify the **Set Presentation Space Service Condition** function before invoking the functions listed above. The conditions set by this function remain in effect until the next **Set Presentation Space Service Condition** function is called. The client sends the following message to set the condition:

```
PostMessage( hServerWnd,
             WM_DDE_POKE,
             hClientWnd,
             MAKELONG(hData, aEPSCOND) );
```

where:

**hData** Identifies a handle to a Windows global memory object containing:

```
typedef struct tagPSSERVCOND
{
    unsigned    unused:13,           //
    unsigned    fRelease:1,         //
    unsigned    fReserved:2;       //
    int         cfFormat;           // Always CF_DSPTEXT
    unsigned    uPSStart;           // PS Position
    unsigned    uPSLength;         // Length of PS
    unsigned    uSearchDir;        // Direction for search
    unsigned    uEOFflag;          // EOF effective switch
    char        szTargetString[1]; // Target String
} PSSERVCOND, FAR *lpPSSERVCOND;
```

The following values are valid at the uSearchDir field:

```
WC_SRCHFRWD    0 // Search forward.
WC_SRCHBKWD    1 // Search backward.
```

The following values are valid at the uEOFflag field:

```
WC_UNEFFECTEOF 0 // The string is not truncated at EOF.
WC_EFFECTEOF   1 // The string is truncated at EOF.
```

**aEPSCOND** Identifies the item for the **Set Presentation Space Service Condition** function.

## Personal Communications Response

If Personal Communications can perform the **Set Presentation Space Service Condition** function, then Personal Communications returns an ACK message:

```
WM_DDE_ACK(wStatus, aEPSCOND)
```

If Personal Communications cannot perform the **Set Presentation Space Service Condition** function, then Personal Communications returns a negative ACK message containing one of the following return codes in the low-order byte of wStatus:

Return Code	Explanation
1	PS position is not valid.
2	Length is not valid.
3	The value of EOF flag is not valid.
4	The value of Search Direction is not valid.
6	The specified format is not valid.
9	A system error occurred.

## Set Session Advise Condition

3270	5250	VT
Yes	Yes	Yes

This function sets the condition for the DDE\_ADVISE of the **Start Session Advise** function. The client can specify a search string and a region of the screen. When the advise condition is met, the server notifies the client of the condition according to the options specified by the **Start Session Advise** function.

**Note:** The client must specify the **Set Session Advise Condition** function before invoking **Start Session Advise**. If the advise condition is set after the **Start Session Advise** function is started, the advise condition will be ignored and the client will receive a negative ACK message. See “Start Session Advise” on page 442 for more information about starting the advise.

The client sends the following message to set the advise condition.

```
PostMessage( hServerWnd,
             WM_DDE_POKE,
             hClientWnd,
             MAKELONG(hData, aPSCOND) );
```

where:

**hData** Identifies a handle to a Windows global memory object containing:

```
typedef struct tagSEARCHDATA
{
    unsigned    unused:13,           //
    unsigned    fRelease:1,         //
    unsigned    fReserved:2;        //
    int         cfFormat;            // Always CF_DSPTXT
    WORD        uPSStart;           // PS Position of string
    WORD        uPSLength           // Length of String
    BOOL        bCaseSensitive;     // Case Sensitive TRUE=YES
    char        SearchString[1];    // Search String
} SEARCHDATA, FAR *lpSEARCHDATA;
```

**aPSCOND** Identifies the item for the **Set Session Advise Condition** function.

## Personal Communications Response

If Personal Communications can perform the **Set Session Advise Condition** function, Personal Communications returns this ACK message:

```
WM_DDE_ACK(wStatus, aPSCOND)
```

If Personal Communications cannot perform the **Set Session Advise Condition** function, then Personal Communications returns an negative ACK message containing one of the following return codes in the low-order byte of wStatus:

Return Code	Explanation
1	Advise is already active.
2	Advise condition is already active.
3	PS position is not valid.
4	String length is not valid.
6	The specified format is not valid.
9	A system error occurred.

## Set Structured Field Service Condition

3270	5250	VT
Yes	Yes	Yes

The **Set Structured Field Service Condition** function passes the Query Reply data provided by the client application.

**Note:** The client must call the **Set Structured Field Service Condition** function before invoking the **Start Read SF** function or the **Write SF** function.

The client sends the following message to set the condition.

```
PostMessage( hServerWnd,
             WM_DDE_POKE,
             hClientWnd,
             MAKELONG(hData, aSFCOND) );
```

where:

**hData** Identifies a handle to a Windows global memory object containing:

```
typedef struct tagSFSERVCOND
{
    unsigned    unused:12,          //
    unsigned    fRelease:1,        //
    unsigned    fReserved:3;       //
    int         cfFormat;           // Always CF_DSPTXT
    WORD        uBufferSize;       // Buffer size of Read SF
    WORD        uQRLength;         // Length of Query Reply data
    char        szQueryReply[1];   // Query Reply data
} SFSERVCOND, FAR *lpSFSERVCOND;
```

**aSFCOND** Identifies the item for the **Set Structured Field Service Condition** function.

## PC/3270 Response

PC/3270 checks the Query Reply ID and Type (not DOID) and the length. If they are valid, then PC/3270 returns an ACK message:

```
WM_DDE_ACK(wStatus, aSFCOND)
```

If PC/3270 cannot perform the **Set Structured Field Service Condition** function, then PC/3270 returns a negative ACK message containing one of the following return codes in the low-order byte of wStatus:

Return Code	Explanation
1	PS SF ID is not valid.
2	Length is not valid.
3	One DDM base type is already connected to this session.
4	Structured Field Service Condition is already set.
6	The specified format is not valid.
9	A system error occurred.

## Start Close Intercept

3270	5250	VT
Yes	Yes	Yes



The **Start Close Intercept** function allows a client application to intercept close requests generated when a user selects the close option from the emulator session window. This function intercepts the close request and discards it until the Stop Close Intercept function is requested. After using this function, the client receives DATA messages notifying it that close requests occurred (CLOSE).

The client sends the following command to begin a session advise.

```
PostMessage( hServerWnd,
            WM_DDE_ADVISE,
            hClientWnd,
            MAKELONG(hOptions, aCLOSE) );
```

where:

**hOptions** Is a handle to a Windows global memory object, with the following structure:

```
typedef struct tagOPTIONS
{
    unsigned reserved:14;           // *** reserved ***
    unsigned fDeferUpd:1;          // Send notification only
    unsigned fAckReq:1;            // Client will ACK all notices
    WORD      cfFormat;             // Clipboard format to use
} OPTIONS, FAR *lpOPTIONS;
```

If the value of fDeferUpd is 1, DDE Data messages will be sent to the client application with the hData set to NULL. The client must then issue a DDE REQUEST to request the data item.

If the value of fAckReq is 1, the server does not notify the client of further close requests until the server receives an ACK message from the client in response to any previous notification.

The cfFormat field specifies the format to send the close request. (Must be CF\_DSPTEXT.)

**aCLOSE** Identified close intercept as the item.

## Personal Communications Response

Personal Communications receives the Start Close Intercept and returns an ACK message if it can start the intercept. Otherwise a negative ACK message is returned to the client with one of the following return codes in the low-order byte of the wStatus field:

```
WM_DDE_ACK(wStatus, aCLOSE)
```

Return Code	Explanation
1	Close Intercept is already working.
6	The specified format is not valid.
9	A system error occurred.

Once the intercept starts, the client receives DATA messages notifying it that the close request is intercepted:

```
WM_DDE_DATA(hData, aCLOSE)
```

where:

**hData** Identifies a handle to a Windows global memory object containing:

```
typedef struct tagCLOSEREQ
{
    unsigned    unused:12,           // *** unused ***
    unsigned    fResponse:1,        // TRUE = DD_REQUEST response
    unsigned    fRelease:1,         // TRUE = Client releases memory
    unsigned    reserved:1,         // *** reserved ***
    unsigned    fAckReq:1,          // TRUE = DDE_ACK is required
    int         cfFormat;           // Always CF_DSPTXT
    WORD        uCloseReqCount;     // Counter of the Close Requests
} CLOSEREQ, FAR *lpCLOSEREQ;
```

The DATA messages continue until a Stop Close Intercept message is sent to Personal Communications.

## Start Keystroke Intercept

3270	5250	VT
Yes	Yes	Yes

The **Start Keystroke Intercept** function allows a client application to filter any keystrokes sent to a session by a terminal operator. After a call to this function, keystrokes are intercepted, and the client receives them (KEYS).

The client sends the following command to begin intercept.

```
PostMessage( hServerWnd,
             WM_DDE_ADVISE,
             hClientWnd,
             MAKELONG(hOptions, aKEYS) );
```

where:

**hOptions** Is a handle to a Windows global memory object, with the following structure:

```
typedef struct tagOPTIONS
{
    unsigned reserved:14;           // Reserved
    unsigned fDeferUpd:1;          // Send notification only
    unsigned fAckReq:1;            // Client will ACK all notices
    WORD      cfFormat;            // Clipboard format to use
} OPTIONS, FAR *lpOPTIONS;
```

If the value of fDeferUpd is 1, DDE Data messages are sent to the client application with the hData set to NULL. The client then issues a DDE REQUEST to request the data item.

If the value of fAckReq is 1, the server does not notify the client of further keystrokes until the server receives an ACK message from the client in response to any previous keystrokes notification.

The cfFormat field specifies the format to send the keystrokes when the keystroke is sent by a terminal operator. (Must be CF\_DSPTXT.)

**aKEYS** Identified keystrokes as the item.

## Personal Communications Response

Personal Communications receives the **Start Keystroke Intercept** and returns an ACK message if it can start the intercept. Otherwise a negative ACK message is returned to the client with one of the following return codes in the low-order byte of the `wStatus` field:

```
WM_DDE_ACK(wStatus, aKEYS)
```

Return Code	Explanation
1	Keystroke Intercept is already started.
6	The specified format is not valid.
9	A system error occurred.

Once the intercept has started, the client receives DATA messages notifying it that the keystroke is intercepted:

```
WM_DDE_DATA(hData, aKEYS)
```

The DATA messages continue until a Stop Keystroke Intercept message is sent to Personal Communications. The format of the data item will be the same format as if the client requested the data item via a DDE\_REQUEST.

## Start Mouse Input Intercept

<i>3270</i>	<i>5250</i>	<i>VT</i>
Yes	Yes	Yes

The **Start Mouse Input Intercept** function allows a client application to intercept mouse input when a terminal operator press the mouse button on emulator session window. After calling this function, the client receives DATA messages that include the PS position where mouse input occurred.

The client sends the following command to begin to intercept the mouse input.

```
PostMessage( hServerWnd,  
            WM_DDE_ADVISE,  
            hClientWnd,  
            MAKELONG(hOptions, aMOUSE) );
```

where:

**hOptions** Is a handle to a Windows global memory object, with the following structure:

```
typedef struct tagOPTIONS
{
    unsigned reserved:14;           // Reserved
    unsigned fDeferUpd:1;          // Send notification only
    unsigned fAckReq:1;            // Client will ACK all notices
    WORD      cfFormat;             // Clipboard format to use
} OPTIONS, FAR *lpOPTIONS;
```

If the value of fDeferUpd is 1, DDE Data messages will be sent to the client application with the hData set to NULL. The client must then issue a DDE REQUEST to request the data item.

If the value of fAckReq is 1, the server does not notify the client of further structured field data until the server receives an ACK message from the client in response to any previous notification.

The cfFormat field specifies the format to send the data item has been updated.

**aMOUSE** Identified MOUSE as the item.

## Personal Communications Response

Personal Communications receives the **Start Mouse Input Intercept** and returns an ACK message if it can start this function. Otherwise a negative ACK message is returned to the client with one of the following return codes in the low-order byte of the wStatus field:

```
WM_DDE_ACK(wStatus, aMOUSE)
```

Return Code	Explanation
1	Mouse Input Intercept has been already started.
6	The specified format is not valid.
9	A system error occurred.

Once the **Mouse Input Intercept** starts, the client receives DATA messages of the structured field:

```
WM_DDE_DATA(hData, aMOUSE)
```

where:

**hData** If the format is CF\_TEXT, Personal Communications returns the mouse input information in the following format:

```
typedef struct tagMOUSE_CF_TEXT
{
    unsigned    unused:12,        // **** Unused ****
    unsigned    fRespons:1,      // TRUE = DDE_REQUEST response
    unsigned    fRelease:1,      // TRUE = Client frees this data
    unsigned    reserved:1,      // **** Reserved ****
    unsigned    fAckReq:1;       // TRUE = Client returns DDE_ACK
    int         cfFormat;        // CF_TEXT
    unsigned char PSPos[4];      // PS position
    unsigned char Tab1[1];       // TAB character
    unsigned char PSRowPos[4];   // PS row position
    unsigned char Tab2[1];       // TAB character
    unsigned char PSColPos[4];   // PS columns position
    unsigned char Tab3[1];       // TAB character
    unsigned char PSSize[4];     // Size of the PS
    unsigned char Tab4[1];       // TAB character
    unsigned char PSRows[4];     // PS number of rows
    unsigned char Tab5[1];       // TAB character
    unsigned char PSCols[4];     // PS number of columns
    unsigned char Tab6[1];       // TAB character
    unsigned char ButtonType[1]; // Pressed button type
    unsigned char Tab7[1];       // TAB character
    unsigned char ClickType[1];  // Click type
    unsigned char Tab8[1];       // TAB character
    unsigned char ClickString[1]; // Retrieved string
} MOUSE_CF_TEXT, FAR *lpMOUSE_CF_TEXT;
```

The following table shows the values in the parameters:

Parameter Name	Meaning	Value
PSPos	PS offset of the position where mouse was clicked	0 ... (PSSize – 1)
PSRowPos	Row number of the position where mouse was clicked	0 ... (PSRows – 1)
PSColPos	Column number of the position where mouse was clicked	0 ... (PSCols – 1)
PSSize	Presentation space size	
PSRows	Number of presentation space rows	
PSCols	Number of presentation space columns	
ButtonType	Type of clicked mouse button	<b>L</b> Left button <b>M</b> Middle button <b>R</b> Right button
ClickType	Type of clicking	<b>S</b> Single click <b>D</b> Double click
ClickString	Retrieved string to which the mouse pointed	A character string terminated with a '\0'

Parameter Name	Meaning	Value
Tab1-8	A tab character for delimiter	'\t'

**hData** If the format is CF\_DSPTTEXT, Personal Communications returns the mouse input information in the following format:

```
typedef struct tagMOUSE_CF_DSPTTEXT
{
    unsigned    unused:12,        // **** Unused ****
    unsigned    fRespons:1,      // TRUE = DDE_REQUEST response
    unsigned    fRelease:1,      // TRUE = client frees the storage
    unsigned    reserved:1,      // **** Reserved ****
    unsigned    fAckReq:1;       // TRUE = client returns DDE_ACK
    int         cfFormat;        // CF_DSPTTEXT
    unsigned    uPSPos;          // PS position
    unsigned    uPSRowPos;       // PS row position
    unsigned    uPSColPos;       // PS column position
    unsigned    uPSSize;         // Size of the presentation space
    unsigned    uPSRows;         // PS number of rows
    unsigned    uPSCols;         // PS number of columns
    unsigned    uButtonType;     // Pressed button type
    unsigned    uClickType;      // Click type
    unsigned char szClickString[1]; // Retrieved string
} MOUSE_CF_DSPTTEXT, FAR *lpMOUSE_CF_DSPTTEXT;
```

The following table shows the values in the parameters:

Parameter Name	Meaning	Value
uPSPos	PS offset of the position where mouse was clicked	0 ... (uPSSize - 1)
uPSRowPos	Row number of the position where mouse was clicked	0 ... (uPSRows - 1)
uPSColPos	Column number of the position where mouse was clicked	0 ... (uPSCols - 1)
uPSSize	Size of the presentation space	
uPSRows	Number of rows of the presentation space	
uPSCols	Number of columns of the presentation space	
uButtonType	Type of the clicked mouse button	<b>0x0001</b> Left button <b>0x0002</b> Middle button <b>0x0003</b> Right button
uClickType	Type of clicking	<b>0x0001</b> Single click <b>0x0002</b> Double click
szClickString	Retrieved string to which the mouse pointed	A character string terminated with a \0

The DATA messages continue until a Stop Mouse Input Intercept message is sent to Personal Communications.

## Start Read SF

3270	5250	VT
Yes	Yes	Yes

The **Start Read SF** function allows a client application to read structured field data from the host application. After using this function, the client receives DATA messages notifying it that close requests occurred.

**Note:** Before using this function, the client must call the **Set Structured Field Service Condition** function to pass the Query Reply data to the server.

The client sends the following command to begin a Read SF.

```
PostMessage( hServerWnd,
             WM_DDE_ADVISE,
             hClientWnd,
             MAKELONG(hOptions, aSF) );
```

where:

**hOptions** Is a handle to a Windows global memory object, with the following structure:

```
typedef struct tagOPTIONS
{
    unsigned reserved:14;           // Reserved
    unsigned fDeferUpd:1;          // Send notification only
    unsigned fAckReq:1;            // Client will ACK all notices
    WORD      cfFormat;            // Clipboard format to use
} OPTIONS, FAR *lpOPTIONS;
```

If the value of fDeferUpd is 1, DDE Data messages will be sent to the client application with the hData set to NULL. The client must then issue a DDE REQUEST to request the data item.

If the value of fAckReq is 1, the server does not notify the client of further structured field data until the server receives an ACK message from the client in response to any previous notification.

The cfFormat field specifies the format to send the structured field data. (It must be CF\_DSPTEXT.)

**aSF** Identified structured field as the item.

### PC/3270 Response

PC/3270 receives the **Start Read SF** and returns an ACK message if it can start the Read SF. Otherwise a negative ACK message is returned to the client with one of the following return codes in the low-order byte of the wStatus field:

```
WM_DDE_ACK(wStatus, aSF)
```

Return Code	Explanation
1	Read SF is already started.
3	No prior Set Structured Field Service Condition function was called.
6	The specified format is not valid.
9	A system error occurred.

Once the Read SF has started, the client receives DATA messages of the structured field:

WM\_DDE\_DATA(hData, aSF)

where:

**hData** Identifies a handle to a Windows global memory object containing:

```
typedef struct tagSFDATA
{
    unsigned    unused:12,           //
    unsigned    fRelease:1,         //
    unsigned    fReserved:3;        //
    int         cfFormat;           // Always CF_DSPTEXT
    WORD        uSFLength;          // Length of SF data
    char        szSFData[1];        // SF data
} SFDATA, FAR *lpSFDATA;
```

The DATA messages continue until a Stop Read SF message is sent to PC/3270.

## Start Session Advise

3270	5250	VT
Yes	Yes	Yes

The **Start Session Advise** function establishes a link between the Personal Communications session and the client. This lets the client receive updates of the presentation space (PS), the operator information area (OIA), or the trim rectangle (TRIMRECT) when the data item is updated.

**Note:** If the client application needs conditional notification when the presentation space is updated, set an advise condition prior to invoking the advise function for the presentation space. See "Set Session Advise Condition" on page 433 .

The client sends the following command to begin a session advise.

```
PostMessage( hServerWnd,
             WM_DDE_ADVISE,
             hClientWnd,
             MAKELONG(hOptions, aItem) );
```



where:

**hOptions** Is a handle to a Windows global memory object. This is the structure:

```
typedef struct tagOPTIONS
{
    unsigned reserved:14;           // Reserved
    unsigned fDeferUpd:1;          // Send notification only
    unsigned fAckReq:1;            // Client will ACK all notices
    WORD      cfFormat;             // Clipboard format to use
} OPTIONS, FAR *lpOPTIONS;
```

If the value of `fDeferUpd` is 1, DDE Data messages are sent to the client application with the `hData` set to `NULL`. The client must then issue a `DDE REQUEST` to request the data item.

If the value of `fAckReq` is 1, the server does not notify the client of further changes to the data item until the server receives an `ACK` message from the client in response to any previous update notification.

The `cfFormat` field specifies the format to send the data item when the item has been updated.

**item** Specifies the item of information being requested; in this case, the value can be `PS`, `OIA`, or `TRIMRECT`.

## Personal Communications Response

Personal Communications receives the **Start Session Advise** and returns an `ACK` message if it can start the advise. Otherwise, a negative `ACK` message is returned to the client with one of the following return codes in the low-order byte of the `wStatus` field:

```
WM_DDE_ACK(wStatus, aItem)
```

Return Code	Explanation
1	Advise already active for data item.
6	Advise parameter not valid.
9	A system error occurred.

Once the advise has started, the client receives `DATA` messages notifying it that the data item (`PS`, `OIA`, or `TRIMRECT`) has changed:

```
WM_DDE_DATA(hData, aItem)
```

The `DATA` messages continue until a `Stop Session Advise` message is sent to Personal Communications. The format of the data item will be the same format as if the client requested the data item via a `DDE_REQUEST`.

## Stop Close Intercept

3270	5250	VT
Yes	Yes	Yes

The **Stop Close Intercept** function ends a client application's ability to intercept close request. The client sends the following command to perform the **Stop Close Intercept** function.

```
PostMessage( hServerWnd,
             WM_DDE_UNADVISE,
             hClientWnd,
             MAKELONG(NULL, aCLOSE) );
```

where:

**aCLOSE** Identified close intercept as the item.

## Personal Communications Response

If Personal Communications can perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing positive status information to the client:

```
WM_DDE_ACK(wStatus, aCLOSE)
```

If Personal Communications cannot perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing negative status information and one of the following return codes in the low-order byte of the wStatus word:

Return Code	Explanation
1	Advise has not started yet.
9	A system error occurred.

## Stop Keystroke Intercept

3270	5250	VT
Yes	Yes	Yes

The **Stop Keystroke Intercept** function ends a client application's ability to intercept keystrokes. The client sends the following command to perform the **Stop Keystroke Intercept** function.

```
PostMessage( hServerWnd,  
            WM_DDE_UNADVISE,  
            hClientWnd,  
            MAKELONG(NULL, aKEYS) );
```

where:

**aKEYS** Identified keystrokes as the item.

## Personal Communications Response

If Personal Communications can perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing positive status information to the client:

```
WM_DDE_ACK(wStatus, aKEYS)
```

If Personal Communications cannot perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing negative status information and one of the following return codes in the low-order byte of the wStatus word.

Return Code	Explanation
1	Advise has not started yet.
9	A system error occurred.

## Stop Mouse Input Intercept

3270	5250	VT
Yes	Yes	Yes

The **Stop Mouse Input Intercept** function ends a client application's ability to intercept mouse input.

The client sends the following command to perform the **Stop Mouse Input Intercept** function.

```
PostMessage( hServerWnd,
            WM_DDE_UNADVISE,
            hClientWnd,
            MAKELONG(NULL, aMOUSE) );
```

where:

**aMOUSE** Identified mouse as the item.

### Personal Communications Response

If Personal Communications can perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing positive status information to the client:

```
WM_DDE_ACK(wStatus, aMOUSE)
```

If Personal Communications cannot perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing negative status information and one of the following return codes in the low-order byte of the wStatus word.

Return Code	Explanation
1	Advise has not started yet.
9	A system error occurred.

### Stop Read SF

3270	5250	VT
Yes	Yes	Yes

The **Stop Read SF** function ends a client application's ability to read structured field data.

The client sends the following command to perform the **Stop Read SF** function.

```
PostMessage( hServerWnd,
            WM_DDE_UNADVISE,
            hClientWnd,
            MAKELONG(NULL, aSF) );
```

where:

**aSF** Identified structured field as the item.

### PC/3270 Response

If PC/3270 can perform the DDE\_UNADVISE, PC/3270 returns an ACK message containing positive status information to the client:

```
WM_DDE_ACK(wStatus, aSF)
```

If PC/3270 cannot perform the DDE\_UNADVISE, PC/3270 returns an ACK message containing negative status information and one of the following return codes in the low-order byte of the wStatus word.

Return Code	Explanation
1	Advise has not started yet.
9	A system error occurred.

## Stop Session Advise

3270	5250	VT
Yes	Yes	Yes

The **Stop Session Advise** function disconnects a link between Personal Communications and the client. The client sends the following command to perform the **Stop Session Advise** function.

```
PostMessage( hServerWnd,
             WM_DDE_UNADVISE,
             hClientWnd,
             MAKELONG(NULL, aItem) );
```

where:

**altem** Specifies the item of information being requested; in this case, the value can be PS, OIA, TRIMRECT, or NULL.

If the value of *altem* is NULL, then the client has requested termination of all active notifications for the conversation.

## Personal Communications Response

If Personal Communications can perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing positive status information to the client:

```
WM_DDE_ACK(wStatus, aItem)
```

If Personal Communications cannot perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing negative status information and one of the following return codes in the low-order byte of the wStatus word.

Return Code	Explanation
1	Advise has not started yet.
9	A system error occurred.

## Terminate Session Conversation

3270	5250	VT
Yes	Yes	Yes

The **Terminate Session Conversation** function disconnects the client from the Personal Communications session the client has previously started a conversation with.

The client sends the following command to terminate a session conversation.

```
SendMessage( hServerWnd,
             WM_DDE_TERMINATE,
             hClientWnd,
             MAKELONG(NULL, NULL) );
```

## Personal Communications Response

Personal Communications acknowledges the terminate command with a terminate message:

WM\_DDE\_TERMINATE

## Terminate Structured Field Conversation

3270	5250	VT
Yes	Yes	Yes

The **Terminate Structured Field Conversation** function disconnects the client from a structured field conversation.

The client sends the following command to terminate a structured field conversation.

```
SendMessage( hServerWnd,  
             WM_DDE_TERMINATE,  
             hClientWnd,  
             MAKELONG(NULL, NULL) );
```

## PC/3270 Response

PC/3270 acknowledges the terminate command with a terminate message:

WM\_DDE\_TERMINATE

## Terminate System Conversation

3270	5250	VT
Yes	Yes	Yes

This disconnects the client from a system conversation.

The client sends the following command to terminate a system conversation.

```
SendMessage( hServerWnd,  
             WM_DDE_TERMINATE,  
             hClientWnd,  
             MAKELONG(NULL, NULL) );
```

## Personal Communications Response

Personal Communications acknowledges the terminate command with this message:

WM\_DDE\_TERMINATE

When the user closes a Personal Communications session, any global memory blocks that were allocated by Personal Communications will be freed by Windows. This can cause problems for the client if the client retains any of these global memory objects for long periods of time. If the client application needs to keep the information in a global memory item for a long period of time, it is suggested that the client make a copy of global memory item into a global memory item the client application owns.

## Write SF

3270	5250	VT
Yes	Yes	Yes

The **Write SF** function allows a client application to write structured field data to the host application.

**Note:** The client must call the **Set Structured Field Service Condition** function before invoking the **Write SF** function.

The client sends the following message to write structured field data.

```
PostMessage( hServerWnd,
             WM_DDE_POKE,
             hClientWnd,
             MAKELONG(hData, aSF) );
```

where:

**hData** Identifies a handle to a Windows global memory object containing:

```
typedef struct tagWRITESF
{
    unsigned    unused:12,           //
    unsigned    fRelease:1,         //
    unsigned    fReserved:3;        //
    int         cfFormat;           // Always CF_DSPTXT
    WORD        uSFLength;          // Length of SF data
    char        Work[8];            // Work area
    char        szSFData[1];        // SF data
} WRITESF, FAR *lpWRITESF;
```

**aSF** Identified structured field as the item.

### PC/3270 Response

PC/3270 receives structured field data and sends them to the host application. If the data transmission completes successfully, then PC/3270 returns an ACK message:

```
WM_DDE_ACK(wStatus, aSF)
```

Otherwise PC/3270 returns a negative ACK message containing one of the following return codes in the low-order byte of wStatus:

Return Code	Explanation
2	Length is not valid.
6	The specified format is not valid.
9	A system error occurred.

---

## Summary of DDE Functions in a 16-Bit Environment

The following table lists the DDE functions that can be used with Personal Communications. The table lists the name of the DDE function, the command the client sends to Personal Communications, and the values that can be used for the variables in the client command.

Table 53. Summary of DDE Functions in a 16-Bit Environment

Function name	Client command
Find Field	PostMessage( hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELONG(cfFormat, aFIELD) );
	cfFormat = CF_DSPTEXT
Get Keystrokes	PostMessage( hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELONG(cfFormat, aKEYS) );
	cfFormat = CF_DSPTEXT
Get Mouse Input	PostMessage( hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELONG(cfFormat, aMOUSE) );
	cfFormat = CF_TEXT   CF_DSPTEXT
Get Number of Close Requests	PostMessage( hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELONG(cfFormat, aCLOSE) );
	cfFormat = CF_DSPTEXT
Get Operator Information Area	PostMessage( hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELONG(cfFormat, aOIA) );
	cfFormat = CF_DSPTEXT
Get Partial Presentation Space	PostMessage( hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELONG(cfFormat, aEPS) );
	cfFormat = CF_TEXT   CF_DSPTEXT
Get Presentation Space	PostMessage( hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELONG(cfFormat, aPS) );
	cfFormat = CF_TEXT   CF_DSPTEXT
Get Session Status	PostMessage( hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELONG(cfFormat, aSSTAT) );
	cfFormat = CF_TEXT
Get System Configuration	PostMessage( hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELONG(cfFormat, aSYSCON) );
	cfFormat = CF_TEXT

Table 53. Summary of DDE Functions in a 16-Bit Environment (continued)

Function name	Client command
Get System Formats	PostMessage( hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELONG(cfFormat, aFORMATS) );
	cfFormat = CF_TEXT
Get System Status	PostMessage( hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELONG(cfFormat, aSTATUS) );
	cfFormat = CF_TEXT
Get System Systems	PostMessage( hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELONG(cfFormat, aSYSITEMS) );
	cfFormat = CF_TEXT
Get System Topics	PostMessage( hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELONG(cfFormat, aTOPICS) );
	cfFormat = CF_TEXT
Get Trim Rectangle	PostMessage( hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELONG(cfFormat, aTRIMRECT) );
	cfFormat = CF_TEXT
Initiate Session Conversation	SendMessage( -1, WM_DDE_INITIATE, hClientWnd, MAKELONG(aIBM327032, aSessionN) );
	N = a session letter A through Z.
Initiate Structured Field Conversation	SendMessage( -1, WM_DDE_INITIATE, hClientWnd, MAKELONG(aIBM327032, aLUN_xxxx)
	N = a session letter A through Z. xxxx = a user defined string.
Initiate System Conversation	SendMessage( -1, WM_DDE_INITIATE, hClientWnd, MAKELONG(aIBM327032, aSystem) );
Put Data to Presentation Space	PostMessage( hServerWnd, WM_DDE_POKE, hClientWnd, MAKELONG(hData, aEPS) );
	hData = Handle to a global memory object



Table 53. Summary of DDE Functions in a 16-Bit Environment (continued)

Function name	Client command
Search for String	PostMessage( hServerWnd, WM_DDE_REQUEST, hClientWnd, MAKELONG(cfFormat, aSTRING) );
	cfFormat = CF_DSPTTEXT
Send Keystrokes	PostMessage( hServerWnd, WM_DDE_POKE, hClientWnd, MAKELONG(hData, aKEYS) );
	hData = Handle to a global memory object
Session Execute Macro	PostMessage( hServerWnd, WM_DDE_EXECUTE, hClientWnd, MAKELONG(NULL, hCommands) );
	hCommands = Handle to a global memory object
Set Cursor Position	PostMessage( hServerWnd, WM_DDE_POKE, hClientWnd, MAKELONG(hData, aSETCURSOR) );
	hData = Handle to a global memory object
Set Mouse Intercept Condition	PostMessage( hServerWnd, WM_DDE_POKE, hClientWnd, MAKELONG(hData, aMOUSE) );
	hData = Handle to a global memory object
Set Presentation Space Service Condition	PostMessage( hServerWnd, WM_DDE_POKE, hClientWnd, MAKELONG(hData, aEPSCOND) );
	hData = Handle to a global memory object
Set Session Advise Condition	PostMessage( hServerWnd, WM_DDE_POKE, hClientWnd, MAKELONG(hData, aPSCOND) );
	hData = Handle to a global memory object
Set Structured Field Service Condition	PostMessage( hServerWnd, WM_DDE_POKE, hClientWnd, MAKELONG(hData, aSFCOND) );
	hData = Handle to a global memory object
Start Close Intercept	SendMessage( hServerWnd, WM_DDE_ADVISE, hClientWnd, MAKELONG(hOptions, aCLOSE) );
	hOptions = Handle to a global memory object

Table 53. Summary of DDE Functions in a 16-Bit Environment (continued)

Function name	Client command
Start Keystroke Intercept	SendMessage( hServerWnd, WM_DDE_ADVISE, hClientWnd, MAKELONG(hOptions, aKEYS) );
	hOptions = Handle to a global memory object
Start Mouse Input Intercept	PostMessage( hServerWnd, WM_DDE_ADVISE, hClientWnd, MAKELONG(hOptions, aMOUSE) );
	hOptions = Handle to a global memory object
Start Read SF	PostMessage( hServerWnd, WM_DDE_ADVISE, hClientWnd, MAKELONG(hOptions, aSF) );
	hOptions = Handle to a global memory object
Start Session Advise	PostMessage( hServerWnd, WM_DDE_ADVISE, hClientWnd, MAKELONG(hOptions, aItem) );
	hOptions = Handle to a global memory object altem = OIA   PS   TRIMRECT
Stop Close Intercept	PostMessage( hServerWnd, WM_DDE_UNADVISE, hClientWnd, MAKELONG(NULL, aCLOSE) );
Stop Keystroke Intercept	PostMessage( hServerWnd, WM_DDE_UNADVISE, hClientWnd, MAKELONG(NULL, aKEYS) );
Stop Mouse Input Intercept	PostMessage( hServerWnd, WM_DDE_UNADVISE, hClientWnd, MAKELONG(NULL, aMOUSE) );
Stop Read SF	PostMessage( hServerWnd, WM_DDE_UNADVISE, hClientWnd, MAKELONG(NULL, aSF) );
Stop Session Advise	PostMessage( hServerWnd, WM_DDE_UNADVISE, hClientWnd, MAKELONG(NULL, aItem) );
	altem = OIA   PS   TRIMRECT   NULL
Terminate Session Conversation	SendMessage( hServerWnd, WM_DDE_TERMINATE, hClientWnd, MAKELONG(NULL, NULL) );

Table 53. Summary of DDE Functions in a 16-Bit Environment (continued)

Function name	Client command
Terminate Structured Field Conversation	SendMessage( hServerWnd, WM_DDE_TERMINATE, hClientWnd, MAKELONG(NULL, NULL) );
Terminate System Conversation	SendMessage( hServerWnd, WM_DDE_TERMINATE, hClientWnd, MAKELONG(NULL, NULL) );
Write SF	PostMessage( hServerWnd, WM_DDE_POKE, hClientWnd, MAKELONG(hData, aSF) );
	hData = Handle to a global memory object

## DDE Menu Item API in a 16-Bit Environment

Personal Communications supports the addition, deletion, and changing of attributes of a dynamic menu item to the session menu bar. A menu will then be created for this menu item with space for up to 16 submenu items.

Personal Communications supports two kinds of DDE conversation. One is Personal Communications, which acts as a DDE menu client application, and the other is Personal Communications, which acts as a DDE menu server.

## DDE Menu Client in a 16-Bit Environment

To add, delete, and change menu items, the following DDE conversation must take place between the session and DDE menu server application.




Figure 10. DDE Menu Server Conversation

The following data hierarchy details the menu map Personal Communications expects when adding a dynamic menu item and submenu to a session menu bar:

```
POPUP "MyMenu"  
BEGIN  
  MENUITEM "Send Files to Host",      SEND  
  MENUITEM "Receive Files from Host", RECEIVE  
  MENUITEM SEPARATOR  
  MENUITEM "Convert Files",          CONVERT  
END
```

When the user selects a menu item from the new menu, Personal Communications will send a DDE Initiate with 3270MenuN or 5250MenuN as the application and itemN token as the topic. If an ACK is received from the DDE application, Personal Communications will inhibit the session from accepting user input. The menu client application can then display a dialog, and so on. When the menu server application has completed processing of the menu item, it will send a DDE Terminate to signal Personal Communications the process is complete. Personal Communications will then reenable the window for the user.

## DDE Menu Server, 32-Bit

To add, delete, and change menu items, the following DDE conversation must take place between the session and a DDE menu client application.




Figure 11. DDE Menu Client Conversation

When the user selects a menu item from the new menu, Personal Communications will send a DDE DATA with aSELECTMENU as the item. When Personal Communications sends DDE DATA to the client application, Personal Communications will inhibit the session from accepting user input. The menu client application can then display a dialog, and so on. When the menu client application has completed processing of the menu item, it will send a DDE ACK to signal Personal Communications the process is complete. Personal Communications will then reenble the window for the user.

## DDE Menu Functions in a 16-bit Environment

The following table lists the DDE Menu Item API functions that are available for use with Personal Communications and the page in this section, where each function is more fully documented. PC/3270 Windows mode and PC400 provide all of the following functions.

Function	Page
Change Menu Item	456
Create Menu Item	461
Initiate Menu Conversation	462

Function	Page
Start Menu Advise	463
Stop Menu Advise	464
Terminate Menu Conversation	464

## Change Menu Item

3270	5250	VT
Yes	Yes	Yes

The **Change Menu Item** function appends, deletes, inserts, modifies, and removes menu items. The client sends the following message to the session to change a menu.

```
PostMessage( hServerWnd,
             WM_DDE_POKE,
             hClientWnd,
             MAKELONG(hData, aCHANGEMENU) );
```

where:

**hData** Identifies a handle to a Windows global memory object that contains the requests for changing a menu. The global memory object contains the following structure:

```
typedef struct tagChangeMenu
{
    unsigned unused:13;    // ** unused **
    unsigned fRelease:1;  // Session frees memory
    unsigned fReserved:2; // ** reserved **
    int      cfFormat;    // Always CF_DSPTEXT
    HANDLE   hMenu;      // Handle of the menu item
    WORD     wPosition;  // The position of the menu
                          // item
    WORD     wIDNew;     // The menu ID of the new
                          // menu item
    WORD     wOperation; // Specifies the operation
    WORD     wFlags;     // Specifies the options
    unsigned char szItemName[1]; // String of the item
} CHANGEMENU, FAR *lpCHANGEMENU;
```

The following operations are supported:

```
MF_APPEND // Appends a menu item to the end of a menu.
MF_CHANGE // Modifies a menu item in a menu.
MF_DELETE // Deletes a menu item from a menu, destroying
           // the menu item.
MF_INSERT // Inserts a menu item into a menu.
MF_REMOVE // Removes a menu item from a menu but does not
           // destroy the menu item.
```

If the MF\_APPEND is specified in the wOperation field, the following fields must be filled:

**hMenu** Identifies the menu to be appended. To append a new item to a pop-up menu, specify the handle that is returned from Personal Communications when **Create Menu Item** function is executed. To append a new item to a top-level menu bar, specify NULL.

<b>wIDNew</b>	Specifies the command ID of the new menu item. If a new item is added to the top-level menu bar, the handle of the menu item returned from Personal Communications when <b>Create Menu Item</b> function is executed.
<b>wFlags</b>	The following options can be set: <pre> MF_CHECKED           // Places a checkmark next to                      // the item. MF_DISABLED          // Disables the menu item so                      // that it cannot be selected,                      // but does not gray it. MF_ENABLED           // Enables the menu item so that                      // it can be selected and                      // restores from its grayed                      // state. MF_GRAYED            // Disables the menu item so                      // that it cannot be selected,                      // and grays it. MF_MENUBARBREAK     // Same as MF_MENUBREAK except                      // that for pop-up menus,                      // separates the new column from                      // the old column with a                      // vertical line. MF_MENUBREAK        // Places the item on a new line                      // for menu bar items.                      // For pop-up menus, places the                      // item in a new column, with                      // no dividing line between the                      // columns. MF_SEPARATOR        // Draws a horizontal dividing                      // line. Can only be used in a                      // pop-up menu. This line cannot                      // be grayed, disabled, or                      // highlighted. The wIDNew and                      // szItemName fields are                      // ignored. MF_UNCHECKED        // Does not place a checkmark                      // next to the item (default). </pre>
<b>szItemName</b>	Specifies the content of the new menu item. Contains a null-terminated character string.

If the MF\_CHANGE is specified in the wOperation field, fill these fields:

<b>hMenu</b>	Identifies the menu to be changed. To change an item of a pop-up menu, specify the handle that is returned from Personal Communications when <b>Create Menu Item</b> function is executed. To change an item to a top-level menu bar, specify NULL.
<b>nPosition</b>	Specifies the menu item to be changed. The interpretation of the wPosition parameter depends on the setting of the wFlags parameter. <p><b>MF_BYPOSITION</b> Specifies the position of the existing menu item. The first item in the menu is at position zero.</p> <p><b>MF_BYCOMMAND</b> Specifies the command ID of the existing menu item.</p>
<b>wIDNew</b>	Specifies the command ID of the menu item. If an item of the top-level menu bar is changed, the handle of the menu item returned from Personal Communications when <b>Create Menu Item</b> function is executed.

**wFlags**

The following options can be set:

```

MF_BYCOMMAND    // Specifies that the nPosition
                 // parameter gives the menu
                 // item control ID number.
                 // This is the default if
                 // neither MF_BYCOMMAND nor
                 // MF_BYPOSITION is set.
MF_BYPOSITION   // Specifies that the nPosition
                 // parameter gives the position
                 // of the menu item to be
                 // changed rather than an ID
                 // number.
MF_CHECKED      // Places a checkmark next to
                 // the item.
MF_DISABLED     // Disables the menu item so
                 // that it cannot be selected,
                 // but does not gray it.
MF_ENABLED      // Enables the menu item so
                 // that it can be selected and
                 // restores from its grayed
                 // state.
MF_GRAYED       // Disables the menu item so
                 // that it cannot be selected,
                 // and grays it.
MF_MENUBARBREAK // Same as MF_MENUBREAK except
                 // that for pop-up menus,
                 // separates the new column
                 // from the old column with a
                 // vertical line.
MF_MENUBREAK    // Places the item on a new
                 // line for menu bar items.
                 // For pop-up menus, places the
                 // item in a new column, with
                 // no dividing line between
                 // the columns.
MF_SEPARATOR    // Draws a horizontal dividing
                 // line. Can only be used in
                 // a pop-up menu. This line
                 // cannot be grayed, disabled,
                 // or highlighted. The wIDNew
                 // and szItemName fields are
                 // ignored.
MF_UNCHECKED    // Does not place a checkmark
                 // next to the item (default).

```

**szItemName**

Specifies the content of the menu item. Contains a null-terminated character string.

If the MF\_DELETE is specified in the wOperation field, fill these fields:

**hMenu**

Identifies the menu to be deleted. To delete an item from a pop-up menu, specify the handle that is returned from Personal Communications when **Create Menu Item** function is executed. To delete an item from a top-level menu bar, specify NULL.

**nPosition**

Specifies the menu item to be deleted. The interpretation of the nPosition parameter depends on the setting of the wFlags parameter.

**MF\_BYPOSITION**

Specifies the position of the existing menu item. The first item in the menu is at position zero.

**MF\_BYCOMMAND**

Specifies the command ID of the existing menu item.



**wFlags**

The following options can be set:

```
MF_BYCOMMAND    // Specifies that the nPosition
                 // parameter gives the menu
                 // item control ID number.
                 // This is the default if
                 // neither MF_BYCOMMAND nor
                 // MF_BYPOSITION is set.
MF_BYPOSITION    // Specifies that the nPosition
                 // parameter gives the position
                 // of the menu item to be
                 // deleted rather than an ID
                 // number.
```

If the MF\_INSERT is specified in the wOperation field, the following fields must be filled:

**hMenu**

Identifies the menu to be inserted. To insert an item to a pop-up menu, specify the handle that is returned from Personal Communications when **Create Menu Item** function is executed. To change an item to a top-level menu bar, specify NULL.

**nPosition**

Specifies the menu item before the new menu item is to be inserted. The interpretation of the nPosition parameter depends on the setting of the wFlags parameter.

**MF\_BYPOSITION**

Specifies the position of the existing menu item. The first item in the menu is at position zero.

**MF\_BYCOMMAND**

Specifies the command ID of the existing menu item.

**wIDNew**

Specifies the command ID of the menu item or, if an item of the top-level menu bar is changed, the handle of the menu item returned from Personal Communications when **Create Menu Item** function is executed.

**wFlags**

The following options can be set:

```

MF_BYCOMMAND    // Specifies that the nPosition
                 // parameter gives the menu
                 // item control ID number. This
                 // is the default if neither
                 // MF_BYCOMMAND nor MF_BYPOSITION
                 // is set.
MF_BYPOSITION   // Specifies that the nPosition
                 // parameter gives the position
                 // of the menu item to be
                 // changed rather than an ID
                 // number.
MF_CHECKED      // Places a checkmark next to
                 // the item.
MF_DISABLED     // Disables the menu item so
                 // that it cannot be selected,
                 // but does not gray it.
MF_ENABLED      // Enables the menu item so
                 // that it can be selected and
                 // restores from its grayed
                 // state.
MF_GRAYED       // Disables the menu item so
                 // that it cannot be selected,
                 // and grays it.
MF_MENUBARBREAK // Same as MF_MENUBREAK except
                 // that for pop-up menus,
                 // separates the new column
                 // from the old column with a
                 // vertical line.
MF_MENUBREAK    // Places the item on a new
                 // line for menu bar items.
                 // For pop-up menus, places the
                 // item in a new column, with
                 // no dividing line between the
                 // columns.
MF_SEPARATOR    // Draws a horizontal dividing
                 // line. Can only be used in
                 // a pop-up menu. This line
                 // cannot be grayed, disabled,
                 // or highlighted. The wIDNew
                 // and szItemName fields are
                 // ignored.
MF_UNCHECKED    // Does not place a checkmark
                 // next to the item (default).

```

**szItemName**

Specifies the content of the menu item. Contains a null-terminated character string.

If the MF\_REMOVE is specified in the wOperation field, the following fields must be filled:

**hMenu**

Identifies the menu to be removed. To remove an item from a pop-up menu, specify the handle that is returned from Personal Communications when **Create Menu Item** function is executed. To remove an item from a top-level menu bar, specify NULL.

**nPosition**

Specifies the menu item to be removed. The interpretation of the nPosition parameter depends upon the setting of the wFlags parameter.

**MF\_BYPOSITION**

Specifies the position of the existing menu item. The first item in the menu is at position zero.

**MF\_BYCOMMAND**

Specifies the command ID of the existing menu item.

## wFlags

The following options can be set:

```
MF_BYCOMMAND    // Specifies that the nPosition
                 // parameter gives the menu
                 // item control ID number.
                 // This is the default if
                 // neither MF_BYCOMMAND nor
                 // MF_BYPOSITION is set.
MF_BYPOSITION    // Specifies that the nPosition
                 // parameter gives the
                 // position of the menu item to
                 // be removed rather than an ID
                 // number.
```

## Personal Communications Response

Personal Communications receives the requests to change a menu and processes them. If the requests cannot be accepted, Personal Communications returns a negative ACK message containing one of the following status codes in the low-order byte of the wStatus word. Otherwise, Personal Communications returns a positive ack message signalling that the keystrokes have been sent.

WM\_DDE\_ACK(wStatus, aCHANGEMENU)

Return code	Explanation
1	The specified parameters are not valid.
6	The specified format is not valid.
9	A system error occurred.

## Create Menu Item

3270	5250	VT
Yes	Yes	Yes

The **Create Menu Item** function requests Personal Communications to add a menu item to the menu bar. A pop-up menu will be created at the same time, but it is initially empty and can be filled with menu items by using this function. The string of the new menu item that will be added to a top-level menu bar, is also specified by using the change menu item function.

The client sends the following message to create a menu item.

```
PostMessage( hServerWnd,
             WM_DDE_REQUEST,
             hClientWnd,
             MAKELONG(cfFormat, aCREATEMENU) );
```

where:

**cfFormat** Identifies the format for the ID of the new menu item. The valid value is CF\_DSPTEXT.

**aCREATEMENU** Identifies the create menu item.

## Personal Communications Response

Personal Communications returns the handle of the newly created menu item in a dde data message if the Personal Communications can create a menu item.

WM\_DDE\_DATA(hData, aCREATEMENU)

or  
 WM\_DDE\_ACK(wStatus, aCREATEMENU)

where:

**hData** Identifies a handle to a windows global memory object that contains the handle of the menu item. The global memory object contains the following structure:

```
typedef struct tagcreatemenu
{
  unsigned   unused:12,           // *** unused ***
  unsigned   fresponse:1,        // true = dd_request response
  unsigned   frelease:1,         // true = client releases memory
  unsigned   reserved:1,         // *** reserved ***
  unsigned   fackreq:1,          // true = dde_ack is required
  int        cfformat;           // always cf_dsptext
  handle     hmemuitem;          // handle of the menu item
} CREATEMENU, FAR *lpCREATEMENU;
```

If Personal Communications cannot create a menu item, one of the following status codes are returned in the low-order byte of the wStatus word:

Return Code	Explanation
6	The specified format is not valid.
9	A system error occurred.

## Initiate Menu Conversation

3270	5250	VT
Yes	Yes	Yes

The **Initiate Menu Conversation** function connects a client application to an available session of Personal Communications. Once a menu conversation is established, the session menu is reserved exclusively for the client until the conversation is terminated.

The client application sends the following message to initiate a DDE conversation with a menu:

```
SendMessage( -1,
             WM_DDE_INITIATE,
             hClientWnd,
             MAKELONG(aIBM327032, SN) );
```

where:

**aIBM327032** Identifies the application atom. The string used to create atom aIBM3270 is IBM3270 In the PC400, the application atom is aIBM5250 and the string IBM5250 is used to create it.

**SN** Identifies the topic atom. The string used to create atom a3270MenuSN is 3270MenuS appended with the session ID A, B, ..., Z. In the PC400, the topic atom is a5250MenuSN and the string 5250MenuS appended with the session ID A, B, ..., Z. is used to create it.

## Personal Communications Response

If Personal Communications can support a conversation with the client application, Personal Communications acknowledges the INITIATE transaction with:

```
WM_DDE_ACK(aIBM327032, SN)
```

## Start Menu Advise

3270	5250	VT
Yes	Yes	Yes

The **Start Menu Advise** function allows a client application to process a user defined routine when the menu item that is added by the client application, is selected. After using this function, the client receives DATA messages indicating which menu item is selected.

The client sends the following command to begin a menu advise.

```
PostMessage( hServerWnd,  
            WM_DDE_ADVISE,  
            hClientWnd,  
            MAKELONG(hOptions, aSELECTMENU) );
```

where:

**hOptions** Is a handle to a Windows global memory object, with the following structure:

```
typedef struct tagOPTIONS  
{  
    unsigned reserved:14;           // Reserved  
    unsigned fDeferUpd:1;           // Send notification only  
                                     // (Must be 0)  
    unsigned fAckReq:1;             // Client will ACK all notices  
                                     // (Must be 1)  
    WORD      cfFormat;             // Always CF_DSPTEXT  
} OPTIONS, FAR *lpOPTIONS;
```

**aSELECTMENU** Identified a menu advise as the item.

## Personal Communications Response

Personal Communications receives the **Start Menu Advise** and returns an ACK message if it can start the function.

```
WM_DDE_ACK(wStatus, aSELECTMENU)
```

Otherwise, a negative ACK message will be returned to the client with one of the following return codes in the low-order byte of the wStatus field.

Return Code	Explanation
1	Menu Advise has been already started.
6	The specified format is not valid.
9	A system error occurred.

Once the menu item (added to the client application) is selected, the client receives DATA messages notifying it which menu item is selected:

```
WM_DDE_DATA(hData, aSELECTMENU)
```

where:

**hData** Identifies a handle to a Windows global memory object containing:

```
typedef struct tagSELECTMENU
{
    unsigned    Unused:12,        // *** unused ***
    unsigned    fResponse:1,     // TRUE = DD_REQUEST response
    unsigned    fRelease:1,     // TRUE = Client releases memory
    unsigned    reserved:1,     // *** reserved ***
    unsigned    fAckReq:1,      // TRUE = DDE_ACK is required
    int         cfFormat;        // Always CF_DSPTEXT
    WORD        uIDSelected;     // Command ID of the
                                // selected menu item
} SELECTMENU, FAR *lpSELECTMENU;
```

The DATA messages continue until a Stop Menu Advise message is sent to Personal Communications.

## Stop Menu Advise

3270	5250	VT
Yes	Yes	Yes

The **Stop Menu Advise** function ends a client application's ability to process a user-defined routine when the menu item added by the client application is selected. The client sends the following command to perform the Stop Menu Advise function.

```
PostMessage( hServerWnd,
             WM_DDE_UNADVISE,
             hClientWnd,
             MAKELONG(NULL, aSELECTMENU) );
```

where:

**aSELECTMENU** Identifies a menu advise as the item.

## Personal Communications Response

If Personal Communications can perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing positive status information to the client:

```
WM_DDE_ACK(wStatus, aCLOSE)
```

If Personal Communications cannot perform the DDE\_UNADVISE, Personal Communications returns an ACK message containing negative status information and one of the following return codes in the low-order byte of the wStatus word:

Return Code	Explanation
1	Advise has not started yet.
9	A system error occurred.

## Terminate Menu Conversation

3270	5250	VT
Yes	Yes	Yes

The **Terminate Menu Conversation** function disconnects the client from the Personal Communications session with which a conversation had been previously started.

The client sends the following command to terminate a session conversation:

```
SendMessage( hServerWnd,  
            WM_DDE_TERMINATE,  
            hClientWnd,  
            MAKELONG(NULL, NULL) );
```

## **Personal Communications Response**

Personal Communications acknowledges the terminate command with this message:

```
WM_DDE_TERMINATE
```





---

## Appendix H. REXX EHLLAPI Functions

This appendix assists application programmers who are using EHLLAPI to write REXX language application programs. You should be familiar with the REXX command language. An overview of REXX EHLLAPI functions is provided. The functions are listed in alphabetic order, and a detailed description accompanies each function. Information about writing applications using REXX and sample programs is included after the function descriptions.

On Windows platforms REXX applications require the use of IBM Object REXX for Windows 95, Windows 98, and Windows NT. OS/2 requires no additional products for REXX application support.

---

### Overview of REXX EHLLAPI Function Calls and Return Values

REXX EHLLAPI is called by either a REXX function or a REXX subroutine. The REXX function returns a value, which is assigned to a variable or return code:

```
rc=HLLAPI( function-string [,parameters ] )
```

The REXX subroutine places the return value in the special REXX variable called `Result` as follows:

```
call HLLAPI function-string [,parameters ]
```

### Installation

The REXX EHLLAPI executable file (SAAHLAPI.DLL) is installed with IBM Personal Communications.

EHLLAPI is provided as an external feature and is loaded into memory only when used. To ensure that REXX EHLLAPI functions are available, REXX application programs must contain the following statement:

```
if rxfuncquery('hllapi') then call rxfuncadd 'hllapi','saahlapi','hllapisrv'
```

REXX EHLLAPI provides a *single* function name, which is used with a set of parameters. The function name is the first parameter of the `rxfuncadd` call above; the default is **HLLAPI**.

### Conventions

Each REXX EHLLAPI function description contains the following:

- Function name
- Prerequisite calls
- Supplied syntax
- Supplied parameters
- Returned parameters
- Additional information

**Function Name** Provides the name and a brief explanation of the function.

<b>Prerequisite Calls</b>	Lists any functions that your application program must call before you can use the present function. The word <i>None</i> indicates that no prerequisite calls are required. Prerequisite calls for all REXX EHLLAPI functions are listed under “Summary of Prerequisite Calls for Functions”.
<b>Supplied Syntax</b>	Illustrates the syntax of the function call. Refer to “Overview of REXX EHLLAPI Function Calls and Return Values” on page 467 for more information.
<b>Supplied Parameters</b>	Lists the parameters that your program must define in order to call the discussed REXX EHLLAPI function.  Every function call uses the name of the function as the first parameter, but the number of parameters that your program must define depends on the function being called. Refer to each function description for the format of the supplied parameters.
<b>Returned Parameters</b>	Places values, as either a return code or actual data, in a single variable. If you are using REXX EHLLAPI as a function, these values are put in the receiving variable. If you are using REXX EHLLAPI as a subroutine, the values are placed in a special variable called <i>result</i> . Refer to each function description for the format of the returned values.
<b>Additional Information</b>	Provides any necessary technical information about the function.

---

## Summary of Prerequisite Calls for Functions

Table 54 lists the prerequisite calls for each REXX EHLLAPI function. Prerequisite calls are required when you use an application program.

*Table 54. Prerequisite Calls for Functions*

<b>Function</b>	<b>Prerequisite Calls</b>
Change_Switch_Name	Connect_PM
Change_Window_Name	Connect_PM
Connect	None
Connect_PM	None
Convert_Pos	None
Copy_Field_To_String	Connect
Copy_OIA	Connect
Copy_PS	Connect
Copy_PS_To_Str	Connect
Copy_Str_To_Field	Connect
Copy_Str_To_PS	Connect
Disconnect	Connect
Disconnect_PM	Connect_PM
Find_Field_Len	Connect
Find_Field_Pos	Connect
Get_Key	Start_Keystroke_Intercept
Get_Window_Status	Connect_PM
Intercept_Status	Start_Keystroke_Intercept
Lock_PMSVC	Connect_PM
Lock_PS	Connect

Table 54. Prerequisite Calls for Functions (continued)

Function	Prerequisite Calls
Pause	None
Query_Close_Intercept	Start_Close_Intercept
Query_Cursor_Pos	Connect
Query_Emulator_Status	None
Query_Field_Attr	Connect
Query_Host_Update	Start_Host_Notify
Query_Session_List	None
Query_Session_Status	None
Query_Sessions	None
Query_System	None
Query_Window_Coord	Connect_PM
Query_Workstation_Profile	None
Receive_File	None
Release	Connect
Reserve	Connect
Reset_System	None
Search_Field	Connect
Search_PS	Connect
Send_File	None
Sendkey	Connect
Set_Cursor_Pos	Connect
Set_Session_Parms	None
Set_Window_Status	Connect_PM
Start_Close_Intercept	None
Start_Communication	None
Start_Host_Notify	None
Start_Keystroke_Intercept	None
Start_Session	None
Stop_Close_Intercept	Start_Close_Intercept
Stop_Communication	None
Stop_Host_Notify	Start_Host_Notify
Stop_Keystroke_Intercept	Start_Keystroke_Intercept
Stop_Session	None
Wait	Connect

## Summary of EHLLAPI and REXX EHLLAPI Functions

Table 55 lists each EHLLAPI and REXX EHLLAPI function.

Table 55. EHLLAPI and REXX EHLLAPI Functions

EHLLAPI	REXX EHLLAPI
CHANGE SWITCH LIST LT NAME (105)	Change_Switch__Name
CHANGE PS WINDOW NAME (106)	Change_Window_Name
CONNECT PRESENTATION SPACE (1)	Connect
CONNECT PM WINDOW SERVICES (101)	Connect_PM
CONVERT POSITION or CONVERT ROWCOL (99)	Convert_Pos
COPY FIELD TO STRING (34)	Copy_Field_To_String
COPY OIA (13)	Copy_OIA
COPY PRESENTATION SPACE (5)	Copy_PS
COPY PRESENTATION SPACE TO STRING (8)	Copy_PS_To_Str
COPY STRING TO FIELD (33)	Copy_Str_To_Field
COPY STRING TO PRESENTATION SPACE (15)	Copy_Str_To_PS
DISCONNECT PRESENTATION SPACE (2)	Disconnect
DISCONNECT PM WINDOW SERVICES (102)	Disconnect_PM
FIND FIELD LENGTH (32)	Find_Field_Len
FIND FIELD POSITION (31)	Find_Field_Pos
GET KEY (51)	Get_Key
PAUSE (18)	Pause
PM WINDOW STATUS (104)	Get_Window_Status and Set_Window_Status
POST INTERCEPT STATUS (52)	Intercept_Status
LOCK PMSVC API (61)	Lock_PMSVC
LOCK PRESENTATION SPACE API (60)	Lock_PS
QUERY CLOSE INTERCEPT (42)	Query_Close_Intercept
QUERY CURSOR LOCATION (7)	Query_Cursor_Pos
QUERY FIELD ATTRIBUTE (14)	Query_Field_Attr
QUERY HOST UPDATE (24)	Query_Host_Update
QUERY PM WINDOW COORDINATES (103)	Query_Window_Coord
QUERY SESSION STATUS (22)	Query_Session_Status
QUERY SESSIONS (10)	Query_Sessions
QUERY SYSTEM (20)	Query_System
RECEIVE FILE (91)	Receive_File
RELEASE (12)	Release
RESERVE (11)	Reserve
RESET SYSTEM (21)	Reset_System

Table 55. EHLLAPI and REXX EHLLAPI Functions (continued)

<b>EHLLAPI</b>	<b>REXX EHLLAPI</b>
SEARCH FIELD (30)	Search_Field
SEARCH PRESENTATION SPACE (6)	Search_PS
SEND FILE (90)	Send_File
SEND KEY (3)	Sendkey
SET CURSOR (40)	Set_Cursor_Pos
SET SESSION PARAMETERS (9)	Set_Session_Parms
START CLOSE INTERCEPT (41)	Start_Close_Intercept
START HOST NOTIFICATION (23)	Start_Host_Notify
START KEYSTROKE INTERCEPT (50)	Start_Keystroke_Intercept
STOP CLOSE INTERCEPT (43)	Stop_Close_Intercept
STOP HOST NOTIFICATION (25)	Stop_Host_Notify
STOP KEYSTROKE INTERCEPT (53)	Stop_Keystroke_Intercept
WAIT (4)	Wait
pcsStartSession	Start_Session
pcsStopSession	Stop_Session
pcsConnectSession	Start_Communications
pcsDisconnectSession	Stop_Communications
pcsQuerySessionList	Query_Session_List
pcsQueryEmulatorStatus	Query_Emulator_Status
pcsQueryWorkstationProfile	Query_Workstation_Profile

## Change\_Switch\_Name

The **Change\_Switch\_Name** function changes or resets the name of the session listed on the window title bar.

### Prerequisite Calls

**Connect\_PM**

### Supplied Syntax

The syntax for **Change\_Switch\_Name** is as follows:

```
HLLAPI( 'Change_switch_name', session_id, type [, new_name ])
```

### Supplied Parameters

**Function name:** **Change\_Switch\_Name**

**session\_id:** The single-character short name of the session to be renamed on the Task List.

**type:** One of the following:

- **Set** renames the session name (title) for session *session\_id* to *new\_name*.
- **Reset** restores the original session name (title).

**Note:** Only the first character of **Set** or **Reset** is significant.

### Returned Parameters

Return Code	Explanation
0	The <b>Change_Switch_Name</b> function was successful.
1	Your program is not currently connected to the host session.
2	An error was made in specifying parameters.
9	A system error occurred.
12	The session stopped.

## Change\_Window\_Name

The **Change\_Window\_Name** function changes or resets the name of the session listed on the host window title bar.

### Prerequisite Calls

**Connect\_PM**

### Supplied Syntax

The syntax for the **Change\_Window\_Name** function is as follows:

```
HLLAPI( 'Change_window_name', session_id, type [, new_name ])
```

### Supplied Parameters

**Function name:** **Change\_Window\_Name**

*session\_id:* The single-character short name of the session to be renamed on the title bar.

*type:* One of the following:

- **Set** changes the window name (title) for session *session\_id* to *new\_name*.
- **Reset** restores the original window name (title).

**Note:** Only the first character of **Set** or **Reset** is significant.

### Returned Parameters

Return Code	Explanation
0	The <b>Change_Window_Name</b> function was successful.
1	Your program is not currently connected to the host session.
2	An error was made in specifying parameters.
9	A system error occurred.
12	The session stopped.

# Connect

The **Connect** function connects the REXX application program to the host presentation space.

## Prerequisite Calls

None.

## Supplied Syntax

The syntax for the **Connect** function is as follows:

```
HLLAPI( 'Connect', session_id )
```

## Supplied Parameters

**Function name:** **Connect**

*session\_id*: The single-character short name of the session window you want to connect to.

## Returned Parameters

Return Code	Explanation
0	The <b>Connect</b> function was successful.
1	An incorrect host presentation space ID was specified. The specified session either does not exist or is a logical printer session. This return code could also mean that the API Setting for DDE/EHLLAPI is not set on.
4	Successful connection was achieved, but the session is busy.
5	Successful connection was achieved, but the session is locked (input-inhibited).
9	A system error occurred.
11	The session is already being used by another system function.



## Connect\_PM

The **Connect\_PM** function connects the REXX application program to the presentation space window.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Connect\_PM** function is as follows:

```
HLLAPI( 'Connect_PM', session_id )
```

### Supplied Parameters

**Function name:** **Connect\_PM**

*session\_id*: The single-character short name of the session window that you want to connect to.

### Returned Parameters

Return Code	Explanation
0	The <b>Connect_PM</b> function was successful.
1	An incorrect host presentation space ID was specified. This return code could also mean that the API Setting for DDE/EHLLAPI is not set on.
9	A system error occurred.
10	The function is not supported by your emulation program.
11	The session is already being used by another system function.

## Convert\_Pos

The **Convert\_Pos** function converts the host presentation space positional value into the display row-column coordinates or converts the display row-column coordinates into the host presentation space positional value for the given session\_ID.

**Note:** If row-column conversion is specified, *column* is the second parameter. The valid row-column values are the values you specified when you configured this session. For example, a session with 24 rows and 80 columns contains positions 1 to 1920.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Convert\_Pos** function is as follows:

```
HLLAPI( 'Convert_pos', session_id, column | position [, row ] )
```

### Supplied Parameters

**Function name:** **Convert\_Pos**  
*session\_id:* The single-character short name of the session.  
*column:* The column to be converted. It must be specified with the row.  
*row:* The row to be converted.  
*position:* The position to be converted.

### Returned Parameters

The following values are valid if row-column conversion is requested:

Return Code	Explanation
0	The specified row or column is outside the presentation space.
n	The position of the specified row and column. For example: HLLAPI ('Convert_pos', 'a', 10, 2) = '170'  converts column 10, row 2 to 170 in a 24x80 presentation space.

The following values are valid if position conversion is requested:

Return Code	Explanation
0	The specified position is outside the presentation space.
c r	Where <b>c</b> is the column number and <b>r</b> is the row number. For example: HLLAPI ('Convert_pos', 'a', 170) = '10 2'  converts position 170 to column 10, row 2 in a 24x80 presentation space.

## Copy\_Field\_To\_Str

The **Copy\_Field\_To\_Str** function transfers characters from a target field into a data string. Use the **Find\_Field\_Pos** and **Find\_Field\_Len** functions to determine the target and its length values.

### Prerequisite Calls

**Connect**

### Supplied Syntax

The syntax for the **Copy\_Field\_To\_Str** function is as follows:

```
HLLAPI( 'Copy_field_to_str', pos, length )
```

### Supplied Parameters

**Function name:** **Copy\_Field\_To\_Str**

*pos*: The target field to be copied.

*length*: The length, in bytes, of the target data string.

### Returned Parameters

Return Code	Explanation
"	Null. No field data was found at <i>pos</i> , or a <i>pos</i> that is not valid was specified.
data	<p>The contents of the returned data string are determined by the extended attribute bytes (EAB) value in the <b>Set_Session_Parms</b> function. If EAB is set off, only text from the presentation space is returned. If EAB is set on, 2 bytes are returned for each byte that is displayed. The first byte contains the EAB value, and the second byte contains the text data.</p> <p>Double-byte EAD can be returned by using the EAD option of the (9) function with the <b>COPY FIELD TO STRING</b> function. If the EAD is specified without specifying the EAB option, EAD is returned after each character. If the EAB option is specified, EAD is returned after EAB.</p>

# Copy\_OIA

This function returns the contents of the operator information area (OIA) from the connected session.

## Prerequisite Calls

Connect

## Supplied Syntax

The syntax for the **Copy\_OIA** function is as follows:

```
HLLAPI( 'Copy_OIA' )
```

## Supplied Parameters

None.

## Returned Parameters

Return Code	Explanation
"	Null. Not connected or other error.
data	The 104-byte copy of the OIA data. Refer to "Copy OIA (13)" on page 44.

# Copy\_PS

The **Copy\_PS** function returns the entire contents of the presentation space for the currently connected session.

## Prerequisite Calls

**Connect**

## Supplied Syntax

The syntax for the **Copy\_PS** function is as follows:

```
HLLAPI( 'Copy_PS' )
```

## Supplied Parameters

None.

## Returned Parameters

Return Code	Explanation
"	Null. Not connected or other error.
data	<p>The contents of the returned data string are determined by the EAB value in the <b>Set_Session_Parms</b> function. If EAB is set off, only text from the presentation space is returned. If EAB is set on, 2 bytes are returned for each byte that is displayed. The first byte contains the EAB value, and the second byte contains the text data.</p> <p>These bytes are returned as a space character if the start position of the copy is the second byte of the double-byte character or if the end position is the first byte of the double-byte character.</p>

## Additional Information

**COPY\_PS** results in two calls to EHLLAPI. The first is **QUERY\_SESSIONS**, which is used to determine the size of the presentation space. The second call, **COPY\_PS\_TO\_STRING**, is used in place of **COPY\_PS** in order to prevent possible buffer overflow.

**COPY\_PS\_TO\_STRING** is used because of the slim possibility that the size of the presentation space might change between the calls to **QUERY\_SESSIONS** and **COPY\_PS\_TO\_STRING**.

**Note:** Should the presentation space increase in size, only the number of bytes returned on the **QUERY\_SESSIONS** are copied. If the size decreases, then the characters beyond the current size should be ignored.

## Copy\_PS\_To\_Str

The **Copy\_PS\_To\_Str** function copies data from the currently connected session into a data string.

### Prerequisite Calls

**Connect**

### Supplied Syntax

The syntax for the **Copy\_PS\_To\_Str** function is as follows:

```
HLLAPI( 'Copy_PS_to_str', pos, length )
```

### Supplied Parameters

**Function name:** **Copy\_PS\_To\_Str.**

*pos:* The target field to be copied.

*length:* The length, in bytes, of the target data string.

**Note:** Do not double the target field value if EAB is set on. REXX EHLLAPI does this for you automatically, if EAD is set on.

### Returned Parameters

Return Code	Explanation
"	Null. Not connected or other error.
data	The contents of the returned data string are determined by the EAB value in the <b>Set_Session_Parms</b> function. If EAB is set off, only text from the presentation space is returned. If EAB is set on, 2 bytes are returned for each byte that is displayed. The first byte contains the EAB value, and the second byte contains the text data.

## Copy\_Str\_To\_Field

The **Copy\_Str\_To\_Field** function copies a string of characters into a specified field at the target field location position of the connected session.

### Prerequisite Calls

**Connect**

### Supplied Syntax

The syntax for the **Copy\_Str\_To\_Field** function is as follows:

```
HLLAPI( 'Copy_str_to_field', string, pos )
```

### Supplied Parameters

**Function name:** **Copy\_Str\_To\_Field**.

*string*: The string containing the data to be transferred to the target field.

*pos*: The target field to be copied.

### Returned Parameters

Return Code	Explanation
0	The <b>Copy_Str_To_Field</b> function was successful.
1	Your program is not currently connected to the host session.
2	Parameter error.
5	The target field was protected or inhibited, or incorrect data was sent to the target field (such as a field attribute).
6	Copy was completed, but data was truncated.
7	The <i>pos</i> parameter was not valid.
9	A system error occurred.
24	The screen has no fields (unformatted).

## Copy\_Str\_To\_PS

The **Copy\_Str\_To\_PS** function copies a string of characters into the host presentation space specified by the *pos* . parameter.

### Prerequisite Calls

**Connect**

### Supplied Syntax

The syntax for the **Copy\_Str\_To\_PS** function is as follows:

```
HLLAPI( 'Copy_str_to_PS', string, pos )
```

### Supplied Parameters

**Function name:** **Copy\_Str\_To\_PS.**

*string:* The string containing the data to be transferred to the presentation space.

*pos:* The presentation space to be copied.

### Returned Parameters

Return Code	Explanation
0	The <b>Copy_Str_To_PS</b> function was successful.
1	Your program is not currently connected to the host session.
2	Parameter error.
5	The target field was protected or inhibited, or incorrect data was sent to the target field (such as a field attribute).
6	Copy was completed, but data was truncated.
7	The <i>pos</i> parameter was not valid.
9	A system error occurred.

Double-byte characters



# Disconnect

The **Disconnect** function disconnects your application program from the currently connected session.

## Prerequisite Calls

**Connect**

## Supplied Syntax

The syntax for the **Disconnect** function is as follows:

```
HLLAPI( 'Disconnect' )
```

## Supplied Parameters

None.

## Returned Parameters

Return Code	Explanation
0	The <b>Disconnect</b> function was successful.
1	Your program is not currently connected to the host presentation space.
9	A system error occurred.

## Disconnect\_PM

The **Disconnect\_PM** function disconnects from the session window.

### Prerequisite Calls

**Connect\_PM**

### Supplied Syntax

The syntax for the **Disconnect\_PM** function is as follows:

```
HLLAPI( 'Disconnect_PM', session_id )
```

### Supplied Parameters

**Function name:** **Disconnect\_PM.**

*session\_id:* The single-character short name of the session you want to connect to.

### Returned Parameters

Return Code	Explanation
0	The <b>Disconnect_PM</b> function was successful.
1	Your program is not currently connected for Window Services.
9	A system error occurred.

## Find\_Field\_Len

The **Find\_Field\_Len** function returns the length of the target field along with the attributes specified by the *search\_option* parameter.

### Prerequisite Calls

**Connect**

### Supplied Syntax

The syntax for the **Find\_Field\_Len** function is as follows:

```
HLLAPI( 'Find_field_len', search_option, pos )
```

### Supplied Parameters

**Function name:** **Find\_Field\_Len.**

*search\_option:* See the following table.

*pos:* The target field to be copied.

The following *search\_option* values are valid:

Value	Explanation
'bb' or 'Tb'	Current field (the field where the cursor is located).
'Nb'	Next field, either protected or unprotected.
'Pb'	Previous field, either protected or unprotected.
'NP'	Next protected field.
'NU'	Next unprotected field.
'PP'	Previous protected field.
'PU'	Previous unprotected field.

### Returned Parameters

Return Code	Explanation
0	The specified field was not found.
data	The length of the specified field.

## Find\_Field\_Pos

The **Find\_Field\_Pos** function returns the location of the target field with the attributes specified by the *search\_option* parameter.

### Prerequisite Calls

**Connect**

### Supplied Syntax

The syntax for the **Find\_Field\_Pos** function is as follows:

```
HLLAPI( 'Find_field_pos', search_option, pos )
```

### Supplied Parameters

**Function name:** **Find\_Field\_Pos.**  
*search\_option:* See the following table.  
*pos:* The target field to be copied.

The following *search\_option* values are valid:

Value	Explanation
'bb' or 'Tb'	The current field (the field where the cursor is located).
'Nb'	The next field, either protected or unprotected.
'Pb'	The previous field, either protected or unprotected.
'NP'	The next protected field.
'NU'	The next unprotected field.
'PP'	The previous protected field.
'PU'	The previous unprotected field.

### Returned Parameters

Return Code	Explanation
0	The specified field was not found.
data	The position of the specified field.

## Get\_Key

The **Get\_Key** function allows your application program to intercept keystrokes from the specified *session\_id*, or from the currently connected session if *session\_id* is blank. The program waits until a keystroke becomes available.

### Prerequisite Calls

**Start\_Keystroke\_Intercept**

### Supplied Syntax

The syntax for the **Get\_Key** function is as follows:

```
HLLAPI( 'Get_key', session_id )
```

### Supplied Parameters

**Function name:** **Get\_Key.**

*session\_id:* The single-character short name of the session.

### Returned Parameters

Return Code	Explanation
"	Null. Error or not connected to <i>session_id</i> .
data string	The contents of the data string depend on the keys pressed by the 3270 or 5250 session operator. Refer to "Keyboard Mnemonics" on page 112.

**Note:** The @ (escape) character is set by specifying ESC= in the **Set\_Session\_Parms** function.

### Additional Information

If keystroke interception is active (through the **Start\_Keystroke\_Intercept** function), no keystrokes are sent to the connected session until you perform the following tasks:

1. Specify the **Get\_Key** function to remove the keystroke from the intercept buffer.
2. Specify the **Intercept\_Status** function to either accept or reject the keystroke. If you specify *Accept*, the keystroke is sent to the connected session by the **Sendkey** function. If you specify *Reject*, the keystroke is discarded.

## Get\_Window\_Status

The **Get\_Window\_Status** function returns the current window status as a string of ASCII characters in hexadecimal format.

### Prerequisite Calls

**Connect\_PM**

### Supplied Syntax

The syntax for the **Get\_Window\_Status** function is as follows:

```
HLLAPI( 'Get_window_status', session_id )
```

### Supplied Parameters

**Function name:** **Get\_Window\_Status.**

*session\_id:* The single-character short name of the session.

### Returned Parameters

Return Code	Explanation
"	Null. Not connected to the window. Refer to the <b>Connect_PM</b> function for more information.
0008	The window is visible.
0010	The window is invisible.
0080	The window is activated.
0100	The window is deactivated.
0400	The window is minimized.
0800	The window is maximized.

**Note:** If more than one of the above states is true, the return codes are added together. For example, if the window is visible (0008), deactivated (0100), and maximized (0800), the return code is 0908.

## Intercept\_Status

The **Intercept\_Status** function informs the session when a keystroke obtained through the **Get\_Key** function was accepted or rejected.

### Prerequisite Calls

**Start\_Keystroke\_Intercept**

### Supplied Syntax

The syntax for the **Intercept\_Status** function is as follows:

```
HLLAPI( 'Intercept_status', session_id, status )
```

### Supplied Parameters

**Function name:** **Intercept\_Status.**

*session\_id:* The single-character short name of the session.

*status:* See the following table:

Value	Explanation
'A'	Accept the keystroke.
'R'	Reject the keystroke. Signal with a beep.

### Returned Parameters

Return Code	Explanation
0	The <b>Interrupt_Status</b> function was successful.
1	The presentation space was not valid.
8	No prior <b>Start_Keystroke_Intercept</b> function was active.
9	A system error occurred.

# Lock\_PMSVC

This function locks or unlocks the presentation space window.

## Prerequisite Calls

### Connect\_PM

## Supplied Syntax

The syntax for the **Lock\_PMSVC** function is as follows:

```
HLLAPI( 'Lock_PMSVC', session_id, status, queue_option )
```

## Supplied Parameters

**Function name:** Lock\_PMSVC.

*session\_id:* The single-character short name of the session.

*status:* See the following table:

Value	Explanation
'L'	Lock the presentation space window.
'U'	Unlock the presentation space window.

*queue\_option:* See the following table:

Value	Explanation
'R'	Return immediately.
'Q'	Queue if the presentation space window is already locked (for lock only).

## Returned Parameters

Return Code	Explanation
0	The <b>Lock_PMSVC</b> function was successful.
1	An incorrect host presentation space was specified or not connected.
2	An error was made in specifying parameters.
9	A system error occurred.
43	The API was already locked by another EHLLAPI application (on LOCK), or API not locked (on UNLOCK).



# Lock\_PS

The **Lock\_PS** function locks or unlocks the presentation space.

## Prerequisite Calls

**Connect**

## Supplied Syntax

The syntax for the **Lock\_PS** function is as follows:

```
HLLAPI( 'Lock_PS', session_id, status, queue_option )
```

## Supplied Parameters

**Function name:** **Lock\_PS.**

*session\_id:* The single-character short name of the session.

*status:* See the following table:

Value	Explanation
'L'	Lock the presentation space.
'U'	Unlock the presentation space.

*queue\_option:* See the following table:

Value	Explanation
'R'	Return immediately.
'Q'	Queue if the presentation space is already locked (for LOCK only).

## Returned Parameters

Return Code	Explanation
0	The <b>Lock_PS</b> function was successful.
1	The presentation space was not valid.
2	An error was made in specifying parameters.
9	A system error occurred.
43	The API was already locked by another EHLLAPI application (on LOCK), or API not locked (on UNLOCK).

# Pause

The **Pause** function causes a timed pause of  $n \frac{1}{2}$ -second intervals to occur.

If the **Set\_Session\_Parms** function is set to IPAUSE and a **Start\_Host\_Notify** function has been called, the pause is also ended by an update to the host screen. If *sessname* is provided and IPAUSE has been set, only updates to the specified session interrupts the pause. Otherwise, updates to any connected session interrupts the pause (if IPAUSE has been set).

## Prerequisite Calls

None.

## Supplied Syntax

The syntax for the **Pause** function is as follows:

```
HLLAPI( 'Pause', n [, sessname] )
```

## Supplied Parameters

**Function name:** **Pause.**

*n*: A timed pause.

*sessname*: An optional parameter. See the following table:

Value	Explanation
'X#'	X is the name of the short-session_id, and # is coded exactly as shown.

## Returned Parameters

Return Code	Explanation
0	The wait duration has expired.
9	A system error occurred.
26	The host session presentation space or OIA has been updated. Refer to "Query_Host_Update" on page 497 for more information.

## Query\_Close\_Intercept

The **Query\_Close\_Intercept** function determines if a close request was started from the session.

### Prerequisite Calls

**Start\_Close\_Intercept**

### Supplied Syntax

The syntax for the **Query\_Close\_Intercept** function is as follows:

```
HLLAPI( 'Query_close_intercept', session_id )
```

### Supplied Parameters

**Function name:** **Query\_Close\_Intercept.**

*session\_id:* The single-character short name of the host session.

### Returned Parameters

Return Code	Explanation
0	A close intercept event did not occur.
1	Your program is not currently connected to the host session.
2	An error was made in specifying parameters.
8	No prior <b>Start_Close_Intercept</b> function was called for this host presentation space.
9	A system error occurred.
12	The session stopped.
26	A close intercept occurred since the last <b>Query_Close_Intercept</b> function call.

## Query\_Cursor\_Pos

The **Query\_Cursor\_Pos** function returns the cursor position for the currently connected session.

### Prerequisite Calls

**Connect**

### Supplied Syntax

The syntax for the **Query\_Cursor\_Pos** function is as follows:

```
HLLAPI( 'Query_cursor_pos' )
```

### Supplied Parameters

None.

### Returned Parameters

Return Code	Explanation
0	Your program is not currently connected to the host session.
data	Cursor position.

## Query\_Emulator\_Status

The **Query\_Emulator\_Status** function returns the status of the specified host session.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Query\_Emulator\_Status** function is as follows:

```
HLLAPI( 'Query_emulator_status', session_id )
```

### Supplied Parameters

**Function name:** **Query\_Emulator\_Status.**

**session\_id:** Specifies the session letter (A-Z) of the session to be queried.

### Returned Parameters

Return Code	Explanation
''	Null. Error has occurred.
1	Session started.
2	Session started and connection to the host requested.
3	Session started, connection requested, and API is enabled for the session.

## Query\_Field\_Attr

The **Query\_Field\_Attr** function returns the hexadecimal representation of the field attribute in the currently connected session.

### Prerequisite Calls

**Connect**

### Supplied Syntax

The syntax for the **Query\_Field\_Attr** function is as follows:

```
HLLAPI( 'Query_field_attr', pos )
```

### Supplied Parameters

**Function name:** **Query\_Field\_Attr.**

*pos:* The target field to be copied.

### Returned Parameters

Return Code	Explanation
1	Your program is not currently connected to the host session.
data	Attribute bytes (printable hexadecimal characters equal to or greater than X'C0').

## Query\_Host\_Update

The **Query\_Host\_Update** function determines if the OIA or presentation space for the session has been updated.

### Prerequisite Calls

**Start\_Host\_Notify**

### Supplied Syntax

The syntax for the **Query\_Host\_Update** function is as follows:

```
HLLAPI( 'Query_host_update', session_id )
```

### Supplied Parameters

**Function name:** **Query\_Host\_Update.**

*session\_id:* The single-character short name of the session.

### Returned Parameters

Return Code	Explanation
0	No updates were made since the last call.
1	An incorrect host presentation space was specified.
8	No prior <b>Start_Host_Notify</b> function was called for the host presentation space ID.
9	A system error occurred.
21	The OIA has been updated.
22	The presentation space was updated.
23	The OIA and the host presentation space were updated.
44	Printing has completed in the printer session.

## Query\_Session\_List

The **Query\_Session\_List** function returns a 2-byte entry of each current host session.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Query\_Session\_List** function is as follows:

```
HLLAPI( 'Query_session_list', )
```

### Supplied Parameters

None.

### Returned Parameters

Return Code	Explanation	
' '	Null. Error has occurred.	
0	No sessions are started.	
data	Position	Definition
	1	Short session ID.
	2	One of the following values: <b>1</b> Session started. <b>2</b> Session started and connection to the host requested. <b>3</b> Session started, connection requested, and API is enabled for the session.



## Query\_Session\_Status

The **Query\_Session\_Status** function returns various status information from the host session, or from the currently connected session if *session\_id* is blank.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Query\_Session\_Status** function is as follows:

```
HLLAPI( 'Query_session_status', session_id )
```

### Supplied Parameters

**Function name:** **Query\_Session\_Status.**

*session\_id:* The single-character short name of the session.

### Returned Parameters

Return Code	Explanation	
' '	Null. Not connected.	
data	Position	Definition
	1	Short session ID.
	2–9	Long name of session.
	10	Session type, where: <ul style="list-style-type: none"> <li>• D=3270 host</li> <li>• E=3270 printer</li> <li>• F=5250 host</li> <li>• G=5250 printer</li> <li>• H=ASCII</li> </ul>
	11	Session characteristics, expressed as a binary number containing the session characteristics byte explained below: <b>0</b> EAB <b>1</b> PSS <b>2–7</b> Reserved.  If bit 0 (EAB) = 0, the session has base attributes. If bit 0 (EAB) = 1, the session has extended attributes. If bit 1 (PSS) = 0, the session does not support programmed symbols. If bit 1 (PSS) = 1, the session supports programmed symbols.
	12–13	Number of rows in the host presentation space. This is a binary number and is not in display format. If the session type is E or G, the value is 0.
	14–15	Number of columns in the host presentation space. This is a binary number and is not in display format. If the session type is E or G, the value is 0.
	16-17	Host code page number, expressed as a binary number.
	18	Reserved.

**Note:** After you parse the last three fields (row, col, codepage) from the string to obtain their decimal values, use `c2d(reverse(x))` to reverse the bytes.

## Query\_Sessions

The **Query\_Sessions** function returns either a 12-byte description of each configured session or a null (") if an error occurs.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Query\_Sessions** function is as follows:

```
HLLAPI( 'Query_sessions' )
```

### Supplied Parameters

None.

### Returned Parameters

Return Code	Explanation	
' '	Null. Error has occurred.	
data	Position	Definition
	1	Short session ID.
	2–9	Long name of session.
	10	Connection type H=host
11–12	Presentation space size. This is a binary number and is not in display format. If the session type is a print session, the value is 0. (See "Query Sessions (10)" on page 92.)	

**Note:** After you parse the last field (pssize) from the string to obtain its decimal values, use `c2d(reverse(x))`.

## Query\_System

The **Query\_System** function returns either a 35-byte system configuration string or a null ("") if an error occurs.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Query\_System** function is as follows:

```
HLLAPI( 'Query_system' )
```

### Supplied Parameters

None.

### Returned Parameters

Return Code	Explanation	
' '	Null. Error has occurred.	
data	<b>Position</b>	<b>Definition</b>
	1	EHLLAPI version number.
	2–3	EHLLAPI level number.
	4–9	Reserved
	10–12	Reserved.
	13	Hardware base U= unable to determine.
	14	Program type, where P =IBM Personal Communications.
	15–16	Reserved.
	17–18	PCOMM version/level as a 2-byte ASCII value.
	19	Reserved.
	20–23	Reserved
	24–27	Reserved
	28–29	Reserved
	30–31	NLS type expressed as a 2–byte binary number.
	32	1-byte printable ASCII code representing the type of monitor used as follows: <ul style="list-style-type: none"><li>• V = VGA</li><li>• H = XGA</li><li>• U = unknown</li></ul>
33–35	Reserved.	

## Query\_Window\_Coord

The **Query\_Window\_Coord** function requests the window coordinates from the window for the host session, or from the currently connected session if *session\_id* is blank.

### Prerequisite Calls

**Connect\_PM**

### Supplied Syntax

The syntax for the **Query\_Window\_Coord** function is as follows:

```
HLLAPI( 'Query_window_coord', session_id )
```

### Supplied Parameters

**Function name:** **Query\_Window\_Coord.**

*session\_id:* The single-character short name of the session window.

### Returned Parameters

Return Code	Explanation
"	Null. Not connected.
data	The data string returns 4 decimal numbers in the following format: xLeft yBottom xRight yTop

## Query\_Workstation\_Profile

The **Query\_Workstation\_Profile** function returns the profile name that was used to start the specified host session.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Query\_Workstation\_Profile** function is as follows:

```
HLLAPI( 'Query_workstation_profile', session_id )
```

### Supplied Parameters

**Function name:** **Query\_Workstation\_Profile.**  
**session\_id:** Specifies the session letter (A-Z) of the session to be queried.

### Returned Parameters

Return Code	Explanation
' '	Null. Error has occurred.
data	The name of the workstation profile used to start the session.

# Receive\_File

The **Receive\_File** function is used to transfer a file from the host session to the workstation session.

**Note:** Do not terminate the Receive program while file transfer is in progress; otherwise you will receive an error message.

## Prerequisite Calls

None.

## Supplied Syntax

The syntax for the **Receive\_File** function is as follows:

```
HLLAPI( 'Receive_file', string )
```

## Supplied Parameters

**Function name:** **Receive\_File.**

*string:* The same parameters that are specified with RECEIVE command. For additional information on parameters, refer to “Receive File (91)” on page 100 .

## Returned Parameters

Return Code	Explanation
2	A parameter error occurred, or you specified a data string length that is too short or too long (0 bytes or more than 128 bytes) for the EHLLAPI buffer. The file transfer was unsuccessful.
3	The file transfer was complete.
4	The file transfer was complete and has segmented records.
9	A system error occurred.
27	Either the file transfer ended by a cancel of a file transfer or, if a timeout was specified by the <b>Set_Session_Parms</b> function, the timeout expired.
101	File transfer was successful (transfer to/from CICS).
300+x	The Win32 error codes reported by EHLLAPI are greater than 300. To determine the Win32 error code, subtract 300 from the return code and refer to the

Other return codes can also be received, which relate to message numbers generated by the host transfer program. For transfers to a CICS host transfer program, subtract 100 from the return code to give you the numeric portion of the message. For example, a return code of 101 would mean that the message number INW0001 was issued by the host. For other host transfer programs, just use the return code as the numerical part of the message. For example, a return of 34 would mean that message TRANS34 was issued by the host transfer program. The documentation for your host transfer program should give more information about the meanings of the specific messages.

# Release

The **Release** function unblocks the connected display session keyboard.

## Prerequisite Calls

**Connect**

## Supplied Syntax

The syntax for the **Release** function is as follows:

```
HLLAPI( 'Release' )
```

## Supplied Parameters

None.

## Returned Parameters

Return Code	Explanation
0	The <b>Release</b> function was successful.
1	Your program is not currently connected to the host session.
9	A system error occurred.

## Additional Information

If you disconnect while the keyboard is locked (through the **Reserve** function), the keyboard is released automatically.



# Reserve

The **Reserve** function blocks the currently connected session from user input until either a **Release** or a **Disconnect** function is executed.

## Prerequisite Calls

**Connect**

## Supplied Syntax

The syntax for the **Reserve** function is as follows:

```
HLLAPI( 'Reserve' )
```

## Supplied Parameters

None.

## Returned Parameters

Return Code	Explanation
0	The <b>Reserve</b> function was successful.
1	Your program is not currently connected to the host session.
5	The presentation space was inhibited.
9	A system error occurred.

## Reset\_System

The **Reset\_System** function reinitializes the session parameters (set by the **Set\_Session\_Parms** function) to their defaults and disconnects from all connected resources.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Reset\_System** function is as follows:

```
HLLAPI( 'Reset_system' )
```

### Supplied Parameters

None.

### Returned Parameters

Return Code	Explanation
0	The <b>Reset_System</b> function was successful.
9	A system error occurred.

## Search\_Field

The **Search\_Field** function searches the currently connected presentation space for the occurrence of a specified string beginning at a particular target field. If the SRCHALL (default) option is specified in the **Set\_Session\_Parms** function, the *pos* parameter is overridden.

### Prerequisite Calls

**Connect**

### Supplied Syntax

The syntax for the **Search\_Field** function is as follows:

```
HLLAPI( 'Search_field', string, pos )
```

### Supplied Parameters

**Function name:** **Search\_Field.**

*string:* The string to search for.

*pos:* The position of the field within the presentation space.

### Returned Parameters

Return Code	Explanation
0	The <i>string</i> was not found or the session was not connected.
data	The position of the <i>string</i> in the connected presentation space.

**DBCS Only:** If the specified start position for the search function is the second byte of the double-byte character, the search starts from the next character for SRCHRFWD or from this character for SRCHBKWD. If the last character of the specified string is the first byte of the double-byte character, it is not included.

During a search, SO/SI pairs are ignored in the presentation space. To search the control character of the double-byte character, the string should be placed between SO (X'0E') and SI (X'0I'). For example, X'0E00C0F' in the data string is treated as the double-byte character FF (X'000C').

## Search\_PS

The **Search\_PS** function searches the host presentation space for a particular string.

### Prerequisite Calls

**Connect**

### Supplied Syntax

The syntax for the **Search\_PS** function is as follows:

```
HLLAPI( 'Search_PS', string, pos )
```

### Supplied Parameters

**Function name:** **Search\_PS.**

*string:* The string to search for.

*pos:* The PS position to begin the search.

### Returned Parameters

Return Code	Explanation
0	The <i>string</i> was not found or the session was not connected.
data	Position of the <i>string</i> in the connected presentation space.

**DBCS Only:** If the specified start position for the search function is the second byte of the double-byte character, the search starts from the next character for SRCHRFWD or from this character for SRCHBKWD. If the last character of the specified string is the first byte of the double-byte character, it is not included.

During a search, SO/SI pairs are ignored in the presentation space. To search the control character of the double-byte character, the string should be placed between SO (X'0E') and SI (X'0I'). For example, X'0E00C0F' in the data string is treated as the double-byte character FF (X'000C').

# Send\_File

The **Send\_File** function transfers a file from the personal computer session where EHLLAPI is running to a host session.

**Note:** Do not terminate the Send program while file transfer is in progress; otherwise, you will receive an error message.

## Prerequisite Calls

None.

## Supplied Syntax

The syntax for the **Send\_File** function is as follows:

```
EHLLAPI( 'Send_file', string )
```

## Supplied Parameters

**Function name:** **Send\_File.**  
*string* The same parameters that are specified with SEND command. For additional information on parameters, refer to “Send File (90)” on page 108 .

## Returned Parameters

Return Code	Explanation
2	A parameter error occurred, or you specified a data string length that was too long or too short for the EHLLAPI buffer. File transfer was unsuccessful.
3	The file transfer was complete.
4	The file transfer was complete and has segmented records.
5	The workstation file name was incorrect or was not found. File transfer was canceled.
9	A system error occurred.
27	Either the file transfer ended by a cancel of a file transfer or, if timeout was specified by the <b>Set_Session_Parms</b> function, the timeout expired.
101	File transfer was successful (transfer to/from CICS).
300+x	The Win32 error codes reported by EHLLAPI are greater than 300. To determine the Win32 error code, subtract 300 from the return code and refer to the

Other return codes can also be received, which relate to message numbers generated by the host transfer program. For transfers to a CICS host transfer program, subtract 100 from the return code to give you the numeric portion of the message. For example, a return code of 101 would mean that the message number INW0001 was issued by the host. For other host transfer programs, just use the return code as the numerical part of the message. For example, a return of 34 would mean that message TRANS34 was issued by the host transfer program. The documentation for your host transfer program should give more information about the meanings of the specific messages.

# Sendkey

The **Sendkey** function sends a keystroke or a string of keystrokes to the currently connected host presentation space. The *string* parameter defines the set of keystrokes, which are sent to the host presentation space. Up to 255 keys can be sent at a time.

## Prerequisite Calls

**Connect**

## Supplied Syntax

The syntax for the **Sendkey** function is as follows:

```
HLLAPI( 'Sendkey', string )
```

## Supplied Parameters

**Function name:** **Sendkey.**

*string:* The string of keystrokes. Refer to "Keyboard Mnemonics" on page 112.

## Returned Parameters

Return Code	Explanation
0	The keystrokes were sent; status was normal.
1	Your program is not currently connected to the host session.
4	The host session was busy; all of the keystrokes could not be sent.
5	Input to the target session was inhibited; keystrokes were rejected, or incorrect keystroke mnemonics were sent. All of the keystrokes could not be sent.
6	Bad keystroke mnemonic.
9	A system error occurred.

## Set\_Cursor\_Pos

The **Set\_Cursor\_Pos** function positions the cursor at the specified target field within the currently connected host presentation space.

### Prerequisite Calls

**Connect**

### Supplied Syntax

The syntax for the **Set\_Cursor\_Pos** function is as follows:

```
HLLAPI( 'Set_cursor_pos', pos )
```

### Supplied Parameters

**Function name:** **Set\_Cursor\_Pos.**

*pos:* The target field to be copied.

### Returned Parameters

Return Code	Explanation
0	Cursor was successfully located at specified position.
1	Your program is not currently connected to the host session.

## Set\_Session\_Parms

The **Set\_Session\_Parms** function sets the current session parameters.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Set\_Session\_Parms** function is as follows:

```
HLLAPI( 'Set_session_parms', string )
```

### Supplied Parameters

**Function name:** **Set\_Session\_Parms.**

*string:* The string containing the session options to be changed.

### Returned Parameters

Return Code	Explanation
0	The session parameters were set.
2	One or more parameters were not valid.
9	A system error occurred.

### Additional Information

The STREOT and EOT options are not supported in the **Set\_Session\_Parms** function.



## Set\_Window\_Status

The **Set\_Window\_Status** function changes the window status of a session.

### Prerequisite Calls

**Connect\_PM**

### Supplied Syntax

The syntax for the **Set\_Window\_Status** function is as follows:

```
HLLAPI( 'Set_window_status', session_id, option [, num1 | option1, num2 ] )
```

### Supplied Parameters

**Function name:** **Set\_Window\_Status.**

*session\_id:* The single-character short name of the session.

*option:* See the following table:

Option	Explanation
'V'	Make the window visible.
'I'	Make the window invisible.
'A'	Make the window active.
'D'	Make the window inactive.
'R'	Restore the window from maximized or minimized state.
'Z'	Change the window placement based on the first character of <i>option1</i> : <b>Top</b> Move the emulation window to the foreground. <b>Bottom</b> Move the emulation window to the background.
'X'	Maximize the window.
'N'	Minimize the window (reduce to icon).
'M'	Where <i>num1</i> and <i>num2</i> represent the decimal position of the lower left corner of the new window position.
'S'	Where <i>num1</i> and <i>num2</i> represent the decimal width and height of the new window.

The *num1* and *num2* parameters are used only for the *Move* ('M') and *Size* ('S') options and the *option1* parameter is used for the *Zorder* ('Z') option.

### Returned Parameters

Return Code	Explanation
0	The <b>Set_Window_Status</b> function was successful.
1	Your program is not currently connected to the host session.
9	A system error occurred.
12	The session stopped.

## Start\_Close\_Intercept

The **Start\_Close\_Intercept** function intercepts close requests for the host session.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Start\_Close\_Intercept** function is as follows:

```
HLLAPI( 'Start_close_intercept', session_id )
```

### Supplied Parameters

**Function name:** **Start\_Close\_Intercept.**

*session\_id:* The single-character short name of the session.

### Returned Parameters

Return Code	Explanation
0	The <b>Start_Close_Intercept</b> function was successful.
1	An incorrect host presentation space was specified.
2	A parameter error occurred.
9	A system error occurred.
10	The function was not supported by the emulation program.

## Start\_Communication

The **Start\_Communication** function starts the communications with the host session for the specified *session\_id*. This call is equivalent to doing a 'Communications->Connect' from the emulator window.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Start\_Communication** function is as follows:

```
HLLAPI( 'Start_communication', session_id )
```

### Supplied Parameters

**Function name:** **Start\_Communication.**

*session\_id:* The single character short-name of the session.

### Returned Parameters

Return Code	Explanation
0	The <b>Start_Communication</b> connection was requested successfully.
1	An incorrect session ID was specified.
2	The specified session has not been started.

## Start\_Host\_Notify

The **Start\_Host\_Notify** function determines if the designated host presentation space or operator information area has been updated.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Start\_Host\_Notify** function is as follows:

```
HLLAPI( 'Start_host_notify', session_id, option )
```

### Supplied Parameters

**Function name:** **Start\_Host\_Notify.**

*session\_id:* The single-character short name of the session.

*E* Asks for notification of completion during a printer session.

*option:* See the following table:

Value	Explanation
'P'	Asks for notification of presentation space update only.
'O'	Asks for notification of OIA update only.
'B'	Asks for notification of both presentation space and OIA updates.

### Returned Parameters

Return Code	Explanation
0	The <b>Start_Host_Notify</b> function was successful.
1	An incorrect host presentation space was specified.
2	An error was made in specifying parameters.
9	A system error occurred.

## Start\_Keystroke\_Intercept

The **Start\_Keystroke\_Intercept** function filters any keystrokes sent to the session specified by the *session\_id* parameter.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Start\_Keystroke\_Intercept** function is as follows:

```
HLLAPI( 'Start_keystroke_intercept', session_id, option )
```

### Supplied Parameters

**Function name:** **Start\_Keystroke\_Intercept.**

*session\_id:* The single-character short name of the session.

*option:* See the following table:

Option	Explanation
'D'	AID keys only.
'L'	All keystrokes.

### Returned Parameters

Return Code	Explanation
0	The <b>Start_Keystroke_Intercept</b> function was successful.
1	The presentation space was not valid.
2	An incorrect option was specified.
4	Resource was unavailable. The requested presentation space was in use by another API application.
9	A system error occurred.

## Start\_Session

The **Start\_Session** function starts a host session using the specified workstation profile and optional session id and start options.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Start\_Session** function is as follows:

```
HLLAPI( 'Start_session', profile_name, option[, session_id] )
```

### Supplied Parameters

**Function name:** **Start\_Session.**

*session\_id:* An optional parameter, specifies the session letter (A-Z) to be associated with the session to be started. If null, the next available session letter will be used.

*profile\_name:* The filename of the workstation profile to be started. The path can be included but is optional.

*option:* See the following table:

Option	Explanation
'V'	Start the session with the window visible.
'I'	Start the session with the window invisible.
'X'	Start the session with the window maximized.
'N'	Start the session with the window minimized.

### Returned Parameters

Return Code	Explanation
0	The <b>Start_Session</b> function was successful.
1	An incorrect session ID was specified.
2	The specified session ID is already in use.
3	The workstation profile name is invalid.
4	An invalid operation was specified.
9	A system error occurred.

## Stop\_Close\_Intercept

The **Stop\_Close\_Intercept** function allows the application to turn off the **Start\_Close\_Intercept** function. After the **Stop\_Close\_Intercept** function is issued, subsequent close requests are accepted for the session specified by *session\_id*.

### Prerequisite Calls

**Start\_Close\_Intercept**

### Supplied Syntax

The syntax for the **Stop\_Close\_Intercept** function is as follows:

```
HLLAPI( 'Stop_close_intercept', session_id )
```

### Supplied Parameters

**Function name:** **Stop\_Close\_Intercept.**

*session\_id:* The single-character short name of the session.

### Returned Parameters

Return Code	Explanation
0	The <b>Stop_Close_Intercept</b> function was successful.
1	An incorrect host presentation space was specified.
8	No previous <b>Start_Close_Intercept</b> function was issued.
9	A system error occurred.
12	The session was stopped.

## Stop\_Communication

The **Stop\_Communication** function stops the communications with the host session for the specified *session\_id*. This call is equivalent to doing a 'Communications->Disconnect' from the emulator window.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Stop\_Communication** function is as follows:

```
HLLAPI( 'Stop_communication', session_id )
```

### Supplied Parameters

**Function name:** **Stop\_Communication.**

*session\_id:* The single character short-name of the session.

### Returned Parameters

Return Code	Explanation
0	The <b>Stop_Communication</b> disconnection was requested successfully.
1	An incorrect session ID was specified.
2	The specified session has not been started.



## Stop\_Host\_Notify

The **Stop\_Host\_Notify** function prevents the **Start\_Host\_Notification** function from determining if the host session identifier has been updated.

### Prerequisite Calls

**Start\_Host\_Notify**

### Supplied Syntax

The syntax for the **Stop\_Host\_Notify** function is as follows:

```
HLLAPI( 'Stop_host_notify', session_id )
```

### Supplied Parameters

**Function name:** **Stop\_Host\_Notify**.

*session\_id*: The single-character short name of the session.

### Returned Parameters

Return Code	Explanation
0	The <b>Stop_Host_Notify</b> function was successful.
1	An incorrect host presentation space was specified.
8	No prior <b>Start_Host_Notify</b> function was issued.
9	A system error occurred.

## Stop\_Keystroke\_Intercept

The **Stop\_Keystroke\_Intercept** function ends your application program's ability to intercept keystrokes for the *session\_id*. The **Start\_Keystroke\_Intercept** function cancels the preceding **Start\_Keystroke\_Intercept** function.

### Prerequisite Calls

**Start\_Keystroke\_Intercept**

### Supplied Syntax

The syntax for the **Stop\_Keystroke\_Intercept** function is as follows:

```
HLLAPI( 'Stop_keystroke_intercept', session_id )
```

### Supplied Parameters

**Function name:** **Stop\_Keystroke\_Intercept.**

*session\_id:* The single-character short name of the session.

### Returned Parameters

Return Code	Explanation
0	The <b>Stop_Keystroke_Intercept</b> function was successful.
1	The host presentation space was not valid.
8	No prior <b>Start_Keystroke_Intercept</b> function was called for this presentation space.
9	A system error occurred.

## Stop\_Session

The **Stop\_Session** function stops the host session specified.

### Prerequisite Calls

None.

### Supplied Syntax

The syntax for the **Stop\_Session** function is as follows:

```
HLLAPI( 'Stop_session', session_id, save_option)
```

### Supplied Parameters

**Function name:** **Stop\_Session.**

*session\_id:* Specifies the session letter (A-Z) of the session to be stopped.

*save\_option:* See the following table:

Option	Explanation
'D'	Use the default profile save option as specified in the profile.
'S'	Save the profile on exit.
'N'	Do not save the profile on exit.

### Returned Parameters

Return Code	Explanation
0	The <b>Stop_Session</b> function was successful.
1	An incorrect session ID was specified.
2	The specified session ID has not been started.

## Wait

The **Wait** function checks the status of the currently connected session. If the controller or host system is busy, this function causes EHLLAPI to wait for a specified time to see if the condition clears. The specified time is determined by the TWAIT, NWAIT, or LWAIT option in the **Set\_Session\_Parms** function.

### Prerequisite Calls

**Connect**

### Supplied Syntax

The syntax for the **Wait** function is as follows:

```
HLLAPI( 'Wait' )
```

### Supplied Parameters

None.

### Returned Parameters

Return Code	Explanation
0	The keyboard was unlocked and ready for input.
1	Your application program was not connected to a valid session.
4	Timeout while busy (in XCLOCK or XSYSTEM state).
5	The keyboard is locked.
9	A system error occurred.

---

## Programming Notes

In the REXX environment, the Personal Communications for OS/2 EHLLAPI does not automatically disconnect and reset a connected session when the REXX application program ends. If the REXX application program ends (either normally or abnormally) without disconnecting the session, the session remains connected. In addition, any options set by the **Set\_Session\_Parms** function remain in effect. Therefore, it is the responsibility of the REXX programmer to ensure that the REXX program properly disconnects and resets under all program termination conditions, including error conditions.

Several EHLLAPI features are not applicable to the REXX EHLLAPI environment. Structured fields of the EHLLAPI features are not supported by REXX EHLLAPI.

---

## Sample Programs

Sample programs demonstrating the use of REXX EHLLAPI features are included on the CD-ROM and diskettes.

The first sample program (QTIME.COMD) sets the system clock based on the VM system time (run this program only if connecting to a VM host session).

The second sample program (CMMACRO.COMD) records key strokes on the host system and plays them back. This function simplifies repetitive tasks.

**Note:** Each sample program disconnects and releases used resources before exiting.



---

## Appendix I. Trademarks

The following terms are trademarks of the IBM Corporation in the United States or other countries, or both:

ACF/VTAM	NetView
AFP	OS/2
AIX	OS/400
AIXwindows	OfficeVision
APL2	PS/2
APPN	PSF
AS/400	Personal System/2
Advanced Peer-to-Peer Networking	Presentation Manager
AnyNet	S/390
Application System/400	SAA
CICS	System/370
CICS/MVS	System/390
CICS/VSE	Systems Application Architecture
COBOL/2	TalkLink
CUA	ThinkPad
Common User Access	VM/ESA
DB2	VM/XA
GDDM	VTAM
Global Network	Virtual Machine/Enterprise Systems Architecture
IBM	WIN-OS/2
IBMLink	WebExplorer
IIN	XGA
IMS	
InfoWindow	
MVS/ESA	
MVS/XA	

C-bus is a registered trademark of Corollary, Inc.

Java and all Java-based trademarks and logos are trademarks of Sun Microsystems, Inc. in the United States and/or other countries.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States and/or other countries.

PC Direct is a registered trademark of Ziff Communications Company and is used by IBM Corporation under license.

ActionMedia, LANDesk, MMX, Pentium, and ProShare are trademarks or registered trademarks of Intel Corporation in the U.S. and other countries.

UNIX is a registered trademark in the United States and other countries licensed exclusively through X/Open Company Limited.

Other company, product, and service names may be trademarks or service marks of others.





---

## Appendix J. Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing  
IBM Corporation  
500 Columbus Avenue  
Thornwood, NY 10594  
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation  
Licensing  
2-31 Roppongi 3-chome, Minato-ku  
Tokyo 106, Japan

**The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:**

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM documentation or non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those documents or Web sites. The materials for those documents or Web sites are not part of the materials for this IBM product and use of those documents or Web sites is at your own risk.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation  
Department T01  
Building 062  
P.O. Box 12195  
RTP, NC 27709-2195  
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement or any equivalent agreement between us.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

#### COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrates programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. You may copy, modify, and distribute these sample programs in any form without payment to IBM for the purposes of developing, using, marketing, or distributing application programs conforming to IBM's application programming interfaces.

---

## Glossary

This glossary includes terms and definitions from:

- The *American National Standard Dictionary for Information Systems*, ANSI X3.172-1990, copyright 1990 by the American National Standards Institute (ANSI). Copies may be purchased from the American National Standards Institute, 11 West 42nd Street, New York, New York 10036. Definitions are identified by the symbol (A) after the definition.
- The ANSI/EIA Standard—440-A, *Fiber Optic Terminology* Copies may be purchased from the Electronic Industries Association, 2001 Pennsylvania Avenue, N.W., Washington, DC 20006. Definitions are identified by the symbol (E) after the definition.
- The *Information Technology Vocabulary* developed by Subcommittee 1, Joint Technical Committee 1, of the International Organization for Standardization and the International Electrotechnical Commission (ISO/IEC JTC1/SC1). Definitions of published parts of this vocabulary are identified by the symbol (I) after the definition; definitions taken from draft international standards, committee drafts, and working papers being developed by ISO/IEC JTC1/SC1 are identified by the symbol (T) after the definition, indicating that final agreement has not yet been reached among the participating National Bodies of SC1.
- The *IBM Dictionary of Computing*, New York: McGraw-Hill, 1994.
- Internet Request for Comments: 1208, *Glossary of Networking Terms*
- Internet Request for Comments: 1392, *Internet Users' Glossary*
- The *Object-Oriented Interface Design: IBM Common User Access Guidelines*, Carmel, Indiana: Que, 1992.

The following cross-references are used in this glossary:

**Contrast with:**

This refers to a term that has an opposed or substantively different meaning.

**Synonym for:**

This indicates that the term has the same meaning as a preferred term, which is defined in its proper place in the glossary.

**Synonymous with:**

This is a backward reference from a defined term to all other terms that have the same meaning.

**See:** This refers the reader to multiple-word terms that have the same last word.

**See also:**

This refers the reader to terms that have a related, but not synonymous, meaning.

**Deprecated term for:**

This indicates that the term should not be used. It refers to a preferred term, which is defined in its proper place in the glossary.

The complete *IBM Software Glossary* is available on the World Wide Web at [www.networking.ibm.com/nsg/nsgmain.htm](http://www.networking.ibm.com/nsg/nsgmain.htm).

## A

**abend.** Abnormal end of task; the termination of a task before its completion because of an error condition that cannot be resolved by recovery facilities while the task is executing.

**accept.** (1) In a VTAM application program, to establish a session with a logical unit (LU) in response to a CINIT request from a system services control point (SSCP). The session-initiation request may begin when a terminal user logs on, a VTAM application program issues a macroinstruction, or a VTAM operator issues a command. (2) An SMP process that moves distributed code and MVS-type programs to the distribution libraries.

**ACCESS.** In the Simple Network Management Protocol (SNMP), the clause in a Management Information Base (MIB) module that defines the minimum level of support that a managed node provides for an object.

**action.** (1) An operation on a managed object, the semantics of which are defined as part of the managed object class definition. (2) In the AIX operating system, a defined task that an application performs. An action modifies the properties of an object or manipulates the object in some way.

**adapter.** (1) A hardware component that must be installed in the personal computer to connect to the SDLC, LAN, asynchronous, DFT, or other communication attachment (possibly connecting through a modem). (2) A part that electrically or physically connects a device to a computer or to another device.

**Advanced Peer-to-Peer Networking (APPN).** An extension to SNA featuring (a) greater distributed network control that avoids critical hierarchical dependencies, thereby isolating the effects of single points of failure; (b) dynamic exchange of network topology information to foster ease of connection, reconfiguration, and adaptive route selection; (c) dynamic definition of network resources; and (d) automated resource registration and directory lookup. APPN extends the LU 6.2 peer orientation for end-user services to network control and supports multiple LU types, including LU 2, LU 3, and LU 6.2.

**Advanced Peer-to-Peer Networking (APPN) end node.** A node that provides a broad range of end-user services and supports sessions between its local control point (CP) and the CP in an adjacent network node. It uses these sessions to dynamically register its resources with the adjacent CP (its network node server), to send and receive directory search requests, and to obtain management services. An APPN end node can also attach to other end nodes.

**Advanced Peer-to-Peer Networking (APPN) node.** An APPN network node or an APPN end node.

**AID.** Attention identifier.

**AID key.** A control key that generates a host attention interrupt.

**allocate.** (1) An LU 6.2 application programming interface (API) verb used to assign a session to a conversation for the conversation's use. (2) Contrast with *deallocate*.

**all points addressable (APA).** In computer graphics, pertaining to the ability to address and display or not display each picture element (pel) on a display surface.

**AP.** Alternate printer.

**APA.** All points addressable.

**API.** Application programming interface.

**APL.** A programming language requiring the use of a special keyboard to represent various operator symbols.

**application.** A collection of software components used to perform specific types of user-oriented work on a computer.

**application program.** (1) A program written for or by a user that applies to the user's work, such as a program that does inventory control or payroll. (2) A program used to connect and communicate with stations in a network, enabling users to perform application-oriented activities.

**Apply.** A push button that carries out the selected choices in a window without closing the window.

**APPN.** Advanced Peer-to-Peer Networking.

**argument.** A parameter passed between a calling program and a called program.

**ASCII (American National Standard Code for Information Interchange).** The standard code, using a coded character set consisting of 7-bit coded characters (8 bits including parity check), that is used for information interchange among data processing systems, data communication systems, and associated equipment. The ASCII set consists of control characters and graphic characters. (A)

**asynchronous (ASYNCR).** (1) Pertaining to two or more processes that do not depend upon the occurrence of specific events such as common timing signals. (T) (2) Without regular time relationship; unexpected or unpredictable with respect to the execution of program instructions.

**asynchronous request.** In VTAM, a request for an asynchronous operation. Contrast with *synchronous request*.

**atom.** A character string that has been reduced to a unique integer value.

**attention identifier (AID).** A character in a data stream indicating that the user has pressed a key, such as the Enter key, that requests an action by the system.

**attribute.** Variable data that is logically a part of an object and that represents a property of the object. For example, a serial number is an attribute of an equipment object.

**autoskip.** A field defined as protected and numeric. Causes the cursor to skip to the next unprotected field.

## B

**Basic Input/Output System (BIOS).** Code that controls basic hardware operations, such as interactions with diskette drives, hard disk drives, and the keyboard.

**batch.** (1) An accumulation of data to be processed. (2) A group of records or data processing jobs brought together for processing or transmission. (3) Pertaining to activity involving little or no user action. Contrast with *interactive*.

**behavior.** (1) Ideally, a collection of assertions that describe the allowed states that a managed object can assume. An assertion can be a precondition, a postcondition, or an invariant. In practice, the behavior is often an informal description of the semantics of attributes, operations, and notifications. (2) The way in which managed objects, name bindings, attributes, notifications, and operations interact with the actual resources that they model and with each other.

**binary.** Pertaining to the base two system of numbers. The binary digits are 0 and 1. Executable files are

generally in binary format rather than the character string format that text files are composed of.

**BIND.** In SNA, a request to activate a session between two logical units (LUs). See also *session activation request*. Contrast with *UNBIND*.

**BIOS.** (1) Basic Input/Output System. (2) See also *NetBIOS*.

**bit.** Either of the digits 0 or 1 when used in the binary numeration system. (T)

**bracket protocol.** In SNA, a data flow control protocol in which exchanges between two session partners are achieved through the use of brackets, with one partner designated at session activation as the first speaker and the other as the bidder. The bracket protocol involves bracket initiation and termination rules.

**buffer.** (1) A routine or storage used to compensate for a difference in rate of flow of data, or time of occurrence of events, when transferring data from one device to another. (A) (2) A portion of storage used to hold input or output data temporarily.

**byte.** (1) A string that consists of a number of bits, treated as a unit, and representing a character. (T) (2) A binary character operated upon as a unit and usually shorter than a computer word. (A) (3) A group of 8 adjacent binary digits that represent one EBCDIC character.

## C

**call.** (1) The action of bringing a computer program, a routine, or a subroutine into effect, usually by specifying the entry conditions and jumping to an entry point. (I) (A) (2) In data communication, the actions necessary to make a connection between two stations on a switched line. (3) In communications, a conversation between two users. (4) To transfer control to a procedure, program, routine, or subroutine. (5) To attempt to contact a user, regardless of whether the attempt is successful.

**calling.** (1) The process of transmitting selection signals in order to establish a connection between data stations. (I) (A) (2) In X.25 communications, pertaining to the location or user that makes a call.

**Cancel.** A push button that removes a window without applying any changes made in that window.

**Caps Lock.** The personal computer keyboard mode entered after the Caps Lock key is pressed. This mode is indicated by a capital A in the operator information area (OIA). When the Shift key is pressed while in this mode, Caps Lock is temporarily discontinued and the OIA indicator changes. Pressing the Shift key again returns the Caps Lock mode.

**case-sensitive.** Pertaining to the ability to distinguish between uppercase and lowercase letters.

**character cell.** The maximum physical boundary of a character on a display screen.

**character set.** A finite group of characters defined for a keyboard or output device.

**CICS.** Customer Information Control System.

**C language.** A language used to develop software applications in compact, efficient code that can be run on different types of computers with minimal change.

**class.** (1) In object-oriented design or programming, a group of objects that share a common definition and that therefore share common properties, operations, and behavior. Members of the group are called instances of the class. (2) In the AIX operating system, pertaining to the I/O characteristics of a device. System devices are classified as block or character devices.

**client.** (1) A functional unit that receives shared services from a server. (T) (2) A user. (3) In an AIX distributed file system environment, a system that is dependent on a server to provide it with programs or access to programs. (4) Synonymous with *requester*.

**clipboard.** An area of storage provided by the system to hold data temporarily.

**Close.** A choice that removes a window and all of the windows associated with it from the workplace. For example, if a user is performing a task in a window and a message appears, or the user asks for help, both the message and the help windows disappear when the user closes the original window.

**CMS.** Conversational monitor system.

**coaxial cable.** A cable consisting of one conductor, usually a small copper tube or wire, within and insulated from another conductor of larger diameter, usually copper tubing or copper braid.

**code page.** (1) A table that defines a coded character set by assignment of a character meaning to each code point in the table for a language or a country. (2) A mapping between characters and their internal binary representation. (3) An assignment of graphic characters and control function meanings to all code points; for example, assignment of characters and meanings to 256 code points for an 8-bit code, assignment of characters and meanings to 128 code points for a 7-bit code. (4) In the Print Management Facility, a font library member that associates code points and character identifiers. A code page also identifies invalid code points. (5) A particular assignment of hexadecimal identifiers to graphic characters. (6) In AFP support, a font file that associates code points and graphic character identifiers.



**command.** (1) A request from a terminal for the performance of an operation or the execution of a particular program. (2) In SNA, any field set in the transmission header (TH), request header (RH), and sometimes portions of a request unit (RU), that initiates an action or that begins a protocol; for example: (a) Bind Session (session-control request unit), a command that activates an LU-LU session, (b) the change-direction indicator in the RH of the last RU of a chain, (c) the virtual route reset window indicator in an FID4 transmission header.

**command list.** In the NetView program, a list of commands and statements designed to perform a specific function for the user. Command lists can be written in REXX or in the NetView command list language.

**command name.** The first term in a command, usually followed by operands.

**command prompt.** A displayed character or string of characters that indicates that a user may enter a command to be processed.

**Communications Manager/2.** See *Communications Server* and *Personal Communications product family*. The function of the Communications Manager/2 product has been incorporated into the Communications Server product and the Personal Communications product family.

**compile.** (1) To translate all or part of a program expressed in a high-level language into a computer program expressed in an intermediate language, an assembly language, or a machine language. (T) (2) To prepare a machine language program from a computer program written in another programming language by making use of the overall logic structure of the program, or generating more than one computer instruction for each symbolic statement, or both, as well as performing the function of an assembler. (A) (3) To translate a source program into an executable program (an object program). (4) To translate a program written in a high-level programming language into a machine language program.

**compiler.** (1) A program that translates a source program into an executable program (an object program). (2) A program that decodes instructions written as pseudo codes and produces a machine language program to be executed at a later time.

**component.** Hardware or software that is part of a functional unit.

**configuration.** (1) The manner in which the hardware and software of an information processing system are organized and interconnected. (T) (2) The devices and programs that make up a system, subsystem, or network. (3) In Personal Communications, the arrangement of personal computers connected to one or

more host systems by one or more attachment types. Examples are: SDLC, LAN, ASYNCH, X.25, or DFT.

**configure.** To describe to a system the devices, optional features, and programs installed on the system.

**conjunction.** The Boolean operation whose result has the Boolean value 1 if and only if each operand has the Boolean value 1. (I) (A)

**connected.** In VTAM, the state of a physical unit (PU) or a logical unit (LU) that has an active physical path to the host processor containing the system services control point (SSCP) that controls the respective PU or LU.

**connection.** (1) In data communication, an association established between functional units for conveying information. (I) (A) (2) In SNA, the network path that links together two logical units (LUs) in different nodes to enable them to establish communications. (3) In TCP/IP, the path between two protocol applications that provides reliable data stream delivery service. In the Internet, a connection extends from a TCP application on one system to a TCP application on another system.

**connectivity.** (1) The capability of a system or device to be attached to other systems or devices without modification. (T) (2) The capability to attach a variety of functional units without modifying them.

**control block.** (1) A storage area used by a computer program to hold control information. (I) (2) In the IBM Token-Ring Network, a specifically formatted block of information provided from the application program to the Adapter Support Interface to request an operation.

**control character.** A character whose occurrence in a particular context specifies a control function. (T)

**controller.** A device that coordinates and controls the operation of one or more input/output devices, such as workstations, and synchronizes the operation of such devices with the operation of the system as a whole.

**control point (CP).** (1) A component of an APPN or LEN node that manages the resources of that node. In an APPN node, the CP is capable of engaging in CP-CP sessions with other APPN nodes. In an APPN network node, the CP also provides services to adjacent end nodes in the APPN network. (2) A component of a node that manages resources of that node and optionally provides services to other nodes in the network. Examples are a system services control point (SSCP) in a type 5 subarea node, a network node control point (NNCP) in an APPN network node, and an end node control point (ENCP) in an APPN or LEN end node. An SSCP and an NNCP can provide services to other nodes.

**Control Program (CP).** In VM/ESA, a component that manages the resources of a single computer so multiple

computing systems appear to exist. Each of these apparent systems, or virtual machines, is the functional equivalent of an IBM System/370, 370-XA, or ESA computer.

**control unit.** A device that manages the flow of data between personal computers used with Personal Communications and a host system.

**control unit terminal (CUT) mode.** An IBM protocol used for communications with an IBM 3174 or 3274 Control Unit or other appropriate interface unit. In this protocol, a program in the workstation emulates a 3278 or 3879 terminal for a user at a virtual terminal, and the interface unit is responsible for enforcing the protocol.

**conversation.** A logical connection between two transaction programs using an LU 6.2 session. Conversations are delimited by brackets to gain exclusive use of a session.

**conversational monitor system (CMS).** A virtual machine operating system that provides general interactive time sharing, problem solving, and program development capabilities, and operates only under control of the VM control program.

**country code.** In X.25 communications, the 3-digit number that precedes the national terminal number in the network user address for public networks.

**CP.** (1) Control point. (2) In VM, Control Program.

**CS.** Current state.

**Customer Information Control System (CICS).** An IBM licensed program that enables transactions entered at remote terminals to be processed concurrently by user-written application programs. It includes facilities for building, using, and maintaining databases.

**customization.** The process of configuring one or more personal computers connected to a host system by the SDLC, LAN, ASYNCH, X.25, DFT, or other attachment. Customization precedes Personal Communications installation and includes the definition of the sessions to be carried out by Personal Communications.

## D

**data stream.** (1) All information (data and control commands) sent over a data link usually in a single read or write operation. (2) A continuous stream of data elements being transmitted, or intended for transmission, in character or binary-digit form, using a defined format.

**DBCS.** Double-byte character set.

**definition file.** A file loaded by default that contains keyboard and screen color characteristics that can be

adapted for a particular session. The lines of a definition file must be coded according to a strict layout.

**delimiter.** (1) A character used to indicate the beginning and end of a character string. (T) (2) A flag that separates and organizes items of data. (A) (3) A character that groups or separates words or values in a line of input. (4) In the IBM Token-Ring Network, a bit pattern that defines the limits of a frame or token.

**destination.** (1) Any point or location, such as a node, station, or a particular terminal, to which information is to be sent. (2) An external logical unit (LU) or application program to which messages or other data are directed.

**device.** A mechanical, electrical, or electronic contrivance with a specific purpose.

**device driver.** (1) A file that contains the code needed to use an attached device. (2) A program that enables a computer to communicate with a specific peripheral device; for example, a printer, a videodisc player, or a CD drive. (3) A collection of subroutines that control the interface between I/O device adapters and the processor.

**dialog.** (1) The interaction between a user and a computer. (2) In an interactive system, a series of related inquiries and responses similar to a conversation between two people. (3) In the AIXwindows Toolkit, a two-way text interface between an application and its user. The interface takes the form of a collection of widgets and gadgets, including a DialogShell widget, a BulletinBoard widget (or a subclass of a BulletinBoard widget or some other container widget), plus various children, including Label, PushButton, and Text widgets.

**directory.** (1) A table of identifiers and references to the corresponding items of data. (l) (A) (2) A named hierarchical grouping of files in a file system. (3) A database in an APPN node that lists names of resources (in particular, logical units) and records the CP name of the node where each resource is located.

**distributed processing.** Processing that takes place across two or more linked systems.

**DLL.** Dynamic link library.

**DOS.** Disk Operating System.

**DOS session.** A session in which a personal computer operates as a stand-alone computer, running under Disk Operating System (DOS). See *host session*.

**double-byte character set (DBCS).** A set of characters in which each character is represented by 2 bytes. Languages such as Japanese, Chinese, and Korean, which contain more symbols than can be represented by 256 code points, require double-byte character sets. Because each character requires 2 bytes, the typing, display, and printing of DBCS

characters requires hardware and programs that support DBCS. Contrast with *single-byte character set (SBCS)*.

**drop.** In the IBM Cabling System, a cable that runs from a faceplate to the distribution panel in a wiring closet. When the IBM Cabling System is used with the IBM Token-Ring Network, a drop may form part of a lobe. Cables between wiring closets are not classified as drops.

**dynamic.** (1) In programming languages, pertaining to properties that can only be established during the execution of a program; for example, the length of a variable-length data object is dynamic. (l) (2) Pertaining to an operation that occurs at the time it is needed rather than at a predetermined or fixed time.

**dynamic data exchange (DDE).** A protocol that allows applications to exchange data.

**dynamic linking.** In the OS/2 operating system, the delayed connection of a program to a routine until load time or run time.

**dynamic link library (DLL).** A file containing executable code and data bound to a program at load time or run time, rather than during linking. The code and data in a dynamic link library can be shared by several applications simultaneously.

## E

**EBCDIC.** Extended binary-coded decimal interchange code. A coded character set of 256 8-bit characters.

**ECF.** Enhanced Connectivity Facility.

**EGA.** Enhanced graphics adapter.

**EHLLAPI.** Emulator High-Level Language Application Programming Interface.

**element.** (1) A field in the network address. (2) In SNA, the particular resource within a subarea that is identified by an element address. See also *subarea*.

**Emulation Program (EP).** (1) An IBM control program that allows a channel-attached IBM communication controller to emulate the functions of an IBM 2701 Data Adapter Unit, an IBM 2702 Transmission Control, or an IBM 2703 Transmission Control. (2) See also *network control program*.

**emulator.** A program that allows a device to operate as if it were a different type of device. Personal Communications, for example, allows supported personal computers and printers to operate as if they were 3270-series workstations.

**Emulator High-Level Language Application Programming Interface (EHLLAPI).** In Communications Manager/2, an application programming interface that provides programming

access to the area in computer memory that corresponds to the user's screen image (this area in memory is known as the "presentation space").

**Enhanced Connectivity Facility (ECF).** (1) A set of programs used for interconnecting IBM personal computers and IBM System/370 or System/390 host computers operating in the MVS/XA or VM/ESA environment. These ECF programs provide a method for sharing resources between workstations and host systems. (2) An IBM communication utility that provides the ability to share resources between workstations and host systems.

**enhanced graphics adapter (EGA).** An adapter, such as the IBM Enhanced Graphics Adapter, that provides high-resolution graphics, allowing the use of a color display for text processing as well as graphics applications.

**entry point (EP).** (1) The address or label of the first instruction executed on entering a computer program, routine, or subroutine. A computer program, routine, or subroutine may have a number of different entry points, each perhaps corresponding to a different function or purpose. (l) (A) (2) In SNA, a type 2.0, type 2.1, type 4, or type 5 node that provides distributed network management support. It sends network management data about itself and the resources it controls to a focal point for centralized processing, and it receives and executes focal-point initiated commands to manage and control its resources.

**EOF.** End of Field

**EOT.** End of Text

**ER.** Explicit route.

**event.** An occurrence of significance to a task; for example, an SNMP trap, the opening of a window or a submap, or the completion of an asynchronous operation.

**exception response (ER).** In SNA, a protocol requested in the form-of-response-requested field of a request header that directs the receiver to return a response only if the request is unacceptable as received or cannot be processed; that is, a negative response, but not a positive response, can be returned. Contrast with *definite response* and *no response*.

**exit list.** In the OS/2 operating system, a list of subroutines that receive control from the base operating system when a particular process ends, either normally or abnormally.

**EXT.** External trace file.

**extended binary-coded decimal interchange code (EBCDIC).** The standard code, using a character set consisting of 8-bit coded characters, used by Personal



Communications for information interchange between personal computers and a host system.

**extended error code.** An 8-byte data string returned by Query System generated by an internal system error that is used by service personnel for diagnosis.

## F

**fault.** An accidental condition that causes a functional unit to fail to perform its required function. (I) (A)

**feature.** A part of an IBM product that may be ordered separately by the customer.

**field.** (1) An area in a record or panel used to contain data. (2) In the IBM 3270 data stream, a group of consecutive positions on a presentation space having similar characteristics that are defined by a field attribute byte at the beginning of the field. (3) An identifiable area in a window. Examples of fields are: an entry field, into which a user can type or place text, and a field of radio button choices, from which a user can select one choice.

**file transfer.** The transfer of one or more files from one system to another over a data link.

**file type.** In VM/CMS, the second field of the file identifier. The file type can be arbitrary, or of significance to the system (for example, SCRIPT, LIST3270, and NOTEBOOK file types).

**filter.** A device or program that separates data, signals, or material in accordance with specified criteria. (A)

**fixed session-level pacing.** A form of session-level pacing in which the data transfer rate is controlled using fixed pacing-window sizes, which are initialized at session-activation time.

**flag.** (1) To mark an information item for selection for further processing. (T) (2) A character that signals the occurrence of some condition, such as the end of a word. (A) (3) A character or bit sequence that marks an occurrence or boundary, such as the end of a word or the beginning or end of a data transmission block.

**flow.** In NetDA/2, the amount of traffic that can pass through a node, connection, or route in both directions during a given period of time.

**frame.** (1) In Open Systems Interconnection architecture, a data structure pertaining to a particular area of knowledge and consisting of slots that can accept the values of specific attributes and from which inferences can be drawn by appropriate procedural attachments. (T) (2) The unit of transmission in some local area networks, including the IBM Token-Ring Network. It includes delimiters, control characters, information, and checking characters. (3) In SDLC, the

vehicle for every command, every response, and all information that is transmitted using SDLC procedures. (4) A data structure (data frame) composed of fields meeting the field specifications of a type of communication protocol. Frames are used to control data transfer across a data link. (5) In SDLC, a sequence of bits delimited by an opening and closing flag. In X.25 packet switching data networks, frames are composed of 8-bit byte sequences delimited by beginning and ending flags; the frames in X.25 control various functions, data transfer, and transmission checking.

**function call.** An expression that moves the path of execution from the current function to a specified function and evaluates to the return value provided by the called function. A function call contains the name of the function to which control moves and a parenthesized list of values.

## H

**handle.** In the Advanced DOS and OS/2 operating systems, a binary value created by the system that identifies a drive, directory, and file so that the file can be found and opened.

**HD.** Half-duplex.

**header.** (1) System-defined control information that precedes user data. (2) The portion of a message that contains control information for the message such as one or more destination fields, name of the originating station, input sequence number, character string indicating the type of message, and priority level for the message.

**header file.** Synonym for *include file*.

**hexadecimal.** (1) Pertaining to a selection, choice, or condition that has 16 possible different values or states. (I) (2) Pertaining to a fixed-radix numeration system, with radix of 16. (I) (3) Pertaining to a system of numbers to the base 16; hexadecimal digits range from 0 through 9 and A through F, where A represents 10 and F represents 15.

**high-level language (HLL).** A programming language that does not reflect the structure of any particular computer or operating system.

**high-level language application programming interface (HLLAPI).** (1) A software product that supports interaction between a host program and an application program running on a personal computer in terminal emulation (usually 3270 terminal emulation). (2) A programming interface that usually operates in conjunction with an emulator, such as 3270 emulation, and allows interaction using 3270 data stream between a host and a remote application program.

**hiragana.** One of the two common Japanese phonetic alphabets (the other is katakana). In hiragana, each character is represented by 1 byte. See also *kanji*.

**HLLAPI.** High-level language application programming interface.

**host.** (1) In the Internet suite of protocols, an end system. The end system can be any workstation; it does not have to be a mainframe. (2) See *host processor*.

**host code page.** The character code page used by the host system to which a gateway connects.

**host print.** A printer session on a local personal computer directed by the host system.

**host session.** A logical connection that enables a personal computer to communicate with a host system. A session can be identified by LU address, LT number, or session ID. See *DOS session*. See also *logical terminal*.

**host system.** In Personal Communications, the computer linked to one or more personal computers by the SDLC, LAN, ASYNCH, X.25, or DFT attachment.

## I

**ID.** (1) Identifier. (2) Identification.

**inbound.** In communications, data that is received from the network.

**include file.** A text file that contains declarations used by a group of functions, programs, or users. Synonymous with *header file*.

**information (I) format.** A format used for information transfer.

**information (I) frame.** A frame in I format used for numbered information transfer.

**inhibited.** In VTAM, pertaining to a logical unit (LU) that has indicated to its system services control point (SSCP) that it is temporarily not ready to establish LU-LU sessions. An initiate request for a session with an inhibited LU will be rejected by the SSCP. The LU can separately indicate whether this applies to its ability to act as a primary logical unit (PLU) or a secondary logical unit (SLU).

**INITIATE.** A network services request sent from a logical unit (LU) to a system services control point (SSCP) requesting that an LU-LU session be established.

**input/output (I/O).** (1) Pertaining to input, output, or both. (A) (2) Pertaining to a device, process, or channel involved in data input, data output, or both.

**INT.** Internal trace table.

**interactive.** Pertaining to the exchange of information between a user and a computer.

**interface.** (1) A shared boundary between two functional units, defined by functional characteristics, signal characteristics, or other characteristics, as appropriate. The concept includes the specification of the connection of two devices having different functions. (T) (2) Hardware, software, or both, that links systems, programs, or devices.

**interrupt.** A suspension of a process, such as execution of a computer program caused by an external event, and performed in such a way that the process can be resumed. (A)

**I/O.** Input/output.

## J

**JISCII.** Japanese Industry Standard Code for Information Interchange. A code used by IBM Personal Computers in Japan. It contains Japanese Industry Standard (JIS) C 6226 "Kanji code for exchanging information" (JIS Kanji set) and user unique characters.

**jump.** To switch to the logical terminal session specified.

## K

**katakana.** One of the two common Japanese phonetic alphabets (the other is hiragana). In katakana, each character is represented by 1 byte. Katakana is primarily used to write foreign words phonetically. See also *kanji*.

**keylock.** In Communications Manager/2, a function that controls access to configuration data and some advanced functions. See also *lock*, *master key*, and *service key*.

**keyword.** (1) In programming languages, a lexical unit that, in certain contexts, characterizes some language construct; for example, in some contexts, IF characterizes an if-statement. A keyword normally has the form of an identifier. (I) (2) One of the predefined words of an artificial language. (A) (3) A significant and informative word in a title or document that describes the content of that document.

## L

**layer.** (1) In network architecture, a group of services that is complete from a conceptual point of view, that is one out of a set of hierarchically arranged groups, and that extends across all systems that conform to the network architecture. (T) (2) In the Open Systems Interconnection reference model, one of seven conceptually complete, hierarchically arranged groups of services, functions, and protocols, that extend across all

open systems. (T) (3) In SNA, a grouping of related functions that are logically separate from the functions in other groups. Implementation of the functions in one layer can be changed without affecting functions in other layers.

**LEN.** Low-entry networking.

**line.** The portion of a data circuit external to data circuit-terminating equipment (DCE), that connects the DCE to a data switching exchange (DSE), that connects a DCE to one or more other DCEs, or that connects a DSE to another DSE. (I)

**link.** (1) The combination of the link connection (the transmission medium) and two link stations, one at each end of the link connection. A link connection can be shared among multiple links in a multipoint or token-ring configuration. (2) To interconnect items of data or portions of one or more computer programs: for example, the linking of object programs by a linkage editor, linking of data items by pointers. (T)

**link connection.** The physical equipment providing two-way communication between one link station and one or more other link stations; for example, a telecommunication line and data circuit-terminating equipment (DCE).

**link level.** A part of Recommendation X.25 that defines the link protocol used to get data into and out of the network across the full-duplex link connecting the subscriber's machine to the network node. LAP and LAPB are the link access protocols recommended by the CCITT.

**load-time dynamic linking.** A mechanism that enables program modules and their external references to dynamic-link libraries to be loaded into memory when the program is loaded.

**local.** (1) Pertaining to a device accessed directly without use of a telecommunication line. (2) Contrast with *remote*. (3) Synonym for *channel-attached*.

**local copy.** A printer session initiated by a personal computer user or host that reproduces a presentation space with all supported graphics.

**lock.** (1) The means by which integrity of data is ensured by preventing more than one user from accessing or changing the same data or object at the same time. (2) In Communications Manager/2, a password-protection system that can be used to prevent access to some advanced functions. See also *keylock*.

**logical terminal.** (1) A destination with a name that is related to one or more physical terminals. (2) The definition of a specific 3270 or 5250 emulation session.

**logical unit (LU).** A type of network accessible unit that enables users to gain access to network resources and communicate with each other.

**low-entry networking (LEN).** A capability of nodes to attach directly to one another using basic peer-to-peer protocols to support multiple and parallel sessions between logical units.

**low-entry networking (LEN) end node.** A LEN node receiving network services from an adjacent APPN network node.

**low-entry networking (LEN) node.** A node that provides a range of end-user services, attaches directly to other nodes using peer protocols, and derives network services implicitly from an adjacent APPN network node, that is, without the direct use of CP-CP sessions.

**LU.** Logical unit.

**LU-LU session.** A logical connection between two logical units (LUs) in an SNA network that typically provides communication between two users.

## M

**maintenance analysis procedure (MAP).** A maintenance document that gives an IBM service representative a step-by-step procedure for tracing a symptom to the cause of a failure.

**manager.** (1) In systems management, a user that, for a particular interaction, has assumed a manager role. (2) An entity that monitors or controls one or more managed objects by (a) receiving notifications regarding the objects and (b) requesting management operations to modify or query the objects. (3) A system that assumes a manager role.

**map.** In NetView for AIX, a database represented by a set of related submaps that provide a graphical and hierarchical presentation of a network and its systems.

**MAP.** Maintenance analysis procedure.

**mapping.** The process of converting data that is transmitted in one format by the sender into the data format that can be accepted by the receiver.

**matching.** In MPTN architecture, pertaining to the relationship between peer transport users or peer transport providers that use the same user protocols or the same transport protocols.

**medium.** (1) A physical carrier of electrical energy. (2) A physical material in or on which data may be represented.

**module.** A program unit that is discrete and identifiable with respect to compiling, combining with other units, and loading; for example, the input to or output from an assembler, compiler, linkage editor, or executive routine. (A)

**module definition file.** In the OS/2 operating system, a file, used at link-edit time, that describes the attributes for the executable file being built (for example, load-on-call or preload attributes for segments).

**monitor.** (1) A device that observes and records selected activities within a data processing system for analysis. Possible uses are to indicate significant departure from the norm, or to determine levels of utilization of particular functional units. (T) (2) Software or hardware that observes, supervises, controls, or verifies operations of a system. (A) (3) The function required to initiate the transmission of a token on the ring and to provide soft-error recovery in case of lost tokens, circulating frames, or other difficulties. The capability is present in all ring stations. (4) In the NetView Graphic Monitor Facility, to open a view that can receive status changes from the NetView program. Problem determination and correction can be performed directly from the view. Contrast with *browse*.

**MVS.** Multiple Virtual Storage. Implies MVS/390, MVS/XA, and MVS/ESA.

## N

**NA.** Not applicable. When this appears in a calling parameter position, it means that PC400 EHLAPI does not require this parameter to perform the specific function.

**national language support (NLS).** The modification or conversion of a United States English product to conform to the requirements of another language or country. This can include the enabling or retrofitting of a product and the translation of nomenclature, machine-readable information (MRI), or documentation of a product. NLS is also known as "internationalization."

**native.** In MPTN architecture, pertaining to the relationship between a transport user and a transport provider that are both based on the same transport protocol.

**NC.** Network control.

**network.** (1) An arrangement of nodes and connecting branches. (T) (2) A configuration of data processing devices and software connected for information interchange. (3) A group of nodes and the links interconnecting them.

**network control (NC).** In SNA, a request/response unit (RU) category used for requests and responses exchanged between physical units (PUs) for such purposes as activating and deactivating explicit and virtual routes and sending load modules to adjust peripheral nodes.

**NLS.** National language support.

**NN.** Network node.

**no response.** In SNA, a protocol requested in the form-of-response-requested field of the request header that directs the receiver of the request not to return any response, regardless of whether or not the request is received and processed successfully.

**normal stop.** In Communications Manager/2, stopping communications after current functions (for example, file transfer) have completed.

**notification.** An unscheduled, spontaneously generated report of an event that has occurred.

**NOTIFY.** A network services request that is sent by a system services control point (SSCP) to a logical unit (LU) to inform the LU of the status of a procedure requested by the LU.

## O

**object.** (1) In object-oriented design or programming, an abstraction consisting of data and the operations associated with that data. See also *class*. (2) An item that a user can manipulate as a single unit to perform a task. An object can appear as text, an icon, or both.

**OEM.** Original equipment manufacturer.

**Off.** A choice that appears in the cascaded menu from the Refresh choice. It sets the refresh function to off.

**offset.** The number of measuring units from an arbitrary starting point in a record, area, or control block, to some other point.

**OIA.** Operator information area.

**On.** A choice that appears in a cascaded menu from the Refresh choice. It immediately refreshes the view in a window.

**open.** (1) A break in an electrical circuit. (2) To make an adapter ready for use.

**Open.** A choice that leads to a window in which users can select the object they want to open.

**operand.** (1) An entity on which an operation is performed. (I) (2) That which is operated upon. An operand is usually identified by an address part of an instruction. (A) (3) Information entered with a command name to define the data on which a command processor operates and to control the execution of the command processor.

**operating system (OS).** Software that controls the execution of programs and that may provide services such as resource allocation, scheduling, input/output control, and data management. Although operating systems are predominantly software, partial hardware implementations are possible. (T)



**operation.** In object-oriented design or programming, a service that can be requested at the boundary of an object. Operations include modifying an object or disclosing information about an object.

**operator.** (1) In a language statement, the lexical entity that indicates the action to be performed on operands. (2) A person or program responsible for managing activities controlled by a given piece of software such as MVS, the NetView program, or IMS. (3) A person who operates a device. (4) A person who keeps a system running.

**operator information area (OIA).** The area near the bottom of the display area where terminal or system status information is displayed.

**operator station task (OST).** The NetView task that establishes and maintains the online session with the network operator. There is one operator station task for each network operator who logs on to the NetView program. See *NetView-NetView task*.

**original equipment manufacturer (OEM).** A manufacturer of equipment that may be marketed by another manufacturer.

**OS.** Operating system.

## P

**parameter.** (1) A variable that is given a constant value for a specified application and that may denote the application. (I) (A) (2) In Basic CUA architecture, a variable used in conjunction with a command to affect its result. (3) An item in a menu for which the user specifies a value or for which the system provides a value when the menu is interpreted. (4) Data passed to a program or procedure by a user or another program, namely as an operand in a language statement, as an item in a menu, or as a shared data structure.

**parent.** A process that has spawned a child process using the fork primitive.

**path.** (1) In a network, any route between any two nodes. A path may include more than one branch. (T) (2) The series of transport network components (path control and data link control) that are traversed by the information exchanged between two network accessible units.

**path control (PC).** The function that routes message units between network accessible units in the network and provides the paths between them. It converts the basic information units (BIUs) from transmission control (possibly segmenting them) into path information units (PIUs) and exchanges basic transmission units containing one or more PIUs with data link control. Path control differs by node type: some nodes (APPN nodes,

for example) use locally generated session identifiers for routing, and others (subarea nodes) use network addresses for routing.

**PC.** (1) Path control. (2) Personal Communications.

**physical connection.** (1) A connection that establishes an electrical circuit. (2) A point-to-point or multipoint connection. (3) Synonymous with *connection*.

**physical unit (PU).** The component that manages and monitors the resources (such as attached links and adjacent link stations) associated with a node, as requested by an SSCP via an SSCP-PU session. An SSCP activates a session with the physical unit in order to indirectly manage, through the PU, resources of the node such as attached links. This term applies to type 2.0, type 4, and type 5 nodes only.

**physical unit (PU) services.** In SNA, the components within a physical unit (PU) that provide configuration services and maintenance services for SSCP-PU sessions.

**PM.** Presentation Manager.

**pointer.** (1) A data element that indicates the location of another data element. (T) (2) An identifier that indicates the location of an item of data. (A)

**pop.** To remove an item from the top of a pushdown list. Contrast with *push*.

**POP.** Post Office Protocol.

**POR.** Power-on reset function.

**post.** (1) To enter a unit of information on a record. (2) To note the occurrence of an event. (3) To add information to a record in order to keep the record current.

**Post Office Protocol (POP).** A protocol used for exchanging network mail and accessing mailboxes.

**power-on reset (POR) function.** A function that allows the user to reset all logical terminals. The key sequence for POR is Ctrl+Pause using the Enhanced or Space Saving keyboards. Otherwise, the sequence is Ctrl+F2.

**Prepare.** A presentation services header that flows as part of commit processing, indicating the partner has begun the first phase of the two-phase commit process.

**presentation space.** (1) A conceptual two-dimensional surface in storage on which data for a portion of the display surface is represented. (2) The space that contains the device-independent definition of a picture. (3) In the context of the Emulator High-Level Language Application Programming Interface (EHLAPI), the area in computer memory that corresponds to the user's screen image. (4) The host display space for the

window. It is the entire window of data, which can exceed the boundaries of a display screen's viewing area.

**presentation space ID (PSID).** In Communications Manager/2, synonym for *short name*.

**private application.** An application maintained for use only on one computer or user, that is not available on the network for other users.

**problem determination.** The process of determining the source of a problem; for example, a program component, machine failure, telecommunication facilities, user or contractor-installed programs or equipment, environmental failure such as a power loss, or user error.

**procedure.** In a programming language, a block, with or without formal parameters, whose execution is invoked by means of a procedure call. (I)

**process.** (1) To perform operations on data in a process. (I) (A) (2) In data processing, the course of events that occurs during the execution of all or part of a program. (T) (3) A course of the events defined by its purpose or by its effect, achieved under given conditions. (4) Any operation or combination of operations on data. (5) A function being performed or waiting to be performed.

**processor.** In a computer, a functional unit that interprets and executes instructions. A processor consists of at least an instruction control unit and an arithmetic and logic unit. (T)

**product-set identification (PSID).** (1) In SNA, a technique for identifying the hardware and software products that implement a network component. (2) A management services common subvector that transports the information described in definition (1).

**programmed operator.** The Emulator High-Level Language Application Programming Interface (EHLAPI) application program that performs and monitors activities in a workstation presentation space. Contrast with *terminal operator*.

**protected field.** A field that holds data for viewing; the data cannot be changed (at the current screen) by the user.

**protocol.** (1) A set of semantic and syntactic rules that determine the behavior of functional units in achieving communication. (I) (2) In Open Systems Interconnection architecture, a set of semantic and syntactic rules that determine the behavior of entities in the same layer in performing communication functions. (T) (3) In SNA, the meanings of, and the sequencing rules for, requests and responses used for managing the network, transferring data, and synchronizing the states of network components.

**PSID.** Presentation space ID.

**PU.** Physical unit.

**PUT.** Program update tape.

**PVC.** Permanent virtual circuit.

## Q

**queue.** (1) A list constructed and maintained so that the next data element to be retrieved is the one stored first. (T) (2) A line or list of items waiting to be processed; for example, work to be performed or messages to be displayed. (3) To arrange in or form a queue.

## R

**RAM.** Random access memory. (A)

**random access memory (RAM).** A storage device into which data is entered and from which data is retrieved in a nonsequential manner.

**Rapid Transport Protocol (RTP).** A connection-oriented, full-duplex transport protocol for carrying session traffic over High-Performance Routing (HPR) routes.

**record.** A set of data treated as a unit. (T)

**remote.** (1) Pertaining to a system, program, or device that is accessed through a telecommunication line. (2) Synonym for *link-attached*. (3) Contrast with *local*.

**requester.** A computer that accesses shared network resources through a server. Synonym for *client*.

**resource.** Any facility of a computing system or operating system required by a job or task, and including main storage, input/output devices, the processing unit, data sets, and control or processing programs.

**resource takeover.** In VTAM, an action initiated by a network operator to transfer control of resources from one domain to another without breaking the connections or disrupting existing LU-LU sessions on the connection.

**response.** In data communication, a reply represented in the control field of a response frame. It advises the primary or combined station of the action taken by the secondary or other combined station to one or more commands.

**response file.** A file that contains a set of predefined answers to questions asked by a program and that is used in place of user dialog. methodology.

**response time monitor.** A function that measures and displays the host response time

**Restructured Extended Executor (REXX).** A general-purpose, procedural language for end-user personal programming, designed for ease by both casual general users and computer professionals. It is also useful for application macros. REXX includes the capability of issuing commands to the underlying operating system from these macros and procedures. Features include powerful character-string manipulation, automatic data typing, manipulation of objects familiar to people, such as words, numbers, and names, and built-in interactive debugging.

**return code.** (1) A code used to influence the execution of succeeding instructions. (A) (2) A value returned to a program to indicate the results of an operation requested by that program.

**REXX.** Restructured Extended Executor.

**route.** (1) An ordered sequence of nodes and transmission groups (TGs) that represent a path from an origin node to a destination node traversed by the traffic exchanged between them. (2) The path that network traffic uses to get from source to destination.

**router.** (1) A computer that determines the path of network traffic flow. The path selection is made from several paths based on information obtained from specific protocols, algorithms that attempt to identify the shortest or best path, and other criteria such as metrics or protocol-specific destination addresses. (2) An attaching device that connects two LAN segments, which use similar or different architectures, at the reference model network layer. (3) In OSI terminology, a function that determines a path by which an entity can be reached. (4) In TCP/IP, synonymous with *gateway*.

**routing.** (1) The process of determining the path to be used for transmission of a message over a network. (T) (2) The assignment of the path by which a message is to reach its destination. (3) In SNA, the forwarding of a message unit along a particular path through a network, as determined by parameters carried in the message unit, such as the destination network address in a transmission header.

**routing table.** A collection of routes used to direct datagram forwarding or to establish a connection. The information is passed among routers to identify network topology and destination feasibility.

**RTP.** Rapid Transport Protocol.

## S

**SBCS.** Single-byte character set.

**SDLC.** Synchronous Data Link Control.

**segment.** (1) A section of cable between components or devices. A segment may consist of a single patch cable, several patch cables that are connected, or a

combination of building cable and patch cables that are connected. (2) In Internet communications, the unit of transfer between TCP functions in different machines. Each segment contains control and data fields; the current byte-stream position and actual data bytes are identified along with a checksum to validate received data.

**segmentation.** A process by which path control (PC) divides basic information units (BIUs) into smaller units, called BIU segments, to accommodate smaller buffer sizes in adjacent nodes. Both segmentation and segment assembly are optional PC features. The support for either or both is indicated in the BIND request and response.

**semaphore.** An indicator used to control access to a file; for example, in a multiuser application, a flag that prevents simultaneous access to a file.

**sequence number.** (1) In communications, a number assigned to a particular frame or packet to control the transmission flow and receipt of data. (2) A numerical value assigned by VTAM to each message exchanged between two nodes. The value (one for messages sent from the application program to the logical unit and another for messages sent from the logical unit to the application program) increases by one for each successive message transmitted unless it is reset by the application program with a set and test sequence numbers (STSN) indicator.

**serial.** (1) Pertaining to a process in which all events occur one after the other; for example, serial transmission of the bits of a character according to V24 CCITT protocol. (T) (2) Pertaining to the sequential or consecutive occurrence of two or more related activities in a single device or channel. (A) (3) Pertaining to the sequential processing of the individual parts of a whole, such as the bits of a character or the characters of a word, using the same facilities for successive parts. (A)

**server.** (1) A functional unit that provides shared services to workstations over a network; for example, a file server, a print server, a mail server. (T) (2) In a network, a data station that provides facilities to other stations; for example, a file server, a print server, a mail server. (A) (3) In the AIX operating system, an application program that usually runs in the background and is controlled by the system program controller. (4) In the Enhanced X-Windows Toolkit, a program that provides the basic windowing mechanism. It handles interprocess communication (IPC) connections from clients, demultiplexes graphics requests onto screens, and multiplexes input back to clients.

**Server-Requester Programming Interface (SRPI).**

An IBM application programming interface (API) used by requester and server programs to communicate with the personal computer or host routers.

**service coordinator.** The person in your organization responsible for answering hardware and software computing questions.

**service point (SP).** An entry point that supports applications that provide network management for resources not under the direct control of itself as an entry point. Each resource is either under the direct control of another entry point or not under the direct control of any entry point. A service point accessing these resources is not required to use SNA sessions (unlike a focal point). A service point is needed when entry point support is not yet available for some network management function.

**session.** (1) In network architecture, for the purpose of data communication between functional units, all the activities which take place during the establishment, maintenance, and release of the connection. (T) (2) A logical connection between two network accessible units (NAUs) that can be activated, tailored to provide various protocols, and deactivated, as requested. Each session is uniquely identified in a transmission header (TH) accompanying any transmissions exchanged during the session. (3) A logical connection between a server and a requester that was initiated by a successful request for a shared resource. See also *host session* and *DOS session*.

**session ID.** An alphabetic ID (*a* through *h*) assigned by Personal Communications to each session or screen. This applies to all types of host sessions and is used in file transfers. See also *short name*.

**session parameters.** In SNA, the parameters that specify or constrain the protocols (such as bracket protocol and pacing) for a session between two network accessible units.

**session services (SS).** One of the types of network services in the control point (CP) and in the logical unit (LU). These services provide facilities for an LU or a network operator to request that a control point (an ENCP, NNCP, or SSCP) assist with initiating or terminating sessions between logical units. Assistance with session termination is needed only by SSCP-dependent LUs.

**shift-in character (SI).** A code extension character used to terminate a sequence that has been introduced by the shift-out character to make effective the graphic characters of the standard character set. (I) (A)

**shift-out character (SO).** A code extension character that substitutes for the graphic characters of the standard character set an alternative set of graphic characters upon which an agreement has been arrived at or that has been designated using code extension procedures. (I) (A)

**short name.** (1) In Personal Communications, a character displayed in column 7 of the operator information area that shows the session ID. See also

*session ID* and *operator information area*. (2) In Communications Manager/2, the one-letter name (A through Z) of the presentation space or emulation session. Synonymous with *presentation space ID (PSID)* and *short-session ID*.

**short-session ID.** In Communications Manager/2, synonym for *short name*.

**SI.** The shift-in character. (I) (A)

**SN.** Subarea node.

**SNA.** Systems Network Architecture.

**SO.** The shift-out character. (I) (A)

**SP.** Service point.

**SRPI.** Server-Requester Programming Interface.

**SS.** Session services.

**SSCP.** System services control point.

**SSCP-LU session.** In SNA, a session between a system services control point (SSCP) and a logical unit (LU). The session enables the LU to request the SSCP to help initiate LU-LU sessions.

**statement.** A language syntactic unit consisting of an operator, or other statement identifier, followed by one or more operands.

**station.** An input or output point of a system that uses telecommunication facilities; for example, one or more systems, computers, terminals, devices, and associated programs at a particular location that can send or receive data over a telecommunication line.

**stream.** (1) To send data from one device to another. (2) See *data stream*.

**subarea node (SN).** A node that uses network addresses for routing and maintains routing tables that reflect the configuration of the network. Subarea nodes can provide gateway function to connect multiple subarea networks, intermediate routing function, and boundary function support for peripheral nodes. Type 4 and type 5 nodes can be subarea nodes.

**subarea PU.** In SNA, a physical unit in a subarea node.

**subdirectory.** A directory contained within another directory in a file system hierarchy.

**subsystem.** A secondary or subordinate system, usually capable of operating independently of, or asynchronously with, a controlling system. (T)

**SVC.** Switched virtual circuit.



**switched virtual circuit (SVC).** An X.25 circuit that is dynamically established when needed. The X.25 equivalent of a switched line.

**synchronous.** (1) Pertaining to two or more processes that depend upon the occurrence of specific events such as common timing signals. (T) (2) Occurring with a regular or predictable time relationship.

**Synchronous Data Link Control (SDLC).** A discipline conforming to subsets of the Advanced Data Communication Control Procedures (ADCCP) of the American National Standards Institute (ANSI) and High-level Data Link Control (HDLC) of the International Organization for Standardization, for managing synchronous, code-transparent, serial-by-bit information transfer over a link connection. Transmission exchanges may be duplex or half-duplex over switched or nonswitched links. The configuration of the link connection may be point-to-point, multipoint, or loop. (I)

**system.** In data processing, a collection of people, machines, and methods organized to accomplish a set of specific functions. (I) (A)

**system configuration.** A process that specifies the devices and programs that form a particular data processing system.

**system services control point (SSCP).** A component within a subarea network for managing the configuration, coordinating network operator and problem determination requests, and providing directory services and other session services for users of the network. Multiple SSCPs, cooperating as peers with one another, can divide the network into domains of control, with each SSCP having a hierarchical control relationship to the physical units and logical units within its own domain.

**system services control point (SSCP) domain.** The system services control point, the physical units (PUs), the logical units (LUs), the links, the link stations, and all the resources that the SSCP has the ability to control by means of activation and deactivation requests.

**Systems Network Architecture (SNA).** The description of the logical structure, formats, protocols, and operational sequences for transmitting information units through, and controlling the configuration and operation of, networks. The layered structure of SNA allows the ultimate origins and destinations of information, that is, the users, to be independent of and unaffected by the specific SNA network services and facilities used for information exchange.

## T

**table.** A repository for data that NetDA/2 uses to design a network. Each table contains information related to the network.

**Task-Related User Exit (TRUE).** A CICS module used for invoking resource managers that are outside of CICS. A TRUE is one of the components of CICS sockets.

**terminal emulator.** See *emulator*.

**terminal operator.** The user of an Emulator High-Level Language Application Programming Interface (EHLAPI) application program. Contrast with *programmed operator*.

**TERMINATE.** In SNA, a request unit that is sent by a logical unit (LU) to its system services control point (SSCP) to cause the SSCP to start a procedure to end one or more designated LU-LU sessions.

**TH.** Transmission header.

**thread.** In the OS/2 operating system, the smallest unit of operation to be performed within a process.

**timeout.** (1) An event that occurs at the end of a predetermined period of time that began at the occurrence of another specified event. (I) (2) A time interval allotted for certain operations to occur; for example, response to polling or addressing before system operation is interrupted and must be restarted.

**Time Sharing Option (TSO).** An option of the MVS operating system that provides interactive time sharing from remote terminals.

**token.** (1) In a local area network, the symbol of authority passed successively from one data station to another to indicate the station temporarily in control of the transmission medium. Each data station has an opportunity to acquire and use the token to control the medium. A token is a particular message or bit pattern that signifies permission to transmit. (T) (2) In LANs, a sequence of bits passed from one device to another along the transmission medium. When the token has data appended to it, it becomes a frame.

**token ring.** (1) According to IEEE 802.5, network technology that controls media access by passing a token (special packet or frame) between media-attached stations. (2) A FDDI or IEEE 802.5 network with a ring topology that passes tokens from one attaching ring station (node) to another.

**trace.** (1) A record of the execution of a computer program. It exhibits the sequences in which the instructions were executed. (A) (2) For data links, a record of the frames and bytes transmitted or received.

**transaction program (TP).** A program that processes transactions in an SNA network. There are two kinds of transaction programs: application transaction programs and service transaction programs. See also *conversation*.

**transmission header (TH).** Control information, optionally followed by a basic information unit (BIU) or a BIU segment, that is created and used by path control to route message units and to control their flow within the network.

**trap.** In the Simple Network Management Protocol (SNMP), a message sent by a managed node (agent function) to a management station to report an exception condition.

**TRUE.** Task-Related User Exit.

**TSO.** Time Sharing Option.

## U

**UA.** Unnumbered acknowledgment.

**UNBIND.** In SNA, a request to deactivate a session between two logical units (LUs).

**unprotected field.** A field that is available for the user to enter or modify data.

**UTC.** Coordinated universal time.

## V

**value.** (1) A specific occurrence of an attribute; for example, "blue" for the attribute "color." (T) (2) A quantity assigned to a constant, a variable, a parameter, or a symbol.

**variable.** (1) In programming languages, a language object that may take different values, one at a time. The values of a variable are usually restricted to a certain data type. (I) (2) A quantity that can assume any of a given set of values. (A) (3) A name used to represent a data item whose value can be changed while the program is running.

**VGA.** Video graphics adapter.

**video graphics adapter (VGA).** A computer adapter that provides high-resolution graphics and a total of 256 colors. See also *enhanced graphics adapter (EGA)*.

**virtual machine (VM).** (1) A virtual data processing system that appears to be at the exclusive disposal of a particular user, but whose functions are accomplished

by sharing the resources of a real data processing system. (T) (2) In VM/ESA, the virtual processors, virtual storage, virtual devices, and virtual channel subsystem allocated to a single user. A virtual machine also includes any expanded storage dedicated to it.

**Virtual Machine/Conversational Monitoring System (VM/CMS).** A time sharing system control program that manages the resources of an IBM System/370 or System/390 such that multiple remote terminal users have a functioning simulation of a computing system at their disposal. The Conversational Monitoring System provides general time sharing, development, and problem-solving facilities.

**Virtual Telecommunications Access Method (VTAM).** An IBM licensed program that controls communication and the flow of data in an SNA network. It provides single-domain, multiple-domain, and interconnected network capability.

**VM.** Virtual machine.

**VM/CMS.** Virtual Machine/Conversational Monitoring System.

**VTAM.** (1) Virtual Telecommunications Access Method. (2) Synonymous with *ACF/VTAM*.

## W

**window.** (1) A portion of a display surface in which display images pertaining to a particular application can be presented. Different applications can be displayed simultaneously in different windows. (A) (2) An area with visible boundaries that presents a view of an object or with which a user conducts a dialog with a computer system. (3) In data communication, the number of data packets a data terminal equipment (DTE) or data circuit-terminating equipment (DCE) can send across a logical channel before waiting for authorization to send another data packet. The window is the main mechanism of pacing, or flow control, of packets.

**window size.** The specified number of frames of information that can be sent before receiving an acknowledgment response.

**WinSock application programming interface (API).** A socket-style transport interface developed for the Windows family of operating systems.

# Index

## Numerics

01, Connect Presentation Space 35  
02, Disconnect Presentation Space 68  
03, Send Key 75, 110, 132, 138  
04, Wait 137  
05, Copy Presentation Space 52  
06, Search Presentation Space 106, 138  
07, Query Cursor Location 86  
08, Copy Presentation Space to String 57  
09, Set Session Parameters 119  
10, Query Sessions 92  
101, Connect Window Services 34  
    Connect Window Services (101) 34  
102, Disconnect Window Service 68  
103, Query Window Coordinates 89  
104, Window Status 138  
105, Change Switch List LT Name 31  
106, Change PS Window Name 30  
11, Reserve 103  
110, Start Playing Macro 134  
12, Release 102, 103  
13, Copy OIA 44  
14, Query Field Attribute 86  
15, Copy String to Presentation Space 64  
16/32 bit considerations 21  
18, Pause 81, 136  
20, Query System 94  
21, Reset System 103, 119  
22, Query Session Status 39, 91  
23, Start Host Notification 81, 88, 129  
24, Query Host Update 82, 88, 136  
25, Stop Host Notification 136  
30, Search Field 104, 138  
31, Find Field Position 40, 71  
32, Find Field Length 40, 69  
32-bit presentation space IDs 11  
3270 terminal emulation 360  
33, Copy String to Field 62  
34, Copy Field to String 39  
40, Set Cursor 118  
41, Start Close Intercept 127  
42, Query Close Intercept 83  
43, Stop Close Intercept 135  
50, Start Keystroke Intercept 132  
51, Get Key 73, 83, 132  
52, Post Intercept Status 83, 132  
53, Stop Keystroke Intercept 136  
61, Lock PMSVC API 80  
90, Send File 108  
91, Receive File 100  
99, Convert Position or Convert RowCol 37

## A

Allocate Communications Buffer (123) 29  
applications  
    error codes 389  
    using SRPI 363

ASCII characters 18  
ASCII Mnemonics 17  
ASCII mnemonics 18  
ASCII Mnemonics  
    general 18  
    get key (51) function 19  
    send key (3) function 19  
Asynchronous Functions, WinHLLAPI 147  
ATTRB 121  
attribute bytes 39, 52, 57, 62, 65, 121  
AUTORESET 123

## B

beep 83  
BLANK 124  
Blocking Routines 155  
buffer size 363

## C

C language  
    init \_ send \_ req \_ parms 364  
    interface 364  
    record definition 365  
    requesters 364  
    send \_ request 364  
    syntax 364  
call (input) parameters  
    general 27  
call/return 358  
calls, prerequisite 27  
Change Menu Item 226, 306, 456  
Change PS Window Name (106) 30  
Change Switch List LT Name (105) 31  
character, escape 19, 74, 111, 122  
characters, ASCII 18  
communication services functions  
    Receive File (91) 100  
    Send File (90) 108  
Communications Manager  
    applications 363  
Communications Manager/2, Compatibility with 381  
Compatibility with Communications Manager/2 381  
Compatibility with Personal Communications V4.1 with  
    Windows 3.1 379  
compiling and linking 9, 10  
Connect for Structured Fields (120) 32  
Connect Presentation Space (1) 35, 110  
    functions where not required 36  
    interaction with disconnect 12  
Connect Window Services (101) 34  
Convert Position or Convert RowCol (99) 37  
Copy Field to String (34) 24, 39  
copy functions  
    Copy Field to String (34) 39  
    Copy OIA (13) 44  
    Copy Presentation Space (5) 52

- copy functions *(continued)*
  - Copy Presentation Space to String (8) 57
  - Copy String to Field (33) 62
  - Copy String to Presentation Space (15) 64
- Copy OIA (13) 23, 44
- Copy Presentation Space (5) 52
- Copy Presentation Space to String (8) 23, 57
- Copy String to Field (33) 24, 62
- Copy String to Presentation Space (15) 64
- CPRB (Connectivity Programming Request Block)
  - storage 363
- create menu item 232, 311, 461
- critical sections 3
- cross platform support 2
- cursor movement 24

## D

- data structures 7
- DDE data items
  - LU Topic 169
  - Session Topic 168
  - System Topic 168
- DDE data items, 16-bit
  - LU Topic 398
  - Session Topic 398
  - System Topic 398
- DDE data items, OS/2
  - LU Topic, OS/2 246
  - Session Topic, OS/2 246
  - System Topic, OS/2 245
- DDE data items in a 16-bit environment 397
- DDE Functions in a 16-Bit Environment 397
  - Find Field 400
  - function list 398
  - Get Keystrokes 401
  - Get Mouse Input 402
  - Get Number of Close Requests 405
  - Get Operator Information Area 406
  - Get Partial Presentation Space 406
  - Get Presentation Space 409
  - Get Session Status 411
  - Get System Configuration 412
  - naming conventions for parameters 399
  - Set Cursor Position 428
  - Set Mouse Intercept Condition 429
  - Set Presentation Space Service Condition 431
  - Set Session Advise Condition 433
  - Set Structured Field Service Condition 434
  - Start Close Intercept 434
  - Start Keystroke Intercept 436
  - Start Mouse Input Intercept 437
  - Start Read SF 441
  - Start Session Advise 442
  - Stop Close Intercept 443
  - Stop Keystroke Intercept 444
  - Stop Mouse Input Intercept 444
  - Stop Read SF 445
  - Stop Session Advise 446
  - summary of DDE functions in a 16-bit environment 448
  - Terminate Session Conversation 446

- DDE Functions in a 16-Bit Environment *(continued)*
  - Terminate Structured Field Conversation 447
  - Terminate System Conversation 447
  - Write SF 448
- DDE functions in a Windows 32-bit environment 167
  - DDE data items, Windows 32-bit 167
    - LU Topic 169
    - Session Topic 168
    - System Topic 168
  - Find Field 172
  - function list 169
  - Get Keystrokes 174
  - Get Mouse Input 175
  - Get Number of Close Requests 178
  - Get Operator Information Area 179
  - Get Partial Presentation Space 180
  - Get Presentation Space 182
  - Get Session Status 184
  - Get System Configuration 186
  - Get System Formats 187
  - Get System Status 187
  - Get System Systems 188
  - Get System Topics 189
  - Get Trim Rectangle 190
  - Initiate Session Conversation 190
  - Initiate Structured Field Conversation 191
  - Initiate System Conversation 192
  - naming conventions for parameters 170
  - Put Data to Presentation Space 192
  - Search for String 193
  - Send Keystrokes 194
  - Session Execute Macro 196
  - Set Cursor Position 203
  - Set Mouse Intercept Condition 204
  - Set Presentation Space Service Condition 207
  - Set Session Advise Condition 208
  - Set Structured Field Service Condition 209
  - Start Close Intercept 210
  - Start Keystroke Intercept 211
  - Start Mouse Input Intercept 212
  - Start Read SF 215
  - Start Session Advise 217
  - Stop Close Intercept 218
  - Stop Keystroke Intercept 219
  - Stop Mouse Input Intercept 219
  - Stop Read SF 220
  - Stop Session Advise 220
  - Terminate Session Conversation 221
  - Terminate Structured Field Conversation 221
  - Terminate System Conversation 222
  - Write SF 222
- DDE functions in an OS/2 environment 244
  - DDE data items, OS/2 244
    - LU Topic, OS/2 246
    - Session Topic, OS/2 246
    - System Topic, OS/2 245
  - Find Field, OS/2 249
  - function list, OS/2 246
  - Get Keystrokes 251
  - Get Mouse Input 253
  - Get Number of Close Requests 256

## DDE functions in an OS/2 environment *(continued)*

- Get Operator Information Area 257
  - Get Partial Presentation Space 258
  - Get Presentation Space 260
  - Get Session Status 262
  - Get System Configuration 264
  - Get System Formats 265
  - Get System Status 266
  - Get System SysItems 267
  - Get System Topics 268
  - Get Trim Rectangle 269
  - Initiate Session Conversation 270
  - Initiate Structured Field Conversation 271
  - Initiate System Conversation 271
  - naming conventions for parameters, OS/2 247
  - Put Data to Presentation Space 272
  - Search for String 273
  - Send Keystrokes 274
  - Session Execute Macro 275
  - Set Cursor Position 282
  - Set Mouse Intercept Condition 283
  - Set Presentation Space Service Condition 286
  - Set Session Advise Condition 287
  - Set Structured Field Service Condition 288
  - Start Close Intercept 289
  - Start Keystroke Intercept 291
  - Start Mouse Input Intercept 292
  - Start Read SF 295
  - Start Session Advise 296
  - Stop Close Intercept 297
  - Stop Keystroke Intercept 298
  - Stop Mouse Input Intercept 299
  - Stop Read SF 300
  - Stop Session Advise 300
  - Terminate Session Conversation 301
  - Terminate Structured Field Conversation 302
  - Terminate System Conversation 302
  - Write SF 302
- ## DDE Functions with a DDE Client Application, Using 325
- DDE Functions for Session Conversation 332
  - DDE Functions for Session Conversation (Hot Link) 340
  - DDE Functions for System Conversation 330
  - Personal Communications DDE Interface 325, 329
  - Visual Basic Sample Program 344
- ## DDE menu functions in a 16-bit environment 453
- Change Menu Item 456
  - create menu item 461
  - Initiate Menu Conversation 462
  - list 455
  - Start Menu Advise 463
  - Stop Menu Advise 464
  - Terminate Menu Conversation 464
- ## DDE menu functions in a OS/2 environment 303
- Change Menu Item 306
  - create menu item 311
  - Initiate Menu Conversation 312
  - list 305
  - Start Menu Advise 313
  - Stop Menu Advise 314

## DDE menu functions in a OS/2 environment *(continued)*

- Terminate Menu Conversation 315
- ## DDE menu functions in a Windows 32-bit environment 223
- Change Menu Item 226
  - create menu item 232
  - Initiate Menu Conversation 233
  - list 225
  - Start Menu Advise 233
  - Stop Menu Advise 235
  - Terminate Menu Conversation 235
- debugging 19
  - default
    - values 362
  - default directory
    - Receive File 102
  - device services functions
    - Get Key (51) 73
    - Post Intercept Status (52) 83
    - Release (12) 102
    - Reserve (11) 103
    - Start Keystroke Intercept (50) 132
    - Stop Keystroke Intercept (53) 136
  - directory, default
    - Receive File 102
    - Send File 110
  - Disconnect from Structured Fields (121) 67
  - Disconnect Presentation Space (2) 68
    - interaction with connect 12
  - Disconnect Window Service (102) 68
  - DOS-Mode EHLLAPI 385
  - DOS-Mode EHLLAPI (OS/2) 387
  - dynamic link method 10

## **E**

- EAB 123
- EHLLAPI
  - functions 27
  - summary 28
- EHLLAPI, DOS-Mode 385
- EHLLAPI (OS/2), DOS-Mode 387
- EHLLAPI call format 6
- EHLLAPI Overviews
  - IBM Enhanced EHLLAPI vs. IBM Standard EHLLAPI 6
  - IBM Standard EHLLAPI 5
  - WinHLLAPI 5
  - WinHLLAPI vs. IBM Standard EHLLAPI 5
- EHLLAPI programming overview 5
- EHLLAPI return codes 8
- Emulator APIs, Introduction to
  - IBM eNetwork Personal Communications Host Access Class Library (ECL) 1
- EOT 121
- error handling 389
- ESC 122
- escape character 19, 74, 111, 122
- exception code values 394
- exception object values 395



## F

- field-formatted PS 40, 104
- field-related functions 86
  - Copy Field to String (34) 39
  - Copy String to Field (33) 62
  - Find Field Length (32) 69
  - Find Field Position (31) 71
  - Search Field (30) 104
- fields, host
  - input protected 110
  - numeric only 110
- file transfer functions
  - Receive File (91) 100
  - Send File (90) 108
- Find Field 172, 400
- Find Field, OS/2 249
- Find Field Length (32) 40, 69
- Find Field Position (31) 40, 71
- flow, requester and server 360
- FPAUSE 121
- Free Communications Buffer (124) 72
- function calls
  - call (input) parameters 27
  - notes on using the function 27
  - page layout conventions 27
  - prerequisite calls 27
  - return (output) parameters 27
  - use of 27

## G

- Get Key (51) 17, 73, 83, 132
- Get Keystrokes 174, 251, 401
- Get Mouse Input 175, 253, 402
- Get Number of Close Requests 178, 256, 405
- Get Operator Information Area 179, 257, 406
- Get Partial Presentation Space 180, 258, 406
- Get Presentation Space 182, 260, 409
- Get Request Completion (125) 76
- Get Session Status 184, 262, 411
- Get System Configuration 186, 264, 412
- Get System Formats 187, 265, 413
- Get System Status 187, 266, 414
- Get System Systems 188, 267, 415
- Get System Topics 189, 268, 416
- Get Trim Rectangle 190, 269, 416

## H

- host
  - computer router 359
  - computer server 359
- host automation scenarios 22
- host-connected presentation space 12
- host fields
  - input protected 110
  - numeric only 110

## I

- IBM Support Center 94

- init \_ send \_ req \_ parms
  - C language 364
- Initialization/Termination Functions 154
- Initiate Menu Conversation 233, 312, 462
- Initiate Session Conversation 190, 270, 417
- Initiate Structured Field Conversation 191, 271, 418
- Initiate System Conversation 192, 271, 418
- input protected fields 110
- introduction to EHLLAPI programming 5
- introduction to Emulator APIs
  - Dynamic Data Exchange (DDE) 1
  - Emulator High Level Language API (EHLLAPI) 1
  - Personal Communications Session API (PCSAPI) 1
  - Server-Requestor Programming Interface (SRPI) 1
- invoking SEND \_ REQUEST 363
- IPAUSE 121

## K

- keyboard, session 17
- keyboard mnemonics
  - See also "mnemonics." 17
- keystroke interception, Get Key (51) 73

## L

- language interface
  - C language 364
- languages 6
- Linking 9
  - Dynamic Link Method 10
  - Static Link Method 10
- Lock Presentation Space API (60) 78
- Lock Window Services API (61) 80
- locking presentation space 16
- LWAIT 123, 138

## M

- memory allocation 8
- mnemonics 65
  - for Send Key 17
- mnemonics, ASCII 18
- mnemonics, shift key 17
- Multi-Threading 11

## N

- NOATTRB 121
- NOBLANK 124
- NOEAB 123
- NOQUIET 122
- NORESET 123
- NOXLATE 124
- NULLATTRB 121
- numeric only fields 110
- NWAIT 123, 138

## O

- OIA 44, 138

- Operator Information Area
  - See "OIA." 44
- operator services functions
  - Pause (18) 81
  - Query Host Update (24) 88
  - Query Session Status (22) 91
  - Query Sessions (10) 92
  - Query System (20) 94
  - Reset System (21) 103
  - Send Key (3) 110
  - Set Session Parameters (9) 119
  - Start Host Notification (23) 129
  - Stop Host Notification (25) 136
  - Wait (4) 137
- options 120, 127

**P**

- parameters
  - call 27
  - returned 362
  - SEND \_ REQUEST 360
  - supplied 361
- path, default
  - Receive File 102
  - Send File 110
- Pause (18) 23, 81, 136
- PCSAPI 159
  - how to use 159
  - pcsConnectSession 160
  - pcsDisconnectSession 160
  - pcsQueryEmulatorStatus 161
  - pcsQuerySessionList 161
  - pcsQueryWorkstationProfile 163
  - pcsSetLinkTimeout 164
  - pcsStartSession 164
  - pcsStopSession 165
- pcsDisconnectSession 160
- pcsQueryEmulatorStatus 161
- pcsQuerySessionList 161
- pcsQueryWorkstationProfile 163
- pcsStartSession 164
- pcsStopSession 165
- performance considerations 363
- Post Intercept Status (52) 26, 83, 132
- prerequisite calls
  - general 27
- presentation services functions
  - Connect Presentation Space (1) 35
  - Copy Field to String (34) 39
  - Copy OIA (13) 44
  - Copy Presentation Space (5) 52
  - Copy Presentation Space to String (8) 57
  - Copy String to Field (33) 62
  - Copy String to Presentation Space (15) 64
  - Disconnect Presentation Space (2) 68
  - Find Field Length (32) 69
  - Find Field Position (31) 71
  - Get Request Completion (125) 76
  - Lock Presentation space API (60) 78
  - Query Cursor Location (7) 86
  - Query Field Attribute (14) 86

- presentation services functions (*continued*)
  - Search Field (30) 104
  - Search Presentation Space (6) 106
  - Set Cursor (40) 118
- presentation space 44
  - character table 45
  - cursor movement 24
  - Enhanced 32-bit interface 11
  - field-formatted 39, 40, 62, 69, 71, 104
  - host-connected 12
    - maximum number of 12
  - how specified 12
  - identifier
    - blank specifier 14
    - function 12
    - how processed 13
    - letter specifier 14
    - null specifier 14
    - processing for functions not requiring connect 13
    - processing for functions requiring connect 13
  - types 12
- presentation space names 12
  - declaring 12
  - maximum number of 12
  - valid names 12
- presentation spaces 11
- programming interface, server-requester 358
- PSID handling
  - functions not requiring connect 13
  - functions requiring connect 13
- Put Data to Presentation Space 192, 272, 419

**Q**

- Query Close Intercept (42) 83
- Query Communications Buffer Size (122) 84
- Query Cursor Location (7) 86
- Query\_Emulator\_Status 495
- Query Field Attribute (14) 86
- Query Host Update (24) 82, 88, 129, 136
- Query Reply Data Structures Supported by EHLLAPI 367
  - Architecture Query Reply 376
  - Cooperative Processing Requester Query Reply 373
  - IBM Auxiliary Device Query Reply 370
    - Direct Access Self-Defining Parameter 371
    - PCLK Protocol Controls Self-Defining Parameter 372
  - OEM Auxiliary Device Query Reply 372
    - Direct Access Self-Defining Parameter 373
    - PCLK Protocol Controls Self-Defining Parameter 373
  - Product-Defined Query Reply 374
    - Direct Access Self-Defining Parameter 375, 376
    - Optional Parameters 374
  - The DDM Query Reply 367
    - Base DDM Query Reply Formats 368
    - DDM Application Name Self-Defining Parameter 368
    - PCLK protocol controls Self-Defining Parameter 368

Query\_Session\_List 498  
Query Session Status (22) 39, 91  
Query Sessions (10) 92  
Query System (20) 94  
Query Window Coordinates (103) 89  
Query\_Workstation\_Profile 504  
QUIET 122

## R

Read Structured Fields (126) 95  
RECEIVE.EXE location 100  
Receive File (91) 24, 100, 122  
    default path for target file 102  
record definition  
    C language 365  
relationship requester server 359  
Release (12) 25, 102, 103  
requester  
    C language 364  
    server flow, and 360  
    server relationship 359  
Reserve (11) 25, 102, 103  
Reset System (21) 102, 103, 119  
return (output) parameters  
    general 27  
return codes 389  
REXX EHLLAPI functions  
    Query\_Emulator\_Status 495  
    Query\_Session\_List 498  
    Query\_Workstation\_Profile 504  
    Send\_File 511  
    Sendkey 512  
    Set\_Cursor\_Pos 513  
    Set\_Session\_Parms 514  
    Set\_Window\_Status 515  
    Start\_Close\_Intercept 516  
    Start\_Communication 517  
    Start\_Host\_Notify 518  
    Start\_Keystroke\_Intercept 519  
    Start\_Session 520  
    Stop\_Close\_Intercept 521  
    Stop\_Communication 522  
    Stop\_Host\_Notify 523  
    Stop\_Keystroke\_Intercept 524  
    Stop\_Session 525  
    Wait 526  
REXX EHLLAPI programming notes 527  
router  
    SRPI 359, 360

## S

sample program, a simple EHLLAPI 20  
sample programs 3  
Scenario 1. A Search Function 22  
Scenario 2. Sending Keystrokes 23  
Scenario 4. File Transfer 24  
Scenario 5. Automation 25  
Scenario 6. Keystroke Filtering 25  
Scenario 7. Keyboard Enhancement 26  
Search Field (30) 104, 138

Search for String 193, 273, 420  
search functions  
    Search Field (30) 104  
    Search Presentation Space (6) 106  
Search Presentation Space (6) 23, 106, 138  
SEND\_REQUEST  
    invoking 363  
    parameters  
        returned 362  
        supplied 361  
    processing errors 389  
    routing 359  
send\_request function  
    C language 364  
Send\_File 511  
Send File (90) 24, 108, 122  
    default path for target file 110  
    SEND.EXE location 108  
Send Key (3) 17, 75, 110, 132, 138  
Send Keystrokes 194, 274, 421  
sending keystrokes  
    mnemonics 17  
    Send Key (3) 110  
Sendkey 512  
server  
    name 362  
    return codes 395  
server-requester programming interface 358  
service 94  
Session Execute Macro 196, 275, 422  
session keyboard 17  
Set Cursor (40) 118  
Set\_Cursor\_Pos 513  
Set Cursor Position 203, 282, 428  
Set Mouse Intercept Condition 204, 283, 429  
Set Presentation Space Service Condition 207, 286,  
    431  
Set Session Advise Condition 208, 287, 433  
Set Session Parameters (9) 111  
    general 119  
    List of affected functions 119  
    Valid Input 120, 127  
Set\_Session\_Parms 514  
Set Structured Field Service Condition 209, 288, 434  
Set\_Window\_Status 515  
shift key mnemonics 17  
size of presentation spaces 12  
source code syntax 21  
specifying strings 65  
SRCHALL 121  
SRCHBKWD 121  
SRCHFROM 121  
SRCHFRWD 121  
SRPI Return Codes 389  
stack size 3  
Start Close Intercept 210, 289, 434  
Start\_Close\_Intercept 516  
Start Close Intercept (41) 127  
Start\_Communication 517  
Start Host Notification (23) 81, 88, 122, 129, 136  
Start\_Host\_Notify 518



- Start Keystroke Intercept 211, 291, 436
- Start\_Keystroke\_Intercept 519
- Start Keystroke Intercept (50) 132
- Start Menu Advise 233, 313, 463
- Start Mouse Input Intercept 212, 292, 437
- Start Playing Macro (110) 134
- Start Read SF 215, 295, 441
- Start\_Session 520
- Start Session Advise 217, 296, 442
- static link method 10
- Stop Close Intercept 218, 297, 443
- Stop\_Close\_Intercept 521
- Stop Close Intercept (43) 135
- Stop\_Communication 522
- Stop Host Notification (25) 136
- Stop\_Host\_Notify 523
- Stop Keystroke Intercept 219, 298, 444
- Stop\_Keystroke\_Intercept 524
- Stop Keystroke Intercept (53) 136
- Stop Keystroke Intercept (53) you can call the 26
- Stop Menu Advise 235, 314, 464
- Stop Mouse Input Intercept 219, 299, 444
- Stop Read SF 220, 300, 445
- Stop\_Session 525
- Stop Session Advise 220, 300, 446
- STREOT 121
- string interception, Get Key (51) 73
- string specification 120
  - Send File 110
- STRLEN 121
- syntax
  - C language 364

## T

- Terminate Menu Conversation 235, 315, 464
- Terminate Session Conversation 221, 301, 446
- Terminate Structured Field Conversation 221, 302, 447
- Terminate System Conversation 222, 302, 447
- TIMEOUT 122
- trademarks 529
- transport layer errors 389
- TWAIT 123, 138
- types of presentation spaces 12

## U

- UERCPRB
  - C language 364
- using API header files 2

## W

- Wait 526
- Wait (4) 23, 111, 137
- window services functions
  - Change PS Window Name (106) 30
  - Change Switch List LT Name (105) 31
  - Lock Window Services API (61) 80
- Window Status (104) 138
- Windows 3.1, Compatibility with Personal Communications 4.1 for 379

- WinHLLAPI Extension Functions 147
  - Asynchronous Functions 147
    - WinHLLAPIAsync 147
    - WinHLLAPICancelAsyncRequest 153
- Blocking Routines 155
  - WinHLLAPICancelBlockingCall 157
  - WinHLLAPIIsBlocking 155
  - WinHLLAPISetBlockingHook 156
  - WinHLLAPIUnhookBlockingHook 156
- Initialization/Termination Functions 154
  - WinHLLAPI Cleanup 155
  - WinHLLAPI Startup 154
- Summary 147
- Write SF 222, 302, 448
- Write Structured Fields (127) 141

## X

- XLATE 124



---

# Readers' Comments — We'd Like to Hear from You

**eNetwork Personal Communications Version 4.3  
for Windows® 95, Windows 98, and Windows NT®  
and Version 4.2 for OS/2  
Emulator Programming**

**Publication No. SC31-8478-02**

**Overall, how satisfied are you with the information in this book?**

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Overall satisfaction	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

**How satisfied are you that the information in this book is:**

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Accurate	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Complete	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Easy to find	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Easy to understand	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Well organized	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Applicable to your tasks	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

**Please tell us how we can improve this book:**

Thank you for your responses. May we contact you?  Yes  No

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

---

Name

---

Address

---

Company or Organization

---

Phone No.



Cut or Fold  
Along Line

Fold and Tape

Please do not staple

Fold and Tape




NO POSTAGE  
NECESSARY  
IF MAILED IN THE  
UNITED STATES

# BUSINESS REPLY MAIL

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

IBM Corporation  
Information Development  
Department CGMD / Bldg 500  
P.O. Box 12195  
Research Triangle Park, NC  
27709-9990



Fold and Tape

Please do not staple

Fold and Tape

Cut or Fold  
Along Line





Printed in the United States of America  
on recycled paper containing 10%  
recovered post-consumer fiber.

SC31-8478-02

