



CLDC/MIDP Installation Guide for Palm OS devices

First Edition (month 2000)

Notice here

© Copyright International Business Machines Corporation 2004. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Chapter 1. Introduction 1

About this document	1
About J9 runtimes	1
About J9 class libraries	1
About PRC packages	1

Chapter 2. Tasks 3

Installing Palm OS 5 runtime components	3
Installing on Palm OS 5 Simulator	4
Removing Palm OS 5 runtime components	4

Chapter 3. J9 command options 5

Common options	5
Advanced options	6

Appendix. Additional information 9

Further Information	9
Notices	9
Trademarks	12

Chapter 1. Introduction

About this document

This document can help you install the **Cldc1.1** and **Midp2.0** configuration that you need to run a J9 VM executable on your Palm OS mobile device.

Note: This document assumes a certain level of knowledge about working with Palm OS mobile devices. For example, if you need further information on how to install files on your device, please refer to the Palm OS documentation.

About J9 runtimes

What is a J9 runtime?

A complete J9 runtime consists of:

- A J9 virtual machine executable

This is a Java™ 2 Micro Edition (J2ME™) application that is built to run on a "virtual machine" (VM) without regard to the processor or operating system of the device it is running on. By isolating the software from these considerations, it is perfectly suited to meet the unique needs of devices with an embedded environment.

- A collection of shared library files

For each supported platform and device, an appropriate runtime environment must be created to allow the J9 application to run. Which library files must be included in your runtime environment is determined by:

- Which processor your device uses
 - Which class library configuration(s) your operating system requires
 - Whether the runtime environment is created with command line tools or the workbench
-

About J9 class libraries

Which J9 class libraries are available for a Palm OS device?

The following J9 class libraries are available for your Palm device:

- `jc1Cldc1.1` for Palm OS is an implementation of the *J2ME Connected Limited Device Configuration 1.1* (JSR-46), based on the *Connected Limited Device Configuration 1.0* (JSR-030).
 - `jc1Midp2.0` for Palm is an implementation of the *J2ME Mobile Information Device Profile 2.0* (JSR-118), based on the *Midp 1.0* specification (JSR-37).
-

About PRC packages

What is a PRC package?

The PRC package is a collection of files packaged together to apply to the Palm OS devices.

The following installer packages are available for your device:

Type of package	PRC name & description	Space required to Run it / Install it
Runtime package	<p><i>J2ME Connected Limited Device Configuration 1.1 (JSR-46)</i></p> <p><i>J2ME Mobile Information Device Profile 2.0 (JSR-118)</i></p> <p>These runtime packages include the:</p> <ul style="list-style-type: none"> • J9 VM runtime • Cldc 1.1/Midp 2.0 Class Libraries <p>The installer for the VM itself and other required components. This is required to be installed in order to run Java applications.</p> <p>Filename: J9JavaVMMidp20.prc</p>	
Developer package	<p>j9pref.prc</p> <p>The developer preferences panel must be installed in order to debug Java applications.</p>	

Chapter 2. Tasks

This chapter provides tasks for installing and removing Palm OS 5 runtime components.

Installing Palm OS 5 runtime components

In order to begin using IBM WebSphere Everplace Micro Environment, you must first install the correct runtime components on your Palm OS 5 handheld or Palm OS 5 Simulator. The runtime components consist of PRC files, which can be found in the `prc\ARM` and `prc\IA32` directories of this distribution. For Palm OS 5 devices, use the PRC files in the `prc\ARM` directory. For Simulator, use the PRC files in the `prc\IA32` directory.

The files for use on devices are:

- `J9JavaVmmidp20.prc`

The installer for the VM itself and other required components. This is required to be installed in order to run Java applications.

- `J9pref.prc`

The developer preferences panel. This must be installed in order to debug Java applications.

For instructions on how to install PRC files, see the documentation that came with your handheld or Simulator.

Once installed, you will see one additional application in your Launcher, MIDlet HQ. This application is the Java application management system (AMS). An additional option, IBM Java VM, will also appear in the Preferences area. You can further confirm that the installation was successful by selecting Info from the Launcher's drop-down menu. The names of the application components are:

- Palm database name
- IBM Java VM
- J9 Exchanger
- J9 Java Launcher
- J9 Java VM
- J9 MIDP Bundle
- MIDlet HQ

The next step is to install a Java application that has been packaged as a PRC file. Note that only applications that have been specifically packaged for this version of WebSphere Micro Environment will work correctly. You will find sample applications that have been correctly packaged in the `samples` directory of this distribution.

Note: `J9JavaVMMidp20.prc` is an installer application that assembles the required components from a single PRC file. Limitations in Palm HotSync prevent code segment sizes greater than 64 kB from being synchronized on or off the device. Due to this limitation the runtime components are not backed up. If you must hard reset your device, the `J9JavaVMMidp20.prc` must be manually reinstalled.

Installing on Palm OS 5 Simulator

On the simulator you must install all PRCs in the prc/IA32 directory. You will also need to copy \prc\IA32\J9JavaVMidp20.dll to the Simulator directory (i.e., where PalmSim.exe resides) in order for the runtime to work correctly. Otherwise, you will receive an error message stating that the file could not load.

Removing Palm OS 5 runtime components

Prior to removing the runtime, make sure any MIDlets downloaded over the air ("OTA") with MIDlet HQ have been deleted from the device. If MIDlets are still present in the MIDlet HQ, they cannot be removed after the runtime has been deleted. From the Palm OS launcher, select **App>Delete...** and delete the following runtime components:

- Palm database name
- IBM Java VM
- J9 Exchanger
- J9 Java Launcher
- J9 Java VM
- J9 MIDP Bundle
- MIDlet HQ

For detailed instructions on how to remove applications, see the documentation that came with your handheld or Simulator.

Chapter 3. J9 command options

Common options

The following table contains common J9 v2.2 command line options.

```
J9 - VM for the Java(TM) platform, Version 2.2
(c) Copyright IBM Corp. 1991, 2004 All Rights Reserved
Target: 20040107_1222 (Windows XP 5.1 build 2600 Service Pack 1 x86)

IBM is a registered trademark of IBM Corp.
Java and all Java-based marks and logos are trademarks or registered
trademarks of Sun Microsystems, Inc.

Usage: j9 [options] classname [args...]
Usage: j9 [options] -jxe:<jxeFile> [args...]

[options]
  -classpath <path>
  -cp <path>          set classpath to <path>.
  -jxe:<jxeFile>      run the named jxe file.
  -D<prop>=<val>     set the value of a system property.
  -debug:<options>   enable debug, JDWP standard <options>.
  -jcl:<config>[:options]
                    specify which JCL DLL to use (e.g. cdc, cldc, ...).
  -verbose[:class,gc,stack,sizes]
                    enable verbose output(default=class).
  -verify            enable class file verification.
  -X                print help on non-standard options.
```

Refer to the following table for a more detailed description of each of these options:

Syntax	Description
-Dprop=<val>	This command option sets the value of the system property. For example, -Dmy.property=some.value sets the value of my.property to some.value. -Dprop sets the value to null. You can use multiple instances of this option by repeating the option statement separated with only a space. Example: j9 -Dprop1=val1 -Dprop2=val2 -Dprop3=val3 Note: Spacing is important in this option's syntax. There is never a space between the initial -D, its property argument, the equals sign, or the value argument.
-debug:<options>	This command enables debug, Java Debug Wire Protocol (JDWP) standard <options>
-verbose[:class, :gc, :stack, :sizes]	This command option turns one of the following: <ul style="list-style-type: none">• :class displays each fully-qualified class name as it is loaded (that is, enable verbose class loading). <i>This is the default value.</i>• :gc displays garbage collection information.• :stack displays stack information.• :sizes displays default VM sizes.

Syntax	Description
-verify	This command option enables CLASS file verification. The -verify option is on by default. To disable bytecode verification specify -noverify.
-X	This command option prints help on non-standard options.

Advanced options

The following options are non-standard and subject to change without notice:

-Xbootclasspath:<path>	set bootstrap classpath to <path>
-Xbootclasspath/p:<path>	prepend <path> to bootstrap classpath
-Xbootclasspath/a:<path>	append <path> to bootstrap classpath
-Xrun<dll>[:options]	start JUMPI profiling
-Xint	run interpreted only (equivalent to -Xnojit -Xnoaot)
-Xnojit	disable to JIT
-Xnoaot	do not run precompiled code
-Xfuture	enable strictest checks, anticipating future default
Arguments to the following options are expressed in bytes. Values suffixed with "k" (kilo) or "m" (mega) will be factored accordingly.	
-Xmca<x>	set RAM class segment increment to <x>
-Xmco<x>	set ROM class segment increment to <x>
-Xmn<x>	set new space size to <x>
-Xms<x>	set old space size to <x>
-Xms<x>	same as -Xms<x>
-Xmoi<x>	set old space increment to <x>
-Xmx<x>	set memory maximum to <x>
-Xmr<x>	set remembered set size to <x>
-Xmso<x>	set OS thread stack size to <x>
-Xiss<x>	set initial java thread stack size to <x>
-Xss<x>	set maximum java thread stack size to <x>
-Xdbg:<options>	enable debug, JDWP standard options
-Xrunjdpw:<options>	enable debug, JDWP standard options
-Xdbginfo:<symbol file path>	enable debug info server
-Xrdbginfo:<host><port>	enable remote debug info server

Refer to the following tables for a more detailed description of each of these options:

Syntax	Description
-Xint	This command option runs interpreted only. Note: This is equivalent to <i>-Xnojit -Xnoaot</i> .
-Xnojit	This command option disables the JIT.
-Xgcpolicy:optthruput	This command option sets no scavenger and no concurrent mark. This is the default.
-Xgcpolicy:optavgpause	This command option sets scavenger and concurrent mark.
-Xfuture	This command option enables the strictest checks, anticipating a future default.

Arguments to the following options are expressed in bytes ("k" for kilo, "m" for mega.)

Syntax	Description
-Xmca<x>	This command line option sets the RAM class segment increment to <x>.
-Xmco<x>	This command line option sets the ROM class segment increment to <x>.
-Xmn<x>	This command line option sets the new space size to <x>. Note: This sets the size of the <i>NewSpace</i> and <i>SurvivorSpace</i> . This command is only relevant if <i>-Xgcpolicy:optavgpause</i> is set.
-Xmnx40M<x>	This command line option sets the maximum new space size to <x>.
-Xmjit<x>	This command line option enables the micro JIT. Note: The micro JIT is not enabled by default. You must explicitly enable the micro JIT on platforms that support it or J9 will run in interpreted mode only.
-Xms<x>	This command line option sets the initial memory size to <x>. Note: This option is the same as <i>-Xmo<x></i> .
-Xmo<x>	This command line option sets the initial memory size to <x>. Note: This option is the same as <i>-Xms<x></i> .
-Xmoi<x>	This command line option sets the old space increment to <x>.
-Xmx<x>	This command line option sets the object memory maximum to <x>.
-Xmr<x>	This command line option sets the remembered set size to <x>.
-Xmso<x>	This command line option sets the OS thread stack size to <x>.
-Xiss<x>	This command line option sets the initial java thread stack size to <x>.
-Xss<x>	This command line option sets the maximum java thread to <x>.

Refer to the following table for a more detailed description of each of the debug options:

Syntax	Description
-Xdbg:<options>	This command line option enables standard Java Debug Wire Protocol (JDWP) debug options.
-Xrunjdp:<options>	This command line option enables standard JDWP debug options. Note: Start a JDWP server. For more information on the JDWP options, see the <i>Connection and Invocation Details</i> web site.
-Xdbginfo:<symbol file path>	This command line option enables the debug info server.
-Xrdbginfo:<host>:<port>	This command line option enables the remote debug info server.

Syntax	Description
vmOption: -DLcdUiHighResolution=true	This command line option enables high resolution mode. The MIDlet will be compatible on higher density displays (greater than 160 x 160 pixels)
vmOption: -XstdoutOnVFS.	This command line option sends debug information to the memory card. Any debug information reported by your MIDlet (i.e. standard out and standard error) will be stored on your device's SD card

The following table shows a detailed description of the deprecated commands:

Syntax	Description
-Xgc:verbose	Use the <i>-verbose:gc</i> option instead of this one.

Appendix. Additional information

Further Information

If you need more information or have questions about our product:

In the United States and Canada, call 1-800-IBM-CALL (1-800-426-2255)

In all other countries, you can submit your questions on the web at:<http://www-306.ibm.com/software/pervasive/support/questions.shtml>

You might find helpful information at the following websites or newsgroup:

- <http://www-306.ibm.com/software/wireless/wme/>
- <http://www-306.ibm.com/software/wireless/wce/>
- <http://www.ibm.com/embedded>
- newsgroup: ibm.software.websphere.studio.device-developer

Notices

This information was developed for products and services offered in the U.S.A. IBM® might not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM might have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10504-1785
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106, Japan

**The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:
INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS**

FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the information. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this information at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation
Department LZKS
11400 Burnet Road
Austin, TX 78758
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurement may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

All IBM prices shown are IBM's suggested retail prices, are current and are subject to change without notice. Dealer prices may vary.

This information is for planning purposes only. The information herein is subject to change before the products described become available.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrates programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written.

These examples have not been thoroughly tested under all conditions.

No warranty

SUBJECT TO ANY STATUTORY WARRANTIES WHICH CAN NOT BE EXCLUDED, IBM MAKES NO WARRANTIES OR CONDITIONS EITHER EXPRESS OR IMPLIED, INCLUDING WITHOUT LIMITATION, THE WARRANTY OF NON-INFRINGEMENT AND THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, REGARDING THE PROGRAM OR TECHNICAL SUPPORT, IF ANY. IBM MAKES NO WARRANTY REGARDING THE CAPABILITY OF THE PROGRAM TO CORRECTLY PROCESS, PROVIDE AND/OR RECEIVE DATE DATA WITHIN AND BETWEEN THE 20TH AND 21ST CENTURIES. The exclusion also applies to any of IBM's subcontractors, suppliers, or program developers (collectively called "Suppliers").

Limitation of Liability

NEITHER IBM NOR ITS SUPPLIERS WILL BE LIABLE FOR ANY DIRECT OR INDIRECT DAMAGES, INCLUDING WITHOUT LIMITATION, LOST PROFITS, LOST SAVINGS, OR ANY INCIDENTAL, SPECIAL, OR OTHER ECONOMIC CONSEQUENTIAL DAMAGES, EVEN IF IBM IS INFORMED OF THEIR POSSIBILITY. SOME JURISDICTIONS DO NOT ALLOW THE EXCLUSION OR LIMITATION OF INCIDENTAL OR CONSEQUENTIAL DAMAGES, SO THE ABOVE EXCLUSION OR LIMITATION MAY NOT APPLY TO YOU.

You may copy, modify, and distribute these sample programs in any form without payment to IBM for the purposes of developing, using, marketing, or distributing application programs conforming to IBM's application programming interfaces.

Each copy or any portion of these sample programs or any derivative work, must include a copyright notice as follows:

© (your company name) (year). Portions of this code are derived from IBM Corp. Sample Programs. © Copyright IBM Corp. 2002 All rights reserved.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

Trademarks

The following terms are trademarks or registered trademarks of International Business Machines Corporation in the United States, or other countries, or both:

IBM

Other company, product or service names may be trademarks or service marks of others.