



IBM Rational Software Conference 2009  
As Real as It Gets!




# DOORS Advanced Topics

Sean Farrell  
sean.farrell@au1.ibm.com


**Rational** software

© 2009 IBM Corporation


IBM Rational Software Conference 2009




## Housekeeping




Evacuation Routes




Breaks & Lunch






Messages



Transport



## What Do We Mean by Remote Deployment?

- Deployment Issues
- RIF
- Kickstart
- Integrations
  - ▶ HP Quality Center
  - ▶ DOORS RQM
  - ▶ Telelogic Change
  - ▶ Telelogic Publishing Engine
  - ▶ DOORS Web Access



IBM Rational Software Conference 2009  
As Real as It Gets!


## DOORS Advanced Topics

Deployment Options


**Rational** software

© 2009 IBM Corporation

### Simplified Processing Model




### Architecture



## Additional Databases

Development DB      Sandpit DB



## What Do We Mean by Remote Deployment?

- Centralized deployment
  - ▶ e.g using IBM Tivoli, Microsoft SMS
  
- Centralized application service
  - ▶ e.g. using Citrix Presentation Server



## Centralized Deployment

DOORS client installer repackaging e.g. Tivoli/SMS  
is **supported from V9.0 ONWARDS**

Beware:

- ▶ Unauthorized local customization
- ▶ Performance in WAN environments



## Centralized Application Service

Supported on Citrix Presentation Server


- ▶ As noted in 'Supported Platforms'

Beware:

- Ensure drives & printers are mapped appropriately
- Give users access to MS Office on the server
- Configure apps to start on the same server in a farm
  - ▶ DOORS works best in *at least* 256 colours




## Typical CITRIX Setup



## Create Additional Databases

DONE ON THE SERVER



```
Microsoft Windows XP [Version 5.2.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\gbnemi>cd c:\pro\tel*\doors 9.0\bin
C:\Program Files\Telelogic\DOORS 9.0\bin>doorsd -minstall
```



## Start New Service

The screenshot shows the Windows Services console with the 'DOORS DB Server 9.0 00001' service selected. A Command Prompt window is overlaid, displaying the following text:

```
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2004 Microsoft Corp.

C:\Documents and Settings\ghnemi>net start "DOORS DB Server 9.0 00001"
The DOORS DB Server 9.0 00001 service is starting.
The DOORS DB Server 9.0 00001 service was started successfully.

C:\Documents and Settings\ghnemi>
```

## Connect a local client to network DB

**OR**  
**-d 36691@hostname**

The screenshot shows the 'Telelogic DOORS 9.0 Properties' dialog box. The 'Target' field is set to: `DOORS 9.0\bin\doors.exe" -d 36691@127.0.0.1`. A callout box points to this field with the text 'OR -d 36691@hostname'.



## Other Command Line Switches

Switch (abbreviation)	Parameter	Description
-addins (-a)	addins_folders	A list of one or more paths to the folders that contain your DXL addins files. Use semicolons (;) to separate the entries in the list. Don't include spaces after the semicolons. Paths can be local paths, conventional drive mappings, or UNC (Universal Naming Convention) paths.
-attributeaddins (-k)	dxi_attributes_folders	A list of one or more paths to the folders that contain the programs that you can use for DXL attributes. Use semicolons (;) to separate the entries in the list. Don't include spaces after the semicolons. Paths can be local paths, conventional drive mappings, or UNC (Universal Naming Convention) paths.
-batch (-b)	dxi_program	Runs Rational DOORS in batch mode, without the GUI. For more information, see <a href="#">Running Rational DOORS in batch mode</a> .
-caching (-k)		Enables streaming for transfer of data between the database server and the client. This option may improve data transfer performance over a WAN. However, using this option offers a potential security risk. Data is cached to the localdata area of the client machine whilst loading, although it is cleared on load completion.
-data (-d)	port@server	Specifies which Rational DOORS database to use. The parameter specifies the port that the server is using and the name of the server computer (for example, 36677@myserver). A Rational DOORS 9.2 client can't use a pre-9.0 database server.
-defopenmode (-o)	One of the following: READ_ONLY READ_WRITE READ_WRITE_SHARED	The default edit mode that formal modules are opened in when you double-click them in the database explorer. The parameter is READ_WRITE for exclusive edit mode and READ_WRITE_SHARED for shareable edit mode. Note that this parameter must be upper case, unless you use the single letter



## Other Command Line Switches

		abbreviations (r, w and s).
-defopenlinkmode (-o)	One of the following: READ_ONLY READ_WRITE READ_WRITE_SHARED	The default edit mode that formal modules are opened in when you open them by clicking a link arrow in another module. The parameter is READ_WRITE for exclusive edit mode and READ_WRITE_SHARED for shareable edit mode. Note that this parameter must be upper case, unless you use the single letter abbreviations (r, w and s).
-dxi (-D)	dxi_string or "#include <dxi_program>"	DXL that is executed immediately after Rational DOORS starts up. The parameter is either: <ul style="list-style-type: none"> <li>A DXL code fragment.</li> <li>A hash include statement that specifies the path to a DXL program.</li> </ul>
-home (-H)	doors_home	The Rational DOORS home folder. This is the path to the folder that Rational DOORS was installed into (the folder that has a bin folder which contains the doors.exe file).
-layoutaddins (-L)	layout_dxi_folders	A list of one or more paths for layout DXL folders. Use semicolons (;) to separate entries in the list. Don't include spaces after the semicolons. Paths can be local paths, conventional drive mappings, or UNC (Universal Naming Convention) paths.
-localdata (-F)	local_folder	A folder on the local computer used as temporary storage for data copied from the Rational DOORS database server.
-logfile (-l)	logfile	A file in which Rational DOORS logs information. This is the full path, including the name of the log file. If you use this switch on the command line, it logs DXL errors in the file. Any reported DXL errors are logged in the file instead of being displayed on the screen. If you use this switch in the registry, it logs the information that is recorded in the Windows event log. The information is logged in the file as well as in the application







## Other Command Line Switches

		log, where the records have DOORS_DB_SERVER in the source field.
-notriggers (-T)		Turn off triggers. You must be either a Database Manager or a Custom user who has the power to manage the database.
-password (-P)	password	The password for the session.
-project (-p)	project_name	The name of the project that you want to open at the start of the session. The contents of the project are displayed in the right pane of the database explorer. If you use the -batch switch, the parameter specifies the current project.
-projectaddins (-I)	project_addins_folders	A list of one or more paths for project DXL addins directories. Use semicolons (;) to separate entries in the list. Don't include spaces after the semicolons. Paths can be local paths, conventional drive mappings, or UNC (Universal Naming Convention) paths.
-user (-u)	username	The username of the user for the session.
-W	nowait	When you are running a batch process, and there are any errors or printed output, they are sent to a command window. Rational DOORS will continue to run until the command window is closed. Using -w as part of the command line when running a batch process closes any command windows automatically and allows Rational DOORS to stop running.



IBM Rational Software Conference 2009  
As Real as It Gets!

**DOORS Advanced Topics**

RIF

Rational software

© 2009 IBM Corporation

## What is RIF?

- Requirements Interchange Format
- the upcoming format for the standardized exchange of requirement information
- to guarantee a lossless exchange of requirement information
- defined via an XML schema
- format and data model which will structure requirements and their attributes, types, access permissions and relationships (links)
- tool independent. Manufacturers of all of the major RM-tools committed to supporting the RIF standard



## DOORS 9.2 RIF Support includes ...

- support for export and import with XML data based on the RIF standard
- data interchange of Rational DOORS data including modules, objects, links
- support for construction of metadata including modules, types, attributes, views
- localized support for history
- support for the transfer of DXL Attributes as plain text



## Current limitations ...

- definitions of RIF packages limited to modules from a single folder location
- support for layout DXL only through converting layout DXL to attribute DXL
- some dialog components are disabled:
  - ▶ project properties, RIF Definitions dialog, *"Recover..."* and *"Imports..."*
  - ▶ edit RIF definition dialog, *"Module version"*, *"Delegated data control mode"*, *"Delegated data control view"*
  - ▶ import RIF package dialog, *"Use existing RIF definition"*
  - ▶ no support for DOORS pictures




## still to come in 9.2 ...

- disperse module selection
- baseline support
- Distributed Data Control:
  - ▶ delegation of requirements activities
  - ▶ partners can modify defined attributes within a module
  - ▶ partners can manipulate links
  - ▶ merge data back into the original module locations
- support for the Layout DXL
- support for DOORS pictures




## RIF definition and expo

- definitions are created from Project Properties
- Data collected is based on a view
- DDC drop down greyed out



## import RIF package

- import into a project
- 'Use existing RIF Definition' dialog box currently unavailable
- creates an identical module based on the original view



## returning the data

- how do you return a package to the source db?
- in forthcoming versions temporary modules will be created which can be merged with the originals
- A major benefit is that you can exchange data with other applications




IBM Rational Software Conference 2009  
As Real as It Gets!

## DOORS Advanced Topics


### Project Kickstart

**Rational** software

© 2009 IBM Corporation




IBM Rational Software Conference 2009  
As Real as It Gets!




## DOORS Advanced Topics

### Integrations




© 2009 IBM Corporation

IBM Rational Software Conference 2009



## Typical Integrations


- HP Quality Center
- DOORS RQM
- Telelogic Change
- Telelogic Publishing Engine
- DOORS Web Access



# HP Quality Center




# Integrating the project team



## Requirements-driven testing

Quality is conformance to requirements




Basing tests on requirements can help ensure that deliverables meet customer expectations

**Process automation and increased focus**  
The test team is working against the right set of requirements



## Role: analyst


- The analyst is a Rational DOORS user principally interested in requirements management
- Specifies the *qualification criteria* that must be met by testing
- Needs to know that requirements are tested
- Performs impact analysis to cover requirements and test
- Wants to be involved with release review boards






## Role: QA/tester

- The QA/tester is a Quality Center user principally interested in test management and execution
- Uses the *qualification criteria as test requirements*
- Needs to be involved with requirements review
- Establishes traceability to requirements
- Investigates test failures




## Facilities within HP Quality Center

- See Rational DOORS data inside the requirements tab in Quality Center
  - ▶ Test against requirements rather than simply against what is built



## Facilities available to the integration administrator

- Data-set definition
  - ▶ Defines how much information should be visible when seeing the same information in Rational DOORS and HP TestDirector for Quality Center
- Attribute mapping
  - ▶ Configures how Rational DOORS information is seen in Quality Center
  - ▶ Configures how Quality Center information is seen in Rational DOORS
- Client installation for remote administration
- Individual named-user authentication to help improve security



## Rational Quality Manager




## Some basic information on RQM

- IBM Rational Quality Manager – RQM
- To install RQM user requires IBM Installation Manager
- The supported version is IBM Rational Quality Manager 1.0.1.1 Standard Edition.
- RQM is built on the Jazz server.
- We only support the DOORS – RQM integration - RQMI. NOT the RQM application.




## Starting RQM Server




## Installing RQMI Server and client

- RQMI server and client installer comes with DOORS 9.2 client custom install option.
- The primary DDBS configuration for the Integration server is completed during the install.
- User specifies RQM server/user and ports for RQM and RQMI server port.
- DOORS username and password is also requested.



## Starting the RQMI Server

- All Programs > IBM Rational > IBM Rational Tools > IBM Rational DOORS for RQM Interface > RQMI Server Start.
- A console window is displayed showing a log of the startup process. When the server has started, the console will display the following log text:  
  
INFO: Server started with            database  
from build v1.01.0001



## Setting up additional DDBS configurations

### To register additional DOORS databases with the RQMI server:

- Open a Command console window on the RQMI server machine.
- Using the DOS cd command, navigate to the folder:

```
$.:\Program~1\IBM\Rational\DOORS\9.2\RQMIInterface\Server\IM\bin\
```

- Execute the command

```
"admin -a {DOORS Host} {DOORS Port} {Username} {Password}"
```



## RQMI automatic synchronizer

- The automatic synchronizer is preconfigured to run at intervals of 1440 minutes (i.e.24 hours) between synchronization cycles.
- The minimum interval possible between synchronizations is 10 minutes.

- To change the synch interval navigate to:

```
$.:\Progra~1\IBM\Rational\DOORS\9.2\RQMIInterface\Server\IM\bin\
```

Command is "**admin -s {minutes}**"

- The command to disable the automatic synchronizer is "**admin -s 0**"
- The command to re-enable the automatic synchronizer is "**admin -s 1**"



## Exporting DOORS requirements to RQM

DOORS user should create a public view that contains objects to be exported to RQM


**Only objects that contain Object Text will be included in the export**

There are 2 phases to the export.

1. The DOORS user initiates the export and the data is packaged prior to posting.
2. The second phase starts when the export request has been posted to the RQM server. This phase is asynchronous, so the DOORS user is then able to continue working with DOORS while the data is being exported to RQM.

The user can check the status of the export via menu option RQM>View Export Status.


Once the export is completed, the dialog has a Go to URL button which opens the target test plan in RQM.



## Requirement data inside RQM 1

- RQM displays a status field which can be either Updated, Removed or Normal
- Normal - (default) requirement is new in RQM or was previously exported to RQM and its object text has not changed in DOORS.
- Updated - requirement was previously exported to RQM and the object text of the source object in DOORS was subsequently updated (see ID 6).
- Removed - requirement was previously exported to RQM and subsequently deleted in DOORS.

**NOTE: RQM synchs will not delete previously exported Requirements in RQM even if they are now purged in DOORS**



## Requirements inside RQM 2

- **Name** field consists of DOORS object identifier and DOORS module name
- After a requirement has been exported to RQM the Name will not change, even if the name of the source DOORS module subsequently changes.
- Clicking the Name hyperlinks to the object in DOORS.
- **Description** field contains Object Text. DOORS OLE's and tables will not be displayed. They will be represented as "OLE Object" and "DOORS Table"

Name	ID	Type	Status	Description
<a href="#">DOORS Object</a>	1	Requirement	Unchanged	DOORS Object
<a href="#">DOORS Table</a>	2	Requirement	Unchanged	DOORS Table
<a href="#">DOORS Table</a>	3	Requirement	Unchanged	DOORS Table
<a href="#">DOORS Table</a>	4	Requirement	Unchanged	DOORS Table
<a href="#">DOORS Table</a>	5	Requirement	Unchanged	DOORS Table
<a href="#">DOORS Table</a>	6	Requirement	Unchanged	DOORS Table
<a href="#">DOORS Table</a>	7	Requirement	Unchanged	DOORS Table
<a href="#">DOORS Table</a>	8	Requirement	Unchanged	DOORS Table
<a href="#">DOORS Table</a>	9	Requirement	Unchanged	DOORS Table
<a href="#">DOORS Table</a>	10	Requirement	Unchanged	DOORS Table

## Associating requirements to test cases

- Once the Requirements have been synced to the Test Plan in RQM, RQM user can now associate test cases to each requirement.
- With these associations made and test cases run, the DOORS user can then generate traceability reports.
- The traceability report will include the DOORS object ID, Object heading and text, the RQM project name and test plan name along with the test case name, id and status.







## Telelogic Publishing Engine

What are the Architectural considerations when using the Telelogic Publishing Engine Integration?



IBM Rational Software Conference 2009  
As Real as It Gets!

### IBM Rational DOORS Web Access 1.2 New Features

**Rational** software

© 2009 IBM Corporation

## Licensing and Roles

- DWA\_Edit
- DWA\_Review
- DWA\_Read has been removed
- Reviewer role allows browse and print
- Editor role allows browse, searching, print, discussion related activities and light edit



## Light Edit

- aimed at those with relatively modest edit needs
- no aim to do things 'just like DOORS'
- the scope of an edit operation is a single attribute
- editors appropriate to the data type

The screenshot displays the 'Light Edit' interface for an 'Industrial area' attribute. The main window shows a list of attributes with checkboxes for selection. The 'Industrial area' dialog box is open, showing the following attributes and their states:

Attribute	State
Electrical	Checked
Environmental	Checked
Electro/mechanical	Unchecked
Safety	Unchecked
Engineering	Checked
Software	Checked

Below the main window, a secondary dialog box titled '1.1.1 Don't Move car' is visible, with a text area containing the text 'Move car'.



## locking & ACLs

- with editing comes locking
- the granularity of a lock is at the single object level
- when a lock cannot be obtained, the user will be provided with the name and scope of the lock holder
- locks are acquired and released automatically
- Access Controls are honoured by all edit operations



## navigation ribbon

- ribbon shows current position relative to other objects
- ribbon shows the heading structure
- hover over the ribbon and a tool tip displays the heading text
- scroll to next group of objects by clicking the 'load' button

The screenshot displays two views of a software development environment. The top view, titled 'Marketing Requirements', shows a navigation ribbon on the left with a tree structure of requirements. The ribbon highlights the current position relative to other objects. The table below the ribbon shows the following data:

Id	View:
TRN-MR-	
3 Undertake journey	ab
3.1 Outward journey	ab
3.1.2 Load car	ab
3.1.2.1 Load luggage	
TRN-MR-	The user shall be ab
TRN-MR-	The user shall be ab
TRN-MR-	
2 Prepare c	
2.1 Check c	
TRN-MR-	The user shall be a

The bottom view, titled 'Module ID No. 0000072b', shows a table of objects with the following data:


Id	View:
CSR-1	1 9vuiB
CSR-702	1.1 RknuZ
CSR-703	wHtdmJ HFR wku 1 L19vntFOkVhb utop5 27xRIn MTwMY3u #
CSR-704	1.2 OMH1M
CSR-705	4LWkaA Sy7 2t1PC YneX93by ETq UPAV 31Advn 9m J2D KC SD2W5jCkTg4dUI pWbpgL5DR7xPM S L7eo t31 dq553CF : W5 gOEG3YHV 2mC jOH179TKwH82TDU



IBM Rational Software Conference 2009

## misc new features; links, go to URL, printing

- Links detail panel will display in, out, external links and link attributes for a given object
- printable display opens in new window / tab
- it is possible to retrieve a URL from an item in DWA



IBM Rational Software Conference 2009

Telelogic DOORS Web Access - Microsoft Internet Explorer

Address <http://localhost:8080/dwa/>

User: Mark, Package: Review Logout

Goto URL Layout Package Help

DOORS Database 9.0

DOORS Database 9.0

DOORS Demos

New Family Car Project

- Requirements
- System Requirements
- Copy of System Requirements
- Entertainment System
- Marketing Requirements
- Stakeholder Requirements
- System Requirements

Recent Items

- System Requirements

Favourites

- User Requirements

System Requirements View: Requirement View

+	-	ID	Car system requirements
		TRN-SR-5	The car shall be able to move forwards at all speeds on standard flat roads with winds of 0 kilometers per hour.
		TRN-SR-7	The car shall be able to move backwards to a maximum speed of 10 kilometers per hour.
		TRN-SR-9	The car shall be able to accelerate from 0 to 100 Kilometers per second on standard flat roads with winds of 0 kilometers per hour.
		TRN-SR-10	The car shall be able to accelerate from 100 to 150 kilometers per second on standard flat roads with winds of 0 kilometers per hour.
		TRN-SR-11	The car shall be able to accelerate from 150 to 200 kilometers per second on standard flat roads with winds of 0 kilometers per hour.
		TRN-SR-14	The car shall be able to discriminate which authorized person is permitted to operate the car.
		TRN-SR-16	The car shall have a foot mechanism to control the speed of the car.
		TRN-SR-17	The speed control shall be infinitely variable from zero to a maximum of 100 kilometers per hour.
		TRN-SR-18	The speed of the car shall be controllable by automatic control.
		TRN-SR-20	The car shall be able to stop from 10 kilometers per hour to a stop.
		TRN-SR-21	The car shall be able to stop from 30 kilometers per hour to a stop.
		TRN-SR-22	The car shall be able to stop from 50 kilometers per hour to a stop.

Attributes Discussions

User

Object Heading

The car shall be able to move forwards at all speeds from 0 to 220 kilometers per hour on standard flat roads with winds of 0 kilometers per hour, with 280 BHP.

Object Text

Object Short Text

Speeds

Comments

Cost

34.000000

Industrial area

Electrical

Electro/mechanical

Engineering

Safety

Object Type

Requirement

Priority

2

Progress

95

Status

Approved

System

Absolute Number

5

Object Number


1.1.1.1.0-1

Last Modified


Copyright © 2008 Telelogic AB. Version 1.0.0.0 (Build 199)




## DOORS Web Access: Architecture



## DOORS Web Access - Requirements



## Launching DOORS Web Access



## DOORS Web Access: Considerations

- Information Security
  - Though the system supports the use of HTTPS to protect communications between the browser and the DWA Server, **there is currently no support for secure communication between different server-side components.**
- Firewalls
  - The default ports used are
    - **Flex 19353**
    - **DWA Broker 61616**
    - **DWA Server 8080**
    - **DoorsDB 36677**
- Additional Interoperability servers
  - Can increase performance by load balancing





© Copyright IBM Corporation 2009. All rights reserved. The information contained in these materials is provided for informational purposes only, and is provided AS IS without warranty of any kind, express or implied. IBM shall not be responsible for any damages arising out of the use of, or otherwise related to, these materials. Nothing contained in these materials is intended to, nor shall have the effect of, creating any warranties or representations from IBM or its suppliers or licensors, or altering the terms and conditions of the applicable license agreement governing the use of IBM software. References in these materials to IBM products, programs, or services do not imply that they will be available in all countries in which IBM operates. Product release dates and/or capabilities referenced in these materials may change at any time at IBM's sole discretion based on market opportunities or other factors, and are not intended to be a commitment to future product or feature availability in any way. IBM, the IBM logo, Rational, the Rational logo, Telelogic, the Telelogic logo, and other IBM products and services are trademarks of the International Business Machines Corporation, in the United States, other countries or both. Other company, product, or service names may be trademarks or service marks of others.

