
Gentran:Server[®] for iSeries[®] Release 3.5 Standards and Tradacoms Standards Installation

Purpose The purpose of this document is to provide instructions for installing the Standards or Tradacoms Standards that you received with Gentran:Server for iSeries Release 3.5.

Note

The DWNSTD/DWNSTDTC job does not have to be run by the QSECOFR user. However, the user must have authority access to the CRTLIB and RSTOBJ iSeries commands that will be used during the job.

Installing Standards

Use the following procedure to install the Standards. You may either add new standards to your online versions or replace all of your online standards with a different list of versions.

1. If installing from CD-ROM, load the Standards CD-ROM. The volume ID is STD35 for the Standards CD-ROM and STD35T for the Tradacoms Standards CD-ROM.

If installing from save files, download the Standards save file onto your iSeries. Refer to the instructions for downloading standards from a save file.

2. For Standards, type **DWNSTD** on the command line and press **F4** (prompt).
For Tradacoms Standards, type **DWNSTDTC** on the command line and press **F4** (prompt).

Note

The ANSI and EDIFACT standards have been broken up into two different CD-ROMs because of size. The older standards are on one CD-ROM (that is, any standard prior to 004010 and D97). The new standards are on another CD-ROM (that is, any standard including 004010 and D97 and newer).

When downloading the standards from the ESD portal, the Tradacoms standards and the older standards are contained in the GSi35STDTO.zip file. The remaining (newer) standards are in the GSi35STD.zip file.

System Response

The system displays the following screen.

```

Standards Selective Download (DWNSTD)

Type choices, press Enter.

Device . . . . . _____ Name, *SAVF
Gentran:Server Standards Library _____ Library
Add or Replace Standards? . . . *ADD, *REPLACE
Library for Stds. Save File . . _____ Character value

Additional Parameters

Auxiliary Storage Pool . . . . . *SAVASP *SAVASP, 1, 2, 3, 4, 5, 6...
Validate Volume ID?. . . . . *YES *YES, *NO
End of tape option . . . . . *UNLOAD *UNLOAD, *REWIND, *LEAVE

Bottom
F3=Exit F4=Prompt F5=Refresh F12=Cancel F13=How to use this display
F24=More keys
    
```



NOTE

For Tradacoms Standards, the screen name is **Tradacoms Standards Download (DWNSTDTC)**. Everything else on the screen is the same.

3. Type the device name where the CD-ROM is loaded, or type ***SAVF** if restoring from a save file.
4. Specify the name of the library where the standards should be loaded (G3X5DTA is the default name).
5. Use this table to determine what value to enter in the Add or Replace Standards field.

IF...	THEN...
You want to add new standards to your online standards,	type *ADD .
You want to replace your on-line standards with a new list of versions,	type *REPLACE .

6. If you are restoring Standards from a save file, enter the library name where your STD35 save file exists.
If you are restoring Tradacoms Standards from a save file, enter the library name where your STD35T save file exists.
7. Press **Enter** when you have entered all of the options.

System Response

The system displays a confirmation screen.

8. Press **Enter**.

System Response

The system displays the list of standards similar to the list shown below. The standards listed will vary depending on which standards you are downloading.

```

DWNSTD1           Standards Selective Download           06/24/1998
Position to Version: _____
Type option press, Enter.
1=Select 6=Inselect

Opt   Version   Description
-     ACH602     ABI BROKERNET DATA STANDARDS
-     ADJL01     ABI BROKERNET DATA STANDARDS
-     ADJL04     ABI BROKERNET DATA STANDARDS
-     ADJL05     ABI BROKERNET DATA STANDARDS
-     ADJL06     ABI BROKERNET DATA STANDARDS
-     ANA001     TRADACOMS UNITED KINGDOM
-     ATRM01     ABI BROKERNET DATA STANDARDS
-     ATRM02     ABI BROKERNET DATA STANDARDS
-     ATRM04     ABI BROKERNET DATA STANDARDS
-     A2/4      TOCC (AIR) VERSION 2 RELEASE 4
-     A2/5      TOCC (AIR) VERSION 2 RELEASE 5
-     A2/6      TOCC (AIR) VERSION 2 RELEASE 6
-     A2/7      TOCC (AIR) VERSION 2 RELEASE 7
                                           +

F3=Continue  F12=Cancel

```

9. Type **1** (Select) beside all versions that you want to add or to replace on this screen. After you have made all your selections on this screen, press **Enter**. Press **Page Down** to view the next screen of versions. Continue to make your selections by typing **1** (Select) and then pressing **Enter** only after you have selected all the versions on that screen.
10. Press **F3** when you have finished selecting the versions you wish to add or replace.

System Response

The download process runs interactively and displays a message when complete.

11. If downloading from a CD-ROM, remove it and store it in a safe place.

Reference

See Chapter 1 in the *Gentran:Server for iSeries Release 3.5 Technical Reference Guide* for more information on printing and installing standards in Gentran:Server for iSeries Release 3.5.

