

Advanced Technical Support – Washington Systems Center

An Introduction to **ZPCR**

IBM's Processor Capacity Reference for System z9 and eServer zSeries

Walt Caprice
John Fitch
IBM Washington Systems Center



Agenda

- What is zPCR
- Inputs
- Usage considerations
- Sample exercise
- Where to get more information



What is **zPCR**

- A Java based PC tool
- Provides the capacity relationships for System z9 and zSeries processors, considering ...
 - SCP/workload environment (based on LSPR workloads)
 - LPAR configuration
- The IBM tool to properly size mainframe upgrades
 - Expected accuracy of ±5%



Inputs to **zPCR**

- RMF CPU Activity Report for the installed machine
 - Machine type and model
 - LPAR definitions
- RMF Workload Activity Report(s)
 - Determine the workload mix for each partition
- Proposed machine
 - Processor type and model
 - LPAR definitions



Usage Considerations

- All capacity results from zPCR are relative to a user defined Reference-CPU. When comparing the capacity of various processors, it is critical all analyses be done using the same reference-CPU setting. Otherwise the ratios between processors will NOT be correct.
- The impact of LPAR on capacity affects all processors, and not necessarily equally. As such, you need to use zPCR to determine the capacity for the LPAR configuration of the current processor as well as the planned replacement. The ratio between these two values is the expected capacity delta.



Inputs for Sample zPCR Exercise

- Current machine characteristics
 - 2084-309 (B16 3,300 MIPS customer defined)


LPAR name	# LCPs (TRAD)	Weight	DASD I/O per Consumed MSU	Operating System Version
WSC1	6	500	17	z/OS 1.4
WSC2	3	250	20	z/OS 1.4
WSC3	3	250	18	z/OS 1.6

- Proposed machine characteristics
 - 2094-707 (S18) with 1 zAAP

LPAR name	# LCPs (TRAD)	Weight	# LCPs (zAAP)	Operating System Version
WSC1	5	500	NA	z/OS 1.4
WSC2	3	250	NA	z/OS 1.4
WSC3	3	250	1	z/OS 1.6



zPCR Logo Window






zPCR Function Selection Window

> (1) Enter Study Identification


zPCR - Function Selection [untitled] File Customize CPcalculator Registration Help **zPCR** Processor Capacity Reference for IBM System z9 and eServer zSeries Study Identification: XYZ Corporation Tab-1: Multi-Image Capacity Tab-2: Single-Image Capacity z/OS-1.6 LSPR Multi-Image Processor Capacity Table General Purpose CPs z/OS 1.6 LSPR FAQ. MI Reference-CPU System z9 Workloads Capacity values will be relative to a 2094-701 assumed at 1.00 LPAR Configuration Capacity Planning Contemporary plan (System z9 and zSeries only), with z/OS-1.6, z/OS-1.4, z/VM, VSE/ESA, Linux, CFCC Legacy plan (adds G6, G5, MP-3000 and prior), but limited to z/OS-1.4 (mixes only), z/VM, VSE/ESA, Linux, CFCC Project Capacity for a specfic LPAR Configuration Configure LPAR SI Reference-CPU Capacity values will be relative to a 2084-301 IBM System z9 Enterprise Class assumed at 1.00 (entire CEC) LSPR Document About Workloads Click on Single-Image Capacity tab for LSPR Single-Image Capacity tables

(2) Click SI Reference-CPU











Click Return




Click Workloads


























Press Configure LPAR







































Contents of Clipboard


Can be pasted into a note or document

zPCR (4.5) - LPAR Capacity Report Based on current LSPR data for System z9 and zSeries Study Identification: XYZ Corporation LPAR Host and Partition Capacity LPAR Host = 2084-B16 configured with 9 CPs: GP=9 Partitions: Active=3 GP=3 zAAP=0 zIIP=0 IFL=0 ICF=0 Capacity is relative to a 2084-309 assumed at 3,300 MIPS LP Definition LP Identification LP Capacity Inc No Type Name SCP Workload Mode #LCPs Weight Weight% Capping Minimum Maximum WSC1 z/0S** LoIO-Mix 500 50.0% Υ 1 GP SHR 6 1,592.2 2,123.0 Υ 2 GP WSC2 z/OS** LoIO-Mix SHR 3 25.0% 805.8 1,074.4 250 3 GP WSC3 z/0S 1.6 LoIO-Mix SHR 250 25.0% 809.2 1,078.9 LPAR configuration capacity summary 3 Partitions in GP RCP pool 3.207.2 0 Partitions in zAAP/IFL/ICF RCP pool 0.0 3 Partitions - combined total 3.207.2































Contents of Clipboard

Can be pasted into a note or document

zPCR (4.5) - LPAR Capacity Report Based on current LSPR data for System z9 and zSeries Study Identification: XYZ Corporation LPAR Host and Partition Capacity LPAR Host = 2094-S18/700 configured with 8 CPs: GP=7 zAAP=1 Partitions: Active=4 GP=3 zAAP=1 zIIP=0 IFL=0 ICF=0 Capacity is relative to a 2084-309 assumed at 3,300 MIPS LP Identification LP Definition LP Capacity SCP Mode #LCPs Weight Weight% Capping Workload Minimum Maximum Inc No Type Name 500 WSC1 z/OS** LoIO-Mix 50.0% 1 GP SHR 5 1,696.3 2,423.3 SHR 3 250 25.0% Υ 2 GP WSC2 z/OS** LoIO-Mix 855.5 1,466.6 z/OS 1.6 LoIO-Mix SHR 3 250 z/OS 1.6 LoIO-Mix SHR 1 250 Υ 3 GP WSC3 25.0% 837.1 1,435.0 3 zAAP WSC3 100.0% 501.8 501.8 LPAR configuration capacity summary 3 Partitions in GP RCP pool 3,388.9 1 Partitions in zAAP RCP pool 501.8 0 Partitions in zIIP RCP pool 0.0 0 Partitions in IFL RCP pool 0.0 0 Partitions in ICF RCP pool 0.0 4 Partitions - combined total 3,890.7




zPCR Results

- Reference-CPU is a 2084-309 assumed to provide 3,300 MIPS (customer defined)
- Current 2084-309 (B16) with LPAR configuration provides approximately 3,207⁽¹⁾ MIPS. (LPAR cost can be inferred as 3,300 – 3,207, or 93 MIPS)
- 2094-707 (S18) with 1 zAAP running the proposed LPAR configuration would deliver approximately 3,389⁽²⁾ GP MIPS. and 502⁽²⁾ zAAP MIPS. for a total capacity of approximately 3,890⁽²⁾ MIPS.
- Capacity ratios, considering ...
 - GP CPs only: $3,389^{(2)} \div 3,207^{(1)}$, or 1.06 (6% more capacity)
 - Overall: $3,890^{(2)} \div 3,207^{(1)}$, or 1.21 (21% more capacity)
 - (assumes that zAAP capacity can be utilized)


^{(1) 2084-309} capacity of 3,207 MIPS is misstated as 3,287 MIPS in the audio presentation

^{(2) 2094-707} capacity results differ slightly from the audio presentation due to zPCR logic improvements since v4.1b











Installing **zPCR**

 The requirement to specify an installation password for zPCR has been removed as of version 7.5b.



Where to Get More Information

- The zPCR User's Guide (implemented both as a PDF document and as online help)
 - Provides information about all the features contained in the tool
- The zPCR Email address
 - Provides defect support

Note: Effective with **zPCR** v4.3, the **zPCR Newsgroup**, discussed in the audio presentation, has been discontinued. Notices, FAQs, etc. can be found on the **zPCR** web site and in the NEWS file, available when **zPCR** is installed.