

Telelogic Synergy
Upgrade Instructions for Windows
Release 6.6a

Before using this information, be sure to read the general information under Appendix “C: Notices” on page 71.

This edition applies to Version 6.6a, Telelogic Synergy (product number 5724V66) and to all subsequent releases and modifications until otherwise indicated in new editions.

© Copyright IBM Corporation 1992, 2008

US Government Users Restricted Rights—Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Table of Contents

Chapter 1: Introduction	1
Before you upgrade	1
Installing Windows clients	1
Readme	1
Upgrade instructions	1
Consulting services	2
IBM Rational Software Support	2
Telelogic documentation	3
Conventions used in this guide	4
Fonts and symbols	4
Release-specific instructions	5
Platform instructions	5
Command line instructions and examples	5
Chapter 2: System Requirements	7
Requirements	7
Disk space requirements	7
Windows installation requirements	7
Windows installation issues	7
Chapter 3: Upgrade Methodology	9
Step 1 – Install Telelogic Synergy	9
Step 2 – Test the new installation using a copy of a production database	9
Step 3 – Upgrade the production server and databases	9

Chapter 4: Upgrade Procedures

11

Introduction	11
Checklist for upgrading an existing server	13
Pre-installation	13
Installation	13
Post-installation	14
Database upgrade	14
Post-upgrade	14
Troubleshooting	14
Pre-installation	15
Plan your upgrade	15
Obtain license information	15
Save the previous installation	16
Back up previous installation	16
Save previous configuration files	16
Back up all databases	16
Shut down the previous Synergy databases	17
Upgrade your operating system	17
Telelogic Synergy installation	17
The CCM_HOME variable	17
Router port number	17
Install Telelogic Synergy	18
How the installation handles configuration, make hosts, and remote execution files	18
Post-installation	19
Reinstall PC integrations	19
Merge your configuration files	19
Verify the installation	20
Upgrade databases to Telelogic Synergy release 6.6a	21
Database upgrade requirements	21
Upgrade base model databases to 6.6a	21
Test the database upgrade	24
Post-upgrade	25
Install Telelogic Change 5.1	25
DCM transfers after upgrade	25

Purposes, processes and process rules	25
Disable 6.5a services	26
Install Windows clients	26
Make databases available for use	26
Troubleshooting	26
Checklist for upgrading to a new server	28
Pre-installation	28
Installation	28
Post-installation	29
Database upgrade	29
Post-upgrade	29
Troubleshooting	29
Pre-installation	30
Plan your upgrade	30
Obtain license information	30
Save the previous installation	31
Back up previous installation	31
Save previous configuration files	31
Back up all databases	31
Pack or dump previous databases	31
Shut down the previous release	33
Delete databases from the previous Informix database server	34
Remove the previous installation and database server	35
Upgrade your operating system	35
Telelogic Synergy installation	36
The CCM_HOME variable	36
Changing your CM administrator user	36
Router port number	36
Install Telelogic Synergy	36
How the installation handles configuration, make hosts, and remote execution files	36
Create a database server	37
Post-installation	37
Reinstall PC integrations	38
Merge your configuration files	38

Verify the installation	39
Upgrade databases to Telelogic Synergy Release 6.6a	40
Database upgrade requirements	40
Unpack or load previous databases	40
Unpack previous database	40
Load previous database	41
Upgrade base model databases to 6.6a	41
Test the database upgrade	44
Post-upgrade	45
Install Telelogic Change 5.1	45
DCM transfers after upgrade	45
Update work areas	45
Purposes, processes and process rules	46
Disable 6.5a services	46
Remove the previous installation	47
Install Windows clients	47
Make databases available for use	47
Troubleshooting	47

Chapter 5: Updating Scripts to Work with Telelogic Synergy 6.6a 49

Introduction	49
New features	49
Changes to existing scripts	49
Contributed scripts	50
Deleting baselines	50
Copying projects	50
Project purpose name changes	50
Reconfigure/update and query-based folders	51
Process rules and reconfigure/update templates	51
Obsolete commands	53
Miscellaneous changes	53

Chapter 6: Upgrading a DCM Cluster	55
Introduction	55
Compatibility with prior releases of Telelogic Synergy	55
Order of upgrading a DCM cluster.	56
Steps to perform after upgrading a database in a DCM cluster.	56
DCM database definitions in the upgraded database	56
DCM database definition for this database in other databases.	57
DCM replication after upgrade	57
Appendix A: The Upgrade Program	59
Command name.	59
Synopsis	59
Role.	59
Description and uses	59
Options and arguments	60
Upgrade actions	62
Appendix B: Upgrade and Synergy 6.6a	63
Consider whether to upgrade	63
Changes in Telelogic Synergy 6.6a	63
Test your data.	65
Test packfiles.	65
Test archived data	65
Test DCM packages	66
Test Save Offline (SOADF) packages	66
Copy utilities from Release 6.5a	66
Check contents of archive with <code>ccm archive_check</code>	67
Copy utilities with <code>ccm_copy_tools</code>	68
Appendix C: Notices	71
Copyright license	73
Trademarks.	73

1

Introduction

Before you upgrade

This chapter explains what you need to know **before** you upgrade an existing Telelogic® Synergy™ Windows® installation to Telelogic Synergy Release 6.6a.

Upgrades of Telelogic Synergy releases prior to 6.5 are not supported by Release 6.6a. To upgrade from a pre-6.5 release, you need to upgrade to one of the releases that is supported by Release 6.6a (that is, 6.5a), and then upgrade to Release 6.6a using the document you are now reading. To upgrade from a release prior to 6.5, refer to the Release 6.5a *Upgrade Instructions*, as appropriate. These documents are available, as explained in “Telelogic documentation” on page 3.

Before Release 6.5, Telelogic Synergy was called SYNERGY/CM. If you are a user of SYNERGY/Change, it is called Telelogic® Change™, as of Release 4.6.

Installing Windows clients

If the Synergy server has been or will be installed elsewhere, and you need to install only the Windows client, you do **not** need to read these *Upgrade Instructions*. Instead, follow the steps in the *Telelogic Synergy Installation Guide for Windows*. You can get this document as explained in “Telelogic documentation” on page 3.

Readme

The *Readme* (formerly called the *Release Notes*) may contain vital news about your Telelogic Synergy software that has been issued **after** the *Telelogic Synergy Upgrade Instructions for Windows* for Release 6.6a is published. Review the *Readme* before upgrading your software. The most current revision of the *Readme* is available as explained in “Telelogic documentation” on page 3.

Upgrade instructions

The *Upgrade Instructions* that you are now reading describe how to upgrade an existing 6.5a Telelogic Synergy Windows installation to Telelogic Synergy Release 6.6a. These instructions explain how to convert existing Telelogic Synergy databases for use with Telelogic Synergy Release 6.6a.

Note To ensure that you have the latest revision of the *Telelogic Synergy Upgrade Instructions for Windows*, download an electronic copy from the Telelogic Synergy Support Web site (support.telelogic.com/synergy/info/docs/).

In addition to these *Upgrade Instructions* and the *Readme*, you will also need to read the *Telelogic Synergy Installation Guide for Windows*. If you are installing Release 6.6a for Windows at a new site, you do not need to read these *Upgrade Instructions*. Instead, follow the steps in the *Telelogic Synergy Installation Guide for Windows*. To learn how to obtain these documents, refer to “Telelogic documentation” on page 3.

Consulting services

The upgrade process for databases that were customized using a custom model database can be complicated, and is not described here. IBM offers consulting services and can perform this work for you. For more information, contact your local sales representative. If you need contact information, visit the Web site at <http://www.ibm.com/planetwide/>

IBM Rational Software Support

Support and information for Telelogic products is currently being transitioned from the Telelogic Support site to the IBM Rational Software Support site. During this transition, your product support location depends on your customer history.

- If you are a heritage customer, meaning you were a Telelogic customer prior to November 1, 2008, visit the Telelogic Synergy Support Web site (<https://support.telelogic.com/synergy>). Telelogic customers will be redirected automatically to the IBM Rational Software Support site after the product information has been migrated.
- If you are a new Rational customer, meaning you did not have Telelogic licensed products prior to November 1, 2008, visit the IBM Rational Software Support site (<http://www.ibm.com/software/rational/support>).

Telelogic documentation

The Telelogic documentation is available in HTML and PDF on the documentation DVD, and in PDF on the IBM Rational Software Support Web site (<http://www.ibm.com/software/rational/support>). The documentation can be available to all users by mounting the DVD on a shared drive.

Note that information in the *Readme* takes precedence over information in the documentation or in any of the Telelogic Synergy Help systems. The most up-to-date version of the *Readme* is available to Telelogic Synergy users on the IBM Rational Software Support Web site.

Conventions used in this guide

The following conventions are used in this guide.

Fonts and symbols

The following table describes the font and symbol conventions used in this guide.

Typeface	Description
<i>Italic</i>	Used for book titles and terminology. Designates names of roles (<i>build_mgr</i>), states (<i>working</i>), groups (<i>ccm_root</i>), and users (<i>ccm_user</i>).
Bold	Used for items that you can select and menu paths, dialog box options and titles, and for emphasis.
Courier	Represents command syntax to be entered verbatim, and commands on buttons. Also used to signify computer output that appears on-screen and the names of files (<code>remexec.cfg</code>), attributes (<code>modify_time</code>), commands (<code>ccm start</code>), functions (<code>remote_type</code>), types (<code>csrc</code>), and paths <code>c:\users\path</code> .
<i>Courier Italic</i>	Represents values in a command string that you supply. For example, <code>c:\users\sue\commands</code>
Greater than (>)	Shows a menu path, prompt, or sequence of actions necessary to complete an operation.
Pipe ()	Shows that, from the choices shown, you can specify only one option or argument.
Brackets ([...])	Shows the different options available for a command.
Ellipses (...)	Shows that you can specify more than one of a particular type of argument.

This document also uses the following conventions:

Note Contains information that should not be overlooked.

Caution Contains critical information that must be observed or damage to the database or system could result.

Release-specific instructions

Unless otherwise stated, all instructions in the following chapters are to be used regardless of whether you are upgrading from 6.5a. Whenever instructions are specific to certain releases, the releases are noted.

Platform instructions

Unless otherwise stated, all instructions in the following chapters are to be used regardless of the platform on which you are running. For a complete list of supported platforms, see the Readme. Whenever instructions are specific to certain platforms, the situations are noted.

Command line instructions and examples

Many instructions and examples are shown as entered from a command line interface. If you prefer, you can do the equivalent graphical operation. For example, you can use Windows Explorer to drag and drop files where these *Upgrade Instructions* use the copy command.

To start a command prompt with the correct path and environment, use the Start menu item **Start > All Programs > Telelogic > Telelogic Lifecycle Solutions Tools > Telelogic Synergy 6.6a > CM Command Prompt**. This path assumes that you used the default program folder during your installation.

Note Unless otherwise noted, the examples in this document assume that your previous installation directory is *Program Files\Telelogic\Synergy CM 6.5a* and your Release 6.6a installation directory is *Program Files\Telelogic\Telelogic Synergy 6.5a*.

2

System Requirements

This chapter summarizes the system requirements for the machine on which Telelogic Synergy Release 6.6a is to be installed. For full information, read the *Telelogic Synergy Installation Guide for Windows*.

Requirements

Disk space requirements

For disk space information, see the Release 6.6a *Telelogic Synergy Installation Guide for Windows*.

In most cases, the upgrade procedures require that the previous installation remain in place while the new installation and upgrade are performed, so sufficient disk space for both installations is required.

You must also allow sufficient space or other media for backups.

Windows installation requirements

This section presents the Windows installation requirements.

Windows installation issues

When upgrading to Telelogic Synergy Release 6.6a for Windows, keep the following installation issues in mind:

- Make sure you are using the most recent version of the *Telelogic Synergy Installation Guide for Windows*.
- When installing a Telelogic Synergy Main or Additional Windows Server, log on as a user who has administrative privileges for the local machine. If you are installing an Additional Windows Server, you must also have administrative privileges for the machine where the Main Windows Server is installed.
- When installing a Telelogic Synergy Client, log on as a user who has administrative privileges for the local machine.
- If you are running Dynamic Host Configuration Protocol (DHCP), you must also run Windows Internet Naming Service (WINS) **and** Domain Name Service (DNS).
- The Telelogic Synergy Windows Server machine must have a static IP address; it cannot obtain an IP address from a DHCP server.

3

Upgrade Methodology

This chapter presents a secure and proven methodology that users typically use to upgrade a Telelogic Synergy installation. Use this methodology when you perform the upgrade procedures in the next chapter.

Step 1 – Install Telelogic Synergy

Typically, you will want to test the new version of Telelogic Synergy to make sure it meets your needs. Thus, the first step in the upgrade process is to install the new version while leaving the old version in place. Follow the sequence presented in the appropriate installation guide, including installation of the licensing tool. This **must** be done on a different machine than the one you are currently using for production.

Step 2 – Test the new installation using a copy of a production database

The second step is to test the new installation using a copy of a production database. To accomplish this, a production database is packed and unpacked onto a test server. The database on this server is then upgraded and tested without affecting work-in-progress.

At a minimum, check the functionality shown in “Test the database upgrade” on page 24. The purpose of this test is to find any problems that may occur during an upgrade. Moreover, the test allows the new installation to be checked with real data. The goal is to eliminate downtime when the production server is upgraded.

Step 3 – Upgrade the production server and databases

Once you have solved any problems that may have occurred during testing and you are satisfied that the new version of Telelogic Synergy meets your needs, update your production server, production database(s), and all of the clients.

4

Upgrade Procedures

Introduction

Two upgrade procedures are presented in this chapter. One is called “Checklist for upgrading an existing server” on page 13 and the other is called “Checklist for upgrading to a new server” on page 28.

You can have more than one installation, with the same or different versions, of Telelogic Synergy on a given machine, for client and engine software. Your existing Synergy databases reside on one or more servers. On Windows, you cannot have more than one Telelogic Synergy Informix server per machine, even for different releases of Telelogic Synergy. Installing a Telelogic Synergy 6.6a server on a Windows machine will upgrade any previously existing Telelogic Synergy servers, and disable use of those servers under the earlier releases.

As a result, there are two ways to upgrade your databases from earlier releases.

Do one of the following:

- Create a new 6.6a server on a different machine, then copy your databases to this new server, and upgrade them. Databases may be copied to the new server using `ccmdb backup` or `ccmdb pack` then `ccmdb unpack`, or using `ccmdb dump` and `ccmdb load` in combination with a copy of the file system portion of the database. Use procedure while testing Synergy 6.6a, and also when upgrading production databases for live use after testing is completed.

OR

- Upgrade an existing 6.5a server to 6.6a, and upgrade all the databases in that server. Note that installing 6.5 using this procedure will immediately perform the server upgrade, and will render the databases unusable under previous releases. Each database on the server must be upgraded to 6.6a before it can be used; the databases do not need to be moved or copied, since they are already in an upgraded server. This procedure should not be used while testing Telelogic Synergy 6.6a, but may be used after you have completed testing on a separate server.

For each server, upgrade the databases on that server using one of these two procedures; you can use different procedures for different servers.

“Upgrading an Existing Server” and “Upgrade to a New Server” are outlined in two different checklists in this chapter. The following paragraphs explain which checklist you need to follow.

Use the “Checklist for upgrading an existing server” on page 13 if:

- Your operating system is or will be compatible with both your previous release of Telelogic Synergy and Release 6.6a, **and**
- You want to keep the same CM administrator user, **and**
- You want to upgrade all your databases on the server at the same time, and all those databases can be concurrently offline until the upgrade is complete, **and**
- You do **not** want to create a new Informix database server - you want to upgrade your existing server and its databases in place.

Note You will receive some performance benefits if you choose to create an Informix database server. Your databases will be unpacked — this causes the database indices to be rebuilt and the data to be defragmented, thereby improving performance.

Use the “Checklist for upgrading to a new server” on page 28 if:

- You are testing the new release of Synergy, **or**
- You need to upgrade to a new operating system that is not compatible with your previous release of Telelogic Synergy, **or**
- You want to change the CM administrator user, **or**
- You want to upgrade only some of the databases on a server at this time, leaving the others accessed through the previous release, **or**
- You want to move some databases between file systems, servers, or machines (including from UNIX to Windows, or from Windows to UNIX), **or**
- You want to create a new Informix database server.

Checklist for upgrading an existing server

If you want to upgrade all your databases on the server at the same time, use the following checklist — in the sequence shown — to install the Telelogic Synergy Release 6.6a software and upgrade your database(s) from a previous release.

Caution Following this procedure and installing the 6.6a software on an existing server will immediately perform the server upgrade, and will render the databases unusable under previous releases. Each database on the server must be upgraded to 6.6a before it can be used; the databases do not need to be moved or copied, since they are already in an upgraded server.

Note To ensure a trouble-free installation, print a copy of this checklist, and check off each item as you work through the list.

Pre-installation

- Review the “Windows installation requirements” (see page 7)
- “Plan your upgrade” (see page 15)
- If applicable, “Obtain license information” (see page 15)
- “Save the previous installation” (see page 16)
- “Back up all databases” (see page 16)
- “Shut down the previous Synergy databases” (see page 17)
- If necessary, “Upgrade your operating system” (see page 17)

Installation

- Do not set “The CCM_HOME variable” (see page 17)
- Allocate a “Router port number” (see page 17)
- “Install Telelogic Synergy” (see page 18)
- Read “How the installation handles configuration, make hosts, and remote execution files” (see page 18)

Post-installation

- If applicable, “Reinstall PC integrations” (see page 19)
- If applicable, “Merge your configuration files” (see page 19)
- “Verify the installation” (see page 20)

Database upgrade

- Review the “Database upgrade requirements” (see page 21)
- “Upgrade base model databases to 6.6a” (see page 21)
- “Test the database upgrade” (see page 24)

Post-upgrade

- If applicable, “Install Telelogic Change 5.1” (see page 25)
- If applicable, read “DCM transfers after upgrade” (see page 25)
- Read about “Purposes, processes and process rules” (see page 25)
- “Disable 6.5a services” (see page 26)

Troubleshooting

- If you are having problems, review “Troubleshooting” (see page 26)

Pre-installation

This section explains what you need to do before you install the Telelogic Synergy software.

Plan your upgrade

Before you run Telelogic Synergy Release 6.6a on a database, that database must have been upgraded to the 6.6a level and must contain a 6.6a model.

The Windows server software must be installed and Informix database servers must be upgraded by following these instructions. In addition, all Windows users must also have the 6.6a client installed. You cannot use older clients with 6.6a servers (nor vice versa). To learn how to install Windows clients, refer to the *Telelogic Synergy Installation Guide for Windows*.

Before starting the upgrade, note the server you are upgrading, and list the databases on that server. Since the databases will all be unavailable during the entire upgrade process, you need to notify the users of those databases and agree on a schedule.

Make sure you have all the information you need, including access to the *Readme* for Release 6.6a, the *Telelogic Synergy Installation Guide for Windows*, and the *Telelogic Synergy Administration Guide for Windows*, as appropriate.

You should print a copy of the “Checklist for upgrading an existing server” on page 13, to mark as you proceed.

Obtain license information

To install and run the Telelogic Synergy software, you need a valid Telelogic® License Server™. For detailed information, see the *Telelogic Directory Server Product Manual* (<https://support.telelogic.com/lifecyclesolutions>).

For updated license server information, see the latest version of the *Readme*, available on the IBM Rational Software Support Web site (<http://www.ibm.com/software/rational/support>).

Save the previous installation

This section explains how to save your previous installation.

Back up previous installation

Regardless of the release from which you are upgrading, back up your previous installation.

Caution Backing up your previous installation is an important safeguard and should not be skipped.

To back up a previous Windows server installation, save all the files in the Telelogic Synergy installation directory.

Save previous configuration files

If you use Telelogic Change, save the previous `ptcli` configuration file if you have modified it. The `ptcli` file is:

```
Program Files\Telelogic\Synergy CM 6.5a\etc\ptcli.cfg
```

Back up all databases

As the CM Administrator, use the `ccmsrv status` command to view all of your databases. Then, regardless of the release from which you are upgrading, back up each of your databases prior to the upgrade.

Note Backing up your databases is an important safeguard and should not be skipped. For more information about backing up databases, refer to the “Telelogic Synergy Database Backup and Recovery” section of the *Telelogic Synergy Administration Guide for Windows*

If you anticipate that the upgrade will still be running when your regular scheduled backups, builds, DCM transfers, and other background jobs are run, temporarily disable those scheduled activities. You must remember to turn them back on after the upgrade.

Use your normal procedures for backing up your databases. You may need to use the `ccmdb backup`, `ccmdb pack`, `ccmdb dump`, or `ccmsrv archive` commands. If you have a customized model database, remember to back it up as well as all your production databases.

Shut down the previous Synergy databases

You must shut down all the databases on the server to be upgraded. Informix users should **not** shut down the database server itself.

1. Log on as the CM Administrator on the server being upgraded.
2. Using your **previous** installation, shut down all current sessions running on this server, using the `ccmdb shutdown` command on each active database.

```
> set path=Program Files\Telelogic\Synergy CM 6.5a\bin;%path%
> ccmdb shutdown database_path (for each database)
```

Upgrade your operating system

To see a list of operating system versions that are supported by Telelogic Synergy Release 6.6a, refer to the *Readme*. If relevant, upgrade your operating system now, after you have shut down your previous installation(s) running on the older operating system version, and before you install a new Telelogic Synergy release that requires a newer operating system version.

If your previous release will not run on your upgraded operating system, make sure that you have an up-to-date pack file for each of your databases. After you have upgraded the operating system and installed Telelogic Synergy Release 6.6a, you must unpack your databases to a new database server; follow the “Checklist for upgrading to a new server” on page 28.

Telelogic Synergy installation

Before installing Telelogic Synergy Release 6.6a, make sure your environment satisfies all the conditions described in “Windows installation requirements” on page 7.

The *CCM_HOME* variable

Do **not** set the *CCM_HOME* environment variable when using or installing Telelogic Synergy on Windows.

Router port number

During the installation process, you are prompted to supply the router port number. This can be any unallocated port number. If you used Telelogic’s reserved port number of 5412 for Release 6.5a, you must choose another number for Release 6.6a. If you did not use port number 5412, use this value now. TCP port number 5412 is reserved for Telelogic by the Internet Assigned Number Authority (IANA).

Install Telelogic Synergy

Caution Do **not** install Telelogic Synergy Release 6.6a over a previous installation. You must keep your previous installation(s) (6.5a) available until the upgrade is complete for all servers using that installation.

Follow the instructions in the *Telelogic Synergy Installation Guide for Windows* to install the license server and Telelogic Synergy Release 6.6a on all your clients and servers.

How the installation handles configuration, make hosts, and remote execution files

When you install the software using the procedures described above, the Telelogic Synergy installation program checks the configuration files in your previous installation directory. The following actions are taken as a result of this check:

- Telelogic Synergy Release 6.6a is installed to a separate directory.
- For users running on Informix, the installer copies the previous database server configuration files, thus making the previous server available under Release 6.6a.
- The installer copies commonly modified files (such as `ccm.ini`) from the previous installation to the new one.
- The installer tells you which files must be merged:
 - If a given configuration file in your previous installation directory is still valid for Release 6.6a, it is automatically used in the Release 6.6a installation directory.
 - If a given configuration file in your previous installation directory is no longer valid for Release 6.6a, it is copied to the Release 6.6a installation directory. However, it is given a different name. This new name is descriptive and is displayed by the installation program when you install Telelogic Synergy. If you modified any of these files in your old release and you want to keep the changes, simply merge your changed files with the new Release 6.6a configuration files.

Following is the list of configuration files that are handled as described above (paths are relative to the Telelogic Synergy installation directory):

```
etc/ccminit
etc/ccm.ini
etc/remexec.cfg
```

Post-installation

This section explains what you need to do after you have installed Telelogic Synergy Release 6.6a.

Reinstall PC integrations

If you used a PC integrations product with your previous Telelogic Synergy release, you must install the appropriate integrations release on top of Release 6.6a.

You do not need to reinstall PC Integrations types into any existing databases. The database upgrade process described in these *Upgrade Instructions* preserves the PC integration types.

Merge your configuration files

If you have not already done so, you should merge the files identified in “How the installation handles configuration, make hosts, and remote execution files” on page 18.

Verify the installation

Verify correct installation by unpacking a test database into the directory set up for Telelogic Synergy databases, on the database server machine. If any of the following steps fail, contact IBM Rational Software Support as described on page 2.

To verify the installation, do the following:

1. Unpack a test database.

Log on as the CM Administrator on the Telelogic Synergy server, and unpack a test database. Telelogic Synergy databases must be on an NTFS file system, and the `ccmdb unpack` command requires a UNC path name for the database to be created. For more information on the `ccmdb unpack` command, refer to the *Telelogic Synergy Administration Guide for Windows*.

```
> ccmdb unpack "Program Files\Telelogic\Telelogic Synergy  
6.5a\packfiles\training.cpk" /t \\server\share\testdb
```

2. Start a Telelogic Synergy session on the test database.

- a. On the Windows taskbar, click **Start > All Programs > Telelogic > Telelogic Synergy 6.6a** to display the **Start Telelogic Synergy** dialog box.

Note The Start menu folder shown in the path above is the default program folder. Your folder may be different based on where you installed the program.

When the **Start Telelogic Synergy** dialog box is displayed, enter the CM Administrator name and password, type the path to the test database in the **Database Path** text box, and the name of this machine in the **Engine Host** text box. Click **Start** to start the session.

The installation is complete when the session(s) start. Stop the sessions by clicking on the close icon in the top right of the Telelogic Synergy client window, or by using the **Task > Exit** menu item.

Upgrade databases to Telelogic Synergy release 6.6a

This section explains how to upgrade your Telelogic Synergy databases to Telelogic Synergy Release 6.6a when using the procedure “Upgrading an Existing Server.”

Database upgrade requirements

Before you can use your Release 6.5a databases with Telelogic Synergy Release 6.6a, you must upgrade these databases. Moreover, before you upgrade these databases, you must have installed Telelogic Synergy Release 6.6a.

This document describes how to upgrade Telelogic Synergy 6.5a base model databases – databases that have **not** been customized via a model install from a model database. Databases customized using the Type Definition facility, or by modifying control files, etc., are still considered base model databases, and should be upgraded using these procedures.

To upgrade model databases and databases that have been customized via a model install, contact Telelogic Synergy Support.

Upgrade base model databases to 6.6a

Perform the following steps for each Windows production database to be upgraded.

1. Log on to the server machine as the CM Administrator.
2. Save manual customizations.

The upgrade program automatically saves your previous `pt` and `notify` directories, and your previous Windows `migrate.rul` file.

If you made changes to other database-specific configuration files, save those changes by making a backup copy of the files.

3. Run the upgrade program.

```
> ccmdb upgrade database_path1 databasepath2 . . . >logfile
```

The `database_path` must be supplied as a UNC path.

You can specify any number of `database_path` UNC paths for a list of databases to be upgraded. The upgrade program can take anywhere from a few minutes for a very small database to many hours for a very large database.

For more details about the upgrade program, see Appendix: “A: The Upgrade Program” on page 59.

4. The upgrade program unprotects the databases. You should re-protect the databases, using `ccmdb protect database_path`, until you have completed the steps below and tested the result.
5. Once the database upgrade is complete, look through the *logfile* that you created in step 3 and your `ccm_ui.log` file to locate any error messages.
6. Restore manual customizations.

If you made changes to database-specific configuration files, such as triggers, merge the changes you saved in step 2 into the converted databases.

Caution You must merge these files with the Release 6.6a versions, not just copy back your saved versions.

7. Modify standard types.

If any standard types were modified in the database since the previous model install, they are automatically exported to the `database_path\old_types` directory. If this is an upgrade from Release 6.3, upgrade will not know when the last model was installed. In this case, `ccmdb upgrade` will export all standard types and use an alternate algorithm to attempt to identify modified types. However, if you manually modified the *access* model attribute after a model install, then this alternate algorithm may not identify changed standard types, but all of the standard types will have been saved. Compare any modified type with the corresponding Release 6.6a type as follows:

- a. Export the Release 6.6a type using the following command:
`ccm typedef /export type_name /dir to_path`
 - b. Compare the Release 6.6a type to the corresponding type that is in the `database_path\old_types` directory. You can do this by comparing XML files.
 - c. If you need to reapply changes, start a session on the upgraded database using Release 6.6a, start the **Type Definition** dialog box and reapply the changes. Do not perform a type definition import of the standard type from a prior release into the upgraded database without examining and understanding all of the differences. In doing so, other properties of the type definition may revert to their definition from a prior release and these could be incompatible with Release 6.6a.
8. Merge Task Attribute customizations.

Settings and possible values for some task attributes are held in the `pt` directory of your databases.

After you have used these *Upgrade Instructions* to upgrade a database from Release 6.5a to Release 6.6a, you have two `pt` directories under that database. To complete the upgrade, you must reapply the changes you made in your previous release to the new `database_path\pt` directory. Your previous `pt` directory was saved in `database_path\oldpt`.

Caution You must merge these files with the Release 6.6a versions, not just copy back your saved versions.

You must also remember to restore any changes you made to the `task` type, such as adding attributes to the `source_attrs` attribute.

9. Merge `notify` customizations.

After you have used these *Upgrade Instructions* to upgrade a database from Release 6.5a to Release 6.6a, you have two `notify` directories under that database. To complete the upgrade, you must reapply the changes you made in your previous release to the new `database_path\notify` directory. Your previous `notify` directory was saved in `database_path\oldnotify`.

Caution You must merge these files with the Release 6.6a versions, not just copy back your saved versions. It is very important that you do this merge if you use Telelogic Change, because it requires modified `notify` scripts.

10. Set site default settings.

If you are using settings other than the default settings for the following options, you need to specify the defaults for your site. These settings apply across all sessions for all interfaces. Edit the following entries in the `ccm.ini` file to set defaults:

```
baseline_template
baseline_template_date_format
baseline_template_repl_char
include_required_tasks
project_subdir_template
wa_path_template
```

For more information about these settings, see the *Defaults* section of the *CLI Help for Telelogic Synergy*.

11. Upgrade DCM settings.

For complete information about upgrading a DCM database, see “Upgrading a DCM Cluster” on page 55.

Your database is now upgraded to Release 6.6a.

Test the database upgrade

You have completed the upgrade to your production database. To test the result, start a Telelogic Synergy session and perform a number of operations. Some important operations are shown below.

If the database was manually protected after the upgrade, you must unprotect it before you can start a session. To run your tests, unprotect the database, start up a session, then immediately protect the database again so that developers do not start to use the database until you have confirmed that it is working correctly. Repeat these steps each time you start a session for testing or for the post-upgrade actions described in the next section.

Start a Telelogic Synergy session on the upgraded database. On the Windows taskbar, click **Start > All Programs > Telelogic > Telelogic Synergy 6.6a** to display the **Start Telelogic Synergy** dialog box.

Test at least the following functionality in each upgraded database:

- Navigate through the explorers and work pane in Telelogic Synergy
- Create a new project
- Create a task and assign it to yourself
- Create one or more source objects in the new project
- Check in one or more of those source objects
- Check out one or more of the source objects you just checked in
- Start the History dialog box for one or more of these source objects
- Use an earlier version of one of the checked-out source objects
- Update your project, and verify that the version you used is replaced
- Make sure you can build your own product using your normal build scripts
- Sync your work area with your database

Post-upgrade

This section explains in detail some things you may need to do once your upgrade is complete.

Install Telelogic Change 5.1

If you use Telelogic Change with this database, install Telelogic Change 5.1. Earlier releases of Telelogic Change are not compatible with Telelogic Synergy 6.6a. For detailed instructions, refer to the *Telelogic Change Installation Guide for Windows*.

Note that you must create or upgrade at least one database before you install Telelogic Change 5.1, because Telelogic Change requires access to a Telelogic Synergy database.

If you saved a modified copy of the previous `ptcli` configuration file as described in “Save previous configuration files” on page 16, you should merge it at this time. The `ptcli` file is:

```
Program Files\Telelogic\Telelogic Synergy 6.5a\etc\ptcli.cfg
```

DCM transfers after upgrade

Release 6.6a requires patches to Release 6.5a to provide DCM compatibility.

For complete information about upgrading a DCM database, see “Upgrading a DCM Cluster” on page 55.

Purposes, processes and process rules

In Release 6.5, **process rules** replaced the objects previously known as *update templates* and *reconfigure templates*. Release 6.5 also introduced the concept of a process, which is a collection of process rules, and renamed some existing purposes. For more information, read the chapter “Updating Scripts to Work with Telelogic Synergy 6.6a” on page 49, the *Telelogic Synergy Help*, and the *Build Manager's Guide*.

Upgrading to 6.6a creates or renames the standard purposes. If you have modified any of the standard purposes, your modified copy will be renamed, starting with a prefix “Saved”.

After the database upgrade has completed, examine any modified purposes and process rules, and adjust them as required. Create one or more processes with your preferred set of process rules.

Note Telelogic Synergy does not replicate processes or process rules from 6.5 to earlier releases, nor does it replicate

reconfigure templates or update templates from earlier releases to 6.6a. If you used DCM to centrally administer update templates in earlier releases, you will have to upgrade all databases in the cluster to achieve the same effect with process rules in Release 6.6a.

Disable 6.5a services

The upgrade process stopped and rendered unusable the previous release on the upgraded server. You should disable 6.5a services using the following steps:

1. On the taskbar, click **Start > Control Panel > Administrative Tools > Services** to display the **Services** window.
2. Repeat the following steps for each 6.5a Synergy service:
 - a. Right-click the service entry, and select **Properties** from the pop-up menu.
 - b. In the **General** tab, change the **Startup type** to **Disabled**.

Caution Do **not** delete the previous Telelogic Synergy installation directory. If you remove it incorrectly, your upgrade could be compromised. For more information, contact “IBM Rational Software Support” as explained on page 2.

Install Windows clients

If needed, install Windows clients for Telelogic Synergy Release 6.6a. You do not need to uninstall clients for previous releases, but you may do so if there is no need to access any databases still using the previous release.

For detailed instructions, see the *Telelogic Synergy Installation Guide for Windows*. To learn how to obtain this document, see “Telelogic documentation” on page 3.

Make databases available for use

Once you have completed the upgrade, tested the results, and performed any required post-upgrade actions, your upgrade is complete. If you protected the databases during the upgrade, test, or post-upgrade process, unprotect them now. You should let the users know the database are ready for use, but remember that users’ client software must also be upgraded.

Troubleshooting

If you have difficulties with a command or process, or if you receive an error message that you do not understand, do the following:

- Refer to the troubleshooting information on the Synergy Support web site and the *Telelogic Synergy Administration Guide for Windows*, as appropriate.

This site also contains Frequently Asked Questions (FAQs), technical bulletins, and a Discussion Forum.

Note A user name and password are required to enter the Telelogic Synergy Support Web site. Follow the on-screen instructions to obtain them.

- If you still have questions, contact IBM Rational Software Support, as explained on page 2.

Checklist for upgrading to a new server

If you want to upgrade your databases at different times, or move some databases to new servers, use the following checklist — in the sequence shown — to install the Telelogic Synergy Release 6.6a software and upgrade your database(s) from a previous release.

Note To ensure a trouble-free installation, print a copy of this checklist, and check off each item as you work through the list.

Pre-installation

- Review the “Windows installation requirements” (see page 7)
- “Plan your upgrade” (see page 30)
- If applicable, “Obtain license information” (see page 30)
- “Save the previous installation” (see page 31)
- “Back up all databases” (see page 31)
- “Pack or dump previous databases” (see page 31)
- In some situations, “Shut down the previous release” (see page 33)
- If necessary, “Upgrade your operating system” (see page 35)

Installation

- Do not set “The CCM_HOME variable” (see page 36)
- Read about “Changing your CM administrator user” (see page 36)
- Allocate a “Router port number” (see page 36)
- “Install Telelogic Synergy” (see page 36)
- Read “How the installation handles configuration, make hosts, and remote execution files” (see page 36)
- “Create a database server” (see page 37)

Post-installation

- If applicable, “Reinstall PC integrations” (see page 38)
- If applicable, “Merge your configuration files” (see page 38)
- “Verify the installation” (see page 39)

Database upgrade

- Review the “Database upgrade requirements” (see page 40)
- “Unpack or load previous databases” (see page 40)
- “Upgrade base model databases to 6.6a” (see page 41)
- “Test the database upgrade” (see page 44)

Post-upgrade

- If applicable, “Install Telelogic Change 5.1” (see page 45)
- If applicable, read “DCM transfers after upgrade” (see page 45)
- Users might have to “Update work areas” (see page 45)
- Read about “Purposes, processes and process rules” (see page 46)
- When no longer needed, “Disable 6.5a services” (see page 46)
- When no longer needed, “Remove the previous installation” (see page 47)
- If applicable, “Install Windows clients” (see page 47)
- “Make databases available for use” (see page 47)

Troubleshooting

- If you are having problems, review “Troubleshooting” (see page 47)

Pre-installation

This section explains what you need to do before you install the Telelogic Synergy software.

Plan your upgrade

Before you run Telelogic Synergy Release 6.6a on a database, that database must have been upgraded to the 6.6a level and must contain a 6.6a model.

The Windows server software must be installed and Informix database servers must be created by following these instructions. In addition, all Windows users must also have the 6.6a client installed. You cannot use older clients with 6.6a servers (nor vice versa). To learn how to install Windows clients, refer to the *Telelogic Synergy Installation Guide for Windows*.

Before starting the upgrade, decide on where the new server is to be and what its configuration is. Make a list of the databases to be moved to that new server as they are upgraded. Since those databases will be unavailable during the upgrade process, you need to notify the users of those databases and agree on a schedule.

You can move a database from Windows to UNIX by packing on Windows and unpacking on UNIX, but you must then run `ccmdb upgrade -w`. See Appendix: “A: The Upgrade Program” on page 59 for more information on the upgrade command. You can move a database from UNIX to Windows by packing on UNIX and unpacking on Windows (either before or after upgrading the UNIX database).

Make sure you have all the information you need, including access to the *Readme* for Release 6.6a, the *Telelogic Synergy Installation Guide for Windows*, and the *Telelogic Synergy Administration Guide for Windows*, as appropriate.

You should print a copy of the “Checklist for upgrading to a new server” on page 28, to mark as you proceed.

Obtain license information

To install and run the Telelogic Synergy software, you need a valid Telelogic License Server. For detailed information, see the *Telelogic Directory Server Product Manual* (<https://support.telelogic.com/lifecycle/solutions>).

For updated license server information, see the latest version of the *Readme*, available on the IBM Rational Software Support Web site (<http://www.ibm.com/software/rational/support>).

Save the previous installation

This section explains how to save your previous installation.

Back up previous installation

Regardless of the release from which you are upgrading, back up your previous installation.

Caution Backing up your previous installation is an important safeguard and should not be skipped.

To back up a previous Windows server installation, save all the files in the Telelogic Synergy installation directory.

Save previous configuration files

If you use Telelogic Change, save the previous `ptcli` configuration file if you have modified it. The `ptcli` file is:

```
Program Files\Telelogic\Synergy CM 6.5a\etc\ptcli.cfg
```

Back up all databases

As the CM Administrator, use the `ccmsrv status` command to view all of your databases. Then, regardless of the release from which you are upgrading, back up each of your databases prior to the upgrade.

Note Copying your databases is both an important safeguard and a critical part of this upgrade process, and must not be skipped. For more information about backing up databases, refer to the “Telelogic Synergy Database Backup and Recovery” section of the *Telelogic Synergy Administration Guide for Windows*

If you anticipate that the upgrade will still be running when your regular scheduled backups, builds, DCM transfers, and other background jobs are run, temporarily disable those scheduled activities. You must remember to turn them back on after the upgrade.

You may use your normal procedures for backing up your databases, but read the next section about the need for a copy of the databases. If you have a customized model database, remember to back it up as well as all your production databases.

Pack or dump previous databases

You must copy your databases from your previous release into a Telelogic Synergy 6.6a server. Use `ccmdb backup` (or `ccmdb pack`) and `ccmdb`

unpack. If your normal backup procedure is to use `ccmsrv archive` or some other method, you **must** use `ccmdb backup`, `ccmdb pack`, or `ccmdb dump` instead of or in addition to your normal backup procedures.

If a database is too large to be packed, you must back up the metadata and file system separately. Back up the metadata using `ccmdb dump`; note that `ccmsrv archive` is not suitable for this purpose. Back up the file system portion of the database using any appropriate tool; one possible such tool, available on both Windows and UNIX, is `ccm_tar`. Note that this step should be performed using your previous release.

```
> set PATH=Program Files\Telelogic\Synergy CM 6.5a\bin;%PATH%
> ccmdb dump unc_database_path /to dumpfile
> cd database_path
> "Program Files\Telelogic\Synergy CM 6.5a\bin\util\ccm_tar" -cf
backup_file .
```


Shut down the previous release

In most cases, you need not shut down your previous release(s) of Telelogic Synergy before installing Release 6.6a. You must shut down your previous release only if:

- You want to delete the previous installation before installing Release 6.6a, to avoid the need for temporary extra disk space (not recommended)

OR

- You intend to delete and replace your existing Informix database server instead of creating an entirely new and separate Informix database server (not recommended).

To shut down a previous release, perform the following steps:

1. Log on as the CM Administrator on the server being upgraded.
2. Using your **previous** installation, shut down all current sessions running on this server, using the `ccmdb shutdown` command on each active database.

```
> set path=Program Files\Telelogic\Synergy CM 6.5a\bin;%path%
> ccmdb shutdown database_path (for each database)
```

Delete databases from the previous Informix database server

If you have shut down your previous release, and you want to reuse the disk space used by your previous Informix database server, you must first delete all databases from the previous server.

Caution If you delete your databases from the previous Informix database server, you will **not** be able to access them using your previous installation.

To delete all databases from your previous server:

1. Make sure that you have a successful backup of all your databases.
2. Log on as the CM Administrator on the database server machine.
3. Point to your old installation directory.

```
> set path=Program Files\Telelogic\Synergy CM 6.5a\bin;Program Files\Telelogic\Synergy CM 6.5a\informix\bin;%path%
```

4. Get a list of databases.

```
> ccmsrv status [/s servername]
```

5. Remove each database.

```
> ccldb delete unc_database_path
```

Remove the previous installation and database server

If you no longer need your old release or if you want to delete your database server and reuse its disk space, you may uninstall the previous release now. During the uninstall, you may select the option to delete the Informix database server; this is safe provided you have taken a copy of all the databases on the server as described earlier.

Upgrade your operating system

To see a list of operating system versions that are supported by Telelogic Synergy Release 6.6a, refer to the *Readme*.

If relevant, upgrade your operating system now, after you have shut down your previous installation(s) running on the older operating system version, and before you install a new Telelogic Synergy release that requires a newer operating system version.

Alternatively, set up a new machine with the newer operating system, and upgrade to Telelogic Synergy Release 6.6a on that system following this checklist.

Telelogic Synergy installation

Before installing Telelogic Synergy Release 6.6a, make sure your environment satisfies all the conditions described in “Windows installation requirements” on page 7.

The CCM_HOME variable

Do **not** set the *CCM_HOME* environment variable when using or installing Telelogic Synergy on Windows.

Changing your CM administrator user

You may change your CM administrator user on upgrade only if you are installing the new release on a different machine from your previous installation. For more information on changing the CM administrator, see the *Administration Guide for Windows*.

Router port number

During the installation process, you are prompted to supply the router port number. This can be any unallocated port number. If you used Telelogic’s reserved port number of 5412 for Release 6.5a, you must choose another number for Release 6.6a. If you did not use port number 5412, use this value now. TCP port number 5412 is reserved for Telelogic by the Internet Assigned Number Authority (IANA).

Install Telelogic Synergy

Caution Do **not** install Telelogic Synergy Release 6.6a over a previous installation. Use a separate installation directory for each release, or uninstall the older release first, as described earlier in this checklist.

Follow the instructions in the *Telelogic Synergy Installation Guide for Windows* to install the license server and Telelogic Synergy Release 6.6a on all your clients and servers. You should elect to create a database server during the installation. You may also elect to unpack a training database during the installation; that database may be used to test the installation.

How the installation handles configuration, make hosts, and remote execution files

If your previous installation is not visible from this machine, you must merge the configuration files manually with those you saved. See “Back up previous installation” on page 31 and “Save previous configuration files” on page 31.

If your previous installation is visible from this machine, when you install the software using the procedures described above the Telelogic Synergy installation program checks the configuration files in your previous installation directory. The following actions are taken as a result of this check:

- Telelogic Synergy Release 6.6a is installed to a separate directory.
- If a previous installation directory is visible, the installer copies commonly modified files (such as `ccm.ini`) from the previous installation to the new one.
- The installer tells you which files must be merged:
 - If a given configuration file in your previous installation directory is still valid for Release 6.6a, it is automatically used in the Release 6.6a installation directory.
 - If a given configuration file in your previous installation directory is no longer valid for Release 6.6a, it is copied to the Release 6.6a installation directory. However, it is given a different name. This new name is descriptive and is displayed by the installation program when you install Telelogic Synergy. If you modified any of these files in your old release and you want to keep the changes, simply merge your changed files with the new Release 6.6a configuration files.

Following is the list of configuration files that are handled as described above (paths are relative to the Telelogic Synergy installation directory):

```
etc/ccmunit
etc/ccm.ini
etc/remexec.cfg
```

Create a database server

If you did not create a database server during the installation of Telelogic Synergy 6.6a on this machine, then create one now, using the `ccmsrv create` command. Follow the instructions in the *Telelogic Synergy Installation Guide for Windows*. Also, read the *Telelogic Synergy Administration Guide for Windows* before creating a database server. To learn how to obtain these documents, see “Telelogic documentation” on page 3.

Post-installation

This section explains what you need to do after you have installed Telelogic Synergy Release 6.6a.

Reinstall PC integrations

If you used a PC integrations product with your previous Telelogic Synergy release, you must install the appropriate integrations release on top of Release 6.6a.

You do not need to reinstall PC Integrations types into any existing databases. The database upgrade process described in these *Upgrade Instructions* preserves the PC integration types.

Merge your configuration files

If you have not already done so, you should merge the files identified in “How the installation handles configuration, make hosts, and remote execution files” on page 36.

Verify the installation

Verify correct installation by unpacking a test database into the directory set up for Telelogic Synergy databases, on the database server machine. If any of the following steps fail, contact IBM Rational Software Support as described on page 2.

To verify the installation, do the following:

1. If you did not elect to unpack a training database during the installation, then you must now unpack a test database.

Log on as the CM Administrator on the Telelogic Synergy server, and unpack a test database. Telelogic Synergy databases must be on an NTFS file system, and the `ccmdb unpack` command requires a UNC path name for the database to be created. For more information on the `ccmdb unpack` command, refer to the *Telelogic Synergy Administration Guide for Windows*.

```
> ccmdb unpack "Program Files\Telelogic\Telelogic Synergy
6.5a\packfiles\training.cpk" /t \\server\share\testdb
```

2. Start a Telelogic Synergy session on the test database.
 - a. On the Windows taskbar, click **Start > All Programs > Telelogic > Telelogic Synergy 6.6a** to display the **Start Telelogic Synergy** dialog box.

Note The **Start** menu folder shown in the path above is the default program folder. Your folder may be different based on where you installed the program.

When the **Start Telelogic Synergy** dialog box is displayed, enter the CM Administrator name and password, type the path to the test database in the **Database Path** text box, and the name of this machine in the **Engine Host** text box. Click **Start** to start the session.

The installation is complete when the session(s) start. Stop the sessions by clicking on the close icon in the top right of the Telelogic Synergy client window, or by using the **Task > Exit** menu item.

Upgrade databases to Telelogic Synergy Release 6.6a

This section explains how to upgrade your Telelogic Synergy databases to Telelogic Synergy Release 6.6a when using the procedure “Upgrade to a New Server.”

Database upgrade requirements

Before you can use your Release 6.5a databases with Telelogic Synergy Release 6.6a, you must upgrade these databases. Moreover, before you upgrade these databases, you must have installed Telelogic Synergy Release 6.6a.

This document describes how to upgrade Telelogic Synergy 6.5a base model databases – databases that have **not** been customized via a model install from a model database. Databases customized using the Type Definition facility, or by modifying control files, etc., are still considered base model databases, and should be upgraded using these procedures.

To upgrade model databases and databases that have been customized via a model install, contact Telelogic Synergy Support.

Unpack or load previous databases

If you followed the instructions in “Create a database server” on page 37, your new server is empty and ready for use. To prepare your databases for upgrade, do one of the following for each database that you are upgrading:

Unpack previous database

If you used `ccmdb backup` or `ccmdb pack` to pack your database from the previous release, unpack it into this new server using Release 6.6a:

```
> ccmdb unpack packfile /to unc_database_path [-s server]
```


Load previous database

If you dumped the metadata for your database, and copied the file system portion manually as described in “Pack or dump previous databases” on page 31, then you need to reconstruct the database in your new Release 6.6a server. For example, suppose you used `ccm_tar` to back up and copy the file system portions of your database:

```
> ccmdb load dumpfile /to unc_database_path [-s server]
> cd database_path
> ren db db.SAVE
> "Program Files\Telelogic\Telelogic Synergy
6.5a\bin\util\ccm_tar" xf backup_file
> ren db db.old
> ren db.SAVE db
> copy db.old\MDL_INFO db
```

Upgrade base model databases to 6.6a

Perform the following steps for each Windows production database to be upgraded.

1. Log on to the server machine as the CM Administrator.
2. Save manual customizations.

The upgrade program automatically saves your previous `pt` and `notify` directories, and your previous Windows `migrate.rul` file.

If you made changes to other database-specific configuration files, save those changes by making a backup copy of the files.

3. Run the upgrade program.

```
> ccmdb upgrade database_path1 databasepath2 . . . >logfile
```

The `database_path` must be supplied as a UNC path.

You can specify any number of `database_path` UNC paths for a list of databases to be upgraded. The upgrade program can take anywhere from a few minutes for a very small database to many hours for a very large database.

For more details about the upgrade program, see Appendix: “A: The Upgrade Program” on page 59.

4. The upgrade program unprotects the databases. You should re-protect the databases, using `ccmdb protect database_path`, until you have completed the steps below and tested the result.

5. Once the database upgrade is complete, look through the *logfile* that you created in step 3 and your `ccm_ui.log` file to locate any error messages.

6. Restore manual customizations.

If you made changes to database-specific configuration files, such as triggers, merge the changes you saved in step 2 into the converted databases.

- Caution** You must merge these files with the Release 6.6a versions, not just copy back your saved versions.

7. Modify standard types.

If any standard types were modified in the database since the previous model install, they are automatically exported to the `database_path\old_types` directory. If this is an upgrade from Release 6.3, upgrade will not know when the last model was installed. In this case, `ccmdb upgrade` will export all standard types and use an alternate algorithm to attempt to identify modified types. However, if you manually modified the *access* model attribute after a model install, then this alternate algorithm may not identify changed standard types, but all of the standard types will have been saved. Compare any modified type with the corresponding Release 6.6a type as follows:

- a. Export the Release 6.6a type using the following command:
`ccm typedef /export type_name /dir to_path`
- b. Compare the Release 6.6a type to the corresponding type that is in the `database_path\old_types` directory. You can do this by comparing XML files.
- c. If you need to reapply changes, start a session on the upgraded database using Release 6.6a, start the **Type Definition** dialog box and reapply the changes. Do not perform a type definition import of the standard type from a prior release into the upgraded database without examining and understanding all of the differences. In doing so, other properties of the type definition may revert to their definition from a prior release and these could be incompatible with Release 6.6a.

8. Merge Task Attribute customizations.

Settings and possible values for some task attributes are held in the `pt` directory of your databases.

After you have used these *Upgrade Instructions* to upgrade a database from Release 6.5a to Release 6.6a, you have two `pt` directories under that database. To complete the upgrade, you must reapply the changes you made in your

previous release to the new `database_path\pt` directory. Your previous `pt` directory was saved in `database_path\oldpt`.

Caution You must merge these files with the Release 6.6a versions, not just copy back your saved versions.

You must also remember to restore any changes you made to the `task` type, such as adding attributes to the `source_attrs` attribute.

9. Merge `notify` customizations.

After you have used these *Upgrade Instructions* to upgrade a database from Release 6.5a to Release 6.6a, you have two `notify` directories under that database. To complete the upgrade, you must reapply the changes you made in your previous release to the new `database_path\notify` directory. Your previous `notify` directory was saved in `database_path\oldnotify`.

Caution You must merge these files with the Release 6.6a versions, not just copy back your saved versions. It is very important that you do this merge if you use Telelogic Change, because it requires modified `notify` scripts.

10. Set site default settings.

If you are using settings other than the default settings for the following options, you need to specify the defaults for your site. These settings apply across all sessions for all interfaces. Edit the following entries in the `ccm.ini` file to set defaults:

```
baseline_template
baseline_template_date_format
baseline_template_repl_char
include_required_tasks
project_subdir_template
wa_path_template
```

For more information about these settings, see the *Defaults* section of the *CLI Help for Telelogic Synergy*.

11. Upgrade DCM settings.

For complete information about upgrading a DCM database, see “Upgrading a DCM Cluster” on page 55.

Your database is now upgraded to Release 6.6a.

Test the database upgrade

You have completed the upgrade to your production database. To test the result, start a Telelogic Synergy session and perform a number of operations. Some important operations are shown below.

If the database was manually protected after the upgrade, you must unprotect it before you can start a session. To run your tests, unprotect the database, start up a session, then immediately protect the database again so that developers do not start to use the database until you have confirmed that it is working correctly. Repeat these steps each time you start a session for testing or for the post-upgrade actions described in the next section.

Start a Telelogic Synergy session on the upgraded database. On the Windows taskbar, click **Start > All Programs > Telelogic > Telelogic Synergy 6.6a** to display the **Start Telelogic Synergy** dialog box.

Test at least the following functionality in each upgraded database:

- Navigate through the explorers and Work pane in Telelogic Synergy.
- Create a new project.
- Create a task and assign it to yourself.
- Create one or more source objects in the new project.
- Check in one or more of those source objects.
- Check out one or more of the source objects you just checked in.
- Start the History for one or more of these source objects.
- Use an earlier version of one of the checked-out source objects.
- Update your project, and verify that the version you used is replaced.
- Make sure you can build your own product using your normal build scripts.
- Sync your work area with your database.

Post-upgrade

This section explains in detail some things you may need to do once your upgrade is complete.

Install Telelogic Change 5.1

If you use Telelogic Change with this database, install Telelogic Change 5.1. Earlier releases of Telelogic Change are not compatible with Telelogic Synergy 6.6a. For detailed instructions, refer to the *Telelogic Change Installation Guide for Windows*.

Note that you must create or upgrade at least one database before you install Telelogic Change 5.1, because Telelogic Change requires access to a Telelogic Synergy database.

If you use Telelogic Change, and if you saved a modified copy of the previous `ptcli` configuration file as described in “Save previous configuration files” on page 31, you should merge it at this time. The `ptcli` file is:

```
Program Files\Telelogic\Synergy CM 6.5a\etc\ptcli.cfg
```

DCM transfers after upgrade

Release 6.6a may require patches to earlier releases to provide DCM compatibility.

For complete information about upgrading a DCM database, see “Upgrading a DCM Cluster” on page 55.

Update work areas

If you moved the database to a new path (perhaps on a new machine) as part of the upgrade, existing work areas must be updated to refer to the new path. This is true for both copy-based and link-based work areas. Each user of a moved database must run the command to update their working projects:

```
> ccm wa /dbpath old_database_path
```

Build managers must also update their *prep* projects, and may need to update shared or static projects, using the appropriate `/scope` options to the `ccm wa /dbpath` command.

Purposes, processes and process rules

Note In Release 6.3, the operation to bring new members into a project was called **reconfigure**. In Releases 6.4 and 6.5, this operation is called **update**.

In Release 6.5, **process rules** replace the objects previously known as Update Templates in 6.4 and Reconfigure Templates in 6.3. Release 6.5 also introduces the concept of a process, which is a collection of process rules, and renames some existing purposes. For more information, read the chapter “Updating Scripts to Work with Telelogic Synergy 6.6a” on page 49, the *Telelogic Synergy Online Help*, and the *Build Manager’s Guide*.

Upgrading to 6.6a creates or renames the standard purposes. If you have modified any of the standard purposes, your modified copy will be renamed, starting with a prefix "Saved".

After the database upgrade has completed, you should examine any modified purposes and process rules, and adjust them as required. Create one or more processes with your preferred set of process rules.

Note Telelogic Synergy does not replicate processes or process rules from 6.5 to earlier releases, nor does it replicate reconfigure templates or update templates from earlier releases to 6.6a. If you used DCM to centrally administer update templates in earlier releases, you will have to upgrade all databases in the cluster to achieve the same effect with process rules in Release 6.6a.

Disable 6.5a services

The upgrade process stopped and rendered unusable the previous release on the upgraded server. You should disable 6.5a services using the following steps:

1. On the taskbar, click **Start > Control Panel > Administrative Tools > Services** to display the **Services** window.
2. Repeat the following steps for each 6.5a Synergy service:
 - a. Right-click the service entry, and select **Properties** from the pop-up menu.
 - b. In the **General** tab, change the **Startup type** to **Disabled**.

Remove the previous installation

Once you no longer need your old release, you may use uninstall it if you used the procedure “Upgrade to a New Server” for all databases.

Caution Do **not** delete the previous Telelogic Synergy installation directory if you used the procedure “Upgrade an Existing Server” on this machine. If you remove it incorrectly, your upgraded server could be compromised. For more information, contact “IBM Rational Software Support” as explained on page 2.

Install Windows clients

If needed, install Windows clients for Telelogic Synergy Release 6.6a. You do not need to uninstall clients for previous releases, but you may do so if there is no need to access any databases still using the previous release.

For detailed instructions, see the *Telelogic Synergy Installation Guide for Windows*. To learn how to obtain this document, see “Telelogic documentation” on page 3.

Make databases available for use

Once you have completed the upgrade, tested the results, and performed any required post-upgrade actions, your upgrade is complete. If you protected the databases during the upgrade, test, or post-upgrade process, unprotect them now. You should let the users know the database are ready for use, but remember that users’ client software must also be upgraded.

Troubleshooting

If you have difficulties with a command or process, or if you receive an error message that you do not understand, do the following:

- Refer to the troubleshooting information on the Synergy Support web site and the *Telelogic Synergy Administration Guide for Windows*, as appropriate.

These and other documents are available on the Telelogic Synergy Support Web site (support.telelogic.com/synergy).

- If you still have questions, contact IBM Rational Software Support, as explained on page 2.

5

Updating Scripts to Work with Telelogic Synergy 6.6a

Introduction

If you have written or used scripts with prior releases of Telelogic Synergy, you should review the following sections for possible changes required for those scripts. When reviewing your scripts, make them as portable as possible to minimize any changes that might be required in a future release. Telelogic strives to make the CLI upwards compatible with each release of Telelogic Synergy. However, this is not always possible when major new features or capabilities are provided in the new release.

New features

Telelogic Synergy Release 6.6a introduces new commands, new command options, and new query functions and keywords. While it is not always necessary to update your scripts to take advantage of these new features, doing so may make your scripts simpler, easier to maintain, and faster. Review the *Readme* for a description of new features in 6.6a.

Changes to existing scripts

The following topics are discussed in this section:

- “Contributed scripts” on page 50
- “Deleting baselines” on page 50
- “Copying projects” on page 50
- “Project purpose name changes” on page 50
- “Reconfigure/update and query-based folders” on page 51
- “Process rules and reconfigure/update templates” on page 51
- Update Templates and Process Rules on page
- “Obsolete commands” on page 53
- “Miscellaneous changes” on page 53

Contributed scripts

Many of the scripts in the `extras` download have been updated to run with Telelogic Synergy Release 6.6a. You can use these scripts as starting points for your own scripts, and for examples of dealing with some of the issues described in this note.

Deleting baselines

In Telelogic Synergy Release 6.3, the command `ccm baseline -delete` deleted a baseline, but by default did not delete the projects and products belonging to the baseline. In Release 6.5, this command defaults to deleting the baseline and the projects and products that were created when the baseline was created, but not any static projects or products that previously existed. To delete only the baseline, use `ccm baseline -delete -np`.

Copying projects

In Telelogic Synergy Release 6.3 and earlier, the `copy_project` command required a `-p` option: `ccm copy_project -p project_spec`. In Release 6.6a, this command does not have a `-p` option: `ccm copy_project project_spec`. You must edit your scripts to remove the `-p` option.

Project purpose name changes

In Release 6.5a, **project purposes** were renamed, as shown in the table below. Additionally, in Release 6.6a, the name *project purposes* was changed to *purposes*. You should update your scripts to use the new purpose names.

Old Purpose Name	New Purpose Name
Custom	Custom Development
Shared	Shared Development
Visible	Visible Development
Master Integration	Master Integration Testing

If a script creates a new release specifying a set of purposes, the script must at the minimum be updated to use the correct new names. Change the scripts to specify the **process** for the new release; a process defines a set of process rules, which replace the objects previously known as reconfigure templates or update templates. For more information on processes and process rules, see the *ReadMe* and the *Build Manager's Guide*.

Reconfigure/update and query-based folders

Note In Releases 6.5a, the reconfigure operation is called **update**.

In scripts that build a complex project hierarchy, you probably want to refresh the tasks in the update properties only once, even though your script needs to update different projects at different times. In Releases 6.3 and earlier, this was usually accomplished by using commands to change the folders from query-based to manual, and back from manual to query-based, at different times during the build process.

Although this technique will still work with Releases 6.5a, it is no longer the recommended approach. Instead, you should update your scripts to use the `-auto_update_baseline_and_tasks`, `-update_baseline_and_tasks`, and `-no_auto_update_baseline_and_tasks` options on the new `ccm project_grouping` or `ccm pg` command. For additional information about this command, see the *Telelogic Synergy CLI Help*.

Process rules and reconfigure/update templates

In Release 6.5a, **process rules** replaced the objects previously known as *update templates* in 6.4 and *reconfigure templates* in 6.3.

The commands `ccm reconfigure_template`, `ccm recon_temp`, and `ccm rt` from 6.3, and the commands `ccm update_template`, `ccm update_temp`, and `ccm ut` from 6.5a, are still available, but they are now aliases to the preferred form of the command: `ccm process_rule` or `ccm pr`. You should update your scripts to use the new form of the command.

The combination of release and purpose no longer forms a unique identifier for process rules, so the old form of reconfigure template or update template specifiers `release:purpose` is not used in the `ccm process_rule` command. You must update your scripts to use the new form of *process_rule_spec*. For more information, see the *Telelogic Synergy CLI Help*.

Process rules no longer support direct task members; you must enclose all tasks with folders or folder templates. For this reason, the following command forms are no longer supported, and you must remove them from your scripts:

```
ccm project_grouping -show individual_tasks
ccm update_template -tasks [-y] [-related] (and all its aliases)
ccm update_template -show tasks (and all its aliases)
```

The `-copy` option may no longer be used to create process rules, but only lets you copy over an existing process rule, and no longer accepts the `-force` option.

Process rules no longer have a DCM transfer option (they are always allowed to be transferred), and so the following command forms are no longer supported:

```
ccm update_template -allow_dcm_transfer
ccm update_template -noallow_dcm_transfer
ccm update_template -show allow_dcm_transfer
```

Obsolete commands

The following commands were removed in Telelogic Synergy 6.4. Use the equivalent commands in their place.

Removed Commands	Equivalent Command
<code>ccm create_task</code>	<code>ccm task -create</code>
<code>ccm default_task</code>	<code>ccm task -default</code>

The 3.2 mode `import` and `export` commands have been removed. These commands are not defined by default; to see if your site has defined them, look for the statements similar to the following in the `ccminit` file in the `etc` directory of your Telelogic Synergy installation or in individual users' personal `.ccminit` files in their home directories. (Your command names may differ.)

```
define export32 migcmds cv_export
define import32 migcmds cv_import
```

You must remove these definitions and use the standard mode `import` and `export` commands in place of the older 3.2 versions.

Miscellaneous changes

Some existing commands have additional options. In general, existing usage should not be affected by these new options. Refer to the *Telelogic Synergy CLI Help* for more definitive information on CLI commands, options, and usage.

6

Upgrading a DCM Cluster

Introduction

This chapter describes additional upgrade considerations when upgrading one or more databases that participate in a DCM cluster. If you are not using DCM or are upgrading a database that is not initialized for DCM, then you may skip this chapter.

Compatibility with prior releases of Telelogic Synergy

Release 6.6a might require patches to earlier releases to provide DCM compatibility.

You can perform DCM transfers between 6.5a and 6.6a databases, between 6.5 and 6.6a, and between 6.6a and 7.0 databases. Before performing any DCM transfers, see the *Readme* for information on required patches.

In general, when a transfer package is generated from a Telelogic Synergy Release 6.6a database, not all data and information may be processed in earlier releases. The additional data will be ignored by prior releases. However, that will also mean that only a subset of the data will be represented in prior releases and not all of the 6.6a features and benefits may necessarily apply across a DCM cluster when some databases are at prior releases.

There were no significant changes to Synergy between versions 6.5a and 6.6a that should affect data transferred between releases. However, to gain full benefit from Release 6.6a, all of the databases in a DCM cluster should be upgraded to 6.6a.

Order of upgrading a DCM cluster

To get the full benefit of the new functionality in Telelogic Synergy Release 6.6a, all databases in the DCM cluster should be updated before resuming DCM operations and regular usage. However, when these databases are located at different sites or when a large number of databases are in the cluster, it may not be practical to upgrade them all at one time. There may thus be some time when some of the cluster has been upgraded to 6.6a and some is at one or more prior releases.

There are several factors that determine the order in which sites and/or databases should be upgraded:

- Hub databases should be updated before the spoke databases that exchange data with them. After a hub database is updated, as each spoke database is upgraded, it will be able to fully use the new facilities in Release 6.6a. Conversely, if two Release 6.6a databases share data via a pre-6.6a hub database, all three databases will be constrained by the reduced functionality of the hub database.
- In Master and Satellite DCM methodology, the master database is where master builds are performed and applications are released. It is preferable to update the master database first, though the satellites must also be upgraded before process rules can be shared.

Steps to perform after upgrading a database in a DCM cluster

DCM database definitions in the upgraded database

After a database has been upgraded, you should review the DCM database definitions in the upgraded database and establish which Telelogic Synergy release they are currently using.

Release 6.6a does not support the old CCM45SP2 export format. Existing database definitions that used the CCM45SP2 format will have the *generate allowed* property turned off, and messages indicating this will be shown in the upgrade log. If these databases have been upgraded to 6.5a, and now use the XML export format, you may re-enable *generate allowed*.

Similarly, Release 6.6a does not support mapping project instances to or from 1. Existing database definitions that had *map project instances* turned on will have the *generate allowed* property turned off, and messages indicating this will be shown in the upgrade log. If these databases have been upgraded to 6.5a, you may re-enable *generate allowed*.

DCM database definition for this database in other databases

After upgrading a database to Release 6.6a from Release 6.5a, you must update the DCM database definitions for that database in all the other databases in the DCM cluster that have a definition for it. In the case of databases at other geographic sites, you should contact the administrators at the sites and advise them of the changes required. You should ensure that these changes have been performed before resuming DCM replication between the upgraded database and those other databases.

These are the checks and steps you or the remote administrator should perform:

1. Verify that all databases in the cluster that can replicate directly or indirectly with the upgraded 6.6a database have themselves been upgraded to 6.6a, or are running 6.5a with the required patches.
2. If you have moved the database to a new location, verify that the database path in the DCM database definition is updated to reflect the new location.
3. If auto-receive is used, verify that the CCM_HOME setting is updated to reflect your new Release 6.6a installation directory.

DCM replication after upgrade

The upgrade to Release 6.6a is designed to minimize touching the `modify_time` of objects. DCM transfer packages generated immediately after upgrade may be slightly larger than normal, but this is not normally expected to cause noticeable impact to regular operation.

Appendix: A: The Upgrade Program

This appendix describes the Telelogic Synergy upgrade program, `ccmdb upgrade`.

Command name

```
ccmdb upgrade
```

Synopsis

```
ccmdb upgrade  
  [/f model_file]  
  [/m] model [model ...]  
  database_path [database_path ...]
```

Role

You must be the CM Administrator to run this command, and you must be logged on to the database server machine.

Description and uses

The upgrade program converts a database from Releases 6.5a to Release 6.6a. You must upgrade a database from a previous release before using it with Release 6.6a.

Note This command does not support individual model installs.

The database to be upgraded must be on a Release 6.6a database server, either by upgrading a previous server using `ccm_install -u -s server`, or by first being packed or dumped from the previous server running the previous release, then unpacked or loaded into a Release 6.6a server.

The following is an example of how to upgrade the two databases `\\elite\ccmdb\production1` and `\\elite\ccmdb\testdb` to Release 6.6a, using the default model file. Log on to `elite` as the CM Administrator, open a command window, and then issue the following command:

```
> ccmdb upgrade \\elite\ccmdb\production1  
               \\elite\ccmdb\testdb
```

Options and arguments

/f model_file

This option specifies the model package file name.

If you do not specify the model file, the Telelogic Synergy default model name `CCM_HOME\packfiles\base.model` is used. Use of non-standard models is not described in this document.

This option must be a UNC path.

/m model [model ...]

This option specifies the list of model names to be installed. The model name is the same name as the model project name in the model database. The default models shipped by Telelogic Synergy are the `base` and `modsup` models.

Note Each model in the model file must have a unique name.

If this option is not specified, `ccmdb upgrade` will read the models that are currently installed on each databases and upgrade them accordingly.

If this option is specified, the new list will be used to override the current models. The sequence of the models listed in this option is the sequence of the models to be installed in the target database. All the current models that are not in the specified list will be removed. As a result, specifying the option `-m base` will cause the database to be upgraded to a Telelogic base model, removing all custom models present in a previous release.

database_path [*database_path* ...]

This option specifies the list of databases to be upgraded.

These must be UNC paths to databases on the server where you are logged on.

Upgrade actions

The upgrade program then performs the following actions on each database that it upgrades:

1. Updates the target database schema to the Release 6.6a schema.
2. Updates the target database version to 6.6a.
3. Saves the previous migrate rules as `database_path\lib\Windows\migrate.old`.
4. Saves the previous pt directory as `database_path\oldpt`.
5. Saves the previous notify directory as `database_path\lib\oldnotify`.
6. Protects the target database.
7. Exports any types that were modified in the target database.
8. Finds the list of models installed in the target database.
9. Installs the required list of models and model additions from the model database to the target database.
10. Unprotects the target database.
11. Restores the original migrate rules file saved in step 3, and performs any upgrade that is required.
12. Starts a 6.6a session on the target database.
13. Runs the `ccm db_update -update` command to update the data in the target database to Release 6.6a format.
14. Changes the logging mode of the target database to be unbuffered.
15. Removes obsolete files from the target database.

Appendix B: Upgrade and Synergy 6.6a

This section discusses special considerations for upgrading to Synergy Release 6.6a.

Consider whether to upgrade

Telelogic Synergy 6.6a has many changes to underlying utilities that could affect your usage. Before deciding whether to upgrade, review the next section, "Changes in Telelogic Synergy 6.6a."

Changes in Telelogic Synergy 6.6a

This section is a summary of changes in Telelogic Synergy 6.6a that you should take into account when planning your upgrade. These changes require additional testing beyond the testing you have done for previous releases.

- ObjectMake (`ccm_make`) and the pre-processor program (`ccm_cpp`) were removed from the product.
- The underlying utilities used for archiving checked-in files have changed. In previous releases, Synergy archived `ascii` files using `rCS`, and binary files using `zip`. Synergy 6.6a contains different versions of these utilities.

The new `rCS` utilities in Release 6.6a are used only to read files that were archived using `rCS` in previous releases. Newly checked-in files are all archived using the new `zip` utility.

This change is transparent to all users and administrators. However, we have provided a test utility for testing your existing archives to ensure that the new `rCS` utilities can read them. You should test the archives for all of your existing databases before upgrading to Synergy 6.6a to ensure that the new utilities can read those files. Instructions for testing archives are provided in this appendix.

If you find issues when you test your archives, you will be able to continue to use the `rCS` utilities from Synergy 6.5a in Synergy 6.6a by following the instructions in this appendix.

- The underlying utilities used for creating and retrieving data from packfiles, DCM packages, and Save Offline (SOADF) packages have changed. Synergy uses `ccm_tar` and `ccm_gzip` utilities to package multiple files into a single, compressed file for these operations. Synergy 6.6a contains different versions of these utilities.

This change is transparent to all users and administrators. However, you should test existing packfiles, DCM packages, and Save Offline packages that were created in a previous release to ensure that the new utilities can read those files. Instructions for testing those files are provided in this appendix.

- The underlying utilities used for compare and merge from Telelogic Synergy Classic CLI, and automated merge from the Classic GUI, have changed. Synergy uses `ccm_diff`, `ccm_diff3`, and `ccm_merge` utilities for these operations, and Release 6.6a contains different versions of these utilities.

This change should be transparent to all users and administrators. However, it is possible that the results of certain merges may differ, because there are sometimes several accurate ways in which conflicts can be resolved depending on how the merge utility analyzes character patterns between files.

If you find issues when you test your data, you will be able to continue to use the old compare and merge utilities from Synergy 6.5a in Synergy 6.6a by following the instructions in this appendix.

The following summary outlines issues to consider before deciding whether or not to upgrade to Release 6.6a.

1. Carefully test the following areas before upgrading to Synergy 6.6a.
 - All packfiles created using Release 6.5a that you intend to use with Synergy 6.6a
 - All archived data checked in while running previous releases
 - All DCM packages created using Releases 6.5a that you intend to use with Synergy 6.6a or follow-on releases
 - All Save Offline (SOADF) packages created in previous releases that you intend to use with Synergy 6.6a or follow-on releases

For detailed information, see “Test your data” on page 65.

2. You can copy the utilities used in Synergy 6.5a for archiving checked-in files to be used in 6.6a in place of the new utilities. See “Copy utilities from Release 6.5a” on page 66.

Test your data

This section provides instructions for testing packfiles, archived data, DCM packages, and Save Offline packages.

All of these tests require you to first install Synergy 6.6a for testing purposes.

Be sure to test your data in a non-production environment before upgrading.

You should do all of these tests before copying utilities from Release 6.5a into your Synergy 6.6a installation, as described in “Copy utilities from Release 6.5a” on page 66.

Test packfiles

Test your packfiles as follows.

1. You must have installed Synergy 6.6a for testing purposes.
2. For each 6.5a packfile, unpack it in Release 6.6a using the `ccmdb unpack` command.
3. If the `ccmdb unpack` command reports any issues, report them to [IBM Rational Software Support](#) for guidance.

Test archived data

To test your archived data, Synergy 6.6a includes a new command called `ccm archive_check`.

1. You must have installed Synergy 6.6a for testing purposes.
2. For each 6.5a database, complete the following:
 - Upgrade a test copy of the database to Release 6.6a.
 - Run the `ccm archive_check` command on the database. Usage is described in “Check contents of archive with `ccm archive_check`” on page 67
3. If the `ccm archive_check` command reports any issues, report them to [IBM Rational Software Support](#).

If the `ccm archive_check` reports issues, copy the archiver utilities from Release 6.5a into your Synergy 6.6a installation, as described in “Copy utilities from Release 6.5a” on page 66.

Test DCM packages

Test your DCM packages as follows.

1. You must have installed Synergy 6.6a for testing purposes.
2. For each DCM package, complete the following:
 - Upgrade a test copy of the receiving database to 6.6a. (You may have done this already when testing archived data.)
 - Receive the DCM packages, in order.
3. If the DCM receive reports any issues, report them to [IBM Rational Software Support](#) for guidance.

Test Save Offline (SOADF) packages

Test your Save Offline packages as follows:

1. You must have installed Synergy 6.6a for testing purposes.
2. For each Save Offline package, complete the following:
 - Upgrade a test copy of the restoring database to 6.6a. (You may have done this already when testing archived data.)
 - Restore the packages, in order.
3. If the restore reports any issues, report them to [IBM Rational Software Support](#) for guidance.

Copy utilities from Release 6.5a

If you find issues when testing with Release 6.6a as described in the section “Test archived data” on page 65, you can copy utilities from a previous release.

To copy utilities, complete the following:

1. You must have installed Synergy 6.6a.
2. Log in as user *ccm_root*.
3. Enter the following command:

```
ccm_copy_tools old_installation_dir
new_installation_dir
```

The `ccm_copy_tools` command supports several variations. You can use it to save a copy of the utilities from a previous installation for future use, and to apply a saved copy of the utilities to Synergy 6.6a. Even if you do not intend to copy the utilities into your 6.6a installation, it is a good idea to save a copy of them from your Synergy 6.5a installation.

See the section “Copy utilities with `ccm_copy_tools`” on page 68 for more information about this program.

Check contents of archive with `ccm archive_check`

Use the new `ccm archive_check` command to check the contents of the archive within a Synergy database. It will confirm that all of the source files archived using a previous release, such as Synergy 6.5a, can be retrieved successfully using the new archive utility in Synergy 6.6a.

You can check all archived files, only files of a particular type, or specific files.

To run this command, you must first install Synergy 6.6a. Users must be in the `ccm_admin` role to use this command.

To test archive files on a database that has already been upgraded to 6.6a, run the command using the syntax described below.

1. Start a Classic CLI session on the older database.
2. Enter the following commands:

```
ccm set role ccm_admin
ccm archive_check ...
```

The following describes the command syntax.

```
ccm archive_check [-t|-type type] [[file_spec...]
[-gnu gnu_dir] [-bsd bsd_dir]
```

where...

`-bsd bsd_dir`

Specifies the Synergy installation directory where the BSD executables (`bsdci`, `bsdco`, `bsdrcs`, `bsdlog`, `ccm_zip`, and `ccm_unzip`) exist. The default is `$CCM_HOME/bin/util/`. You should not need to specify this argument if you are running this command in your Synergy 6.6a installation.

`file_spec`

Indicates a specific file or set of files whose archive you want to check.

`-gnu gnu_dir`

Specifies the Synergy installation directory where the GNU executables (`ccm_gci`, `ccm_gco`, `ccm_glog`, `ccm_grcs`, and `ccm_gzip`) exist. The default value is `$CCM_HOME/bin/util/`, but if you have not copied the utilities from a previous release using the `ccm_copy_tools` command, you should specify the path to the `bin/util/` directory in your Synergy 6.5a or 6.4 server installation directory.

`-type|-t`

Indicates to check files of the specified type only. If you have a very large database, this command enables you to check subsets of data in separate commands.

Examples

- Check all archives in the current Synergy 6.6a database, using the GNU utilities from the Synergy 6.5a installation.

```
ccm archive_check -gnu /usr/local/ccm65a/bin/util/
```

- Check all archives for objects of the type `java` in the current Synergy 6.6a database, using the GNU utilities from the Synergy 6.5a installation.

```
ccm archive_check -gnu /usr/local/ccm65a/bin/util/  
-t java
```

- Check the archives for version 14 of `main.c` in the current Synergy 6.6a database, using the GNU utilities from the Synergy 6.5a installation.

```
ccm archive_check -gnu /usr/local/ccm65a/bin/util/  
main.c-14
```

Copy utilities with `ccm_copy_tools`

This is a script that copies utilities from a Synergy 6.5a installation directory to the Synergy 6.6a installation directory. Alternatively, you can use it to save the utilities from a previous release, or apply previously saved utilities into a Synergy Release 6.6a installation.

This command must be run as user `ccm_root` because it must be able to write to your Synergy 6.6a installation directory.

The following describes the command syntax.

```
ccm_copy_tools old_installation_dir new_installation_dir
```

In this form of the command, 6.5a tools are copied directly from the old Synergy installation directory to the new one.

You'll see an error in the following cases:

- Either of the two installation directories does not exist.
- The two installation directories refer to the same directory.
- The new installation directory is not from Synergy 6.6a.

Note that it is legal for the `old_installation_directory` to refer to an existing Synergy 6.6a directory that was previously updated with 6.5a

tools; this makes it possible to copy tools from one 6.6a installation to another.

```
ccm_copy_tools -o output_file old_installation_dir
```

This form of the command copies 6.5a tools from an existing Synergy 6.5a or 6.6a installation to a saved file for later installation elsewhere. This is useful when the previous and new Synergy installations are not visible to each other, so the direct copying performed in the previous form of the command cannot be used.

```
ccm_copy_tools -i input_file [new_installation_dir]
```

This form of the command copies 6.5a tools from a saved file into an existing Synergy 6.6a installation. The saved file must have been produced by an earlier use of the `ccm_copy_tools -o` command. You'll see an error if the new installation directory is not from Synergy 6.6a.

In all modes, you can also use the following options:

- m Copy the files used for ObjectMake.

- d Copy the tools used for data archiving.

The default for -m and -d is to copy both sets of files.

- v Show the path to each file as it is copied.

Appendix C: Notices

This information was developed for products and services offered in the U.S.A. IBM® may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send written license inquiries to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10504-1785
U.S.A.

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send written inquiries to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106-0032, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:
INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions. Therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who want to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

Intellectual Property Dept. for Rational® Software
IBM Corporation
1 Rogers Street
Cambridge, Massachusetts 02142
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of

performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

Copyright license

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs.

Each copy or any portion of these sample programs or any derivative work, must include a copyright notice as follows:

© (your company name) (year). Portions of this code are derived from IBM Corp. (Sample Programs.) © Copyright IBM Corp. 1992 - 2008.

Trademarks

IBM, the IBM logo, ibm.com, Rational, Telelogic, Telelogic Synergy, Telelogic Change, SYNERGY/CM, SYNERGY/Change, Telelogic Lifecycle Solution Tools, Telelogic License Server, Distributed CM, DCM, and Telelogic Synergy Distributed are trademarks or registered trademarks of International Business Machines Corporation in the United States, other countries, or both. These and other IBM trademarked terms are marked on their first occurrence in this information with the appropriate symbol (® or ™), indicating US registered or common law trademarks owned by IBM at the time this information was published. Such trademarks may also be registered or common law trademarks in other countries. A current [list of IBM trademarks](http://www.ibm.com/legal/copytrade.html) is available on the Web at <http://www.ibm.com/legal/copytrade.html>.

HP and HP-UX are registered trademarks of Hewlett-Packard Corporation.

Informix is a registered trademark of International Business Machines Corporation in the United States, other countries, or both.

Linux is a trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows Explorer, Windows 2003, Windows XP, Windows Vista and/or other Microsoft products referenced herein are either trademarks or registered trademarks of Microsoft Corporation.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates.

Sun, Sun Microsystems, Sun OpenWindows, and Solaris are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and other countries.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product or service names may be trademarks or service marks of others.

