



Netcool Service Quality Manager
Module for Mobile User Plane Service



Version 1.2



Interface Control Guide

Note: Before you use this information and the product it supports, read the information in [Notices](#).

This edition applies to version 1, release 2 of IBM Tivoli Netcool Service Quality Manager Module for Mobile User Plane Service (Product number 5724-V48) and to all subsequent releases and modifications until otherwise indicated in new editions.

© **Copyright International Business Machines Corporation 2011.** US
Government Users Restricted Rights - Use, duplication or disclosure
restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

1	About this publication	1
1.1	Intended audience.....	1
1.2	What this publication contains	1
1.3	Publications.....	2
1.3.1	IBM Tivoli Netcool Service Quality Manager core library.....	2
1.3.2	IBM Tivoli Netcool Service Quality Manager Module for Mobile User Plane Service library ..	3
1.3.3	Accessing terminology online	4
1.3.4	Accessing publications online.....	4
1.3.5	Ordering publications	4
1.4	Tivoli technical training	4
1.5	Tivoli user groups.....	5
1.6	Support information	5
1.6.1	Online	5
1.6.2	IBM Support Assistant.....	5
1.7	Conventions used in this guide	5
1.7.1	Typeface conventions	5
1.7.2	Operating system-dependent variables and paths	6
2	Interface specifications	7
2.1	Data collection and transfer mechanisms	8
2.2	Data compression	9
2.3	Data specification.....	9
2.3.1	Data file aggregation	14
2.4	Custom resource mapping.....	15
3	Enumerations and definitions	17
3.1	TRANSACTIONTYPE	17
3.2	CAUSETYPE	20
3.3	RAT	21
3.4	CAUSECODE Values.....	21
4	Service provisioning	29
4.1	Resource instance provisioning	29
4.2	Provisioning examples	30
4.2.1	Resource type 1 SERVICE.....	30
4.2.2	Resource type 2 GGSN.....	30
4.2.3	Resource type 3 SGSN	30
4.2.4	Resource type 4 APN.....	30
4.2.5	Resource type 5 MIMETYPE.....	30
4.2.6	Resource type 6 UTRAN.....	30
Appendix A: Provisioning		31
Appendix B: Data field types		33
Appendix C: Product acronyms		35
Index		37
Notices		39

**TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL
GUIDE**

1 About this publication

This publication details the IBM® Tivoli® Netcool® Service Quality Manager Module for Mobile User Plane Service input interface, such as comma-separated value (CSV) input files, in terms of:

- File-naming conventions and upload directory
- Data file format, granularity, and latency
- Supported delivery and collection mechanism and frequency
- Custom resource mapping

This guide also details the set of resources that must be provisioned, including the provisioning details that are specific to the Tivoli Netcool Service Quality Manager Module for Mobile User Plane Service module.

1.1 Intended audience

This publication is intended for parties who want to provide mediated data to the Tivoli Netcool Service Quality Manager Module for Mobile User Plane Service version 1.2.

Readers need to be familiar with the following topics:

- IT principles
- UNIX® operating systems

1.2 What this publication contains

This publication contains the following chapters:

- Chapter 2 "Interface specifications"
Provides interface specifications and file-naming conventions.
- Chapter 3 "Enumerations and definitions"
Provides a description of the enumeration types.
- Chapter 4 "Service provisioning"
Provides a description of the steps you take to provision the customer-specific portions of a service module.

This publication contains the following appendixes:

- Appendix A "Provisioning"

Provides a description of the provisioning system and resource types.

- Appendix B " Data field types"

Provides a description of data field types.

- Appendix C " Product acronyms"

Provides a description of product acronyms.

1.3 Publications

The following publications are available:

- IBM Tivoli Netcool Service Quality Manager core library
- IBM Tivoli Netcool Service Quality Manager Module for Mobile User Plane Service library

1.3.1 IBM Tivoli Netcool Service Quality Manager core library

The IBM Tivoli Netcool Service Quality Manager core library contains the following publications:

- *IBM Tivoli Netcool Service Quality Manager AIX Server Installation Guide, GC23-9847-00*

Describes how to install the Tivoli Netcool Service Quality Manager Server system on IBM AIX® systems.

- *IBM Tivoli Netcool Service Quality Manager Solaris Server Installation Guide, GC23-9846-00*

Describes how to install the Tivoli Netcool Service Quality Manager Server system on Solaris systems.

- *IBM Tivoli Netcool Service Quality Manager Client Installation Guide, GC23-9850-00*

Describes how to install the Tivoli Netcool Service Quality Manager client.

- *IBM Tivoli Netcool Service Quality Manager Upgrade Guide, SC23-9842-00*

Details how to upgrade from one Tivoli Netcool Service Quality Manager version to another.

- *IBM Tivoli Netcool Service Quality Manager AIX System Administration Guide, SC23-9845-00*

Provides an overview of the IBM AIX® Tivoli Netcool Service Quality Manager administrative tasks including instructions on how to complete the following tasks:

- Starting and stopping Tivoli Netcool Service Quality Manager.
- Running batch processes such as archiving trace files and log files.
- Backing up and restoring the system.

- *IBM Tivoli Netcool Service Quality Manager Solaris System Administration Guide, SC23-9844-00*

Provides an overview of the Solaris Tivoli Netcool Service Quality Manager administrative tasks including instructions on how to complete the following tasks:

- Starting and stopping Tivoli Netcool Service Quality Manager.
- Running batch processes such as archiving trace files and log files.
- Backing up and restoring the system.

- *IBM Tivoli Netcool Service Quality Manager Provisioning Service SI Guide, SC23-9852-00*
Reference guide containing information for provisioning the Tivoli Netcool Service Quality Manager system.
- *IBM Tivoli Netcool Service Quality Manager Customer Experience Manager Provisioning Guide, SC23-9843-00*
Provides information for provisioning the Tivoli Netcool Customer Experience Manager system.
- *IBM Tivoli Netcool Service Quality Manager Customer Experience Manager Monitoring Guide, SC23-9482-00*
Describes how to use and monitor the Tivoli Netcool Customer Experience Manager feature in Tivoli Netcool Service Quality Manager.
- *IBM Tivoli Netcool Service Quality Manager Monitoring Guide, SC23-9103-01*
Describes monitoring (Service level agreement (SLA) monitor, Key quality indicator (KQI) analyzer, alarm monitor, audit manager and SLA Webview applications) in Tivoli Netcool Service Quality Manager.
- *IBM Tivoli Netcool Service Quality Manager Configuration Guide, SC23-9102-01*
Describes SLA provisioning (parties, SLAs, and SLA templates applications) and Tivoli Netcool Service Quality Manager provisioning (services resources, KQI models, and service models applications) in Tivoli Netcool Service Quality Manager.
- *IBM Tivoli Netcool Service Quality Manager BusinessObjects Installation and Configuration Guide, SC23-9473-00*
Provides information on the steps required to install and configure the BusinessObjects server and client for use with Tivoli Netcool Service Quality Manager.
- *IBM Tivoli Netcool Customer Experience Manager Customer Relationship Management Development Guide, SC23-9857-00*
Provides an overview of the Customer Relationship Management (CRM) proxy server and the CRM plug-in module. The CRM plug-in modules, developed using Java™ code, mediate between the Tivoli Netcool Customer Experience Management framework and an external CRM system.
- *IBM Tivoli Netcool Service Quality Manager Release Notes, G111-9221-00*
Provides information on the Tivoli Netcool Service Quality Manager release contents, platform requirements, installation and upgrade procedures, and known issues.

1.3.2 IBM Tivoli Netcool Service Quality Manager Module for Mobile User Plane Service library

The IBM Tivoli Netcool Service Quality Manager Module for Mobile User Plane Service library contains the following publications:

- *IBM Tivoli Netcool Service Quality Manager Module for Mobile User Plane Service Installation Guide*
Provides the steps required to install the service module and its data sources.
- *IBM Tivoli Netcool Service Quality Manager Module for Mobile User Plane Service Overview Guide*

Provides an overview of the product architecture.

- *IBM Tivoli Netcool Service Quality Manager Module for Mobile User Plane Service Interface Control Guide*

Provides details of the input interface for the service module.

- *IBM Tivoli Netcool Service Quality Manager Module for Mobile User Plane Service Release Notes*

Provides information on the service module release contents, platform requirements, installation procedures, and known issues.

1.3.3 Accessing terminology online

The IBM Terminology Web site consolidates the terminology from IBM product libraries in one convenient location. You can access the Terminology Web site at : www.ibm.com/software/globalization/terminology.

1.3.4 Accessing publications online

The product CD contains the publications that are in the product library. The format of the publications is PDF.

IBM posts publications for Tivoli products, as they become available and whenever they are updated, to the Tivoli Documentation Central Web site at <http://www.ibm.com/tivoli/documentation>.

Note: If you print PDF documents on other than letter-sized paper, set the option in the **File -> Print** window that allows Adobe® Reader to print letter-sized pages on your local paper.

1.3.5 Ordering publications

You can order many Tivoli publications online at <http://www.ibm.com/e-business/linkweb/publications/servlet/pbi.wss>.

You can also order by telephone by calling one of these numbers:

- In the United States: 800-879-2755
- In Canada: 800-426-4968

In other countries, contact your software account representative to order Tivoli publications. To locate the telephone number of your local representative, perform the following steps:

1. Go to <http://www.ibm.com/e-business/linkweb/publications/servlet/pbi.wss>.
2. Select your country from the list and click **Go**.
3. Click **About this site** in the main panel to see an information page that includes the telephone number of your local representative.

1.4 Tivoli technical training

For Tivoli technical training information, refer to the following IBM Tivoli Education Web site at <http://www.ibm.com/software/tivoli/education>.

1.5 Tivoli user groups

Tivoli user groups are independent, user-run membership organizations that provide Tivoli users with information to assist them in the implementation of Tivoli Software solutions. Through these groups, members can share information and learn from the knowledge and experience of other Tivoli users. Tivoli user groups include the following members and groups:

- 23,000+ members
- 144+ groups

Access the link for the Tivoli Users Group at www.tivoli-ug.org.

1.6 Support information

If you have a problem with your IBM software, you want to resolve it quickly. IBM provides the following ways for you to obtain the support you need:

1.6.1 Online

Access the Tivoli Software Support site at

<http://www.ibm.com/software/sysmgmt/products/support/index.html?ibmprd=tivmanok>.

Access the IBM Software Support site at <http://www.ibm.com/software/support/probsub.html>.

1.6.2 IBM Support Assistant

The IBM Support Assistant is a free local software serviceability workbench that helps you resolve questions and problems with IBM software products. The Support Assistant provides quick access to support-related information and serviceability tools for problem determination. To install the Support Assistant software, go to: <http://www.ibm.com/software/support/isa>

1.7 Conventions used in this guide

This publication uses several conventions for special terms and actions, operating system-dependent commands and paths, and margin graphics.

1.7.1 Typeface conventions

This publication uses the following typeface conventions:

Bold

- Lowercase commands and mixed case commands that are otherwise difficult to distinguish from surrounding text.
- Interface controls (check boxes, push buttons, radio buttons, spin buttons, fields, folders, icons, list boxes, items inside list boxes, multicolumn lists, containers, menu choices, menu names, tabs, property sheets), labels (such as **Tip:** and **Operating system considerations:**)
- Keywords and parameters in text.

Italics

- Citations (examples: titles of publications, diskettes, and CDs)
- Words defined in text (example: a non-switched line is called a *point-to-point line*)

- Emphasis of words and letters (words as words example: "Use the word *that* to introduce a restrictive clause."; letters as letters example: "The LUN address must start with the letter *L*.")
- New terms in text (except in a definition list): a *view* is a frame in a workspace that contains data.
- Variables and values you must provide (example: ...where *myname* represents...)

Monospace

- Examples and code examples.
- File names, programming keywords, and other elements that are difficult to distinguish from surrounding text.
- Message text and prompts addressed to the user.
- Text that the user must type.
- Values for arguments or command options.

1.7.2 Operating system-dependent variables and paths

This publication uses the UNIX convention for specifying environment variables and for directory notation. When using the Windows® command line, replace *\$variable* with *%variable%* for environment variables and replace each forward slash (/) with a backslash (\) in directory paths. The names of environment variables are not always the same in the Windows and UNIX environments. For example, *%TEMP%* in Windows environments is equivalent to *\$TMPDIR* in UNIX environments.

Note: If you are using the bash shell on a Windows system, you can use the UNIX conventions.

2 Interface specifications

The interface between the Tivoli Netcool Service Quality Manager product and the mediation subsystem can be specified. This interface is used to collect raw data.

Table 1: Interface specifications summary

Service module version	1.2.
Data type	ASCII files; comma-separated values; header row (or predefined field order); optionally compressed using the GNU file compression (gzip) utility
	Map file
Collection method	Local directory
Transfer method	Defined by mediation
Mapping files in use? Y N	Yes
File name syntax	<p><i>A</i><startdate><starttime>-<enddate><endtime>[_ <Optional>].csv</p> <p>The timestamps on the file name are mandatory and identify the collection period. The format is YYYYMMDD.HHMMshhmm where:</p> <p><startdate> and <enddate>:</p> <ul style="list-style-type: none"> • <i>YYYY</i> is the year in 4-digit notation; • <i>MM</i> is the month in 2-digit notation (01 - 12); • <i>DD</i> is the day in 2-digit notation (01 - 31); <p><starttime> and <endtime>:</p> <ul style="list-style-type: none"> • <i>HH</i> is the 2-digit hour of the day (local time), based on 24-hour clock (00 - 23); • <i>MM</i> is the 2-digit minute of the hour (local time) • <i>s</i> (optional) is the sign of the local time differential from UTC (+ or -), in case the time differential to UTC is 0 then the sign may be arbitrarily set to "+" or "-" • <i>hh</i> (optional) is the 2-digit number of hours of the local time differential from UTC (00-23) • <i>mm</i> (optional) is the 2-digit number of minutes of the local time differential from UTC (00-59) <p>The <i>Optional</i> part of the naming is used to uniquely identify attributes</p>

	<p>such as:</p> <p><i>[recommended]</i> The service module, for example, <code>_VoIP</code></p> <p>The input data source type, for example, <code>_CDR</code></p> <p>The mediation instance providing the files.</p> <p>The file name may have multiple optional tokens, for example, <code>[_<Optional 1>][_<Optional 2>]</code>.</p> <p>File name examples:</p> <p style="padding-left: 40px;"><code>A20050907.1030+0000-20050907.1100+0000_MUP.csv</code></p> <p style="padding-left: 40px;"><code>A20050907.1030-20050907.1100_MUP_mediation1.csv</code></p> <p>Meaning: Start of first granularity period 07 September 2005, 10:30 local time, end of last granularity period 07 September 2005, 11:00 local time, with a time differential of 0 against UTC time.</p>
--	--

2.1 Data collection and transfer mechanisms

Use the Tivoli Netcool Service Quality Manager adapter to collect input data for processing. You can also use the adapter to define how the data files are transferred from the mediation subsystem to the adapter.

Table 2: Data collection and transfer mechanisms

Collection method	Local directory
Collection point (default data directory¹)	<code>\${SAVARDIR}/adapter/sqm_mup_prb_loader/</code>
Collection frequency	15 minutes
Distribution method	Data push
Distribution frequency²	15 minutes
Max delivery latency³	30 minutes
Compression	Files may be compressed using the gzip utility.
¹ Default data directory, configured in the Tivoli Netcool Service Quality Manager adapter.	
² The distribution frequency indicates how often the mediation component should provide input data to the adapter process. This value is often identical to the collection frequency.	
³ Max latency, configured in the Tivoli Netcool Service Quality Manager adapter known as a <i>grace period</i> . Data files that arrive past this time are not processed. Typically, by default it is configured to be two times the collection interval. Max latency is configured in the <code>\${WMCROOT}/conf/adapter/collector/sqm_mup_prb_loader.properties</code> file.	

Data files are collected by the Tivoli Netcool Service Quality Manager adapter or delivered by the mediation. Transfer protocols such as file transfer protocol (FTP), secure file transfer protocol

(SFTP), secure copy protocol (SCP), UNIX-to-UNIX copy protocol (UUCP), and local copy are most often used to transfer data. The transfer protocol is defined by the mediation capabilities or agreed on by the Tivoli Netcool Service Quality Manager customer and the party providing the mediation.

Where the collection mechanism is *Local directory*, the mediation must deliver the data files to the defined *Collection point* directory. This transfer or distribution mechanism is referred to as *data push*, where data is pushed to the adapters.

The default value for the root data directory (`${SAVARDIR}`) is `/appl/sa/var`.

2.2 Data compression

The interface supports data files compressed by the `gzip` utility. In such cases, the files without a time zone offset are similar to the following format:

```
A20050907.1030-20050907.1100_MUP_mediation1.gz
```

Such compression is used in deployments to reduce network bandwidth, improve link latency, and so on. However data compression can increase both disk Input/Output and CPU load.

The interface also support archive files such as archives that contain multiple comma-separated value (CSV) files.

The following files are not currently supported:

- Tar files, or files that include the `.tar` file name extension.
- Tar files that are compressed with the `gzip` utility. These files include the `tar.gz` or `.tgz` file name extension.
- UNIX compressed files that include the `.z` file name extension.
- Compressed files that include the `.zip` file name extension.

2.3 Data specification

The content format of the data files is defined.

Table 3: Data file format

Field name	Type ¹	Maximum length	Constraints	Field description	Notes
IMSI	Long		NON NULLABLE	The International Mobile Subscriber Identity (IMSI) of the subscriber. IMSI uniquely identifies the Customer who instigated each	

TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL GUIDE

Field name	Type ¹	Maximum length	Constraints	Field description	Notes
				<p>specific transaction type.</p> <p>The IMSI is comprised of the MCC, MNC and MSIN where:</p> <ul style="list-style-type: none"> • MCC is the mobile country code. • MNC is the mobile network code. • MSIN is the mobile subscriber identity number. 	
IMEISV	Varchar	16	NULLABLE	<p>The IMSI and Software Version Number associated with the customer's handset or terminal.</p> <p>The format of the IMEISV is TAC-SNR-SV where:</p> <ul style="list-style-type: none"> • TAC is the type allocation code • SNR is the serial number. • SV is the software version number <p>The older IMEI format which only includes the TAC and SNR is also supported.</p>	
SRC_IPADDRESS	Varchar	64	NULLABLE	The source or client IP address	
DEST_IPADDRESS	Varchar	64	NULLABLE	<p>The destination or host IP address.</p> <p>This field can identify the remote server IP address that the client communicates with.</p> <p>For example, the destination IP address might be the IP address of the SMTP server for a SMTP_TRANS transaction or the application Web server for a HTTP GET transaction or the destination GGSN or PDSN for the client command.</p> <p>If the DEST_IPADDRESS is non-null, see the DEST_IPADDRESS to</p>	

TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL GUIDE

Field name	Type ¹	Maximum length	Constraints	Field description	Notes
				DEST_HOST mapping file to resolve to the DestDomain ResourceType	
SRC_PORT	Integer		NULLABLE > 0 Integer	The source or client port number	
DEST_PORT	Integer		NULLABLE > 0 Integer	The destination or HOST port number	
DEST_URI	Varchar	256	NULLABLE	<p>The partial Uniform Resource Identifier (URI) is a compact string of characters used to identify or name a destination resource on the Internet/Intranet that is used for the set of user data transaction types.</p> <p>The URI syntax is essentially a URI scheme name like "http", "ftp", "mailto", "dns", "imap" etc., followed by a colon character, and then a scheme-specific part.</p> <p>Note: any trailing path, parameter, query or fragment strings following the authority string (hostname:port) is excluded from the DEST_URI field. You are only interested in the Domain the DEST_URI is pointing to.</p> <p>For example: imap://[<user>[;AUTH=<type>]@]<host>[:<port>]/</p> <p>Examples: http://www.ibm.com/ 152.16.78.100:10021/</p>	
CGI	Varchar	32	NON NULLABLE	<p>The CGI is the cell global identity for the current cell.</p> <p>The format of the CGI is MCC-MNC-LAC-CI where:</p> <ul style="list-style-type: none"> • MCC is the mobile country code. • MNC is the mobile network code. • LAC is the location area code • CI is the cell identifier <p>It is also possible to use service area identifier (SAI) = MCC-</p>	

TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL GUIDE

Field name	Type ¹	Maximum length	Constraints	Field description	Notes
				MNC-LAC-SAC SAC = Service area code or routing area identifier (RAI) = MCC-MNC-LAC-RAC RAC = routing area code Where CGI is not available in the data source.	
SGSN	Varchar	64	NON NULLABLE	The name or IP address of the SGSN.	
GGSN	Varchar	64	NON NULLABLE	The name or IP address of the GGSN.	
APN	Varchar	64	NULLABLE	The access point name (APN) that is associated with the current PDP context.	
RAT	ENUM		NULLABLE	The Radio Access Technology (RAT) that this application layer protocol crosses. See section 3 Enumerations and definitions for a list of valid values	
USERAGENT	Varchar	256	NULLABLE	A user agent is the client application used with a particular network protocol; For example: Go!Zilla 3.x (www.gozilla.com) Mozilla/4.0 (compatible; MSIE 4.01; Windows 95) Python-urllib/2.0a1	
MIMETYPE	Varchar	128	NULLABLE	The Multipurpose Internet Mail Extension (MIME) type name for the particular TRANSACTIONTYPE For example: text/html application/x-java-jnlp-file application/xhtml+xml	
TRANSACTIONTYPE	ENUM		NON NULLABLE	The TransactionType to which the data on this row applies See section 3 Enumerations and	

TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL GUIDE

Field name	Type ¹	Maximum length	Constraints	Field description	Notes
				definitions for a list of valid values.	
CAUSETYPE	ENUM		NON NULLABLE	The protocol-specific cause code type that is required to interpret the transaction termination cause. See section 3 Enumerations and definitions for a list of valid values.	
CAUSECODE	ENUM		NON NULLABLE	The protocol-specific cause code that identifies the reason for the termination of the transaction. See section 3 Enumerations and definitions for a list of valid values.	
COUNT	Integer		NON NULLABLE >= 1	The number of transactions associated with the unique combination of IMSI, IMEI, GGSN, RAT, USER_AGENT, MIMETYPE, SRC_IPADDRESS, DEST_IPADDRESS, URI, SRC_PORT, DEST_PORT, CAUSETYPE, TRANSACTIONTYPE, and CAUSECODE for this row. COUNT should always be >= 1.	
DURATION	Integer		NULLABLE >= 0	This is the total transaction duration or round trip time (RTT) in milliseconds for the transactions reported on this row.	
UPTOTDATACOUNT	Double		NULLABLE >= 0	Upload total data count - represents the total number of user data kilobytes sent in the uplink direction for the set of transactions reported in this row.	
DOWNTOTDATACOUNT	Double		NULLABLE >= 0	Download total data count - represents the total number of user data kilobytes sent in the downlink direction for the set of transactions reported in this row.	

TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL GUIDE

Field name	Type ¹	Maximum length	Constraints	Field description	Notes
¹ The list of valid data types and their descriptions is given in Appendix B.					

Example:

```
IMSI, IMEISV, SRC_IPADDRESS, DEST_IPADDRESS, SRC_PORT, DEST_PORT, DEST_URI, CGI, SGSN, GGSN, APN, RAT, USERAGENT, MIMETYPE, TRANSACTIONTYPE, CAUSETYPE, CAUSECODE, COUNT, DURATION, UPTOTDATABCOUNT, DOWNTOTDATABCOUNT  
  
3104100230000000, VDO0000000000000000, 40.309.445.479, 303.75.433.49, 2517, 80, www.ibm.com, 78941084D7F99F, MUP_SGSN1, MUP_GGSN1, MUP_net, 1, Nokia2626/2.0 (06.80) Profile/MIDP-2.0 Configuration/CLDC-1.1, image-gif, 15, 83, 1, 1, 205, 0.75, 120.56
```

2.3.1 Data file aggregation

The CSV data file must contain a row for each unique combination of the following data field values:

- IMSI
- CAUSETYPE
- TRANSACTIONTYPE
- CAUSECODE

Additionally, new rows are created for the following columns if the supplied column values are not null:

- IMEI
- GGSN
- SGSN
- APN
- CGI
- RAT
- MIMETYPE
- USERAGENT
- SRC_IPADDRESS
- DEST_IPADDRESS
- DEST_URI

- SRC_PORT
- DEST_PORT

Each data value that is displayed in a row is aggregated to provide a single value for this combination of key field values.

The following columns contain the data sums in each row based on the previously specified grouping:

- COUNT
- DURATION
- UPTOTDATACOUNT
- DOWNTOTDATACOUNT

2.4 Custom resource mapping

The Tivoli Netcool Service Quality Manager product uses mapping files to resolve some fields and keys in the input data files. For instance, the input file can contain an IMSI field where the map file resolves to an IMSI group or provides additional information.

Table 4: Custom mapping files

Data type	ASCII files; comma-separated values; header row
Default location	\${SAVARDIR}/adapter/mappings/resources/
File name syntax	sqm_mup_cellarea.map sqm_mup_service.map sqm_mup_rnc.map

The map files are reloaded at the beginning of every adapter data interval. By using map-file reloading, the map files can be updated at any time.

Example: Cells and cell areas

The following example shows a mapping between cells (CGI) and cell areas:

```
78941007E43150,Cell Area 0,
78941007EF1600,Cell Area 0,
789410083DC360,Cell Area 0,
789410083DC5C0,Cell Area 1,
7894100BCE00C0,Cell Area 1,
7894100BCF20F0,Cell Area 1,
7894100BD622D0,Cell Area 1,
7894100BD70B10,Cell Area 2,
```

Example: Destination URIs and services

The following example shows a mapping between destination URIs (DEST_URI) and services:

```
http://www.socialnetwork.com/,Social_network,  
https://210.10.11.12/,Social_network,  
www.socialnetwork.co.uk/,Social_network,  
ftp://10.111.120.134,IBM_FTP_Server,
```

Example: Cells and RNCs

The following example shows a mapping between cells (CGI) and RNCs:

```
78941007E43150,RNC0,  
78941007EF1600,RNC0,  
789410083DC360,RNC0,  
789410083DC5C0,RNC1,  
7894100BCE00C0,RNC1,  
7894100BCF20F0,RNC1,  
7894100BD622D0,RNC2,  
7894100BD70B10,RNC2,
```

3 Enumerations and definitions

Enumerations are used by the mediation when creating the data files for the adapter.

3.1 TRANSACTIONTYPE

Table 5: TRANSACTIONTYPE ENUM VALUES

<i>ID</i>	<i>Description</i>
1	HTTP_GET
2	HTTP_PUT
3	HTTP_POST
4	HTTP_DELETE
5	HTTP_HEAD
6	HTTP_CONNECT
7	SMTP_EHLO
8	SMTP_HELO
9	SMTP_MAILFROM
10	SMTP_VRFY
11	SMTP_EXPN
12	SMTP_RCPTTO
12	SMTP_DATA
14	SMTP_QUIT
15	POP_USER
16	POP_AUTH
17	POP_RETR
18	POP_PASS
19	POP_APOP
20	POP_UIDL
21	POP_LIST

**TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL
GUIDE**

<i>ID</i>	<i>Description</i>
22	POP_STAT
23	POP_DELE
24	POP_RSET
25	POP_QUIT
26	IMAP_CAPABILITY
27	IMAP_LOGOUT
28	IMAP_STARTTLS
29	IMAP_AUTHENTICATE
30	IMAP_LOGIN
31	IMAP_SELECT
32	IMAP_EXAMINE
33	IMAP_CREATE
34	IMAP_DELETE
35	IMAP_RENAME
36	IMAP_SUBSCRIBE
37	IMAP_UNSUBSCRIBE
38	IMAP_STATUS
39	IMAP_LSUB
40	IMAP_APPEND
41	IMAP_CHECK
42	IMAP_CLOSE
43	IMAP_EXPUNGE
44	IMAP_SEARCH
45	IMAP_FETCH
46	IMAP_STORE
47	IMAP_COPY
48	IMAP_UID
49	DNS_Query
50	WSP_GET
51	WSP_PUT

**TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL
GUIDE**

<i>ID</i>	<i>Description</i>
52	WSP_POST
53	WSP_DELETE
54	WSP_HEAD
55	WSP_CONNECT
56	WSP_PUSH
57	WSP_CONFIRM_PUSH
58	WSP_DISCONNECT
59	WSP_SUSPEND
60	WSP_RESUME
61	FTP_SMNT
62	FTP_CWD
63	FTP_CDUP
64	FTP_REIN
65	FTP_STOR
66	FTP_RETR
67	FTP_USER
68	FTP_PASS
69	FTP_QUIT
70	FTP_REST
71	FTP_ABOR
72	FTP_PWD
73	FTP_MODE
74	FTP_STOU
75	FTP_RNFR
76	FTP_RNTO
77	FTP_RMD
78	FTP_MKD
79	FTP_LIST
80	FTP_DELE
81	TCP_CONNECTION

TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL GUIDE

<i>ID</i>	<i>Description</i>
82	ACCESS_REQUEST
800	SMTP
801	HTTP
802	WSP
803	POP
804	DNS
805	FTP
806	IMAP
807	TCP
808	RADIUS

Note: The TransactionType ENUM Values 800 to 808 are used when mapping to the individual User Plane Protocol TransactionTypes such as HTTP_GET, HTTP_POST, FTP_RETR, and so on, are not available from the data source or where data compression is needed for performance reasons. When mediating to the adapter by using the TransactionType ENUM Values 800 to 808, do not use another TransactionType ENUM Value, which can cause a double counting of transactions.

3.2 CAUSETYPE

Table 6: CAUSETYPE ENUM VALUES

<i>Id</i>	<i>Description</i>
99	Unrecognized Cause
80	SMTP
81	HTTP
82	WSP
83	POP
84	DNS
85	FTP
86	IMAP
87	TCP
88	RADIUS

3.3 RAT

Table 7: Radio access technology (RAT) ENUM VALUES

<i>Id</i>	<i>Description</i>
1	GPRS
2	UMTS

3.4 CAUSECODE Values

Table 8: CAUSECODE VALUES

<i>CAUSETYPE</i>	<i>CAUSECODE Id</i>	<i>Description</i>
Unrecognized Cause	-1	Unrecognized Cause Type
SMTP	211	System status, or system help reply
SMTP	214	Help message
SMTP	220	Service ready
SMTP	250	Requested mail action okay, completed
SMTP	251	User not local; will forward to <forward-path>
SMTP	252	Cannot VRFY user, but will accept message and attempt delivery
SMTP	354	Start mail input; end with <CRLF>.<CRLF>
SMTP	421	<domain> Service not available, closing transmission channel
SMTP	450	Requested mail action not taken: mailbox unavailable
SMTP	451	Requested action aborted: local error in processing
SMTP	452	Requested action not taken: insufficient system storage
SMTP	455	Server unable to accommodate parameters
SMTP	500	Syntax error, command unrecognized
SMTP	501	Syntax error in parameters or arguments
SMTP	502	Command not implemented
SMTP	503	Bad sequence of commands
SMTP	504	Command parameter not implemented
SMTP	550	Requested action not taken: mailbox unavailable
SMTP	551	User not local; please try <forward-path>
SMTP	552	Requested mail action aborted: exceeded storage allocation
SMTP	553	Requested action not taken: mailbox name not allowed
SMTP	554	Transaction failed
SMTP	555	MAIL FROM/RCPT TO parameters not recognized or not implemented
HTTP	100	Continue
HTTP	101	Switching Protocols

**TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL
GUIDE**

CAUSETYPE	CAUSECODE Id	Description
HTTP	102	Processing
HTTP	200	OK
HTTP	201	Created
HTTP	202	Accepted
HTTP	203	Non-Authoritative Information (since HTTP/1.1)
HTTP	204	No Content
HTTP	205	Reset Content
HTTP	206	Partial Content
HTTP	207	Multi-Status
HTTP	300	Multiple Choices
HTTP	301	Moved Permanently
HTTP	302	Found
HTTP	303	See Other
HTTP	304	Not Modified
HTTP	305	Use Proxy
HTTP	306	Switch Proxy
HTTP	307	Temporary Redirect
HTTP	400	Bad Request
HTTP	401	Unauthorized
HTTP	402	Payment Required
HTTP	403	Forbidden
HTTP	404	Not Found
HTTP	405	Method Not Allowed
HTTP	406	Not Acceptable
HTTP	407	Proxy Authentication Required
HTTP	408	Request Timeout
HTTP	409	Conflict
HTTP	410	Gone
HTTP	411	Length Required
HTTP	412	Precondition Failed
HTTP	413	Request Entity Too Large
HTTP	414	Request-URI Too Long
HTTP	415	Unsupported Media Type
HTTP	416	Requested Range Not Satisfiable
HTTP	417	Expectation Failed
HTTP	422	Unprocessable Entity
HTTP	423	Locked
HTTP	424	Failed Dependency

**TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL
GUIDE**

CAUSETYPE	CAUSECODE Id	Description
HTTP	425	Unordered Collection
HTTP	426	Upgrade Required
HTTP	449	Retry With
HTTP	450	Blocked
HTTP	500	Internal Server Error
HTTP	501	Not Implemented
HTTP	502	Bad Gateway
HTTP	503	Service Unavailable
HTTP	504	Gateway Timeout
HTTP	505	HTTP Version Not Supported
HTTP	506	Variant Also Negotiates (Experimental)
HTTP	507	Insufficient Storage
HTTP	509	Bandwidth Limit Exceeded
HTTP	510	Not Extended
WSP	100	Continue
WSP	101	Switching Protocols
WSP	102	Processing
WSP	200	OK
WSP	201	Created
WSP	202	Accepted
WSP	203	Non-Authoritative Information (since WAP/1.1)
WSP	204	No Content
WSP	205	Reset Content
WSP	206	Partial Content
WSP	207	Multi-Status
WSP	300	Multiple Choices
WSP	301	Moved Permanently
WSP	302	Found
WSP	303	See Other
WSP	304	Not Modified
WSP	305	Use Proxy
WSP	306	Switch Proxy
WSP	307	Temporary Redirect
WSP	400	Bad Request
WSP	401	Unauthorized
WSP	402	Payment Required
WSP	403	Forbidden
WSP	404	Not Found

**TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL
GUIDE**

CAUSETYPE	CAUSECODE Id	Description
WSP	405	Method Not Allowed
WSP	406	Not Acceptable
WSP	407	Proxy Authentication Required
WSP	408	Request Timeout
WSP	409	Conflict
WSP	410	Gone
WSP	411	Length Required
WSP	412	Precondition Failed
WSP	413	Request Entity Too Large
WSP	414	Request-URI Too Long
WSP	415	Unsupported Media Type
WSP	416	Requested Range Not Satisfiable
WSP	417	Expectation Failed
WSP	422	Unprocessable Entity
WSP	423	Locked
WSP	424	Failed Dependency
WSP	425	Unordered Collection
WSP	426	Upgrade Required
WSP	449	Retry With
WSP	450	Blocked
WSP	500	Internal Server Error
WSP	501	Not Implemented
WSP	502	Bad Gateway
WSP	503	Service Unavailable
WSP	504	Gateway Timeout
WSP	505	HTTP Version Not Supported
WSP	506	Variant Also Negotiates (Experimental)
WSP	507	Insufficient Storage
WSP	509	Bandwidth Limit Exceeded
WSP	510	Not Extended
POP	1	OK
POP	2	ERR
POP	3	IN-USE
POP	4	LOGIN-DELAY
POP	5	SYS/TEMP
POP	6	SYS/PERM
POP	7	AUTHENTICATION
DNS	0	No Error Condition

**TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL
GUIDE**

CAUSETYPE	CAUSECODE Id	Description
DNS	1	Format error
DNS	2	Server failure
DNS	3	Name Error
DNS	4	Not Implemented
DNS	5	Refused
DNS	6	YXDomain
DNS	7	YXRSet
DNS	8	NXRSet
DNS	9	NotAuth
DNS	10	NotZone
DNS	15	Unassigned (11-15)
DNS	16	BADSIG
DNS	17	BADKEY
DNS	18	BADTIME
DNS	19	BADMODE
DNS	20	BADNAME
DNS	21	BADALG
DNS	22	BADTRUNC
FTP	110	Restart marker reply
FTP	120	Service ready in nnn minutes
FTP	125	Data connection already open; transfer starting
FTP	150	File status okay; about to open data connection
FTP	200	Command okay.
FTP	202	Command not implemented, superfluous at this site.
FTP	211	System status, or system help reply
FTP	212	Directory status
FTP	213	File Status
FTP	214	Help message.
FTP	215	NAME system type
FTP	220	Service ready for new user.
FTP	221	Service closing control connection.
FTP	225	Data connection open; no transfer in progress.
FTP	226	Closing data connection.
FTP	227	Entering Passive Mode (h1,h2,h3,h4,p1,p2).
FTP	230	User logged in, proceed.
FTP	250	Requested file action okay, completed.
FTP	257	"PATHNAME" created.
FTP	331	User name okay, need password.

TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL GUIDE

CAUSETYPE	CAUSECODE Id	Description
FTP	332	Need account for login.
FTP	350	Requested file action pending further information.
FTP	421	Service not available, closing control connection.
FTP	425	Can't open data connection.
FTP	426	Connection closed; transfer aborted.
FTP	450	Requested file action not taken.
FTP	451	Requested action aborted: local error in processing
FTP	452	Requested action not taken.
FTP	500	Syntax error, command unrecognized.
FTP	501	Syntax error in parameters or arguments.
FTP	502	Command not implemented.
FTP	503	Bad sequence of commands.
FTP	504	Command not implemented for that parameter.
FTP	530	Not logged in.
FTP	532	Need account for storing files.
FTP	550	Requested action not taken. File unavailable (for example, file not found, no access).
FTP	551	Requested action aborted: page type unknown.
FTP	552	Requested file action aborted. Exceeded storage allocation (for current directory or dataset).
FTP	553	Requested action not taken. File name not allowed.
IMAP	1	OK
IMAP	2	NO
IMAP	3	BAD
TCP	0	OK, no problem
TCP	2	Missing SU
TCP	3	Abnormal End
TCP	4	Suspicious sequence of MSUs
TCP	15	Unknown MSU
TCP	64	Collision seizure
TCP	128	Timer Expiry
TCP	101	Problem has occurred during decoding
TCP	102	Collision, collision of two Begins
TCP	203	Unrecognized PDU
TCP	205	Unexpected PDU
TCP	248	End, missing or abnormal end
TCP	249	Node not allocated, memory limitation
TCP	250	Internal Error
TCP	251	Unexpected, missing beginning of the procedure

**TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL
GUIDE**

CAUSETYPE	CAUSECODE Id	Description
TCP	252	Not accepted MSU
TCP	253	Not matched MSU
TCP	254	Out of sequence
RADIUS	2	Access-Accept
RADIUS	3	Access-Reject
RADIUS	11	Access-Challenge

**TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL
GUIDE**

4 Service provisioning

You can provision the customer-specific portions of this service module. Provisioning examples for the service module and customer provisioning for the Tivoli Netcool Service Quality Manager solutions are provided.

To install a package, invoke the `package_mgmt` script with the `-i` flag followed by the package name. Similarly, to clean a package, invoke the `package_mgmt` script with the `-c` flag followed by the package name.

For a normal installation, if an element already exists, the installation fails and an error file is generated for that package. By using the force option (pass a `-f` flag at the end of the command), the operation does not fail if an element already exists. Always use the `-f` option for service module installations if the service module contains elements that have already been provisioned elsewhere.

For more information on provisioning, see “Appendix A: Provisioning.”

4.1 Resource instance provisioning

Resource types must be provisioned for this service module.

Table 9: Resources to provision

Resource type key		
Resource type name	Roll-up level	Auto-discovery
Service	Service	No
GGSN	GGSN	No
SGSN	SGSN	No
APN	APN	No
MIMETYPE	MIMETYPE	No
UTRAN	H_RNC	No

Note: The expected maximum granularity of resource instances for the service resource type is approximately 200 services. Service is a grouping of destination URIs based on the DEST_URI field from the CSV, which is mapped using the sqm_mup_service.map file. Many domains (DEST_URI) can map to the one service. For example, a service that has distributed application servers all DEST_URI domains for the service can map to one service name. The sqm_mup_service.map file in section 2.4 uses the example where three different DEST_URI domains map to the one Social_Network service. All DEST_URI domains that are not mapped in the cem_mup_service.map file default to the unknown_Service resource instance for monitoring. Verify any deviation more than the maximum of 200 services with the IBM Software Support personnel.

4.2 Provisioning examples

4.2.1 Resource type 1 SERVICE

```
<resource>
  <key name="abc" resourceType="SERVICE" level="service" />
</resource>
```

4.2.2 Resource type 2 GGSN

```
<resource>
  <key name="GGSN1" resourceType="GGSN" level="ggsn" />
</resource>
```

4.2.3 Resource type 3 SGSN

```
<resource>
  <key name="SGSN1" resourceType="SGSN" level="sgsn" />
</resource>
```

4.2.4 Resource type 4 APN

```
<resource>
  <key name="net" resourceType="APN" level="apn" />
</resource>
```

4.2.5 Resource type 5 MIMETYPE

```
<resource>
  <key name="application-vnd.wap.wbxml" resourceType="MIMETYPE" level="mimetype" />
</resource>
```

4.2.6 Resource type 6 UTRAN

```
<resource>
  <key name="SampleRNC01" resourceType="UTRAN" level="H_RNC" />
</resource>
```

Appendix A: Provisioning

Provisioning is performed by using the `package_mgmt` interface. This script supports the following commands:

```
Usage:
  package_mgmt {i|c} [options]

Commands:
  install   : package_mgmt -i package_name [-f] [-e entity_key]
  clean     : package_mgmt -c package_name [-f] [-e entity_key]

Options:
  -f       : force install or clean
```

The provisioning files for the solution are located in the `$WMCROOT/packages` directory. Do not modify existing packages. Create a new package in this folder instead. This package consists of a `package.properties` file and several XML provisioning files for the entities to be provisioned. These files are located in the `admin/provision` directory underneath the main package directory, for example, `$WMCROOT/packages/sqm_mup_prb_1.2/admin/provision`.

CombinedModels_package.xml
ServiceElements_package.xml
SimpleModels_package.xml
DsTypes_package.xml
ServiceModels_package.xml
Slats_package.xml
package.properties

The `package.properties` file contains key and value pairs that map between a provisioning entity such as resource types and a comma-separated list of XML provisioning files for that entity type. The valid entity type keys are listed in the following table.

```
combinedKQIModel=CombinedModels_package.xml
simpleKQIModel=SimpleModels_package.xml
serviceModel=ServiceModels_package.xml
serviceElement=ServiceElements_package.xml
SLAT=Slats_package.xml
dataSourceType=DsTypes_package.xml
```

Table 10: Provisioning keys and entities

Key	Entity type
combinedKQIModel	Combined key quality indicator (KQI) model
dataSourceType	Data source type
kpiModel	Key performance indicator (KPI) model
party	Party
report	Report
resource	Resource
resourceGroup	Resource group
resourceType	Resource type
Service	Service
serviceElement	Service element
serviceModel	Service model
simpleKQIModel	Simple KQI model
SLAT	Service-level agreement template(SLAT)

For more information on provisioning, see the *IBM Tivoli Netcool Service Quality Manager Provisioning Service SI Guide*.

Appendix B: Data field types

The following table lists the data field types and their descriptions:

Table 11: Data field type descriptions

<i>Data field type</i>	<i>Description</i>
Integer	Number with no decimal fraction.
Long	Number with no decimal fraction.
Float	Real number with decimal fraction.
Double	Real number with decimal fraction.
Varchar	Variable length character string, consisting of letters and numbers.
Enum	Number with no decimal fraction.

**TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL
GUIDE**

Appendix C: Product acronyms

Table 12: Description of product acronyms

<i>Acronym</i>	<i>Description</i>
AIX	Advanced Interactive Executive
CDR	Call Data Record
CPU	Central Processing Unit
CRM	Custom Resource Mapping
CSV	Comma-Separated Value
FTP	File Transfer Protocol
IMSI	International Mobile Subscriber Identity
IO	Input Output
IP	Internet Protocol
IT	Information Technology
KPI	Key Performance
KQI	Key quality indicator
PDF	Portable Document Format
RAT	Radio Access Technology
SCP	Secure Copy Protocol
SFTP	Secure File Transfer Protocol
SLA	Service-Level Agreement
UTC	Universal Time Coordinated
UUCP	UNIX-To-UNIX Copy Protocol
XML	Extensible Markup Language

**TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL
GUIDE**

Index

A

audience, 1

C

cause codes, 21
cause types, 20
conventions
 paths, 6
 typeface, 5
 variables, 6
core library, 2
custom mapping files, 15
custom resource
 mapping, 15

D

data
 collection, 8
 compression, 9
 specification, 9
data collection, 8
 frequency, 8
 method, 8
 point, 8
data compression, 9
data field types, 33
data file
 aggregation, 14
 format, 9
data file aggregation, 14
data file format, 9
data specification, 9
data transfer mechanisms, 8

E

enumerations, 17

F

file name syntax, 7

I

IBM Support Assistant, 5
interface specifications, 7

O

online publications, 4
online support, 5
online terminology, 4

P

package.properties file, 31
publication, 1

R

radio access technology values, 21
RAT values, 21
resource instance
 provisioning, 29

S

service
 provisioning, 29
service module library, 3
support, 5
 IBM Support Assistant, 5
 online, 5

T

technical training, 4
transaction types, 17
transfer mechanisms, 8

U

user groups, 5

**TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL
GUIDE**

Notices

IBM may not offer the products, services, or features discussed in this document in all countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk NY 10504-1785
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing
Legal and Intellectual Property Law
IBM Japan Ltd.
1623-14, Shimotsuruma, Yamato-shi
Kanagawa 242-8502 Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

TIVOLI NETCOOL SERVICE QUALITY MANAGER MODULE FOR MOBILE USER PLANE SERVICE INTERFACE CONTROL GUIDE

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation
5300 Cork Airport Business Park
Kinsale Road
Cork
Ireland.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

Trademarks

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at “Copyright and trademark information” at www.ibm.com/legal/copytrade.shtml.

Adobe, the Adobe logo, PostScript, and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

Java and all Java-based trademarks and logos are trademarks of Sun Microsystems, Inc. in the United States, other countries, or both.



Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product or service names may be trademarks or service marks of others.

®

Printed in the Republic of Ireland.